

# Process Management Interface for Exascale (PMIx) Standard

Version 5.0 (Draft)

Created on June 22, 2021

This document describes the Process Management Interface for Exascale (PMIx) Standard, version 5.0 (Draft).

Comments: Please provide comments on the PMIx Standard by filing issues on the document repository <a href="https://github.com/pmix/pmix-standard/issues">https://github.com/pmix/pmix-standard/issues</a> or by sending them to the PMIx Community mailing list at <a href="https://groups.google.com/forum/#!forum/pmix">https://groups.google.com/forum/#!forum/pmix</a>. Comments should include the version of the PMIx standard you are commenting about, and the page, section, and line numbers that you are referencing. Please note that messages sent to the mailing list from an unsubscribed e-mail address will be ignored.

Copyright © 2018-2020 PMIx Administrative Steering Committee (ASC). Permission to copy without fee all or part of this material is granted, provided the PMIx ASC copyright notice and the title of this document appear, and notice is given that copying is by permission of PMIx ASC.



# **Contents**

1.	Intro	duction			1
	1.1.	Background			1
	1.2.	PMIx Architecture Overview	ļ	, ,	1
	1.3.	Portability of Functionality			3
		1.3.1. Attributes in PMIx			3
2.	PMIx	Terms and Conventions			6
	2.1.	Notational Conventions			8
	2.2.	Semantics			9
	2.3.	Naming Conventions			10
	2.4.	Procedure Conventions			10
3.	Data	Structures and Types			12
	3.1.	Constants			13
		3.1.1. PMIx Return Status Constants			14
		3.1.1.1. User-Defined Error and Event Constants			16
	3.2.	Data Types			16
		3.2.1. Key Structure			16
		3.2.1.1. Key support macros			17
		3.2.2. Namespace Structure			18
		3.2.2.1. Namespace support macros			18
		3.2.3. Rank Structure			19
	A	3.2.3.1. Rank support macros			19
		3.2.4. Process Structure			20
		3.2.4.1. Process structure support macros			20
		3.2.5. Process State Structure			23
		3.2.6. Process Information Structure			24
		3.2.6.1. Process information structure support macros			25
		3.2.7. Job State Structure			26

	3.2.8.	Value Structure	27
	3	3.2.8.1. Value structure support macros	28
	3.2.9.	Info Structure	32
	3	3.2.9.1. Info structure support macros	32
	3	3.2.9.2. Info structure list macros	34
	3.2.10.	Info Type Directives	37
	3	3.2.10.1. Info Directive support macros	38
	3.2.11.	Environmental Variable Structure	40
	3	3.2.11.1. Environmental variable support macros	40
	3.2.12.	Byte Object Type	42
	3	3.2.12.1. Byte object support macros	42
	3.2.13.	Data Array Structure	43
	3	3.2.13.1. Data array support macros	43
	3.2.14.	Argument Array Macros	45
	3.2.15.	Set Environment Variable	48
3.3.		ized Data Types Used for Packing/Unpacking	49
3.4.	General	Callback Functions	51
	3.4.1.	Release Callback Function	51
	3.4.2.	Op Callback Function	52
	3.4.3.	Value Callback Function	52
	3.4.4.	Info Callback Function	53
	3.4.5.	Handler registration callback function	53
3.5.	PMIx D	atatype Value String Representations	54
01:			
		ization and Finalization	<b>58</b>
4.1.		Initialized	58
4.2.		Get_version	<b>59</b>
4.3.	7	Init	59
	4.3.1.	Initialization events	62
	4.3.2.	Initialization attributes	62
		4.3.2.1. Connection attributes	62
		4.3.2.2. Programming model attributes	63
4.4.		Finalize	64
	4.4.1.	Finalize attributes	64

	4.5.	PMIx_Progress	64
5.	Sync	chronization and Data Access Operations	66
	5.1.	PMIx_Fence	66
	5.2.	PMIx_Fence_nb	68
		5.2.1. Fence-related attributes	70
	5.3.	PMIx_Get	71
		5.3.1. PMIx_Get_nb	73
		5.3.2. Retrieval attributes	76
	5.4.	Query	77
		5.4.1. PMIx_Resolve_peers	78
		5.4.2. PMIx_Resolve_nodes	78
		5.4.3. PMIx_Query_info	79
		5.4.4. PMIx_Query_info_nb	84
		5.4.5. Query-specific constants	88
		5.4.6. Query attributes	89
		5.4.7. Query Structure	91
		5.4.7.1. Query structure support macros	92
	5.5.	Using Get vs Query	94
	5.6.	Accessing attribute support information	94
_	_		
6.		erved Keys	97
	6.1.	Data realms	97
		6.1.1. Session realm attributes	98
		6.1.2. Job realm attributes	100
		6.1.3. Application realm attributes	102
		6.1.4. Process realm attributes	103
		6.1.5. Node realm keys	104
	6.2.	Retrieval rules for reserved keys	106
		6.2.1. Accessing information: examples	106
		6.2.1.1. Session-level information	107
		6.2.1.2. Job-level information	108
		6.2.1.3. Application-level information	108
		6.2.1.4. Process-level information	109

		6.2.1.5. Node-level information	109
7.	Proc	ess-Related Non-Reserved Keys	111
	7.1.	Posting Key/Value Pairs	112
		7.1.1. <b>PMIx_Put</b>	112
		7.1.1.1. Scope of Put Data	113
		7.1.2. <b>PMIx_Store_internal</b>	113
		7.1.3. <b>PMIx_Commit</b>	114
	7.2.	Retrieval rules for non-reserved keys	115
8.	Publ	ish/Lookup Operations	117
	8.1.	PMIx_Publish	117
	8.2.	PMIx_Publish_nb	119
	8.3.	Publish-specific constants	120
	8.4.	Publish-specific attributes	120
	8.5.	Publish-Lookup Datatypes	121
		8.5.1. Range of Published Data	121
		8.5.2. Data Persistence Structure	121
	8.6.	PMIx_Lookup	122
	8.7.	PMIx_Lookup_nb	123
		8.7.1. Lookup Returned Data Structure	125
		8.7.1.1. Lookup data structure support macros	126
		8.7.2. Lookup Callback Function	128
	8.8.	Retrieval rules for published data	129
	8.9.	PMIx_Unpublish	130
	8.10.	PMIx_Unpublish_nb	131
9.	Even	at Notification	133
	9.1.	Notification and Management	133
		9.1.1. Events versus status constants	135
		9.1.2. PMIx_Register_event_handler	135
		9.1.3. Event registration constants	138
		9.1.4. System events	139
		9.1.5. Event handler registration and notification attributes	139
		0.1.5.1 Fault tolerance event attributes	140

	9	2.1.5.2. Hybrid programming event attributes	140
	9.1.6.	Notification Function	141
	9.1.7.	PMIx_Deregister_event_handler	142
	9.1.8.	PMIx_Notify_event	143
	9.1.9.	Notification Handler Completion Callback Function	147
	9	.1.9.1. Completion Callback Function Status Codes	147
10. Data	Packing	g and Unpacking	148
10.1.	Data Bu	ffer Type	148
10.2.	Support	Macros	149
10.3.	General	Routines	150
	10.3.1.	PMIx_Data_pack	150
	10.3.2.	PMIx_Data_unpack	152
	10.3.3.	PMIx_Data_copy	154
	10.3.4.	PMIx_Data_print	154
	10.3.5.	PMIx_Data_copy_payload	155
11.Proc	ess Mar	nagement	157
11.1.	Abort .		157
	11.1.1.	PMIx_Abort	157
11.2.	Process	Creation	158
	11.2.1.	PMIx_Spawn	159
	11.2.2.	PMIx_Spawn_nb	164
	11.2.3.	Spawn-specific constants	169
	11.2.4.	Spawn attributes	170
	11.2.5.	Application Structure	173
	1	1.2.5.1. App structure support macros	174
	1	1.2.5.2. Spawn Callback Function	176
11.3.	Connect	ing and Disconnecting Processes	176
	11.3.1.	PMIx_Connect	177
	11.3.2.	PMIx_Connect_nb	179
	11.3.3.	PMIx_Disconnect	181
	11.3.4.	PMIx_Disconnect_nb	183

11.4.	Process Locality	185
	11.4.1. PMIx_Load_topology	185
	11.4.2. PMIx_Get_relative_locality	186
	11.4.2.1. Topology description	186
	11.4.2.2. Topology support macros	187
	11.4.2.3. Relative locality of two processes	188
	11.4.2.4. Locality keys	188
	11.4.3. PMIx_Parse_cpuset_string	188
	11.4.4. <b>PMIx_Get_cpuset</b>	189
	11.4.4.1. Binding envelope	189
	11.4.5. PMIx_Compute_distances	190
	11.4.6. PMIx_Compute_distances_nb	191
	11.4.7. Device Distance Callback Function	192
	11.4.8. Device type	192
	11.4.9. Device Distance Structure	193
	11.4.10. Device distance support macros	194
	11.4.11. Device distance attributes	195
12 Joh I	Management and Reporting	196
	Allocation Requests	196
12.1.	12.1.1. PMIx_Allocation_request	196
	12.1.2. PMIx_Allocation_request_nb	190
	12.1.3. Job Allocation attributes	202
	12.1.4. Job Allocation Directives	204
12.2	Job Control	204
12.2.	12.2.1. PMIx_Job_control	205
	12.2.2. PMIx_Job_control_nb	207
	12.2.3. Job control constants	210
	12.2.4. Job control events	210
	12.2.5. Job control attributes	211
12.3		212
12.3.		212
		214
	12.3.3 PMIx Heartbeat	216

	12.3.4.	Monitoring events	217
	12.3.5.	Monitoring attributes	217
12.4.	Logging		218
	12.4.1.	PMIx_Log	218
	12.4.2.	PMIx_Log_nb	221
	12.4.3.	Log attributes	224
13. Proc	ess Sets	s and Groups	226
13.1.	Process	Sets	226
	13.1.1.	Process Set Constants	227
	13.1.2.	Process Set Attributes	228
13.2.	Process	Groups	228
	13.2.1.	Relation to the host environment	228
	13.2.2.	Construction procedure	229
	13.2.3.	Destruct procedure	230
	13.2.4.	Process Group Events	230
	13.2.5.	Process Group Attributes	231
	13.2.6.	PMIx_Group_construct	233
	13.2.7.	PMIx_Group_construct_nb	236
	13.2.8.	PMIx_Group_destruct	239
	13.2.9.	PMIx_Group_destruct_nb	240
	13.2.10.	PMIx_Group_invite	242
	13.2.11.	PMIx_Group_invite_nb	245
	13.2.12.	PMIx_Group_join	247
	13.2.13.	PMIx_Group_join_nb	249
	1	3.2.13.1. Group accept/decline directives	251
	13.2.14.	PMIx_Group_leave	251
	13.2.15.	PMIx_Group_leave_nb	252
14. Fabri	ic Supp	ort Definitions	<b>25</b> 4
14.1.	Fabric S	upport Events	257
		upport Datatypes	257
	14.2.1.	Fabric Endpoint Structure	257
	14.2.2.	Fabric endpoint support macros	258

	14.2.3.	Fabric Coordinate Structure	259
	14.2.4.	Fabric coordinate support macros	259
	14.2.5.	Fabric Geometry Structure	261
	14.2.6.	Fabric geometry support macros	261
	14.2.7.	Fabric Coordinate Views	262
	14.2.8.	Fabric Link State	263
	14.2.9.	Fabric Operation Constants	263
	14.2.10.	Fabric registration structure	264
	1	4.2.10.1. Initialize the fabric structure	267
14.3.	Fabric S	Support Attributes	267
14.4.	Fabric S	Support Functions	270
	14.4.1.	PMIx_Fabric_register	271
	14.4.2.	PMIx_Fabric_register_nb	272
	14.4.3.	PMIx_Fabric_update	273
	14.4.4.	PMIx_Fabric_update_nb	274
	14.4.5.	PMIx_Fabric_deregister	274
	14.4.6.	PMIx_Fabric_deregister_nb	275
15. Secu	•		276
15.1.		ng Credentials	276
		PMIx_Get_credential	277
	15.1.2.	PMIx_Get_credential_nb	278
	15.1.3.	Credential Attributes	279
15.2.		ng Credentials	280
		PMIx_Validate_credential	280
	15.2.2.	PMIx_Validate_credential_nb	281
16. Serv	er-Spec	ific Interfaces	284
		nitialization and Finalization	284
10,11		PMIx server init	284
		PMIx_server_finalize	288
	16.1.3.	Server Initialization Attributes	288
16.2		Support Functions	289
10.2.		PMTv gonorato rogov	280

16.2.2. PMIx_generate_ppn	<b>29</b> 1
16.2.3. PMIx_server_register_nspace	291
16.2.3.1. Namespace registration attributes	302
16.2.3.2. Assembling the registration information	303
16.2.4. PMIx_server_deregister_nspace	312
16.2.5. PMIx_server_register_resources	312
16.2.6. PMIx_server_deregister_resources	313
16.2.7. PMIx_server_register_client	314
16.2.8. PMIx_server_deregister_client	316
16.2.9. PMIx_server_setup_fork	317
16.2.10. PMIx_server_dmodex_request	317
16.2.10.1. Server Direct Modex Response Callback Function	319
16.2.11. PMIx_server_setup_application	319
16.2.11.1. Server Setup Application Callback Function	323
16.2.11.2. Server Setup Application Attributes	323
16.2.12. PMIx_Register_attributes	324
16.2.12.1. Attribute registration constants	325
16.2.12.2. Attribute registration structure	325
16.2.12.3. Attribute registration structure descriptive attributes	326
16.2.12.4. Attribute registration structure support macros	326
16.2.13. PMIx_server_setup_local_support	328
16.2.14. PMIx_server_IOF_deliver	330
16.2.15. PMIx_server_collect_inventory	331
16.2.16. PMIx_server_deliver_inventory	332
16.2.17. PMIx_server_generate_locality_string	333
16.2.18. PMIx_server_generate_cpuset_string	334
16.2.18.1. Cpuset Structure	335
16.2.18.2. Cpuset support macros	335
16.2.19. PMIx_server_define_process_set	336
16.2.20. PMIx_server_delete_process_set	337
Server Function Pointers	337
16.3.1. pmix_server_module_t Module	338
1632 pmix server client connected for t	339

16.3.3. pmix_server_client_connected2_fn_t	340
16.3.4. pmix_server_client_finalized_fn_t	342
16.3.5. pmix_server_abort_fn_t	343
16.3.6. pmix_server_fencenb_fn_t	345
16.3.6.1. Modex Callback Function	348
16.3.7. pmix_server_dmodex_req_fn_t	348
16.3.7.1. Dmodex attributes	350
16.3.8. pmix_server_publish_fn_t	350
16.3.9. pmix_server_lookup_fn_t	352
16.3.10. pmix_server_unpublish_fn_t	355
16.3.11. pmix_server_spawn_fn_t	357
16.3.11.1. Server spawn attributes	362
16.3.12. pmix_server_connect_fn_t	362
16.3.13. pmix_server_disconnect_fn_t	363
16.3.14. pmix_server_register_events_fn_t	365
16.3.15. pmix_server_deregister_events_fn_t	367
16.3.16. pmix_server_notify_event_fn_t	369
16.3.17. pmix_server_listener_fn_t	370
16.3.17.1.PMIx Client Connection Callback Function	371
16.3.18. pmix_server_query_fn_t	372
16.3.19. pmix_server_tool_connection_fn_t	374
16.3.19.1. Tool connection attributes	377
16.3.19.2. PMIx Tool Connection Callback Function	377
16.3.20. pmix_server_log_fn_t	377
16.3.21. pmix_server_alloc_fn_t	379
16.3.22. pmix_server_job_control_fn_t	382
16.3.23. pmix_server_monitor_fn_t	385
16.3.24. pmix_server_get_cred_fn_t	388
16.3.24.1. Credential callback function	389
16.3.25. pmix_server_validate_cred_fn_t	390
16.3.26. Credential validation callback function	392
16.3.27. pmix_server_iof_fn_t	393
16.3.27.1 IOE delivery function	306

	16.3.28.	<pre>pmix_server_stdin_fn_t</pre>	397
	16.3.29.	<pre>pmix_server_grp_fn_t</pre>	398
	1	6.3.29.1. Group Operation Constants	401
	16.3.30.	<pre>pmix_server_fabric_fn_t</pre>	401
17. Tools	and De	ebuggers	403
17.1.	Connect	ion Mechanisms	403
	17.1.1.	Rendezvousing with a local server	406
	17.1.2.	Connecting to a remote server	407
	17.1.3.	Attaching to running jobs	408
	17.1.4.	Tool initialization attributes	408
	17.1.5.	Tool initialization environmental variables	409
	17.1.6.	Tool connection attributes	409
17.2.	Launchi	ng Applications with Tools	410
	17.2.1.	Direct launch	410
	17.2.2.	Indirect launch	414
	1	7.2.2.1. Initiator-based command line parsing	415
	1	7.2.2.2. Intermediate Launcher (IL)-based command line parsing	418
	17.2.3.	Tool spawn-related attributes	419
	17.2.4.	Tool rendezvous-related events	420
17.3.	IO Forw	varding	420
	17.3.1.	Forwarding stdout/stderr	421
	17.3.2.	Forwarding stdin	423
	17.3.3.	IO Forwarding Channels	424
	17.3.4.	IO Forwarding constants	425
	17.3.5.	IO Forwarding attributes	425
17.4.	Debugge	er Support	426
	17.4.1.	Co-Location of Debugger Daemons	428
	17.4.2.	Co-Spawn of Debugger Daemons	430
	17.4.3.	Debugger Agents	431
	17.4.4.	Tracking the job lifecycle	432
	1	7.4.4.1. Job lifecycle events	433
	1	7.4.4.2. Job lifecycle attributes	434
	17.4.5.	Debugger-related constants	434

		17.4.6.	Debugge	r attributes				 	 			. 434
	17.5.	Tool-Spe	ecific APIs	s				 	 			. 436
		17.5.1.	PMIx_t	ool_init	٤			 	 			. 436
		17.5.2.	PMIx_t	ool_fina	alize.			 	 			. 439
		17.5.3.	PMIx_t	ool_dis	connect			 	 			. 440
		17.5.4.	PMIx_t	ool_atta	ach_to_	_serv	er	 	 		K	. 441
		17.5.5.	PMIx_t	ool_get_	_server	s .		 	 			. 442
		17.5.6.	PMIx_t	ool_set_	_server	·		 	 			. 443
		17.5.7.	PMIx_I	OF_pull				 	 0.	<b>?</b> / (.		. 444
		17.5.8.	PMIx_I	OF_dere	gister			 	 <b>.</b>			. 446
		17.5.9.	PMIx_I	OF_push				 	 •	<i>p</i>		. 447
18	.Stora	age Sup	port Defi	nitions								450
	18.1.	Storage	support co	onstants .				 	 			. 450
	18.2.	Storage	support at	tributes .		$\Delta$		 	 			. 452
Α.	Pyth	on Bind	ings									454
	A.1.	Design (	Considerat	tions	<b>5</b>		<b>.</b>	 	 			. 454
		A.1.1.	Error Co	des vs Pyth	on Excep	tions		 	 			. 454
		A.1.2.	Represen	tation of St	ructured	Data		 	 			. 454
	A.2.	Datatype	e Definitio	ons	,			 	 			. 455
		A.2.1.	Example					 	 			. 461
	A.3.	Callback	Function	Definition	s			 	 			. 462
		A.3.1.	IOF Deli	very Functi	ion			 	 			. 462
		A.3.2.	Event Ha	ndler				 	 			. 462
		A.3.3.	Server M	odule Fund	ctions			 	 			. 463
		A	A.3.3.1. C	Client Conn	ected .			 	 			. 463
		A	A.3.3.2. C	Client Final	ized			 	 			. 464
		A	A.3.3.3. C	Client Abor	ted			 	 			. 464
		A	A.3.3.4. F	Fence				 	 			. 465
		A	A.3.3.5. I	Direct Mod	ex			 	 			. 466
		A	A.3.3.6. F	Publish				 	 			. 466
		A	A.3.3.7. I	Lookup				 	 			. 467
		A	. 220 т	Innublish								167

	A	A.3.3.9. Spawn	468
	A	A.3.3.10. Connect	468
	A	A.3.3.11. Disconnect	469
	A	A.3.3.12. Register Events	469
	A	A.3.3.13. Deregister Events	470
	A	A.3.3.14. Notify Event	470
	A	A.3.3.15. Query	470
	A	A.3.3.16. Tool Connected	471
	A	A.3.3.17. Log	471
	A	A.3.3.18. Allocate Resources	472
	A	A.3.3.19. Job Control	472
	A	A.3.3.20. Monitor	473
	A	A.3.3.21. Get Credential	473
	A	A.3.3.22. Validate Credential	474
	A	A.3.3.23. IO Forward	474
			475
			475
	A	A.3.3.26. Fabric Operations	476
A.4.	PMIxCli	ient	477
	A.4.1.		477
	A.4.2.	Client.initialized	477
	A.4.3.	Client.get_version	478
	A.4.4.	Client.finalize	478
	A.4.5.	Client.abort	478
	A.4.6.	Client.store_internal	479
	A.4.7.	Client.put	479
	A.4.8.	Client.commit	480
4	A.4.9.	Client.fence	480
	A.4.10.	Client.get	481
		1	481
	A.4.12.	Client.lookup	482
	A.4.13.	Client.unpublish	482
	A.4.14.	Client.spawn	483

A.4.15.	Client.connect	483
A.4.16.	Client.disconnect	484
A.4.17.	Client.resolve_peers	484
A.4.18.	Client.resolve_nodes	485
A.4.19.	Client.query	485
A.4.20.	Client.log	486
A.4.21.	Client.allocation_request	486
A.4.22.	Client.job_ctrl	487
A.4.23.	Client.monitor	487
A.4.24.	Client.get_credential	488
A.4.25.	Client.validate_credential	488
A.4.26.	Client.group_construct	489
A.4.27.	Client.group_invite	489
A.4.28.	Client.group_join	490
A.4.29.	Client.group_leave	491
A.4.30.	Client.group_destruct	491
A.4.31.	Client.register_event_handler	491
A.4.32.	Client.deregister_event_handler	492
A.4.33.	Client.notify_event	492
A.4.34.	Client.fabric_register	493
A.4.35.	Client.fabric_update	493
A.4.36.	Client.fabric_deregister	494
A.4.37.	Client.load_topology	494
A.4.38.	Client.get_relative_locality	495
A.4.39.	Client.get_cpuset	495
A.4.40.	Client.parse_cpuset_string	495
A.4.41.	Client.compute_distances	496
A.4.42.	Client.error_string	496
A.4.43.	Client.proc_state_string	497
A.4.44.	Client.scope_string	497
A.4.45.	Client.persistence_string	498
A.4.46.	Client.data_range_string	498
A.4.47.	Client.info_directives_string	498

	A.4.48.	Client.data_type_string	499
	A.4.49.	Client.alloc_directive_string	499
	A.4.50.	Client.iof_channel_string	500
	A.4.51.	Client.job_state_string	500
	A.4.52.	Client.get_attribute_string	500
	A.4.53.	Client.get_attribute_name	501
	A.4.54.	Client.link_state_string	501
	A.4.55.	Client.device_type_string	502
	A.4.56.	Client.progress	502
A.5.	PMIxSe	rver	502
	A.5.1.	Server.init	502
	A.5.2.	Server.finalize	503
	A.5.3.	Server.generate_regex	503
	A.5.4.	Server.generate_ppn	504
	A.5.5.	Server.generate_locality_string	504
	A.5.6.	Server.generate_cpuset_string	505
	A.5.7.	Server.register_nspace	505
	A.5.8.	Server.deregister_nspace	506
	A.5.9.	Server.register_resources	506
	A.5.10.		507
	A.5.11.	Server.register_client	507
	A.5.12.	Server.deregister_client	508
	A.5.13.	Server.setup_fork	508
	A.5.14.	Server.dmodex_request	508
	A.5.15.	Server.setup_application	509
	A.5.16.	Server.register_attributes	509
	A.5.17.	Server.setup_local_support	510
	A.5.18.	Server.iof_deliver	510
	A.5.19.	Server.collect_inventory	511
	A.5.20.	Server.deliver_inventory	511
	A.5.21.	Server.define_process_set	512
	A.5.22.	Server.delete_process_set	512
	A 5 22	Convention designation approximate	512

		A.5.24.	Server.deregister_resources	513
	A.6.	PMIxTo	ol	514
		A.6.1.	Tool.init	514
		A.6.2.	Tool.finalize	514
		A.6.3.	Tool.disconnect	514
		A.6.4.	Tool.attach_to_server	515
		A.6.5.	Tool.get_servers	515
		A.6.6.	Tool.set_server	516
		A.6.7.	Tool.iof_pull	516
		A.6.8.	Tool.iof_deregister	517
		A.6.9.	Tool.iof_push	517
	A.7.	Example	e Usage	518
		A.7.1.	Python Client	518
		A.7.2.	Python Server	520
R	Rovi	sion His	story	524
υ.	B.1.		1.0: June 12, 2015	524
	B.2.		2.0: Sept. 2018	525
	D.2.	B.2.1.	Removed/Modified Application Programming Interfaces (APIs)	525
		B.2.2.	Deprecated constants	525
		B.2.3.	Deprecated attributes	526
	B.3.		2.1: Dec. 2018	526
	B.4.		2.2: Jan 2019	527
	B.5.		3.0: Dec. 2018	527
		B.5.1.	Removed constants	528
		B.5.2.	Deprecated attributes	528
		B.5.3.	Removed attributes	528
	B.6.	Version	3.1: Jan. 2019	529
	B.7.	Version	3.2: Oct. 2020	529
		B.7.1.	Deprecated constants	530
		B.7.2.	Deprecated attributes	531
	B.8.		4.0: Dec. 2020	532
		B.8.1.	Added Constants	534
		B.8.2.	Added Attributes	537

		B.8.3.	Added Environmental Variables	550
		B.8.4.	Added Macros	550
		B.8.5.	Deprecated APIs	550
		B.8.6.	Deprecated constants	551
		B.8.7.	Removed constants	551
		B.8.8.	Deprecated attributes	552
		B.8.9.	Removed attributes	553
	B.9.	Version 4	4.1: TBD	554
		B.9.1.	Added Data Structures (Provisional)	554
		B.9.2.	Added Constants (Provisional)	554
		B.9.3.	Added Attributes (Provisional)	555
_	<b>Ackn</b>	owledge	omente	557
C.	C.1.	•		557
	C.1.		4.0	
	C.2.		2.0	<ul><li>558</li><li>559</li></ul>
			1.0	560
	C.4.	VEISIOII	1.0	300
Bil	oliogr	aphy		<b>562</b>
Inc	dex			<b>563</b>
Index of APIs 568			565	
Inc	dex of	Suppor	rt Macros	<b>572</b>
Index of Data Structures 576			<b>576</b>	
Inc	Index of Constants 578			578
Inc	dex of	Enviror	nmental Variables	588
Inc	dex of	Attribut	tes	589

#### **CHAPTER 1**

## Introduction

Process Management Interface - Exascale (PMIx) is an application programming interface standard that provides libraries and programming models with portable and well-defined access to commonly needed services in distributed and parallel computing systems. A typical example of such a service is the portable and scalable exchange of network addresses to establish communication channels between the processes of a parallel application or service. As such, PMIx gives distributed system software providers a better understanding of how programming models and libraries can interface with and use system-level services. As a standard, PMIx provides APIs that allow for portable access to these varied system software services and the functionalities they offer. Although these services can be defined and implemented directly by the system software components providing them, the community represented by the ASC feels that the development of a shared standard better serves the community. As a result, PMIx enables programming languages and libraries to focus on their core competencies without having to provide their own system-level services.

## 1.1 Background

The Process Management Interface (PMI) has been used for quite some time as a means of exchanging wireup information needed for inter-process communication. Two versions (PMI-1 and PMI-2 [2]) have been released as part of the MPICH effort, with PMI-2 demonstrating better scaling properties than its PMI-1 predecessor.

PMI-1 and PMI-2 can be implemented using PMIx though PMIx is not a strict superset of either. Since its introduction, PMIx has expanded on earlier PMI efforts by providing an extended version of the PMI APIs which provide necessary functionality for launching and managing parallel applications and tools at scale.

The increase in adoption has motivated the creation of this document to formally specify the intended behavior of the PMIx APIs.

More information about the PMIx standard and affiliated projects can be found at the PMIx web site: https://pmix.org

## 1.2 PMIx Architecture Overview

The presentation of the PMIx APIs within this document makes some basic assumptions about how these APIs are used and implemented. These assumptions are generally made only to simplify the presentation and explain PMIx with the expectation that most readers have similar concepts on how

computing systems are organized today. However, ultimately this document should only be assumed to define a set of APIs.

A concept that is fundamental to PMIx is that a PMIx implementation might operate primarily as a *messenger*, and not a *doer* — i.e., a PMIx implementation might rely heavily or fully on other software components to provide functionality [1]. Since a PMIx implementation might only deliver requests and responses to other software components, the API calls include ways to provide arbitrary information to the backend components that actually implement the functionality. Also, because PMIx implementations generally rely heavily on other system software, a PMIx implementation might not be able to guarantee that a feature is available on all platforms the implementation supports. These aspects are discussed in detail in the remainder of this chapter.




Figure 1.1.: PMIx-SMS Interactions

Fig. 1.1 shows a typical PMIx implementation in which the application is built against a PMIx client library that contains the client-side APIs, attribute definitions, and communication support for interacting with the local PMIx server. PMIx clients are processes which are started through the PMIx infrastructure, either by the PMIx implementation directly or through a System Management Software stack (SMS) component, and have registered as clients. A PMIx client is created in such a way that the PMIx client library will be have sufficient information available to authenticate with the PMIx server. The PMIx server will have sufficient knowledge about the process which it created, either directly or through other SMS, to authenticate the process and provide information the process requests such as its identity and the identity of its peers.

As clients invoke PMIx APIs, it is possible that some client requests can be handled at the client level. Other requests might require communication with the local PMIx server, which subsequently might request services from the host SMS (represented here by a Resource Manager (RM) daemon). The interaction between the PMIx server and SMS are achieved using callback functions registered during server initialization. The host SMS can indicate its lack of support for any

operation by simply providing a *NULL* for the associated callback function, or can create a function entry that returns *not supported* when called.

Recognizing the burden this places on SMS vendors, the PMIx community has included interfaces by which the host SMS (containing the local PMIx service instance) can request support from local SMS elements via the PMIx API. Once the SMS has transferred the request to an appropriate location, a PMIx server interface can be used to pass the request between SMS subsystems. For example, a request for network traffic statistics can utilize the PMIx networking abstractions to retrieve the information from the Fabric Manager. This reduces the portability and interoperability issues between the individual subsystems by transferring the burden of defining the interoperable interfaces from the SMS subsystems to the PMIx community, which continues to work with those providers to develop the necessary support.

Fig. 1.1 shows how tools can interact with the PMIx architecture. Tools, whether standalone or embedded in job scripts, are an exception to the normal client registration process. A process can register as a tool, provided the PMIx client library has adequate rendezvous information to connect to the appropriate PMIx server (either hosted on the local machine or on a remote machine). This allows processes which were not created by the PMIx infrastructure to request access to PMIx functionality.

## 1.3 Portability of Functionality

It is difficult to define a portable API that will provide access to the many and varied features underlying the operations for which PMIx provides access. For example, the options and features provided to request the creation of new processes varied dramatically between different systems existing at the time PMIx was introduced. Many RMs provide rich interfaces to specify the resources assigned to processes. As a result, PMIx is faced with the challenge of attempting to meet the seamingly conflicting goals of creating an API which allows access to these diverse features while being portable across a wide range of existing software environments. In addition, the functionalities required by different clients vary greatly. Producing a PMIx implementation which can provide the needs of all possible clients on all of its target systems could be so burdensome as to discourage PMIx implementations.

To help address this issue, the PMIx APIs are designed to allow resource managers and other system management stack components to decide on support of a particular function and allow client applications to query and adjust to the level of support available. PMIx clients should be written to account for the possibility that a PMIx API might return an error code indicating that the call is not supported. The PMIx community continues to look at ways to assist SMS implementers in their decisions on what functionality to support by highlighting functions and attributes that are critical to basic application execution (e.g., PMIx\_Get) for certain classes of applications.

### 1.3.1 Attributes in PMIx

An area where differences between support on different systems can be challenging is regarding the attributes that provide information to the client process and/or control the behavior of a PMIx API.

Most PMIx API calls can accept additional information or attributes specified in the form of key/value pairs. These attributes provide information to the PMIx implementation that influence the behavior of the API call. In addition to API calls being optional, support for the individual attributes of an API call can vary between systems or implementations.

An application can adapt to the attribute support on a particular system in one of two ways. PMIx provides an API to enable an application to query the attributes supported by a particular API (See 5.6). Through this API, the PMIx implementation can provide detailed information about the attributes supported on a system for each API call queried. Alternatively, the application can mark attributes as required using a flag within the <code>pmix\_info\_t</code> (See 3.2.9). If the required attribute is not available on the system or the desired value for the attribute is not available, the call will return the error code for *not supported*.

For example, the **PMIX\_TIMEOUT** attribute can be used to specify the time (in seconds) before the requested operation should time out. The intent of this attribute is to allow the client to avoid "hanging" in a request that takes longer than the client wishes to wait, or may never return (e.g., a **PMIX\_Fence** that a blocked participant never enters).

The application can query the attribute support for **PMIx\_Fence** and search whether **PMIX\_TIMEOUT** is listed as a supported attribute. The application can also set the required flag in the **pmix\_info\_t** for that attribute when making the **PMIx\_Fence** call. This will return an error if this attribute is not supported. If the required flag is not set, the library and SMS host are allowed to treat the attribute as optional, ignoring it if support is not available.

It is therefore critical that users and application implementers:

- a) consider whether or not a given attribute is required, marking it accordingly; and
- b) check the return status on all PMIx function calls to ensure support was present and that the request was accepted. Note that for non-blocking APIs, a return of **PMIX\_SUCCESS** only indicates that the request had no obvious errors and is being processed the eventual callback will return the status of the requested operation itself.

PMIx clients (e.g., tools, parallel programming libraries) may find that they depend only on a small subset of interfaces and attributes to work correctly. PMIx clients are strongly advised to define a document itemizing the PMIx interfaces and associated attributes that are required for correct operation, and are optional but recommended for full functionality. The PMIx standard cannot define this list for all given PMIx clients, but such a list is valuable to RMs desiring to support these clients.

A PMIx implementation may be able to support only a subset of the PMIx API and attributes on a particular system due to either its own limitations or limitations of the SMS with which it interfaces. A PMIx implementation may also provide additional attributes beyond those defined herein in order to allow applications to access the full features of the underlying SMS. PMIx implementations are strongly advised to document the PMIx interfaces and associated attributes they support, with any annotations about behavior limitations. The PMIx standard cannot define this support for implementations, but such documentation is valuable to PMIx clients desiring to support a broad range of systems.

While a PMIx library implementer, or an SMS component server, may choose to support a particular PMIx API, they are not required to support every attribute that might apply to it. This would pose a significant barrier to entry for an implementer as there can be a broad range of applicable attributes to a given API, at least some of which may rarely be used.

Note that an environment that does not include support for a particular attribute/API pair is not "incomplete" or of lower quality than one that does include that support. Vendors must decide where to invest their time based on the needs of their target markets, and it is perfectly reasonable for them to perform cost/benefit decisions when considering what functions and attributes to support.

Attributes in this document are organized according to their primary usage, either grouped with a specific API or included in an appropriate functional chapter. Attributes in the PMIx Standard all start with "PMIX" in their name, and many include a functional description as part of their name (e.g., the use of "PMIX\_FABRIC\_" at the beginning of fabric-specific attributes). The PMIx Standard also defines an attribute that can be used to indicate that an attribute variable has not yet been set:

#### PMIX\_ATTR\_UNDEF "pmix.undef" (NULL)

A default attribute name signifying that the attribute field of a PMIx structure (e.g., a pmix\_info\_t) has not yet been defined.

#### **CHAPTER 2**

## **PMIx Terms and Conventions**

In this chapter we describe some common terms and conventions used throughout this document. The PMIx Standard has adopted the widespread use of key-value *attributes* to add flexibility to the functionality expressed in the existing APIs. Accordingly, the ASC has chosen to require that the definition of each standard API include the passing of an array of attributes. These provide a means of customizing the behavior of the API as future needs emerge without having to alter or create new variants of it. In addition, attributes provide a mechanism by which researchers can easily explore new approaches to a given operation without having to modify the API itself.

In an effort to maintain long-term backward compatibility, PMIx does not include large numbers of APIs that each focus on a narrow scope of functionality, but instead relies on the definition of fewer generic APIs that include arrays of key-value attributes for "tuning" the function's behavior. Thus, modifications to the PMIx standard primarily consist of the definition of new attributes along with a description of the APIs to which they relate and the expected behavior when used with those APIs.

The following terminology is used throughout this document:

- session refers to a pool of resources with a unique identifier (a.k.a., the session ID) assigned by the WorkLoad Manager (WLM) that has been reserved for one or more users. Historically, High Performance Computing (HPC) sessions have consisted of a static allocation of resources e.g., a block of nodes assigned to a user in response to a specific request and managed as a unified collection. However, this is changing in response to the growing use of dynamic programming models that require on-the-fly allocation and release of system resources. Accordingly, the term session in this document refers to a potentially dynamic entity, perhaps comprised of resources accumulated as a result of multiple allocation requests that are managed as a single unit by the WLM.
- *job* refers to a set of one or more *applications* executed as a single invocation by the user within a session with a unique identifier (a.k.a, the *job ID*) assigned by the RM or launcher. For example, the command line "*mpiexec -n 1 app1 : -n 2 app2*" generates a single Multiple Program Multiple Data (MPMD) job containing two applications. A user may execute multiple *jobs* within a given session, either sequentially or in parallel.
- namespace refers to a character string value assigned by the RM or launcher (e.g., mpiexec) to a job. All applications executed as part of that job share the same namespace. The namespace assigned to each job must be unique within the scope of the governing RM and often is implemented as a string representation of a numerical job ID. The namespace and job terms will be used interchangeably throughout the document.
- application refers to a single executable (binary, script, etc.) member of a job.

process refers to an operating system process, also commonly referred to as a heavyweight process. A process is often comprised of multiple lightweight threads, commonly known as simply threads.
 client refers to a process that was registered with the PMIx server prior to being started, and

- client refers to a process that was registered with the PMIx server prior to being started, and
  connects to that PMIx server via PMIx\_Init using its assigned namespace and rank with the
  information required to connect to that server being provided to the process at time of start of
  execution.
- clone refers to a process that was directly started by a PMIx client (e.g., using fork/exec) and calls
   PMIx\_Init, thus connecting to its local PMIx server using the same namespace and rank as its
   parent process.
- rank refers to the numerical location (starting from zero) of a process within the defined scope. Thus, job rank is the rank of a process within its job and is synonymous with its unqualified rank, while application rank is the rank of that process within its application.
- peer refers to another process within the same job.
- workflow refers to an orchestrated execution plan frequently involving multiple jobs carried out under the control of a workflow manager process. An example workflow might first execute a computational job to generate the flow of liquid through a complex cavity, followed by a visualization job that takes the output of the first job as its input to produce an image output.
- *scheduler* refers to the component of the SMS responsible for scheduling of resource allocations. This is also generally referred to as the *system workflow manager* for the purposes of this document, the *WLM* acronym will be used interchangeably to refer to the scheduler.
- resource manager is used in a generic sense to represent the subsystem that will host the PMIx server library. This could be a vendor-supplied resource manager or a third-party agent such as a programming model's runtime library.
- *host environment* is used interchangeably with *resource manager* to refer to the process hosting the PMIx server library.
- *node* refers to a single operating system instance. Note that this may encompass one or more physical objects.
- package refers to a single object that is either soldered or connected to a printed circuit board via a mechanical socket. Packages may contain multiple chips that include (but are not limited to) processing units, memory, and peripheral interfaces.
- processing unit, or PU, is the electronic circuitry within a computer that executes instructions. Depending upon architecture and configuration settings, it may consist of a single hardware thread or multiple hardware threads collectively organized as a core.
- *fabric* is used in a generic sense to refer to the networks within the system regardless of speed or protocol. Any use of the term *network* in the document should be considered interchangeable with *fabric*.

- fabric device (or fabric devices) refers to an operating system fabric interface, which may be physical or virtual. Any use of the term Network Interface Card (NIC) in the document should be considered interchangeable with fabric device.
- *fabric plane* refers to a collection of fabric devices in a common logical or physical configuration. Fabric planes are often implemented in HPC clusters as separate overlay or physical networks controlled by a dedicated fabric manager.
- attribute refers to a key-value pair comprised of a string key (represented by a pmix\_key\_t structure) and an associated value containing a PMIx data type (e.g., boolean, integer, or a more complex PMIx structure). Attributes are used both as directives when passed as qualifiers to APIs (e.g., in a pmix\_info\_t array), and to identify the contents of information (e.g., to specify that the contents of the corresponding pmix\_value\_t in a pmix\_info\_t represent the PMIX UNIV SIZE).
- key refers to the string component of a defined attribute. The PMIx Standard will often refer to passing of a key to an API (e.g., to the PMIx\_Query\_info or PMIx\_Get APIs) as a means of identifying requested information. In this context, the data type specified in the attribute's definition indicates the data type the caller should expect to receive in return. Note that not all attributes can be used as keys as some have specific uses solely as API qualifiers.
- *instant on* refers to a PMIx concept defined as: "All information required for setup and communication (including the address vector of endpoints for every process) is available to each process at start of execution"

The following sections provide an overview of the conventions used throughout the PMIx Standard document.

## 2.1 Notational Conventions

24	Some sections of this document describe programming language specific examples or APIs. Text
25	that applies only to programs for which the base language is C is shown as follows:
	C
26	C specific text
27	int foo = 42;
	C
28	Some text is for information only, and is not part of the normative specification. These take several
29	forms, described in their examples below:
30	Note: General text

#### ----- Rationale -Throughout this document, the rationale for the design choices made in the interface specification is 1 2 set off in this section. Some readers may wish to skip these sections, while readers interested in interface design may want to read them carefully. 3 Advice to users 4 Throughout this document, material aimed at users and that illustrates usage is set off in this section. Some readers may wish to skip these sections, while readers interested in programming 5 6 with the PMIx API may want to read them carefully. Advice to PMIx library implementers -7 Throughout this document, material that is primarily commentary to PMIx library implementers is 8 set off in this section. Some readers may wish to skip these sections, while readers interested in 9 PMIx implementations may want to read them carefully. Advice to PMIx server hosts -Throughout this document, material that is primarily commentary aimed at host environments (e.g., 10 11 RMs and RunTime Environments (RTEs)) providing support for the PMIx server library is set off in 12 this section. Some readers may wish to skip these sections, while readers interested in integrating PMIx servers into their environment may want to read them carefully. 13 Attributes added in this version of the standard are shown in *magenta* to distinguish them from 14 15 those defined in prior versions, which are shown in **black**. Deprecated attributes are shown in green 16 and may be removed in a future version of the standard. 2.2 **Semantics** The following terms will be taken to mean: 18 19 • shall, must and will indicate that the specified behavior is required of all conforming implementations 20 21 • should and may indicate behaviors that a complete implementation would include, but are not 22 required of all conforming implementations

## 2.3 Naming Conventions

- 2 The PMIx standard has adopted the following conventions:
  - PMIx constants and attributes are prefixed with PMIX.
  - Structures and type definitions are prefixed with pmix.
  - Underscores are used to separate words in a function or variable name.
  - Lowercase letters are used in PMIx client APIs except for the PMIx prefix (noted below) and the first letter of the word following it. For example, **PMIx\_Get\_version**.
  - PMIx server and tool APIs are all lower case letters following the prefix e.g.,
     PMIx\_server\_register\_nspace.
  - The **PMIx** prefix is used to denote functions.
  - The **pmix**\_ prefix is used to denote function pointer and type definitions.

Users should not use the "PMIX", "PMIx", or "pmix" prefixes in their applications or libraries so as to avoid symbol conflicts with current and later versions of the PMIx Standard.

## 4 2.4 Procedure Conventions

While the current APIs are based on the C programming language, it is not the intent of the PMIx Standard to preclude the use of other languages. Accordingly, the procedure specifications in the PMIx Standard are written in a language-independent syntax with the arguments marked as IN, OUT, or INOUT. The meanings of these are:

- IN: The call may use the input value but does not update the argument from the perspective of the caller at any time during the calls execution,
- OUT: The call may update the argument but does not use its input value
- INOUT: The call may both use and update the argument.

Many PMIx interfaces, particularly nonblocking interfaces, use a (void\*) callback data object passed to the function that is then passed to the associated callback. On the client side, the callback data object is an opaque, client-provided context that the client can pass to a non-blocking call. When the nonblocking call completes, the callback data object is passed back to the client without modification by the PMIx library, thus allowing the client to associate a context with that callback. This is useful if there are many outstanding nonblocking calls.

A similar model is used for the server module functions (see 16.3.1). In this case, the PMIx library is making an upcall into its host via the PMIx server module callback function and passing a specific callback function pointer and callback data object. The PMIx library expects the host to call the cbfunc with the necessary arguments and pass back the original callback data obect upon completing the operation. This gives the server-side PMIx library the ability to associate a context

with the call back (since multiple operations may be outstanding). The host has no visibility into the contents of the callback data object object, nor is permitted to alter it in any way.

1



#### **CHAPTER 3**

## **Data Structures and Types**

This chapter defines PMIx standard data structures (along with macros for convenient use), types, and constants. These apply to all consumers of the PMIx interface. Where necessary for clarification, the description of, for example, an attribute may be copied from this chapter into a section where it is used.

A PMIx implementation may define additional attributes beyond those specified in this document.

#### Advice to PMIx library implementers

Structures, types, and macros in the PMIx Standard are defined in terms of the C-programming language. Implementers wishing to support other languages should provide the equivalent definitions in a language-appropriate manner.

If a PMIx implementation chooses to define additional attributes they should avoid using the "PMIX" prefix in their name or starting the attribute string with a "pmix" prefix. This helps the end user distinguish between what is defined by the PMIx standard and what is specific to that PMIx implementation, and avoids potential conflicts with attributes defined by the Standard.

#### Advice to users ·

Use of increment/decrement operations on indices inside PMIx macros is discouraged due to unpredictable behavior. For example, the following sequence:

```
PMIX_INFO_LOAD(&array[n++], "mykey", &mystring, PMIX_STRING);
PMIX_INFO_LOAD(&array[n++], "mykey2", &myint, PMIX_INT);
```

will load the given key-values into incorrect locations if the macro is implemented as:

```
define PMIX_INFO_LOAD(m, k, v, t)
    do {
        if (NULL != (k)) {
            pmix_strncpy((m)->key, (k), PMIX_MAX_KEYLEN);
        }
        (m)->flags = 0;
        pmix_value_load(&((m)->value), (v), (t));
    } while (0)
```

since the index is cited more than once in the macro. The PMIx standard only governs the existence and syntax of macros - it does not specify their implementation. Given the freedom of implementation, a safer call sequence might be as follows:

Users are also advised to use the macros for creating, loading, and releasing PMIx structures to avoid potential issues with release of memory. For example, pointing a <code>pmix\_envar\_t</code> element at a static string variable and then using <code>PMIX\_ENVAR\_DESTRUCT</code> to clear it would generate an error as the static string had not been allocated.

## 3.1 Constants

PMIx defines a few values that are used throughout the standard to set the size of fixed arrays or as a means of identifying values with special meaning. The community makes every attempt to minimize the number of such definitions. The constants defined in this section may be used before calling any PMIx library initialization routine. Additional constants associated with specific data structures or types are defined in the section describing that data structure or type.

**PMIX\_MAX\_NSLEN** Maximum namespace string length as an integer.

Advice to PMIx library implementers -

**PMIX\_MAX\_NSLEN** should have a minimum value of 63 characters. Namespace arrays in PMIx defined structures must reserve a space of size **PMIX\_MAX\_NSLEN+1** to allow room for the **NULL** terminator

**PMIX\_MAX\_KEYLEN** Maximum key string length as an integer.

Advice to PMIx library implementers -

**PMIX\_MAX\_KEYLEN** should have a minimum value of 63 characters. Key arrays in PMIx defined structures must reserve a space of size **PMIX\_MAX\_KEYLEN**+1 to allow room for the **NULL** terminator

**PMIX\_APP\_WILDCARD** A value to indicate that the user wants the data for the given key from every application that posted that key, or that the given value applies to all applications within the given namespace.

#### 3.1.1 PMIx Return Status Constants

The **pmix\_status\_t** type is an **int** compatible value for return status values. PMIx return values other than **PMIX\_SUCCESS** are required to always be negative. The return status value for a successful operation is **PMIX\_SUCCESS**, which must have an integer value of 0:

PMIX SUCCESS Success.

Advice to PMIx library implementers

A PMIx implementation must define all of the return status constants defined in the PMIx standard, even if the implementation will never return the specific value to the caller.

#### Advice to users

Other than PMIX\_SUCCESS (which is required to be zero), the integer value of any PMIx error constant is left to the PMIx library implementer with the constraint that it be negative and greater magnitude (i.e. of larger absolute value) than PMIX\_EXTERNAL\_ERR\_BASE. Thus, users are advised to always refer to constants by name, and not by a specific implementation's integer value, for portability between implementations and compatibility across library versions.

The presentation of each API in this document includes a list of return status constants which are either specific to that API or are expected to be returned by the API in normal use.

In addition, the following are general constants covering a variety of possible reasons an implementation of an API may return a constant other than one of the constants presented with the API. Although implementations can define and return additional error constants, implementations are encouraged to return one of the return constants listed with the API or in the list presented here to encourage portability across implementations.

PMIX ERROR General Error.

**PMIX\_ERR\_EXISTS** Requested operation would overwrite an existing value - typically returned when an operation would overwrite an existing file or directory.

**PMIX\_ERR\_EXISTS\_OUTSIDE\_SCOPE** The requested key exists, but was posted in a *scope* (see Section 7.1.1.1) that does not include the requester

**PMIX\_ERR\_INVALID\_CRED** Invalid security credentials.

**PMIX ERR WOULD BLOCK** Operation would block.

**PMIX\_ERR\_UNKNOWN\_DATA\_TYPE** The data type specified in an input to the PMIx library is not recognized by the implementation.

**PMIX\_ERR\_TYPE\_MISMATCH** The data type found in an object does not match the expected data type as specified in the API call - e.g., a request to unpack a **PMIX\_BOOL** value from a buffer that does not contain a value of that type in the current unpack location.

**PMIX\_ERR\_UNPACK\_INADEQUATE\_SPACE** Inadequate space to unpack data - the number of values in the buffer exceeds the specified number to unpack.

1	PMIX_ERR_UNPACK_READ_PAST_END_OF_BUFFER Unpacking past the end of the
2	provided buffer - the number of values in the buffer is less than the specified number to
3	unpack, or a request was made to unpack a buffer beyond the buffer's end.
4	<b>PMIX_ERR_UNPACK_FAILURE</b> The unpack operation failed for an unspecified reason.
5	PMIX_ERR_PACK_FAILURE The pack operation failed for an unspecified reason.
6	PMIX_ERR_NO_PERMISSIONS The user lacks permissions to execute the specified
7	operation.
8	<b>PMIX_ERR_TIMEOUT</b> Either a user-specified or system-internal timeout expired.
9	<b>PMIX_ERR_UNREACH</b> The specified target server or client process is not reachable - i.e., a
0	suitable connection either has not been or can not be made.
1	<b>PMIX_ERR_BAD_PARAM</b> One or more incorrect parameters (e.g., passing an attribute with a
2	value of the wrong type), or multiple parameters containing conflicting directives (e.g.,
3	multiple instances of the same attribute with different values, or different attributes specifying
4	conflicting behaviors), were passed to a PMIx API.
5	<b>PMIX_ERR_EMPTY</b> An array or list was given that has no members in it - i.e., the object is
6	empty.
7	<b>PMIX_ERR_RESOURCE_BUSY</b> Resource busy - typically seen when an attempt to establish a
8	connection to another process (e.g., a PMIx server) cannot be made due to a communication
9	failure.
0	<b>PMIX_ERR_OUT_OF_RESOURCE</b> Resource exhausted.
1	<b>PMIX_ERR_INIT</b> The requested operation requires that the PMIx library be initialized prior
2	to being called.
3	PMIX_ERR_NOMEM Out of memory.
4	<b>PMIX_ERR_NOT_FOUND</b> The requested information was not found.
5	<b>PMIX_ERR_NOT_SUPPORTED</b> The requested operation is not supported by either the PMIx
6	implementation or the host environment.
7	PMIX_ERR_PARAM_VALUE_NOT_SUPPORTED The requested operation is supported by the
8	PMIx implementation and (if applicable) the host environment. However, at least one
9	supplied parameter was given an unsupported value, and the operation cannot therefore be
0	executed as requested.
1	<b>PMIX_ERR_COMM_FAILURE</b> Communication failure - a message failed to be sent or
2	received, but the connection remains intact.
3	<b>PMIX_ERR_LOST_CONNECTION</b> Lost connection between server and client or tool.
4	<b>PMIX_ERR_INVALID_OPERATION</b> The requested operation is supported by the
5	implementation and host environment, but fails to meet a requirement (e.g., requesting to
6	disconnect from processes without first connecting to them, inclusion of conflicting
7	directives, or a request to perform an operation that conflicts with an ongoing one).
8	PMIX_OPERATION_IN_PROGRESS A requested operation is already in progress - the
9	duplicate request shall therefore be ignored.
0	<b>PMIX_OPERATION_SUCCEEDED</b> The requested operation was performed atomically - no
1	callback function will be executed.

The operation is considered successful but not all elements 1 PMIX\_ERR\_PARTIAL\_SUCCESS 2 of the operation were concluded (e.g., some members of a group construct operation chose 3 not to participate). **User-Defined Error and Event Constants** 3.1.1.1 PMIx establishes a boundary for constants defined in the PMIx standard. Negative values larger 5 (i.e., more negative) than this (and any positive values greater than zero) are guaranteed not to 6 7 conflict with PMIx values. 8 PMIX EXTERNAL ERR BASE A starting point for user-level defined error and event constants. Negative values that are more negative than the defined constant are guaranteed not 9 to conflict with PMIx values. Definitions should always be based on the 10 11 PMIX\_EXTERNAL\_ERR\_BASE constant and not a specific value as the value of the constant 12 may change. 3.2 **Data Types** This section defines various data types used by the PMIx APIs. The version of the standard in 14 15 which a particular data type was introduced is shown in the margin. **Key Structure** 3.2.1 The pmix\_key\_t structure is a statically defined character array of length 17 PMIX\_MAX\_KEYLEN+1, thus supporting keys of maximum length PMIX\_MAX\_KEYLEN while 18 19 preserving space for a mandatory **NULL** terminator. *PMIx v2.0* typedef char pmix\_key\_t[PMIX\_MAX\_KEYLEN+1]; 20 Characters in the key must be standard alphanumeric values supported by common utilities such as 21 22 strcmp. Advice to users 23 References to keys in PMIx v1 were defined simply as an array of characters of size PMIX MAX KEYLEN+1. The pmix key t type definition was introduced in version 2 of the 24 25 standard. The two definitions are code-compatible and thus do not represent a break in backward compatibility. 26 27 Passing a pmix\_key\_t value to the standard size of utility can result in compiler warnings of incorrect returned value. Users are advised to avoid using sizeof(pmix key t) and instead rely on 28 29 the PMIX\_MAX\_KEYLEN constant.

#### 3.2.1.1 **Key support macros** 2 The following macros are provided for convenience when working with PMIx keys. Check key macro 3 Compare the key in a **pmix\_info\_t** to a given value. PMIx v3.0 5 PMIX\_CHECK\_KEY(a, b) 6 IN 7 Pointer to the structure whose key is to be checked (pointer to pmix\_info\_t) IN 8 9 String value to be compared against (**char**\*) 10 Returns **true** if the key matches the given value Check reserved key macro 11 Check if the given key is a PMIx reserved key as described in Chapter 6. 12 PMIx v4.0 13 PMIX\_CHECK\_RESERVED\_KEY(a) IN 14 String value to be checked (char\*) 15 Returns **true** if the key is reserved by the Standard. 16 17 Load key macro Load a key into a pmix info t. 18 PMIx v4.0 19 PMIX LOAD KEY(a, b) 20 IN 21 Pointer to the structure whose key is to be loaded (pointer to pmix\_info\_t) 22 IN 23 String value to be loaded (char\*) 24 No return value.

#### 3.2.2 **Namespace Structure** 2 The pmix\_nspace\_t structure is a statically defined character array of length 3 PMIX\_MAX\_NSLEN+1, thus supporting namespaces of maximum length PMIX\_MAX\_NSLEN 4 while preserving space for a mandatory **NULL** terminator. 5 typedef char pmix\_nspace\_t[PMIX\_MAX\_NSLEN+1]; 6 Characters in the namespace must be standard alphanumeric values supported by common utilities 7 such as *strcmp*. Advice to users 8 References to namespace values in PMIx v1 were defined simply as an array of characters of size 9 PMIX MAX NSLEN+1. The pmix nspace t type definition was introduced in version 2 of the standard. The two definitions are code-compatible and thus do not represent a break in backward 10 compatibility. 11 12 Passing a pmix\_nspace\_t value to the standard size of utility can result in compiler warnings of 13 incorrect returned value. Users are advised to avoid using sizeof(pmix\_nspace\_t) and instead rely on the PMIX MAX NSLEN constant. 14 3.2.2.1 Namespace support macros 15 The following macros are provided for convenience when working with PMIx namespace 16 17 structures. Check namespace macro 18 Compare the string in a pmix\_nspace\_t to a given value. 19 *PMIx v3.0* 20 PMIX CHECK NSPACE (a, b) IN 21 22 Pointer to the structure whose value is to be checked (pointer to pmix nspace t)

String value to be compared against (char\*)

Returns **true** if the namespace matches the given value

23 24

25

IN

1 2		Load namespace macro Load a namespace into a pmix_nspace_t.  C
3		PMIX_LOAD_NSPACE(a, b)
4 5 6		<pre>IN a     Pointer to the target structure (pointer to pmix_nspace_t) IN b</pre>
7 8		String value to be loaded - if <b>NULL</b> is given, then the target structure will be initialized to zero's ( <b>char</b> *)
9		No return value.
10	3.2.3	Rank Structure
11	PMIx v1.0	The pmix_rank_t structure is a uint32_t type for rank values.
12		<pre>typedef uint32_t pmix_rank_t;</pre>
13 14 15		The following constants can be used to set a variable of the type <code>pmix_rank_t</code> . All definitions were introduced in version 1 of the standard unless otherwise marked. Valid rank values start at zero.
16 17 18		<b>PMIX_RANK_UNDEF</b> A value to request job-level data where the information itself is not associated with any specific rank, or when passing a <b>pmix_proc_t</b> identifier to an operation that only references the namespace field of that structure.
19 20		<b>PMIX_RANK_WILDCARD</b> A value to indicate that the user wants the data for the given key from every rank that posted that key.
21 22		<b>PMIX_RANK_LOCAL_NODE</b> Special rank value used to define groups of ranks. This constant defines the group of all ranks on a local node.
23 24 25		<b>PMIX_RANK_LOCAL_PEERS</b> Special rank value used to define groups of ranks. This constant defines the group of all ranks on a local node within the same namespace as the current process.
26 27		PMIX_RANK_INVALID An invalid rank value.  PMIX_RANK_VALID Define an upper boundary for valid rank values.
28	3.2.3.1	Rank support macros
29		The following macros are provided for convenience when working with PMIx ranks.

```
Check rank macro
 1
               Check two ranks for equality, taking into account wildcard values
 2
               PMIX CHECK RANK(a, b)
 3
               IN
 5
                    Rank to be checked (pmix_rank_t)
               IN
 6
 7
                    Rank to be checked (pmix_rank_t)
               Returns true if the ranks are equal, or at least one of the ranks is PMIX_RANK_WILDCARD
             Process Structure
    3.2.4
10
               The pmix_proc_t structure is used to identify a single process in the PMIx universe. It contains
               a reference to the namespace and the pmix_rank_t within that namespace.
11
  PMIx v1.0
12
               typedef struct pmix_proc {
13
                    pmix_nspace_t nspace;
14
                    pmix_rank_t rank;
15
               } pmix_proc_t;
    3.2.4.1
              Process structure support macros
               The following macros are provided to support the pmix_proc_t structure.
17
               Initialize the proc structure
18
               Initialize the pmix_proc_t fields.
19
  PMIx v1.0
               PMIX_PROC_CONSTRUCT (m)
20
21
               IN
22
                    Pointer to the structure to be initialized (pointer to pmix_proc_t)
```

1 2	Destruct the proc structure  Destruct the pmix_proc_t fields.
2	C C
3	PMIX_PROC_DESTRUCT (m)
4 5	IN m Pointer to the structure to be destructed (pointer to pmix_proc_t)
6 7 8	There is nothing to release here as the fields in <code>pmix_proc_t</code> are either a statically-declared array (the namespace) or a single value (the rank). However, the macro is provided for symmetry in the code and for future-proofing should some allocated field be included some day.
9 10 <i>PMIx v1.0</i>	Create a proc array Allocate and initialize an array of pmix_proc_t structures.
11	PMIX_PROC_CREATE(m, n)
12 13 14 15	INOUT m  Address where the pointer to the array of pmix_proc_t structures shall be stored (handle)  IN n  Number of structures to be allocated (size_t)
16 17 <i>PMIx v4.0</i>	Free a proc structure Release a pmix_proc_t structure.
18	PMIX_PROC_RELEASE (m)
19 20	IN m Pointer to a pmix_proc_t structure (handle)
21 22	Free a proc array Release an array of pmix_proc_t structures.
<i>PMIx v1.0</i> 23	PMIX_PROC_FREE(m, n)
24 25	IN m Pointer to the array of pmix_proc_t structures (handle)
26 27	IN n  Number of structures in the array (size_t)

```
Load a proc structure
 1
               Load values into a pmix_proc_t.
 2
  PMIx v2.0
 3
               PMIX PROC LOAD (m, n, r)
               IN
 5
                    Pointer to the structure to be loaded (pointer to pmix_proc_t)
               IN
 6
 7
                    Namespace to be loaded (pmix_nspace_t)
               IN
 8
 9
                    Rank to be assigned (pmix_rank_t)
10
               No return value. Deprecated in favor of PMIX_LOAD_PROCID
               Compare identifiers
11
12
               Compare two pmix_proc_t identifiers.
  PMIx v3.0
13
               PMIX_CHECK_PROCID(a, b)
               IN
14
15
                    Pointer to a structure whose ID is to be compared (pointer to pmix_proc_t)
               IN
16
                    Pointer to a structure whose ID is to be compared (pointer to pmix_proc_t)
17
18
               Returns true if the two structures contain matching namespaces and:
               • the ranks are the same value
19
               • one of the ranks is PMIX_RANK_WILDCARD
20
21
               Load a procID structure
               Load values into a pmix_proc_t.
22
  PMIx v4.0
               PMIX_LOAD_PROCID(m, n, r)
23
               IN
24
25
                    Pointer to the structure to be loaded (pointer to pmix_proc_t)
               IN
26
27
                    Namespace to be loaded (pmix_nspace_t)
               IN
28
                    Rank to be assigned (pmix_rank_t)
29
```

```
Construct a multi-cluster namespace
 1
 2
               Construct a multi-cluster identifier containing a cluster ID and a namespace.
               PMIX MULTICLUSTER NSPACE CONSTRUCT (m, n, r)
 3
               IN
 5
                    pmix_nspace_t structure that will contain the multi-cluster identifier (pmix_nspace_t)
               IN
 6
 7
                    Cluster identifier (char*)
               IN
 8
                    Namespace to be loaded (pmix_nspace_t)
 9
10
               Combined length of the cluster identifier and namespace must be less than PMIX_MAX_NSLEN-2.
               Parse a multi-cluster namespace
11
12
               Parse a multi-cluster identifier into its cluster ID and namespace parts.
   PMIx v4.0
13
               PMIX MULTICLUSTER NSPACE PARSE (m, n, r)
               IN
14
                    pmix_nspace_t structure containing the multi-cluster identifier (pointer to
15
                    pmix_nspace_t)
16
               IN
17
                    Location where the cluster ID is to be stored (pmix_nspace_t)
18
19
               IN
                    Location where the namespace is to be stored (pmix_nspace_t)
20
    3.2.5
              Process State Structure
   PMIx v2.0
               The pmix proc state t structure is a uint8 t type for process state values. The following
23
               constants can be used to set a variable of the type pmix proc state t.
                                                   Advice to users
24
                The fine-grained nature of the following constants may exceed the ability of an RM to provide
25
               updated process state values during the process lifetime. This is particularly true of states for
26
               short-lived processes.
```

```
1
               PMIX_PROC_STATE_UNDEF
                                              Undefined process state.
 2
               PMIX_PROC_STATE_PREPPED
                                                Process is ready to be launched.
 3
               PMIX_PROC_STATE_LAUNCH_UNDERWAY
                                                          Process launch is underway.
 4
                                                Process is ready for restart.
               PMIX PROC STATE RESTART
 5
               PMIX PROC STATE TERMINATE
                                                   Process is marked for termination.
               PMIX_PROC_STATE_RUNNING
                                                Process has been locally fork'ed by the RM.
 6
 7
               PMIX PROC STATE CONNECTED
                                                   Process has connected to PMIx server.
                                                      Define a "boundary" between the terminated states
8
               PMIX_PROC_STATE_UNTERMINATED
9
                   and PMIX_PROC_STATE_CONNECTED so users can easily and quickly determine if a
10
                   process is still running or not. Any value less than this constant means that the process has not
11
                   terminated.
12
               PMIX PROC STATE TERMINATED
                                                    Process has terminated and is no longer running.
               PMIX_PROC_STATE_ERROR
                                             Define a boundary so users can easily and quickly determine if
13
14
                   a process abnormally terminated. Any value above this constant means that the process has
15
                   terminated abnormally.
16
               PMIX_PROC_STATE_KILLED_BY_CMD
                                                        Process was killed by a command.
                                                Process was aborted by a call to PMIx_Abort.
               PMIX_PROC_STATE_ABORTED
17
                                                          Process failed to start.
18
               PMIX_PROC_STATE_FAILED_TO_START
19
               PMIX PROC STATE ABORTED BY SIG
                                                         Process aborted by a signal.
                                                      Process exited without calling PMIx Finalize.
20
               PMIX PROC STATE TERM WO SYNC
                                                     Process communication has failed.
21
               PMIX PROC STATE COMM FAILED
               PMIX_PROC_STATE_SENSOR_BOUND_EXCEEDED
22
                                                                  Process exceeded a specified sensor
23
                   limit.
24
               PMIX_PROC_STATE_CALLED_ABORT
                                                      Process called PMIx Abort.
               PMIX_PROC_STATE_HEARTBEAT_FAILED
                                                            Frocess failed to send heartbeat within
25
26
                   specified time limit.
                                                  Process failed and is waiting for resources before
27
               PMIX_PROC_STATE_MIGRATING
28
                   restarting.
               PMIX_PROC_STATE_CANNOT_RESTART
                                                         Process failed and cannot be restarted.
29
30
               PMIX PROC STATE TERM NON ZERO
                                                        Process exited with a non-zero status.
31
               PMIX PROC STATE FAILED TO LAUNCH
                                                            Unable to launch process.
```

# 2 3.2.6 Process Information Structure

The pmix\_proc\_info\_t structure defines a set of information about a specific process including it's name, location, and state.

PMIx v2.0

33

```
typedef struct pmix proc info {
1
                  /** Process structure */
 3
                  pmix_proc_t proc;
                  /** Hostname where process resides */
 5
                  char *hostname;
6
                  /** Name of the executable */
 7
                  char *executable name;
8
                  /** Process ID on the host */
9
                  pid_t pid;
10
                  /** Exit code of the process. Default: 0 */
                  int exit code;
11
                  /** Current state of the process */
12
13
                  pmix_proc_state_t state;
              } pmix_proc_info_t;
14
   3.2.6.1
             Process information structure support macros
             The following macros are provided to support the pmix_proc_info_t structure.
16
             Initialize the process information structure
17
             Initialize the pmix_proc_info_t fields.
18
  PMIx v2.0
19
             PMIX PROC INFO CONSTRUCT (m)
             IN
20
                 Pointer to the structure to be initialized (pointer to pmix_proc_info_t)
21
             Destruct the process information structure
22
             Destruct the pmix_proc_info_t fields.
23
  PMIx v2.0
24
             PMIX PROC INFO DESTRUCT (m)
25
26
                  Pointer to the structure to be destructed (pointer to pmix_proc_info_t)
```

```
Create a process information array
 1
 2
               Allocate and initialize a pmix proc info t array.
 3
               PMIX PROC INFO CREATE (m, n)
               INOUT m
                    Address where the pointer to the array of pmix proc info t structures shall be stored
 5
 6
                    (handle)
 7
               IN
 8
                    Number of structures to be allocated (size_t)
               Free a process information structure
 9
10
               Release a pmix_proc_info_t structure.
   PMIx v2.0
11
               PMIX PROC INFO RELEASE (m)
               IN
12
                    m
13
                    Pointer to a pmix_proc_info_t structure (handle)
               Free a process information array
14
               Release an array of pmix_proc_info_t structures.
15
   PMIx v2.0
16
               PMIX PROC INFO FREE (m, n)
               IN
17
                    Pointer to the array of pmix_proc_info_t structures (handle)
18
               IN
19
20
                    Number of structures in the array (size t)
              Job State Structure
    3.2.7
22 PMIx v4.0
               The pmix_job_state_t structure is a uint8_t type for job state values. The following
               constants can be used to set a variable of the type pmix job state t.
23
                                                  Advice to users
24
               The fine-grained nature of the following constants may exceed the ability of an RM to provide
25
               updated job state values during the job lifetime. This is particularly true for short-lived jobs.
```

```
Undefined job state.
 1
               PMIX_JOB_STATE_UNDEF
 2
               PMIX_JOB_STATE_AWAITING ALLOC
                                                           Job is waiting for resources to be allocated to it.
 3
               PMIX_JOB_STATE_LAUNCH_UNDERWAY
                                                            Job launch is underway.
 4
               PMIX JOB STATE RUNNING
                                                 All processes in the job have been spawned and are executing.
 5
               PMIX JOB STATE SUSPENDED
                                                    All processes in the job have been suspended.
6
               PMIX JOB STATE CONNECTED
                                                    All processes in the job have connected to their PMIx
 7
                    server.
8
                                                        Define a "boundary" between the terminated states
               PMIX JOB STATE UNTERMINATED
9
                    and PMIX JOB STATE TERMINATED so users can easily and quickly determine if a job is
10
                    still running or not. Any value less than this constant means that the job has not terminated.
11
               PMIX JOB STATE TERMINATED
                                                     All processes in the job have terminated and are no
                    longer running - typically will be accompanied by the job exit status in response to a query.
12
               PMIX JOB STATE TERMINATED WITH ERROR
                                                                    Define a boundary so users can easily
13
                    and quickly determine if a job abnormally terminated - typically will be accompanied by a
14
15
                    job-related error code in response to a query Any value above this constant means that the job
16
                    terminated abnormally.
```

#### 7 3.2.8 Value Structure

The pmix\_value\_t structure is used to represent the value passed to PMIx\_Put and retrieved by PMIx Get, as well as many of the other PMIx functions.

A collection of values may be specified under a single key by passing a **pmix\_value\_t** containing an array of type **pmix\_data\_array\_t**, with each array element containing its own object. All members shown below were introduced in version 1 of the standard unless otherwise marked.

PMIx v1.0

18

19 20

21

22

```
24
             typedef struct pmix_value {
                 pmix_data_type_t type;
25
26
                 union {
27
                     bool flag;
28
                      uint8_t byte;
29
                      char *string;
30
                      size_t size;
31
                     pid_t pid;
32
                     int integer;
33
                      int8 t int8;
34
                      int16 t int16;
35
                     int32_t int32;
36
                     int64 t int64;
37
                      unsigned int uint;
```

```
uint8_t uint8;
 1
2
                      uint16 t uint16;
                      uint32 t uint32;
 3
 4
                      uint64_t uint64;
5
                       float fval:
6
                      double dval;
7
                       struct timeval tv;
8
                                                           // version 2.0
                      time t time;
9
                      pmix status t status;
                                                            // version 2.0
10
                      pmix_rank_t rank;
                                                            // version 2.0
11
                      pmix_proc_t *proc;
                                                            // version 2.0
                      pmix_byte_object_t bo;
12
13
                      pmix_persistence_t persist;
                                                            // version 2.0
                                                            // version 2.0
14
                      pmix_scope_t scope;
15
                      pmix_data_range_t range;
                                                            // version 2.0
                      pmix_proc_state_t state;
                                                            // version 2.0
16
                      pmix_proc_info_t *pinfo;
17
                                                            // version 2.0
18
                      pmix_data_array_t *darray;
                                                            // version 2.0
19
                                                            // version 2.0
                      void *ptr;
20
                      pmix alloc directive t adir;
                                                            // version 2.0
                  } data;
21
22
             } pmix value t;
   3.2.8.1
             Value structure support macros
24
             The following macros are provided to support the pmix_value_t structure.
             Initialize the value structure
25
26
             Initialize the pmix value t fields.
  PMIx v1.0
             PMIX VALUE CONSTRUCT (m)
27
28
             IN
29
                 Pointer to the structure to be initialized (pointer to pmix_value_t)
             Destruct the value structure
30
             Destruct the pmix_value_t fields.
31
  PMIx v1.0
32
             PMIX_VALUE_DESTRUCT (m)
             IN
33
                 Pointer to the structure to be destructed (pointer to pmix value t)
34
```

1	Create a value array
2	Allocate and initialize an array of <b>pmix_value_t</b> structures.
<i>PMIx v1.0</i>	C
3	PMIX_VALUE_CREATE (m, n)
	C
4	INOUT m
5	Address where the pointer to the array of <b>pmix_value_t</b> structures shall be stored (handle)
6	IN n
7	Number of structures to be allocated (size_t)
,	(SIZE_C)
8	Free a value structure
9	Release a pmix_value_t structure.
<i>PMIx v4.0</i>	C
10	PMIX VALUE RELEASE (m)
10	PMIX_VALUE_RELEASE (III)
	C
11	IN m
12	Pointer to a pmix_value_t structure (handle)
10	Eroo o voluo orrov
13 14	Free a value array
PMIx v1.0	Release an array of pmix_value_t structures.
PMIX VI.O	
15	PMIX_VALUE_FREE (m, n)
	C
4.0	
16	IN m
17	Pointer to the array of <b>pmix_value_t</b> structures (handle)
18	IN n
19	Number of structures in the array (size_t)
20	Load a value structure
21	Load data into a pmix_value_t structure.
PMIx v2.0	

	· ·
1	PMIX_VALUE_LOAD(v, d, t);
2	IN v
3	The pmix_value_t into which the data is to be loaded (pointer to pmix_value_t)
4	IN d
5	Pointer to the data value to be loaded (handle)
6	IN t
7	Type of the provided data value (pmix_data_type_t)
8 9	This macro simplifies the loading of data into a <b>pmix_value_t</b> by correctly assigning values to the structure's fields.
	Advice to users
0	The data will be copied into the <code>pmix_value_t</code> - thus, any data stored in the source value can be modified or free'd without affecting the copied data once the macro has completed.
2 3 <i>PMIx v2.2</i>	Unload a value structure Unload data from a pmix_value_t structure.
4	PMIX_VALUE_UNLOAD(r, v, d, t);
5	OUT r
6	Status code indicating result of the operation <pre>pmix_status_t</pre>
7	
8 9	The <pre>pmix_value_t</pre> from which the data is to be unloaded (pointer to <pre>pmix_value_t</pre> ) <pre>INOUT d</pre>
20	Pointer to the location where the data value is to be returned (handle)
.u ?1	INOUT t
22	Pointer to return the data type of the unloaded value (handle)
23	This macro simplifies the unloading of data from a <b>pmix_value_t</b> .
	Advice to users —
24	Memory will be allocated and the data will be in the <b>pmix_value_t</b> returned - the source
25	pmix_value_t will not be altered.
	A not be dicted.

```
Transfer data between value structures
 1
 2
               Transfer the data value between two pmix value t structures.
 3
               PMIX VALUE XFER(r, d, s);
               OUT r
 5
                    Status code indicating success or failure of the transfer (pmix_status_t)
               IN
 6
 7
                    Pointer to the pmix_value_t destination (handle)
               IN
 8
 9
                    Pointer to the pmix_value_t source (handle)
10
               This macro simplifies the transfer of data between two pmix value t structures, ensuring that
               all fields are properly copied.
11
                                                   Advice to users
12
               The data will be copied into the destination pmix value t - thus, any data stored in the source
               value can be modified or free'd without affecting the copied data once the macro has completed.
13
               Retrieve a numerical value from a value struct
14
15
               Retrieve a numerical value from a pmix_value_t structure.
   PMIx v3.0
16
               PMIX VALUE GET NUMBER(s, m, n,
               OUT s
17
18
                    Status code for the request (pmix_status_t)
19
               IN
                    Pointer to thepmix_value_t structure (handle)
20
               OUT n
21
22
                    Variable to be set to the value (match expected type)
23
               IN
                     Type of number expected in m (pmix_data_type_t)
24
25
               Sets the provided variable equal to the numerical value contained in the given pmix value t,
               returning success if the data type of the value matches the expected type and
26
27
               PMIX ERR BAD PARAM if it doesn't
```

#### 3.2.9 Info Structure

```
2
               The pmix_info_t structure defines a key/value pair with associated directive. All fields were
               defined in version 1.0 unless otherwise marked.
 3
               typedef struct pmix_info_t {
 5
                    pmix_key_t key;
 6
                    pmix info directives t flags;
                                                                // version 2.0
 7
                    pmix value t value;
 8
               } pmix info t;
    3.2.9.1
               Info structure support macros
10
               The following macros are provided to support the pmix_info_t structure.
               Initialize the info structure
11
12
               Initialize the pmix info t fields.
  PMIx v1.0
13
               PMIX INFO CONSTRUCT (m)
               IN
14
                    Pointer to the structure to be initialized (pointer to pmix_info_t)
15
               Destruct the info structure
16
17
               Destruct the pmix info t fields.
  PMIx v1.0
               PMIX_INFO_DESTRUCT (m)
18
               IN
19
                    Pointer to the structure to be destructed (pointer to pmix info t)
20
               Create an info array
21
22
               Allocate and initialize an array of info structures.
  PMIx v1.0
23
               PMIX INFO CREATE (m, n)
               INOUT m
24
                    Address where the pointer to the array of pmix info t structures shall be stored (handle)
25
               IN
26
27
                    Number of structures to be allocated (size t)
```

1	Free an info array
2	Release an array of pmix_info_t structures.
<i>PMIx v1.0</i>	<b>▼</b>
3	PMIX_INFO_FREE(m, n)
	C
4	IN m
5	Pointer to the array of pmix_info_t structures (handle)
6	IN n
7	Number of structures in the array (size_t)
8 <sub>PMIx v1.0</sub>	Load key and value data into a info struct
9	PMIX_INFO_LOAD(v, k, d, t);
	C
10	IN v
11	Pointer to the pmix_info_t into which the key and data are to be loaded (pointer to
12	<pre>pmix_info_t)</pre>
13	IN k
14	String key to be loaded - must be less than or equal to PMIX_MAX_KEYLEN in length
15	(handle)
16	IN d
17	Pointer to the data value to be loaded (handle)
18	IN t
19	Type of the provided data value (pmix_data_type_t)
20	This macro simplifies the loading of key and data into a pmix_info_t by correctly assigning
21	values to the structure's fields.
	Advice to users
22	Both key and data will be copied into the <b>pmix_info_t</b> - thus, the key and any data stored in the
23	source value can be modified or free'd without affecting the copied data once the macro has
24	completed.

```
Copy data between info structures
 1
 2
               Copy all data (including key, value, and directives) between two pmix info t structures.
 3
               PMIX INFO XFER(d, s);
               IN
 5
                    Pointer to the destination pmix_info_t (pointer to pmix_info_t)
               IN
 6
 7
                    Pointer to the source pmix_info_t (pointer to pmix_info_t)
 8
               This macro simplifies the transfer of data between twopmix info_t structures.
                                                   Advice to users
               All data (including key, value, and directives) will be copied into the destination pmix_info_t -
 9
               thus, the source pmix_info_t may be free'd without affecting the copied data once the macro
10
11
               has completed.
               Test a boolean info struct
12
13
               A special macro for checking if a boolean pmix_info_t is true.
  PMIx v2.0
14
               PMIX INFO TRUE (m)
               IN
15
                    Pointer to a pmix_info_t structure (handle)
16
               A pmix_info_t structure is considered to be of type PMIX_BOOL and value true if:
17
18
               • the structure reports a type of PMIX_UNDEF, or
               • the structure reports a type of PMIX_BOOL and the data flag is true
19
    3.2.9.2
               Info structure list macros
20
21
               Constructing an array of pmix info t is a fairly common operation. The following macros are
22
               provided to simplify this construction.
```

1	Start a list of pmix_info_t structures
2	Initialize a list of <b>pmix_info_t</b> structures. The actual list is opaque to the caller and is
3	implementation-dependent.
	C
4	PMIX_INFO_LIST_START (m)
7	PMIX_INFO_BISI_START(III)
5	IN m
6	A void* pointer (handle)
7	
7	Note that the pointer will be initialized to an opaque structure whose elements are
8	implementation-dependent. The caller must not modify or dereference the object.
9	Add a pmix_info_t structure to a list
10	Add a pmix_info_t structure containing the specified value to the provided list.
PMIx v4.0	C
11	PMIX_INFO_LIST_ADD(rc, m, k, d, t)
	C
12	INOUT rc
13	Return status for the operation (pmix_status_t)
14	IN m
15	A void* pointer initialized via PMIX_INFO_LIST_START (handle)
16	IN k
17	String key to be loaded - must be less than or equal to <b>PMIX_MAX_KEYLEN</b> in length
18	(handle)
19	IN d
20	Pointer to the data value to be loaded (handle)
21	IN t
22	Type of the provided data value (pmix_data_type_t)
	Advice to users —
23	Both key and data will be copied into the <b>pmix_info_t</b> on the list - thus, the key and any data
24	stored in the source value can be modified or free'd without affecting the copied data once the
25	macro has completed.
	has completed.

```
Transfer a pmix_info_t structure to a list
 1
 2
               Transfer the information in a pmix info t structure to the provided list.
 3
               PMIX INFO LIST XFER(rc, m, s)
               INOUT rc
 4
 5
                    Return status for the operation (pmix_status_t)
               IN
 6
 7
                    A void* pointer initialized via PMIX INFO LIST START (handle)
 8
               IN
 9
                    Pointer to the source pmix_info_t (pointer to pmix_info_t)
                                                  Advice to users
               All data (including key, value, and directives) will be copied into the destination pmix info t
10
11
               on the list - thus, the source pmix info t may be free'd without affecting the copied data once
12
               the macro has completed.
               Convert a pmix_info_t list to an array
13
14
               Transfer the information in the provided pmix info t list to a pmix data array t array
  PMIx v4.0
15
               PMIX_INFO_LIST_CONVERT(rc, m, d)
               INOUT rc
16
                    Return status for the operation (pmix_status_t)
17
18
               IN
                    A void* pointer initialized via PMIX_INFO_LIST_START (handle)
19
               IN
20
21
                    Pointer to an instantiated pmix data array t structure where the pmix info t array
22
                    is to be stored (pointer to pmix data array t)
               Release a pmix_info_t list
23
24
               Release the provided pmix_info_t list
  PMIx v4.0
25
               PMIX INFO LIST RELEASE (m)
               IN
26
27
                    A void* pointer initialized via PMIX_INFO_LIST_START (handle)
28
               Information contained in the pmix info t on the list shall be released in addition to whatever
29
               backing storage the implementation may have allocated to support construction of the list.
```

# 3.2.10 Info Type Directives

PMIx v2.0

The **pmix\_info\_directives\_t** structure is a **uint32\_t** type that defines the behavior of command directives via **pmix\_info\_t** arrays. By default, the values in the **pmix\_info\_t** array passed to a PMIx are *optional*.

#### Advice to users

A PMIx implementation or PMIx-enabled RM may ignore any <code>pmix\_info\_t</code> value passed to a PMIx API that it does not support or does not recognize if it is not explicitly marked as <code>PMIX\_INFO\_REQD</code>. This is because the values specified default to optional, meaning they can be ignored in such circumstances. This may lead to unexpected behavior when porting between environments or PMIx implementations if the user is relying on the behavior specified by the <code>pmix\_info\_t</code> value. Users relying on the behavior defined by the <code>pmix\_info\_t</code> are advised to set the <code>PMIX\_INFO\_REQD</code> flag using the <code>PMIX\_INFO\_REQUIRED</code> macro.

# Advice to PMIx library implementers

The top 16-bits of the <code>pmix\_info\_directives\_t</code> are reserved for internal use by PMIx library implementers - the PMIx standard will *not* specify their intent, leaving them for customized use by implementers. Implementers are advised to use the provided <code>PMIX\_INFO\_IS\_REQUIRED</code> macro for testing this flag, and must return <code>PMIX\_ERR\_NOT\_SUPPORTED</code> as soon as possible to the caller if the required behavior is not supported.

The following constants were introduced in version 2.0 (unless otherwise marked) and can be used to set a variable of the type **pmix\_info\_directives\_t**.

**PMIX\_INFO\_REQD** The behavior defined in the **pmix\_info\_t** array is required, and not optional. This is a bit-mask value.

PMIX\_INFO\_REQD\_PROCESSED Mark that this required attribute has been processed. A required attribute can be handled at any level - the PMIx client library might take care of it, or it may be resolved by the PMIx server library, or it may pass up to the host environment for handling. If a level does not recognize or support the required attribute, it is required to pass it upwards to give the next level an opportunity to process it. Thus, the host environment (or the server library if the host does not support the given operation) must know if a lower level has handled the requirement so it can return a PMIX\_ERR\_NOT\_SUPPORTED error status if the host itself cannot meet the request. Upon processing the request, the level must therefore mark the attribute with this directive to alert any subsequent levels that the requirement has been met.

**PMIX\_INFO\_ARRAY\_END** Mark that this **pmix\_info\_t** struct is at the end of an array created by the **PMIX\_INFO\_CREATE** macro. This is a bit-mask value.

**PMIX\_INFO\_DIR\_RESERVED** A bit-mask identifying the bits reserved for internal use by implementers - these currently are set as **0xffff0000**.

#### Advice to PMIx server hosts Host environments are advised to use the provided PMIX\_INFO\_IS\_REQUIRED macro for 1 testing this flag and must return PMIX\_ERR\_NOT\_SUPPORTED as soon as possible to the caller if 2 the required behavior is not supported. 3 3.2.10.1 Info Directive support macros 5 The following macros are provided to support the setting and testing of **pmix\_info\_t** directives. Mark an info structure as required 6 Set the **PMIX\_INFO\_REQD** flag in a **pmix\_info\_t** structure. *PMIx v2.0* PMIX INFO REQUIRED (info); 8 IN 9 info Pointer to the pmix info t (pointer to pmix info t) 10 This macro simplifies the setting of the **PMIX\_INFO\_REQD** flag in **pmix\_info\_t** structures. 11 Mark an info structure as optional 12 13 Unsets the **PMIX\_INFO\_REQD** flag in a **pmix\_info\_t** structure. PMIx v2.0PMIX\_INFO\_OPTIONAL(info); 14 15 IN info Pointer to the pmix\_info\_t (pointer to pmix\_info\_t) 16 This macro simplifies marking a pmix\_info\_t structure as optional. 17 Test an info structure for *required* directive 18 Test the PMIX\_INFO\_REQD flag in a pmix\_info\_t structure, returning true if the flag is set. 19 PMIx v2.0PMIX INFO IS REQUIRED (info); 20 IN info 21 Pointer to the pmix\_info\_t (pointer to pmix\_info\_t) 22

This macro simplifies the testing of the required flag in pmix\_info\_t structures.

```
Test an info structure for optional directive
 1
               Test a pmix_info_t structure, returning true if the structure is optional.
 2
               PMIX INFO IS OPTIONAL (info);
 3
               IN
                    info
 5
                    Pointer to the pmix_info_t (pointer to pmix_info_t)
 6
               Test the PMIX INFO REQD flag in a pmix info t structure, returning true if the flag is not
 7
               set.
               Mark a required attribute as processed
8
               Mark that a required pmix_info_t structure has been processed.
9
   PMIx v4.0
10
               PMIX INFO PROCESSED (info);
               IN
11
                    info
                    Pointer to the pmix info t (pointer to pmix info t)
12
13
               Set the PMIX INFO REOD PROCESSED flag in a pmix info t structure indicating that is
14
               has been processed.
               Test if a required attribute has been processed
15
16
               Test that a required pmix_info_t structure has been processed.
   PMIx v4.0
17
               PMIX INFO WAS PROCESSED (info);
18
               IN
                    info
19
                    Pointer to the pmix_info_t (pointer to pmix_info_t)
               Test the PMIX INFO REQD PROCESSED flag in a pmix info t structure.
20
               Test an info structure for end of array directive
21
               Test a pmix_info_t structure, returning true if the structure is at the end of an array created by
22
23
               the PMIX INFO CREATE macro.
   PMIx v2.2
24
               PMIX_INFO_IS_END(info);
               IN
25
                    info
26
                    Pointer to the pmix info t (pointer to pmix info t)
27
               This macro simplifies the testing of the end-of-array flag in pmix info t structures.
```

# 3.2.11 Environmental Variable Structure

```
2 PMIx v3.0
               Define a structure for specifying environment variable modifications. Standard environment
 3
               variables (e.g., PATH, LD_LIBRARY_PATH, and LD_PRELOAD) take multiple arguments
 4
               separated by delimiters. Unfortunately, the delimiters depend upon the variable itself - some use
               semi-colons, some colons, etc. Thus, the operation requires not only the name of the variable to be
 5
 6
               modified and the value to be inserted, but also the separator to be used when composing the
 7
               aggregate value.
 8
               typedef struct {
 9
                     char *envar;
10
                     char *value;
11
                     char separator;
               } pmix_envar_t;
12
    3.2.11.1
                Environmental variable support macros
               The following macros are provided to support the pmix_envar_t structure.
14
               Initialize the envar structure
15
16
               Initialize the pmix_envar_t fields
  PMIx v3.0
17
               PMIX ENVAR CONSTRUCT (m)
               IN
18
                    m
                    Pointer to the structure to be initialized (pointer to pmix_envar_t)
19
               Destruct the envar structure
20
21
               Clear the pmix_envar_t fields.
  PMIx v3.0
22
               PMIX_ENVAR_DESTRUCT (m)
               IN
23
```

Pointer to the structure to be destructed (pointer to pmix\_envar\_t)

```
Create an envar array
 1
               Allocate and initialize an array of pmix_envar_t structures.
 2
 3
               PMIX ENVAR CREATE (m, n)
               INOUT m
                    Address where the pointer to the array of pmix_envar_t structures shall be stored (handle)
 5
               IN
 6
 7
                    Number of structures to be allocated (size t)
               Free an envar array
 8
               Release an array of pmix_envar_t structures.
   PMIx v3.0
10
               PMIX ENVAR FREE (m, n)
               IN
11
12
                    Pointer to the array of pmix_envar_t structures (handle)
               IN
13
                    Number of structures in the array (size_t)
14
               Load an envar structure
15
16
               Load values into a pmix_envar_t.
   PMIx v2.0
17
               PMIX_ENVAR_LOAD(m, e, v, s)
18
               IN
                    Pointer to the structure to be loaded (pointer to pmix_envar_t)
19
20
               IN
                    Environmental variable name (char*)
21
               IN
22
23
                    Value of variable (char*)
24
               IN
25
                    Separator character (char)
```

# 3.2.12 Byte Object Type

```
2
              The pmix_byte_object_t structure describes a raw byte sequence.
              typedef struct pmix_byte_object {
3
 4
                   char *bytes;
 5
                   size_t size;
6
               } pmix byte object t;
    3.2.12.1
               Byte object support macros
              The following macros support the pmix_byte_object_t structure.
8
              Initialize the byte object structure
9
              Initialize the pmix_byte_object_t fields.
10
  PMIx v2.0
              PMIX BYTE OBJECT CONSTRUCT (m)
11
12
              IN
                   m
13
                   Pointer to the structure to be initialized (pointer to pmix_byte_object_t)
14
              Destruct the byte object structure
              Clear the pmix_byte_object_t fields.
15
                                                        C
  PMIx v2.0
              PMIX_BYTE_OBJECT_DESTRUCT (m)
16
17
              IN
                   m
                   Pointer to the structure to be destructed (pointer to pmix_byte_object_t)
18
              Create a byte object structure
19
20
              Allocate and intitialize an array of pmix_byte_object_t structures.
  PMIx v2.0
21
              PMIX BYTE OBJECT CREATE (m, n)
22
              INOUT m
                   Address where the pointer to the array of pmix_byte_object_t structures shall be stored
23
                   (handle)
24
              IN
25
26
                   Number of structures to be allocated (size t)
```

```
Free a byte object array
 1
2
              Release an array of pmix byte object t structures.
 3
              PMIX BYTE OBJECT FREE (m, n)
              IN
 5
                   Pointer to the array of pmix_byte_object_t structures (handle)
              IN
 6
 7
                   Number of structures in the array (size_t)
              Load a byte object structure
8
              Load values into a pmix_byte_object_t.
   PMIx v2.0
10
              PMIX_BYTE_OBJECT_LOAD(b, d, s)
              IN
11
                   b
                   Pointer to the structure to be loaded (pointer to pmix_byte_object_t)
12
              IN
13
                   Pointer to the data to be loaded (char*)
14
15
              IN
                   Number of bytes in the data array (size_t)
16
    3.2.13
              Data Array Structure
18
              The pmix_data_array_t structure defines an array data structure.
   PMIx v2.0
19
              typedef struct pmix_data_array {
20
                   pmix_data_type_t type;
21
                   size_t size;
22
                   void *array;
23
              } pmix_data_array_t;
    3.2.13.1
               Data array support macros
25
              The following macros support the pmix_data_array_t structure.
```

```
Initialize a data array structure
 1
 2
               Initialize the pmix data array t fields, allocating memory for the array of the indicated type.
               PMIX DATA ARRAY CONSTRUCT (m, n,
 3
               IN
 4
                    Pointer to the structure to be initialized (pointer to pmix_data_array_t
 5
               IN
 6
 7
                    Number of elements in the array (size t)
 8
               IN
 9
                    PMIx data type of the array elements (pmix data type t)
10
               Destruct a data array structure
               Destruct the pmix_data_array_t, releasing the memory in the array.
11
  PMIx v2.2
12
               PMIX_DATA_ARRAY_CONSTRUCT (m)
               IN
13
14
                    Pointer to the structure to be destructed (pointer to pmix data array t)
               Create a data array structure
15
               Allocate memory for the pmix data array t object itself, and then allocate memory for the
16
17
               array of the indicated type.
  PMIx v2.2
               PMIX DATA ARRAY CREATE (m, n, t)
18
               INOUT m
19
                    Variable to be set to the address of the structure (pointer to pmix_data_array_t
20
               IN
21
22
                    Number of elements in the array (size t)
               IN
23
24
                    PMIx data type of the array elements (pmix_data_type_t)
               Free a data array structure
25
               Release the memory in the array, and then release the pmix data array t object itself.
26
  PMIx v2.2
27
               PMIX_DATA_ARRAY_FREE (m)
               IN
28
                    Pointer to the structure to be released (pointer to pmix data array t)
29
```

#### 3.2.14 Argument Array Macros The following macros support the construction and release of NULL-terminated argv arrays of 2 3 strings. **Argument array extension** 4 Append a string to a NULL-terminated, argy-style array of strings. 5 6 PMIX ARGV APPEND (r, a, b); OUT r 7 Status code indicating success or failure of the operation (pmix\_status\_t) 8 9 INOUT a 10 Argument list (pointer to NULL-terminated array of strings) IN 11 Argument to append to the list (string) 12 13 This function helps the caller build the argy portion of pmix app t structure, arrays of keys for querying, or other places where argy-style string arrays are required. 14 Advice to users 15 The provided argument is copied into the destination array - thus, the source string can be free'd 16 without affecting the array once the macro has completed. Argument array prepend 17 Prepend a string to a NULL-terminated, argy-style array of strings. 18 PMIX ARGV PREPEND(r, a, b); 19 OUT r 20 Status code indicating success or failure of the operation (pmix status t) 21 22 INOUT a Argument list (pointer to NULL-terminated array of strings) 23 IN 24 25 Argument to append to the list (string) This function helps the caller build the argv portion of pmix\_app\_t structure, arrays of keys for 26 querying, or other places where argy-style string arrays are required. 27

	Advice to users
1	The provided argument is copied into the destination array - thus, the source string can be free'd
2	without affecting the array once the macro has completed.
3	Argument array extension - unique
4	Append a string to a NULL-terminated, argy-style array of strings, but only if the provided
5	argument doesn't already exist somewhere in the array.
-	
6	PMIX_ARGV_APPEND_UNIQUE(r, a, b);
	C
7	OUT r
8	Status code indicating success or failure of the operation (pmix_status_t)
9	INOUT a
10	Argument list (pointer to NULL-terminated array of strings)
11	IN b
12	Argument to append to the list (string)
13	This function helps the caller build the <b>argv</b> portion of <b>pmix_app_t</b> structure, arrays of keys for
14	querying, or other places where argy-style string arrays are required.
	Advice to users
15	The provided argument is copied into the destination array - thus, the source string can be free'd
16	without affecting the array once the macro has completed.
17	Argument array release
18	Free an argy-style array and all of the strings that it contains.
19	PMIX_ARGV_FREE(a);
	C
00	
20	IN a
21	Argument list (pointer to NULL-terminated array of strings)
22	This function releases the array and all of the strings it contains.

1 2	Argument array split Split a string into a NULL-terminated argv array.
	▼ C -
3	PMIX_ARGV_SPLIT(a, b, c);
4 5 6 7 8 9	OUT a Resulting argv-style array (char**)  IN b String to be split (char*)  IN c Delimiter character (char)
10 11	Split an input string into a NULL-terminated argv array. Do not include empty strings in the resulting array.
	Advice to users
2  3  4	All strings are inserted into the argv array by value; the newly-allocated array makes no references to the src_string argument (i.e., it can be freed after calling this function without invalidating the output argv array)
15 16	Argument array join  Join all the elements of an argy array into a single newly-allocated string.
17	PMIX_ARGV_JOIN(a, b, c);
18 19	OUT a Resulting string (char*)
20	IN b
21	Argv-style array to be joined (char**)
22 23	IN c Delimiter character (char)
24	Join all the elements of an argy array into a single newly-allocated string.

```
Argument array count
 1
               Return the length of a NULL-terminated argv array.
 2
 3
               PMIX_ARGV_COUNT(r, a);
 4
               OUT r
                    Number of strings in the array (integer)
 5
               IN
 6
 7
                    Argy-style array (char**)
 8
               Count the number of elements in an argy array
               Argument array copy
 9
               Copy an argy array, including copying all of its strings.
10
               PMIX_ARGV_COPY(a, b);
11
               OUT a
12
                    New argy-style array (char**)
13
14
               IN
15
                    Argv-style array (char**)
16
               Copy an argy array, including copying all of its strings.
    3.2.15
               Set Environment Variable
17
18
               Summary
               Set an environment variable in a NULL-terminated, env-style array.
19
20
               PMIX_SETENV(r, name, value, env);
               OUT r
21
                    Status code indicating success or failure of the operation (pmix status t)
22
23
               IN 
24
                    Argument name (string)
               IN
                    value
25
26
                    Argument value (string)
               INOUT env
27
                    Environment array to update (pointer to array of strings)
28
```

#### Description

1

3

5

6

8

9

10

11

12

13 14

15

Similar to **setenv** from the C API, this allows the caller to set an environment variable in the specified **env** array, which could then be passed to the **pmix\_app\_t** structure or any other destination.

#### Advice to users

The provided name and value are copied into the destination environment array - thus, the source strings can be free'd without affecting the array once the macro has completed.

# 3.3 Generalized Data Types Used for Packing/Unpacking

The pmix\_data\_type\_t structure is a uint16\_t type for identifying the data type for packing/unpacking purposes. New data type values introduced in this version of the Standard are shown in magenta.

# Advice to PMIx library implementers

The following constants can be used to set a variable of the type <code>pmix\_data\_type\_t</code>. Data types in the PMIx Standard are defined in terms of the C-programming language. Implementers wishing to support other languages should provide the equivalent definitions in a language-appropriate manner. Additionally, a PMIx implementation may choose to add additional types.

```
16
              PMIX UNDEF
                               Undefined.
17
                              Boolean (converted to/from native true/false) (bool).
              PMIX BOOL
                              A byte of data (uint8_t).
18
              PMIX BYTE
19
              PMIX STRING
                                NULL terminated string (char*).
20
              PMIX SIZE
                              Size size t.
21
                             Operating Process IDentifier (PID) (pid_t).
              PMIX PID
22
                             Integer (int).
              PMIX_INT
23
              PMIX INT8
                              8-byte integer (int8_t).
24
                               16-byte integer (int16 t).
              PMIX INT16
25
              PMIX INT32
                               32-byte integer (int32_t).
                               64-byte integer (int64 t).
26
              PMIX INT64
27
              PMIX UINT
                              Unsigned integer (unsigned int).
                               Unsigned 8-byte integer (uint8_t).
28
              PMIX_UINT8
                                Unsigned 16-byte integer (uint16_t).
29
              PMIX UINT16
30
              PMIX UINT32
                                Unsigned 32-byte integer (uint32_t).
                                Unsigned 64-byte integer (uint64 t).
31
              PMIX UINT64
32
                               Float (float).
              PMIX FLOAT
33
              PMIX DOUBLE
                                Double (double).
```

```
1
                                 Time value (struct timeval).
              PMIX_TIMEVAL
2
              PMIX TIME
                             Time (time t).
 3
              PMIX STATUS
                                Status code pmix_status_t.
 4
                              Value (pmix_value_t).
              PMIX VALUE
 5
              PMIX PROC
                             Process (pmix proc t).
6
              PMIX APP
                            Application context.
 7
                             Info object.
              PMIX INFO
8
                              Pointer to data.
              PMIX_PDATA
9
              PMIX_BUFFER
                                Buffer.
10
              PMIX_BYTE_OBJECT
                                      Byte object (pmix_byte_object_t).
                             Key/value pair.
11
              PMIX_KVAL
12
              PMIX PERSIST
                                 Persistance (pmix persistence t).
              PMIX POINTER
                                 Pointer to an object (void*).
13
14
              PMIX SCOPE
                              Scope (pmix scope t).
                                     Range for data (pmix_data_range_t).
15
              PMIX DATA RANGE
16
              PMIX_COMMAND
                                 PMIx command code (used internally).
17
              PMIX_INFO_DIRECTIVES
                                           Directives flag for pmix_info_t
18
                   (pmix_info_directives_t).
                                   Data type code (pmix_data_type_t).
19
              PMIX_DATA_TYPE
20
                                     Process state (pmix_proc_state_t).
              PMIX_PROC_STATE
21
              PMIX PROC INFO
                                   Process information (pmix_proc_info_t).
22
                                     Data array (pmix data array t).
              PMIX DATA ARRAY
                                   Process rank (pmix_rank_t).
23
              PMIX PROC RANK
24
              PMIX QUERY
                              Query structure (pmix_query_t).
                                             String compressed with zlib (char*).
25
              PMIX COMPRESSED STRING
              PMIX_COMPRESSED_BYTE_OBJECT
                                                   Byte object whose bytes have been compressed with
26
27
                   zlib (pmix_byte_object_t).
28
              PMIX_ALLOC_DIRECTIVE
                                           Allocation directive (pmix_alloc_directive_t).
29
              PMIX_IOF_CHANNEL
                                      Input/output forwarding channel (pmix iof channel t).
30
              PMIX ENVAR
                              Environmental variable structure (pmix envar t).
31
              PMIX COORD
                              Structure containing fabric coordinates (pmix coord t).
32
              PMIX REGATTR
                                 Structure supporting attribute registrations (pmix regattr t).
                              Regular expressions - can be a valid NULL-terminated string or an arbitrary
33
              PMIX REGEX
34
                   array of bytes.
35
              PMIX JOB STATE
                                   Job state (pmix_job_state_t).
36
              PMIX_LINK_STATE
                                     Link state (pmix_link_state_t).
              PMIX_PROC_CPUSET
37
                                      Structure containing the binding bitmap of a process
38
                   (pmix_cpuset_t).
39
              PMIX GEOMETRY
                                  Geometry structure containing the fabric coordinates of a specified
40
                   device.(pmix_geometry_t).
              PMIX DEVICE DIST
                                      Structure containing the minimum and maximum relative distance
41
42
                   from the caller to a given fabric device. (pmix device distance t).
```

1 PMIX ENDPOINT Structure containing an assigned endpoint for a given fabric device. 2 (pmix endpoint t). 3 PMIX TOPO Structure containing the topology for a given node. (pmix\_topology\_t). Bitmask containing the types of devices being referenced. 4 PMIX DEVTYPE 5 (pmix\_device\_type\_t). 6 PMIX\_LOCTYPE Bitmask describing the relative location of another process. 7 (pmix\_locality\_t). 8 PMIX\_DATA\_TYPE\_MAX A starting point for implementer-specific data types. Values above 9 this are guaranteed not to conflict with PMIx values. Definitions should always be based on the PMIX\_DATA\_TYPE\_MAX constant and not a specific value as the value of the constant 10 may change. 11

# 3.4 General Callback Functions

PMIx provides blocking and nonblocking versions of most APIs. In the nonblocking versions, a callback is activated upon completion of the operation. This section describes many of those callbacks.

# 3.4.1 Release Callback Function

(void \*cbdata);

#### Summary

13 14

15

17 18

19 20

23

24 25

26

27

28

The pmix\_release\_cbfunc\_t is used by the pmix\_modex\_cbfunc\_t and pmix\_info\_cbfunc\_t operations to indicate that the callback data may be reclaimed/freed by the caller.

# 21 PMIx v1.0 Format 22 typedef void (\*pmix\_release\_cbfunc\_t)

#### INOUT cbdata

Callback data passed to original API call (memory reference)

#### Description

Since the data is "owned" by the host server, provide a callback function to notify the host server that we are done with the data so it can be released.

# 3.4.2 Op Callback Function

```
Summarv
2
 3
               The pmix_op_cbfunc_t is used by operations that simply return a status.
               typedef void (*pmix_op_cbfunc_t)
4
 5
                    (pmix status t status, void *cbdata);
               IN
                  status
6
 7
                   Status associated with the operation (handle)
8
               IN
                   cbdata
9
                   Callback data passed to original API call (memory reference)
10
               Description
               Used by a wide range of PMIx API's including PMIx Fence nb,
11
12
               pmix_server_client_connected2_fn_t, PMIx_server_register_nspace. This
13
               callback function is used to return a status to an often nonblocking operation.
   3.4.3 Value Callback Function
               Summary
15
16
               The pmix_value_cbfunc_t is used by PMIx_Get_nb to return data.
  PMIx v1.0
               typedef void (*pmix_value_cbfunc_t)
17
18
                    (pmix_status_t status,
19
                     pmix_value_t *kv, void *cbdata);
               IN
20
                    status
21
                   Status associated with the operation (handle)
               IN
22
23
                   Key/value pair representing the data (pmix value t)
24
               IN
25
                   Callback data passed to original API call (memory reference)
               Description
26
               A callback function for calls to PMIx_Get_nb. The status indicates if the requested data was
27
28
               found or not. A pointer to the pmix_value_t structure containing the found data is returned.
29
               The pointer will be NULL if the requested data was not found.
```

# 3.4.4 Info Callback Function

```
Summarv
 3
              The pmix_info_cbfunc_t is a general information callback used by various APIs.
              typedef void (*pmix_info_cbfunc_t)
4
 5
                    (pmix_status_t status,
6
                    pmix_info_t info[], size_t ninfo,
 7
                    void *cbdata,
8
                    pmix_release_cbfunc_t release_fn,
9
                    void *release cbdata);
10
              IN
                  status
                   Status associated with the operation (pmix_status_t)
11
              IN
12
                   Array of pmix_info_t returned by the operation (pointer)
13
14
              IN
                  ninfo
15
                   Number of elements in the info array (size t)
16
              IN cbdata
                   Callback data passed to original API call (memory reference)
17
              IN release fn
18
                   Function to be called when done with the info data (function pointer)
19
20
              IN
                   release_cbdata
21
                   Callback data to be passed to release_fn (memory reference)
              Description
22
23
              The status indicates if requested data was found or not. An array of pmix info t will contain
24
              the key/value pairs.
             Handler registration callback function
    3.4.5
              Summary
26
27
              Callback function for calls to register handlers, e.g., event notification and IOF requests.
              Format
   PMIx v3.0
29
              typedef void (*pmix_hdlr_reg_cbfunc_t)
30
                    (pmix_status_t status,
                     size_t refid,
31
32
                    void *cbdata);
```

```
IN
 1
                    status
 2
                   PMIX_SUCCESS or an appropriate error constant (pmix_status_t)
 3
               IN
                   reference identifier assigned to the handler by PMIx, used to deregister the handler (size t)
 5
               IN
                    cbdata
                   object provided to the registration call (pointer)
 6
               Description
               Callback function for calls to register handlers, e.g., event notification and IOF requests.
    3.5
            PMIx Datatype Value String Representations
               Provide a string representation for several types of values. Note that the provided string is statically
10
               defined and must NOT be free'd.
11
               Summary
12
               String representation of a pmix status t.
13
  PMIx v1.0
14
               const char*
               PMIx_Error_string(pmix_status_t status);
15
               Summary
16
               String representation of a pmix_proc_state_t.
17
  PMIx v2.0
18
               const char*
               PMIx Proc state string(pmix proc state t state);
19
20
               Summary
21
               String representation of a pmix_scope_t.
  PMIx v2.0
```

const char\*

22

23

PMIx\_Scope\_string(pmix\_scope\_t scope);

```
Summary
1
2
             String representation of a pmix persistence t.
3
             const char*
             PMIx_Persistence_string(pmix_persistence_t persist);
             Summary
5
6
             String representation of a pmix_data_range_t.
  PMIx v2.0
             const char*
8
             PMIx_Data_range_string(pmix_data_range_t range);
             Summary
9
             String representation of a pmix_info_directives_t.
10
  PMIx v2.0
11
             const char*
12
             PMIx_Info_directives_string(pmix_info_directives_t directives);
             Summary
13
14
             String representation of a pmix_data_type_t.
  PMIx v2.0
             const char*
15
16
             PMIx_Data_type_string(pmix_data_type_t type);
             Summary
17
18
             String representation of a pmix_alloc_directive_t.
  PMIx v2.0
19
             const char*
20
             PMIx_Alloc_directive_string(pmix_alloc_directive_t directive);
```

```
Summary
 1
2
             String representation of a pmix iof channel t.
 3
             const char*
 4
             PMIx_IOF_channel_string(pmix_iof_channel_t channel);
             Summary
5
6
             String representation of a pmix_job_state_t.
  PMIx v4.0
             const char*
8
             PMIx_Job_state_string(pmix_job_state_t state);
             Summary
9
             String representation of a PMIx attribute.
10
  PMIx v4.0
11
             const char*
             PMIx Get_attribute_string(char *attributename);
12
13
             Summary
             Return the PMIx attribute name corresponding to the given attribute string.
14
  PMIx v4.0
             const char*
15
16
             PMIx_Get_attribute_name(char *attributestring);
             Summary
17
18
             String representation of a pmix link state t.
  PMIx v4.0
19
             const char*
20
             PMIx_Link_state_string(pmix_link_state_t state);
```

```
Summary
1
           String representation of a pmix_device_type_t.
2
3
            const char*
            PMIx_Device_type_string(pmix_device_type_t type);
```

# **CHAPTER 4**

# **Client Initialization and Finalization**

1 2 3	The PMIx library is required to be initialized and finalized around the usage of most PMIx functions or macros. The APIs that may be used outside of the initialized and finalized region are noted. All other APIs must be used inside this region.
4 5 6 7	There are three sets of initialization and finalization functions depending upon the role of the process in the PMIx Standard - those associated with the PMIx <i>client</i> are defined in this chapter. Similar functions corresponding to the roles of <i>server</i> and <i>tool</i> are defined in Chapters 16 and 17, respectively.
8 9 10 11 12	Note that a process can only call <i>one</i> of the initialization/finalization functional pairs from the set of three - e.g., a process that calls the client initialization function cannot also call the tool or server initialization functions, and must call the corresponding client finalization function. Regardless of the role assumed by the process, all processes have access to the client APIs. Thus, the <i>server</i> and <i>tool</i> roles can be considered supersets of the PMIx client.
13 <b>4.1</b> I	PMIx_Initialized
14 15 16	<b>Summary</b> Determine if the PMIx library has been initialized. This function may be used outside of the initialized and finalized region, and is usable by servers and tools in addition to clients.
17 <i>PMIx v1.0</i>	Format
18	int PMIx_Initialized(void)
19	A value of 1 (true) will be returned if the PMIx library has been initialized, and 0 (false) otherwise.  Rationale
20	The return value is an integer for historical reasons as that was the signature of prior PMI libraries.
21	Description
22	Check to see if the PMIx library has been initialized using any of the init functions: PMIx_Init,
23	PMIx_server_init, or PMIx_tool_init.

# 1 4.2 PMIx\_Get\_version

2 3 4		<b>Summary</b> Get the PMIx version information. This function may be used outside of the initialized and finalized region, and is usable by servers and tools in addition to clients.
5	PMIx v1.0	Format C
6		const char* PMIx_Get_version(void)
7 8 9		<b>Description</b> Get the PMIx version string. Note that the provided string is statically defined and must <i>not</i> be free'd.
10	4.3 P	MIx_Init
11 12		Summary Initialize the PMIx client library
13	PMIx v1.2	Format
14 15 16		<pre>pmix_status_t PMIx_Init(pmix_proc_t *proc,</pre>
17 18		INOUT proc proc structure (handle)
19		<pre>IN info Array of pmix_info_t structures (array of handles)</pre>
21 22		IN ninfo  Number of elements in the <i>info</i> array (size_t)
23		Returns <b>PMIX SUCCESS</b> or a negative value corresponding to a PMIx error constant.

 Optional Attributes
Optional / ttinbatoo

The following attributes are optional for implementers of PMIx libraries: 1 2 PMIX USOCK DISABLE "pmix.usock.disable" (bool) 3 Disable legacy UNIX socket (usock) support. If the library supports Unix socket connections, this attribute may be supported for disabling it. 4 5 PMIX\_SOCKET\_MODE "pmix.sockmode" (uint32\_t) POSIX mode t (9 bits valid). If the library supports socket connections, this attribute may 6 be supported for setting the socket mode. 7 8 PMIX SINGLE LISTENER "pmix.sing.listnr" (bool) Use only one rendezvous socket, letting priorities and/or environment parameters select the 9 active transport. If the library supports multiple methods for clients to connect to servers, 10 11 this attribute may be supported for disabling all but one of them. PMIX\_TCP\_REPORT\_URI "pmix.tcp.repuri" (char\*) 12 If provided, directs that the TCP Uniform Resource Identifier (URI) be reported and indicates 13 the desired method of reporting: '-' for stdout, '+' for stderr, or filename. If the library 14 supports TCP socket connections, this attribute may be supported for reporting the URI. 15 16 PMIX\_TCP\_IF\_INCLUDE "pmix.tcp.ifinclude" (char\*) 17 Comma-delimited list of devices and/or Classless Inter-Domain Routing (CIDR) notation to include when establishing the TCP connection. If the library supports TCP socket 18 connections, this attribute may be supported for specifying the interfaces to be used. 19 20 PMIX\_TCP\_IF\_EXCLUDE "pmix.tcp.ifexclude" (char\*) 21 Comma-delimited list of devices and/or CIDR notation to exclude when establishing the TCP connection. If the library supports TCP socket connections, this attribute may be 22 23 supported for specifying the interfaces that are *not* to be used. 24 PMIX TCP IPV4 PORT "pmix.tcp.ipv4" (int) The IPv4 port to be used.. If the library supports IPV4 connections, this attribute may be 25 supported for specifying the port to be used. 26 PMIX TCP IPV6 PORT "pmix.tcp.ipv6" (int) 27 The IPv6 port to be used. If the library supports IPV6 connections, this attribute may be 28 supported for specifying the port to be used. 29 30 PMIX\_TCP\_DISABLE\_IPV4 "pmix.tcp.disipv4" (bool) 31 Set to **true** to disable IPv4 family of addresses. If the library supports IPV4 connections, this attribute may be supported for disabling it. 32 PMIX\_TCP\_DISABLE\_IPV6 "pmix.tcp.disipv6" (bool) 33 Set to **true** to disable IPv6 family of addresses. If the library supports IPV6 connections. 34

this attribute may be supported for disabling it.

PMIX EXTERNAL PROGRESS "pmix.evext" (bool)

35

36

1	The host shall progress the PMIx library via calls to PMIx_Progress
2 3 4 5 6 7 8	PMIX_EVENT_BASE "pmix.evbase" (void*)  Pointer to an event_base to use in place of the internal progress thread. All PMIx library events are to be assigned to the provided event base. The event base <i>must</i> be compatible with the event library used by the PMIx implementation - e.g., either both the host and PMIx library must use libevent, or both must use libev. Cross-matches are unlikely to work and should be avoided - it is the responsibility of the host to ensure that the PMIx implementation supports (and was built with) the appropriate event library.
9 10	If provided, the following attributes are used by the event notification system for inter-library coordination:
11 12	PMIX_PROGRAMMING_MODEL "pmix.pgm.model" (char*) Programming model being initialized (e.g., "MPI" or "OpenMP").
13 14	<pre>PMIX_MODEL_LIBRARY_NAME "pmix.mdl.name" (char*)     Programming model implementation ID (e.g., "OpenMPI" or "MPICH").</pre>
15 16	PMIX_MODEL_LIBRARY_VERSION "pmix.mld.vrs" (char*)  Programming model version string (e.g., "2.1.1").
17 18	<pre>PMIX_THREADING_MODEL "pmix.threads" (char*) Threading model used (e.g., "pthreads").</pre>
19 20	<pre>PMIX_MODEL_NUM_THREADS "pmix.mdl.nthrds" (uint64_t) Number of active threads being used by the model.</pre>
21 22	<pre>PMIX_MODEL_NUM_CPUS "pmix.mdl.ncpu" (uint64_t) Number of cpus being used by the model.</pre>
23 24	<pre>PMIX_MODEL_CPU_TYPE "pmix.mdl.cputype" (char*) Granularity - "hwthread", "core", etc.</pre>
25 26 27 28	<pre>PMIX_MODEL_AFFINITY_POLICY "pmix.mdl.tap" (char*) Thread affinity policy - e.g.: "master" (thread co-located with master thread), "close" (thread located on cpu close to master thread), "spread" (threads load-balanced across available cpus).</pre>

#### 1 Description

2

3

5

6

7

8

9

10

11 12

13 14

15

16

17

18

19

27

29

30 31

32

33

34

Initialize the PMIx client, returning the process identifier assigned to this client's application in the provided <code>pmix\_proc\_t</code> struct. Passing a value of **NULL** for this parameter is allowed if the user wishes solely to initialize the PMIx system and does not require return of the identifier at that time.

When called, the PMIx client shall check for the required connection information of the local PMIx server and establish the connection. If the information is not found, or the server connection fails, then an appropriate error constant shall be returned.

If successful, the function shall return **PMIX\_SUCCESS** and fill the *proc* structure (if provided) with the server-assigned namespace and rank of the process within the application. In addition, all startup information provided by the resource manager shall be made available to the client process via subsequent calls to **PMIx\_Get**.

The PMIx client library shall be reference counted, and so multiple calls to **PMIx\_Init** are allowed by the standard. Thus, one way for an application process to obtain its namespace and rank is to simply call **PMIx\_Init** with a non-NULL *proc* parameter. Note that each call to **PMIx\_Init** must be balanced with a call to **PMIx\_Finalize** to maintain the reference count.

Each call to **PMIx\_Init** may contain an array of **pmix\_info\_t** structures passing directives to the PMIx client library as per the above attributes.

Multiple calls to **PMIx\_Init** shall not include conflicting directives. The **PMIx\_Init** function will return an error when directives that conflict with prior directives are encountered.

#### 4.3.1 Initialization events

- 21 The following events are typically associated with calls to **PMIx Init**:
- 22 **PMIX MODEL DECLARED** Model declared.
- 23 **PMIX MODEL RESOURCES** Resource usage by a programming model has changed.
- 24 PMIX\_OPENMP\_PARALLEL\_ENTERED An OpenMP parallel code region has been entered.
- 25 PMIX\_OPENMP\_PARALLEL\_EXITED An OpenMP parallel code region has completed.

# 6 4.3.2 Initialization attributes

The following attributes influence the behavior of **PMIx\_Init**.

## 28 4.3.2.1 Connection attributes

These attributes are used to describe a TCP socket for rendezvous with the local RM by passing them into the relevant initialization API - thus, they are not typically accessed via the **PMIx\_Get** API.

PMIX TCP REPORT URI "pmix.tcp.repuri" (char\*)

If provided, directs that the TCP URI be reported and indicates the desired method of reporting: '-' for stdout, '+' for stderr, or filename.

```
1
              PMIX_TCP_URI "pmix.tcp.uri" (char*)
2
                    The URI of the PMIx server to connect to, or a file name containing it in the form of
                    file: <name of file containing it>.
 3
 4
              PMIX TCP IF INCLUDE "pmix.tcp.ifinclude" (char*)
5
                    Comma-delimited list of devices and/or CIDR notation to include when establishing the
6
                    TCP connection.
7
              PMIX_TCP_IF_EXCLUDE "pmix.tcp.ifexclude" (char*)
                    Comma-delimited list of devices and/or CIDR notation to exclude when establishing the
8
9
                    TCP connection.
              PMIX_TCP_IPV4_PORT "pmix.tcp.ipv4" (int)
10
                    The IPv4 port to be used...
11
              PMIX_TCP_IPV6_PORT "pmix.tcp.ipv6" (int)
12
                    The IPv6 port to be used.
13
14
              PMIX_TCP_DISABLE_IPV4 "pmix.tcp.disipv4" (bool)
                    Set to true to disable IPv4 family of addresses.
15
              PMIX_TCP_DISABLE_IPV6 "pmix.tcp.disipv6" (bool)
16
                    Set to true to disable IPv6 family of addresses.
17
   4.3.2.2 Programming model attributes
18
              These attributes are associated with programming models.
19
              PMIX_PROGRAMMING_MODEL "pmix.pgm.model" (char*)
20
                    Programming model being initialized (e.g., "MPI" or "OpenMP").
21
              PMIX_MODEL_LIBRARY_NAME "pmix.mdl.name" (char*)
22
                    Programming model implementation ID (e.g., "OpenMPI" or "MPICH").
23
              PMIX_MODEL_LIBRARY_VERSION "pmix.mld.vrs" (char*)
24
                    Programming model version string (e.g., "2.1.1").
25
              PMIX_THREADING_MODEL "pmix.threads" (char*)
26
                    Threading model used (e.g., "pthreads").
27
              PMIX_MODEL_NUM_THREADS "pmix.mdl.nthrds" (uint64_t)
28
29
                    Number of active threads being used by the model.
30
              PMIX MODEL NUM CPUS "pmix.mdl.ncpu" (uint64 t)
                    Number of cpus being used by the model.
31
              PMIX MODEL CPU TYPE "pmix.mdl.cputype" (char*)
32
                    Granularity - "hwthread", "core", etc.
33
34
              PMIX MODEL PHASE NAME "pmix.mdl.phase" (char*)
                    User-assigned name for a phase in the application execution (e.g., "cfd reduction").
35
              PMIX_MODEL_PHASE_TYPE "pmix.mdl.ptype" (char*)
36
                    Type of phase being executed (e.g., "matrix multiply").
37
              PMIX MODEL AFFINITY POLICY "pmix.mdl.tap" (char*)
38
39
                    Thread affinity policy - e.g.: "master" (thread co-located with master thread), "close" (thread
40
                    located on cpu close to master thread), "spread" (threads load-balanced across available
41
                    cpus).
```

# 1 4.4 PMIx\_Finalize

2		Summary Finalize the PMIx client library.
4	PMIx v1.0	Format
5 6	PMIX VI.U	<pre>pmix_status_t PMIx_Finalize(const pmix_info_t info[], size_t ninfo)</pre>
7		IN info
8		Array of pmix_info_t structures (array of handles)
9 10		IN ninfo Number of elements in the <i>info</i> array (size_t)
11		Returns <b>PMIX_SUCCESS</b> or a negative value indicating the error.
		▼ Optional Attributes
12		The following attributes are optional for implementers of PMIx libraries:
13 14 15 16		PMIX_EMBED_BARRIER "pmix.embed.barrier" (bool)  Execute a blocking fence operation before executing the specified operation.  PMIx_Finalize does not include an internal barrier operation by default. This attribute directs PMIx_Finalize to execute a barrier as part of the finalize operation.
17 18 19 20		<b>Description</b> Decrement the PMIx client library reference count. When the reference count reaches zero, the library will finalize the PMIx client, closing the connection with the local PMIx server and releasing all internally allocated memory.
21	4.4.1	Finalize attributes
22		The following attribute influences the behavior of PMIx_Finalize.
23 24 25 26		<pre>PMIX_EMBED_BARRIER "pmix.embed.barrier" (bool)     Execute a blocking fence operation before executing the specified operation. PMIx_Finalize does not include an internal barrier operation by default. This attribute directs PMIx_Finalize to execute a barrier as part of the finalize operation.</pre>
27	4.5	PMIx_Progress
28		Summary
29		Progress the PMIx library.

1 Format C

2 void
3 PMIx\_Progress (void)

4 Description
5 Progress the PMIx library. Note that special care must be taken to avoid deadlocking in PMIx callback functions and APIs.

#### **CHAPTER 5**

1

3

5

6

7 8

9

10

27

# Synchronization and Data Access Operations

Applications may need to synchronize their operations at various points in their execution. Depending on a variety of factors (e.g., the programming model and where the synchronization point lies), the application may choose to execute the operation using PMIx. This is particularly useful in situations where communication by other means is not yet available since PMIx relies on the host environment's infrastructure for such operations.

Synchronization operations also offer an opportunity for processes to exchange data at a known point in their execution. Where required, this can include information on communication endpoints for subsequent wireup of various messaging protocols.

This chapter covers both the synchronization and data retrieval functions provided under the PMIx Standard.

# 5.1 PMIx Fence

```
Summary
12
13
               Execute a blocking barrier across the processes identified in the specified array, collecting
14
               information posted via PMIx Put as directed.
<sup>15</sup> PMIx v1.0
               Format
               pmix status t
16
               PMIx Fence(const pmix proc t procs[], size t nprocs,
17
18
                              const pmix_info_t info[], size_t ninfo);
19
               IN
                    procs
                    Array of pmix_proc_t structures (array of handles)
20
               IN
21
22
                    Number of elements in the procs array (integer)
23
               IN
                    Array of info structures (array of handles)
               IN
25
                    ninfo
26
                    Number of elements in the info array (integer)
```

Returns **PMIX SUCCESS** or a negative value indicating the error.

	collect all data posted by the participants using PMIx_Put that has been committed via PMIx_Commit, making the collection locally available to each participant at the end of the operation. By default, this will include all job-level information that was locally generated by PMIx servers unless excluded using the PMIX_COLLECT_GENERATED_JOB_INFO
PMIX	attribute.  COLLECT_GENERATED_JOB_INFO "pmix.collect.gen" (bool)  Collect all job-level information (i.e., reserved keys) that was locally generated by PMIx servers. Some job-level information (e.g., distance between processes and fabric devices) is best determined on a distributed basis as it primarily pertains to local processes. Should remote processes need to access the information, it can either be obtained collectively using the PMIx_Fence operation with this directive, or can be retrieved one peer at a time using PMIx_Get without first having performed the job-wide collection.
<b>~</b>	Optional Attributes
The fo	ollowing attributes are optional for PMIx implementations:
PMIX	ALL_CLONES_PARTICIPATE "pmix.clone.part" (bool) All clones of the calling process must participate in the collective operation.
	ollowing attributes are optional for host environments:
The fo	

#### Description

1

3

4

5

6

7

8

9

10

11

12

13

15 16

17

Passing a **NULL** pointer as the *procs* parameter indicates that the fence is to span all processes in the client's namespace. Each provided **pmix\_proc\_t** struct can pass **PMIX\_RANK\_WILDCARD** to indicate that all processes in the given namespace are participating.

The *info* array is used to pass user directives regarding the behavior of the fence operation. Note that for scalability reasons, the default behavior for **PMIx\_Fence** is to not collect data posted by the operation's participants.

#### Advice to PMIx library implementers

**PMIx\_Fence** and its non-blocking form are both *collective* operations. Accordingly, the PMIx server library is required to aggregate participation by local clients, passing the request to the host environment once all local participants have executed the API.

#### Advice to PMIx server hosts

The host will receive a single call for each collective operation. It is the responsibility of the host to identify the nodes containing participating processes, execute the collective across all participating nodes, and notify the local PMIx server library upon completion of the global collective.

# 14 5.2 PMIx\_Fence\_nb

#### Summary

Execute a nonblocking **PMIx\_Fence** across the processes identified in the specified array of processes, collecting information posted via **PMIx\_Put** as directed.

1	Format C
2 3 4 5	<pre>pmix_status_t PMIx_Fence_nb(const pmix_proc_t procs[], size_t nprocs,</pre>
6 7 8 9 10 11 12 13	IN procs Array of pmix_proc_t structures (array of handles)  IN nprocs Number of elements in the procs array (integer)  IN info Array of info structures (array of handles)  IN ninfo Number of elements in the info array (integer)  IN cbfunc
15 16 17	Callback function (function reference)  IN cbdata  Data to be passed to the callback function (memory reference)
18 19 20	A successful return indicates that the request is being processed by the host environment and the result will be returned in the provided <i>cbfunc</i> . Note that the library must not invoke the callback function prior to returning from the API. In all other cases, the <i>cbfunc</i> will <i>not</i> be called.
21	Returns PMIX_SUCCESS or one of the following error codes when the condition described occurs:
22 23 24	• PMIX_OPERATION_SUCCEEDED, indicating that the request was immediately processed and returned <i>success</i> - the <i>cbfunc</i> will <i>not</i> be called. This can occur if the collective involved only processes on the local node.
25 26	If none of the above return codes are appropriate, then an implementation must return either a general PMIx error code or an implementation defined error code as described in Section 3.1.1.
27	The callback function <i>cbfunc</i> is only called when <b>PMIX_SUCCESS</b> is returned.
	Required Attributes
28	The following attributes are required to be supported by all PMIx libraries:
29 30 31 32 33 34	PMIX_COLLECT_DATA "pmix.collect" (bool)  Collect all data posted by the participants using PMIx_Put that has been committed via PMIx_Commit, making the collection locally available to each participant at the end of the operation. By default, this will include all job-level information that was locally generated by PMIx servers unless excluded using the PMIX_COLLECT_GENERATED_JOB_INFO attribute.
35	<pre>PMIX_COLLECT_GENERATED_JOB_INFO "pmix.collect.gen" (bool)</pre>

1 Collect all job-level information (i.e., reserved keys) that was locally generated by PMIx 2 servers. Some job-level information (e.g., distance between processes and fabric devices) is 3 best determined on a distributed basis as it primarily pertains to local processes. Should 4 remote processes need to access the information, it can either be obtained collectively using 5 the **PMIx** Fence operation with this directive, or can be retrieved one peer at a time using 6 **PMIx\_Get** without first having performed the job-wide collection. **Optional Attributes** 7 The following attributes are optional for PMIx implementations: 8 PMIX ALL CLONES PARTICIPATE "pmix.clone.part" (bool) 9 All *clones* of the calling process must participate in the collective operation. 10 The following attributes are optional for host environments that support this operation: PMIX\_TIMEOUT "pmix.timeout" (int) 11 12 Time in seconds before the specified operation should time out (zero indicating infinite) and 13 return the PMIX ERR TIMEOUT error. Care should be taken to avoid race conditions 14 caused by multiple layers (client, server, and host) simultaneously timing the operation. Description 15 Nonblocking version of the PMIx\_Fence routine. See the PMIx\_Fence description for further 16 details. 17 5.2.1 Fence-related attributes 19 The following attributes are defined specifically to support the fence operation: PMIX COLLECT DATA "pmix.collect" (bool) 20 21 Collect all data posted by the participants using **PMIx Put** that has been committed via 22 **PMIx** Commit, making the collection locally available to each participant at the end of the 23 operation. By default, this will include all job-level information that was locally generated 24 by PMIx servers unless excluded using the PMIX COLLECT GENERATED JOB INFO 25 attribute. PMIX\_COLLECT\_GENERATED\_JOB\_INFO "pmix.collect.gen" (bool) 26 27 Collect all job-level information (i.e., reserved keys) that was locally generated by PMIx servers. Some job-level information (e.g., distance between processes and fabric devices) is 28 29 best determined on a distributed basis as it primarily pertains to local processes. Should 30 remote processes need to access the information, it can either be obtained collectively using the **PMIx** Fence operation with this directive, or can be retrieved one peer at a time using 31

32

33 34 **PMIx\_Get** without first having performed the job-wide collection.

All *clones* of the calling process must participate in the collective operation.

PMIX ALL CLONES PARTICIPATE "pmix.clone.part" (bool)

# 1 5.3 PMIx\_Get

2	Summary
3	Retrieve a key/value pair from the client's namespace.
4 PMIx	Format C
5 6 7 8	<pre>pmix_status_t PMIx_Get(const pmix_proc_t *proc, const pmix_key_t key,</pre>
10 11 12	Process identifier - a <b>NULL</b> value may be used in place of the caller's ID (handle)  IN key  Key to retrieve (pmix_key_t)
13 14 15 16 17	IN info Array of info structures (array of handles)  IN ninfo Number of elements in the <i>info</i> array (integer)  OUT val value (handle)
19 20	A successful return indicates that the requested data has been returned in the manner requested (.e.g., in a provided static memory location ).
21	Returns PMIX_SUCCESS or one of the following error codes when the condition described occurs:
22 23 24	<ul> <li>PMIX_ERR_BAD_PARAM A bad parameter was passed to the function call - e.g., the request included the PMIX_GET_STATIC_VALUES directive, but the provided storage location was NULL</li> </ul>
25 26	• PMIX_ERR_EXISTS_OUTSIDE_SCOPE The requested key exists, but was posted in a <i>scope</i> (see Section 7.1.1.1) that does not include the requester.
27	• PMIX_ERR_NOT_FOUND The requested data was not available.
28 29	If none of the above return codes are appropriate, then an implementation must return either a general PMIx error code or an implementation defined error code as described in Section 3.1.1.  Required Attributes
30	The following attributes are required to be supported by all PMIx libraries:
31 32 33	PMIX_OPTIONAL "pmix.optional" (bool)  Look only in the client's local data store for the requested value - do not request data from the PMIx server if not found.

1 2 3	PMIX_IMMEDIATE "pmix.immediate" (bool)  Specified operation should immediately return an error from the PMIx server if the requested data cannot be found - do not request it from the host RM.
4 5	PMIX_DATA_SCOPE "pmix.scope" (pmix_scope_t) Scope of the data to be searched in a PMIx_Get call.
6 7	PMIX_SESSION_INFO "pmix.ssn.info" (bool)  Return information regarding the session realm of the target process.
8 9 0	<pre>PMIX_JOB_INFO "pmix.job.info" (bool) Return information regarding the job realm corresponding to the namespace in the target process' identifier.</pre>
1 2 3 4 5 6 7	PMIX_APP_INFO "pmix.app.info" (bool)  Return information regarding the application realm to which the target process belongs - the namespace of the target process serves to identify the job containing the target application. If information about an application other than the one containing the target process is desired, then the attribute array must contain a PMIX_APPNUM attribute identifying the desired target application. This is useful in cases where there are multiple applications and the mapping of processes to applications is unclear.
8 9 20 21 22 23 24	PMIX_NODE_INFO "pmix.node.info" (bool)  Return information from the node realm regarding the node upon which the specified process is executing. If information about a node other than the one containing the specified process is desired, then the attribute array must also contain either the PMIX_NODEID or PMIX_HOSTNAME attribute identifying the desired target. This is useful for requesting information about a specific node even if the identity of processes running on that node are not known.
25 26 27 28	<pre>PMIX_GET_STATIC_VALUES "pmix.get.static" (bool)    Request that the data be returned in the provided storage location. The caller is responsible for destructing the pmix_value_t using the PMIX_VALUE_DESTRUCT macro when done.</pre>
9 80 81	<pre>PMIX_GET_POINTER_VALUES "pmix.get.pntrs" (bool) Request that any pointers in the returned value point directly to values in the key-value store. The user must not release any returned data pointers.</pre>
92 93 94 95 96 97	PMIX_GET_REFRESH_CACHE "pmix.get.refresh" (bool)  When retrieving data for a remote process, refresh the existing local data cache for the process in case new values have been put and committed by the process since the last refresh. Local process information is assumed to be automatically updated upon posting by the process. A NULL key will cause all values associated with the process to be refreshed otherwise, only the indicated key will be updated. A process rank of PMIX_RANK_WILDCARD can be used to update job-related information in dynamic

environments. The user is responsible for subsequently updating refreshed values they may 1 2 have cached in their own local memory. Optional Attributes 3 The following attributes are optional for host environments: 4 PMIX TIMEOUT "pmix.timeout" (int) Time in seconds before the specified operation should time out (zero indicating infinite) and 5 return the PMIX ERR TIMEOUT error. Care should be taken to avoid race conditions 6 7 caused by multiple layers (client, server, and host) simultaneously timing the operation. **Description** 8 Retrieve information for the specified key associated with the process identified in the given 9 pmix\_proc\_t. See Chapters 6 and 7 for details on rules governing retrieval of information. 10 Information will be returned according to provided directives: 11 • In the absence of any directive, the returned **pmix\_value\_t** shall be an allocated memory 12 object. The caller is responsible for releasing the object when done. 13 • If PMIX GET POINTER\_VALUES is given, then the function shall return a pointer to a 14 pmix value t in the PMIx library's memory that contains the requested information. 15 • If PMIX GET STATIC VALUES is given, then the function shall return the information in the 16 17 provided pmix value t pointer. In this case, the caller must provide storage for the structure 18 and pass the pointer to that storage in the val parameter. If the implementation cannot return a static value, then the call to PMIx Get must return the PMIX ERR NOT SUPPORTED status. 19 20 This is a blocking operation - the caller will block until the retrieval rules of Chapters 6 or 7 are met. 21 The *info* array is used to pass user directives regarding the get operation.

# 2 5.3.1 PMIx\_Get\_nb

23

24

#### Summary

Nonblocking **PMIx\_Get** operation.

1	Format C
2	pmix_status_t
3	PMIx_Get_nb(const pmix_proc_t *proc, const char key[],
4	<pre>const pmix_info_t info[], size_t ninfo,</pre>
5	<pre>pmix_value_cbfunc_t cbfunc, void *cbdata);</pre>
	C
6	IN proc
7	Process identifier - a <b>NULL</b> value may be used in place of the caller's ID (handle)
8	IN key
9	Key to retrieve (string)
0	IN info
1	Array of info structures (array of handles)
2	IN ninfo
3	Number of elements in the <i>info</i> array (integer)
4	IN cbfunc
5	Callback function (function reference)
6	IN cbdata
7	Data to be passed to the callback function (memory reference)
8	A successful return indicates that the request is being processed by the host environment and the
9	result will be returned in the provided <i>cbfunc</i> . Note that the library must not invoke the callback
20	function prior to returning from the API. In all other cases, the <i>cbfunc</i> will <i>not</i> be called.
21	The callback function <i>cbfunc</i> is only called when <b>PMIX_SUCCESS</b> is returned.
22	If executed, the status returned in the provided callback function will be one of the following
 !3	constants:
24	• PMIX_SUCCESS The requested data has been returned.
25	• PMIX_ERR_EXISTS_OUTSIDE_SCOPE The requested key exists, but was posted in a <i>scope</i>
26	(see Section 7.1.1.1) that does not include the requester.
27	• PMIX_ERR_NOT_FOUND The requested data was not available.
28	• a non-zero PMIx error constant indicating a reason for the request's failure.
	Required Attributes
29	The following attributes are required to be supported by all PMIx libraries:
30	PMIX_OPTIONAL "pmix.optional" (bool)
31	Look only in the client's local data store for the requested value - do not request data from
12	the PMIx server if not found.
12	DMIX IMMEDIATE "pmix immediate" (beel)

Specified operation should immediately return an error from the PMIx server if the requested data cannot be found - do not request it from the host RM.

PMIX\_DATA\_SCOPE "pmix.scope" (pmix\_scope\_t)

# Scope of the data to be searched in a **PMIx\_Get** call.

# PMIX\_SESSION\_INFO "pmix.ssn.info" (bool) Return information regarding the session realm of the target process.

#### PMIX\_JOB\_INFO "pmix.job.info" (bool)

Return information regarding the job realm corresponding to the namespace in the target process' identifier.

#### PMIX\_APP\_INFO "pmix.app.info" (bool)

Return information regarding the application realm to which the target process belongs - the namespace of the target process serves to identify the job containing the target application. If information about an application other than the one containing the target process is desired, then the attribute array must contain a **PMIX\_APPNUM** attribute identifying the desired target application. This is useful in cases where there are multiple applications and the mapping of processes to applications is unclear.

#### PMIX\_NODE\_INFO "pmix.node.info" (bool)

Return information from the node realm regarding the node upon which the specified process is executing. If information about a node other than the one containing the specified process is desired, then the attribute array must also contain either the <code>PMIX\_NODEID</code> or <code>PMIX\_HOSTNAME</code> attribute identifying the desired target. This is useful for requesting information about a specific node even if the identity of processes running on that node are not known.

#### PMIX\_GET\_POINTER\_VALUES "pmix.get.pntrs" (bool)

Request that any pointers in the returned value point directly to values in the key-value store. The user *must not* release any returned data pointers.

#### PMIX\_GET\_REFRESH\_CACHE "pmix.get.refresh" (bool)

When retrieving data for a remote process, refresh the existing local data cache for the process in case new values have been put and committed by the process since the last refresh. Local process information is assumed to be automatically updated upon posting by the process. A NULL key will cause all values associated with the process to be refreshed - otherwise, only the indicated key will be updated. A process rank of PMIX\_RANK\_WILDCARD can be used to update job-related information in dynamic environments. The user is responsible for subsequently updating refreshed values they may have cached in their own local memory.

The following attributes are required for host environments that support this operation:

```
PMIX WAIT "pmix.wait" (int)
```

Caller requests that the PMIx server wait until at least the specified number of values are 1 found (a value of zero indicates all and is the default). 2 Optional Attributes The following attributes are optional for host environments that support this operation: 3 PMIX\_TIMEOUT "pmix.timeout" (int) 4 Time in seconds before the specified operation should time out (zero indicating infinite) and 5 return the PMIX ERR TIMEOUT error. Care should be taken to avoid race conditions 6 caused by multiple layers (client, server, and host) simultaneously timing the operation. 7 **Description** 8 9 The callback function will be executed once the retrieval rules of Chapters 6 or 7 are met. See PMIx Get for a full description. Note that the non-blocking form of this function cannot support 10 the PMIX GET STATIC VALUES attribute as the user cannot pass in the required pointer to 11 12 storage for the result. Retrieval attributes 5.3.2 14 The following attributes are defined for use by retrieval APIs: 15 PMIX OPTIONAL "pmix.optional" (bool) Look only in the client's local data store for the requested value - do not request data from 16 17 the PMIx server if not found. 18 PMIX IMMEDIATE "pmix.immediate" (bool) Specified operation should immediately return an error from the PMIx server if the requested 19 20 data cannot be found - do not request it from the host RM. PMIX GET POINTER VALUES "pmix.get.pntrs" (bool) 21 22 Request that any pointers in the returned value point directly to values in the key-value store. The user *must not* release any returned data pointers. 23 PMIX GET STATIC VALUES "pmix.get.static" (bool) 24 25 Request that the data be returned in the provided storage location. The caller is responsible 26 for destructing the pmix value t using the PMIX VALUE DESTRUCT macro when 27 PMIX GET REFRESH CACHE "pmix.get.refresh" (bool) 28

1 When retrieving data for a remote process, refresh the existing local data cache for the 2 process in case new values have been put and committed by the process since the last refresh. 3 Local process information is assumed to be automatically updated upon posting by the 4 process. A **NULL** key will cause all values associated with the process to be refreshed -5 otherwise, only the indicated key will be updated. A process rank of 6 PMIX RANK WILDCARD can be used to update job-related information in dynamic 7 environments. The user is responsible for subsequently updating refreshed values they may 8 have cached in their own local memory. 9 PMIX DATA SCOPE "pmix.scope" (pmix scope t)

Scope of the data to be searched in a **PMIx Get** call.

PMIX TIMEOUT "pmix.timeout" (int)

Time in seconds before the specified operation should time out (zero indicating infinite) and return the PMIX ERR TIMEOUT error. Care should be taken to avoid race conditions caused by multiple layers (client, server, and host) simultaneously timing the operation.

PMIX WAIT "pmix.wait" (int)

Caller requests that the PMIx server wait until at least the specified number of values are found (a value of zero indicates all and is the default).

#### Query 5.4

10 11

12 13

14 15

16

17

19

20

21

22

23 24

25

26

27

28 29

30

31

32 33

34

35

36 37

38 39

40

As the level of interaction between applications and the host SMS grows, so too does the need for the application to query the SMS regarding its capabilities and state information. PMIx provides a generalized query interface for this purpose, along with a set of standardized attribute keys to support a range of requests. This includes requests to determine the status of scheduling queues and active allocations, the scope of API and attribute support offered by the SMS, namespaces of active jobs, location and information about a job's processes, and information regarding available resources.

An example use-case for the **PMIx Query info nb** API is to ensure clean job completion. Time-shared systems frequently impose maximum run times when assigning jobs to resource allocations. To shut down gracefully (e.g., to write a checkpoint before termination) it is necessary for an application to periodically query the resource manager for the time remaining in its allocation. This is especially true on systems for which allocation times may be shortened or lengthened from the original time limit. Many resource managers provide APIs to dynamically obtain this information, but each API is specific to the resource manager.

PMIx supports this use-case by defining an attribute key (PMIX TIME REMAINING) that can be used with the PMIx Query info nb interface to obtain the number of seconds remaining in the current job allocation. Note that one could alternatively use the PMIx Register event handler API to register for an event indicating incipient job termination, and then use the **PMIx Job control** nb API to request that the host SMS generate an event a specified amount of time prior to reaching the maximum run time. PMIx provides such alternate methods as a means of maximizing the probability of a host system supporting at least one method by which the application can obtain the desired service.

The following APIs support query of various session and environment values.

# 2 5.4.1 PMIx\_Resolve\_peers

#### Summary

1

10

11 12

13 14

15

16 17

18

19 20

21 22

23

24

26 27 Obtain the array of processes within the specified namespace that are executing on a given node.

#### IN nodename

Name of the node to query - **NULL** can be used to denote the current local node (string)

#### IN nspace

namespace (string)

#### OUT procs

Array of process structures (array of handles)

#### OUT nprocs

Number of elements in the *procs* array (integer)

Returns **PMIX\_SUCCESS** or a negative value indicating the error.

#### Description

Given a *nodename*, return the array of processes within the specified *nspace* that are executing on that node. If the *nspace* is **NULL**, then all processes on the node will be returned. If the specified node does not currently host any processes, then the returned array will be **NULL**, and *nprocs* will be zero. The caller is responsible for releasing the *procs* array when done with it. The **PMIX\_PROC\_FREE** macro is provided for this purpose.

## 5.4.2 PMIx Resolve nodes

#### Summary

Return a list of nodes hosting processes within the given namespace.

```
Format
 1
 2
               pmix status t
 3
               PMIx_Resolve_nodes(const char *nspace, char **nodelist);
               IN
4
                    nspace
                    Namespace (string)
 5
               OUT nodelist
6
                    Comma-delimited list of nodenames (string)
 7
8
               Returns PMIX_SUCCESS or a negative value indicating the error.
               Description
9
10
               Given a nspace, return the list of nodes hosting processes within that namespace. The returned
11
               string will contain a comma-delimited list of nodenames. The caller is responsible for releasing the
12
               string when done with it.
    5.4.3
             PMIx Query info
14
               Summary
15
               Query information about the system in general.
               Format
   PMIx v4.0
17
               pmix_status_t
18
               PMIx_Query_info(pmix_query_t queries[], size_t nqueries,
19
                                    pmix_info_t *info[], size_t *ninfo);
20
               IN
                    queries
                    Array of query structures (array of handles)
21
22
               IN
                    nqueries
23
                    Number of elements in the queries array (integer)
24
               INOUT info
25
                    Address where a pointer to an array of pmix_info_t containing the results of the query can
                    be returned (memory reference)
26
               INOUT ninfo
27
28
                    Address where the number of elements in info can be returned (handle)
               A successful return indicates that all data was found and has been returned.
29
30
               Returns PMIX SUCCESS or one of the following error codes when the condition described occurs:
               • PMIX ERR NOT FOUND None of the requested data was available.
31
```

• PMIX\_ERR\_PARTIAL\_SUCCESS Some of the requested data was found. The *info* array shall 1 2 contain an element for each query key that returned a value. 3 If none of the above return codes are appropriate, then an implementation must return either a 4 general PMIx error code or an implementation defined error code as described in Section 3.1.1. If a value other than PMIX SUCCESS or PMIX ERR PARTIAL SUCCESS is returned, the info 5 array shall be **NULL** and *ninfo* zero. 6 Required Attributes PMIx libraries and host environments that support this API are required to support the following 7 8 attributes: PMIX\_QUERY\_REFRESH\_CACHE "pmix.qry.rfsh" (bool) 9 Retrieve updated information from server. NO QUALIFIERS. 10 PMIX\_SESSION\_INFO "pmix.ssn.info" (bool) 11 12 Return information regarding the session realm of the target process. PMIX\_JOB\_INFO "pmix.job.info" (bool) 13 Return information regarding the job realm corresponding to the namespace in the target 14 process' identifier. 15 PMIX\_APP\_INFO "pmix.app.info" (bool) 16 Return information regarding the application realm to which the target process belongs - the 17 namespace of the target process serves to identify the job containing the target application. If 18 19 information about an application other than the one containing the target process is desired, then the attribute array must contain a **PMIX APPNUM** attribute identifying the desired 20 target application. This is useful in cases where there are multiple applications and the 21 mapping of processes to applications is unclear. 22 23 PMIX NODE INFO "pmix.node.info" (bool) Return information from the node realm regarding the node upon which the specified 24 process is executing. If information about a node other than the one containing the specified 25 26 process is desired, then the attribute array must also contain either the PMIX NODEID or **PMIX HOSTNAME** attribute identifying the desired target. This is useful for requesting 27 information about a specific node even if the identity of processes running on that node are 28 not known... 29 30 PMIX PROC INFO "pmix.proc.info" (bool) Return information regarding the target process. This attribute is technically not required as 31

the **PMIx** Get API specifically identifies the target process in its parameters. However, it is

PMIX\_PROCID "pmix.procid" (pmix\_proc\_t)

included here for completeness.

32

33

34

 Process identifier. Used as a key in **PMIx\_Get** to retrieve the caller's own process identifier in a portion of the program that doesn't have access to the memory location in which it was originally stored (e.g., due to a call to **PMIx\_Init**). The process identifier in the **PMIx\_Get** call is ignored in this instance. In this context, specifies the process ID whose information is being requested - e.g., a query asking for the **pmix\_proc\_info\_t** of a specified process. Only required when the request is for information on a specific process.

#### PMIX\_NSPACE "pmix.nspace" (char\*)

Namespace of the job - may be a numerical value expressed as a string, but is often an alphanumeric string carrying information solely of use to the system. Required to be unique within the scope of the host environment. Specifies the namespace of the process whose information is being requested. Must be accompanied by the PMIX\_RANK attribute. Only required when the request is for information on a specific process.

#### PMIX\_RANK "pmix.rank" (pmix\_rank\_t)

Process rank within the job, starting from zero. Specifies the rank of the process whose information is being requested. Must be accompanied by the **PMIX\_NSPACE** attribute. Only required when the request is for information on a specific process.

#### PMIX\_QUERY\_ATTRIBUTE\_SUPPORT "pmix.qry.attrs" (bool)

Query list of supported attributes for specified APIs. REQUIRED QUALIFIERS: one or more of PMIX\_CLIENT\_FUNCTIONS, PMIX\_SERVER\_FUNCTIONS, PMIX\_TOOL\_FUNCTIONS, and PMIX\_HOST\_FUNCTIONS.

# PMIX\_CLIENT\_ATTRIBUTES "pmix.client.attrs" (bool)

Request attributes supported by the PMIx client library.

# PMIX\_SERVER\_ATTRIBUTES "pmix.srvr.attrs" (bool)

Request attributes supported by the PMIx server library.

#### PMIX\_HOST\_ATTRIBUTES "pmix.host.attrs" (bool)

Request attributes supported by the host environment.

#### PMIX\_TOOL\_ATTRIBUTES "pmix.setup.env" (bool)

Request attributes supported by the PMIx tool library functions.

Note that inclusion of both the PMIX\_PROCID directive and either the PMIX\_NSPACE or the PMIX\_RANK attribute will return a PMIX\_ERR\_BAD\_PARAM result, and that the inclusion of a process identifier must apply to all keys in that pmix\_query\_t. Queries for information on multiple specific processes therefore requires submitting multiple pmix\_query\_t structures, each referencing one process.

PMIx libraries are not required to directly support any other attributes for this function. However, all provided attributes must be passed to the host SMS daemon for processing. The PMIx library is required to add the PMIX\_USERID and the PMIX\_GRPID attributes of the client process making the request.

	▼ Optional Attributes
4	·
1	The following attributes are optional for host environments that support this operation:
2 3	PMIX_QUERY_NAMESPACES "pmix.qry.ns" (char*) Request a comma-delimited list of active namespaces. NO QUALIFIERS.
4 5 6	<pre>PMIX_QUERY_JOB_STATUS "pmix.qry.jst" (pmix_status_t) Status of a specified, currently executing job. REQUIRED QUALIFIER: PMIX_NSPACE indicating the namespace whose status is being queried.</pre>
7 8	PMIX_QUERY_QUEUE_LIST "pmix.qry.qlst" (char*) Request a comma-delimited list of scheduler queues. NO QUALIFIERS.
9 10 11 12	PMIX_QUERY_QUEUE_STATUS "pmix.qry.qst" (char*)  Returns status of a specified scheduler queue, expressed as a string. OPTIONAL QUALIFIERS: PMIX_ALLOC_QUEUE naming specific queue whose status is being requested.
13 14 15 16	PMIX_QUERY_PROC_TABLE "pmix.qry.ptable" (char*)  Returns a (pmix_data_array_t) array of pmix_proc_info_t, one entry for each process in the specified namespace, ordered by process job rank. REQUIRED QUALIFIER: PMIX_NSPACE indicating the namespace whose process table is being queried.
17 18 19 20 21 22 23	PMIX_QUERY_LOCAL_PROC_TABLE "pmix.qry.lptable" (char*)  Returns a (pmix_data_array_t) array of pmix_proc_info_t, one entry for each process in the specified namespace executing on the same node as the requester, ordered by process job rank. REQUIRED QUALIFIER: PMIX_NSPACE indicating the namespace whose local process table is being queried. OPTIONAL QUALIFIER: PMIX_HOSTNAME indicating the host whose local process table is being queried. By default, the query assumes that the host upon which the request was made is to be used.
24 25	PMIX_QUERY_SPAWN_SUPPORT "pmix.qry.spawn" (bool)  Return a comma-delimited list of supported spawn attributes. NO QUALIFIERS.
26 27	<pre>PMIX_QUERY_DEBUG_SUPPORT "pmix.qry.debug" (bool) Return a comma-delimited list of supported debug attributes. NO QUALIFIERS.</pre>
28 29 30 31	PMIX_QUERY_MEMORY_USAGE "pmix.qry.mem" (bool)  Return information on memory usage for the processes indicated in the qualifiers.  OPTIONAL QUALIFIERS: PMIX_NSPACE and PMIX_RANK, or PMIX_PROCID of specific process(es) whose memory usage is being requested.
32 33	PMIX_QUERY_REPORT_AVG "pmix.qry.avg" (bool)  Report only average values for sampled information. NO QUALIFIERS.

36 PMIX\_QUERY\_ALLOC\_STATUS "pmix.query.alloc" (char\*)

PMIX\_QUERY\_REPORT\_MINMAX "pmix.qry.minmax" (bool)

Report minimum and maximum values. NO QUALIFIERS.

34

35

1	String identifier of the allocation whose status is being requested. NO QUALIFIERS.
2 3 4 5	PMIX_TIME_REMAINING "pmix.time.remaining" (char*)  Query number of seconds (uint32_t) remaining in allocation for the specified namespace.  OPTIONAL QUALIFIERS: PMIX_NSPACE of the namespace whose info is being requested (defaults to allocation containing the caller).
6 7 8	PMIX_SERVER_URI "pmix.srvr.uri" (char*)  URI of the PMIx server to be contacted. Requests the URI of the specified PMIx server's PMIx connection. Defaults to requesting the information for the local PMIx server.
9 10 11	PMIX_CLIENT_AVG_MEMORY "pmix.cl.mem.avg" (float)  Average Megabytes of memory used by client processes on node. OPTIONAL  QUALIFERS: PMIX_HOSTNAME or PMIX_NODEID (defaults to caller's node).
12 13 14	PMIX_DAEMON_MEMORY "pmix.dmn.mem" (float)  Megabytes of memory currently used by the RM daemon on the node. OPTIONAL QUALIFERS: PMIX_HOSTNAME or PMIX_NODEID (defaults to caller's node).
15 16	<pre>PMIX_QUERY_AUTHORIZATIONS "pmix.qry.auths" (bool) Return operations the PMIx tool is authorized to perform. NO QUALIFIERS.</pre>
17 18	PMIX_PROC_PID "pmix.ppid" (pid_t) Operating system PID of specified process.
19 20 21	<pre>PMIX_PROC_STATE_STATUS "pmix.proc.state" (pmix_proc_state_t) State of the specified process as of the last report - may not be the actual current state based on update rate.</pre>

### **Description**

Query information about the system in general. This can include a list of active namespaces, fabric topology, etc. Also can be used to query node-specific info such as the list of peers executing on a given node. The host environment is responsible for exercising appropriate access control on the information.

The returned *status* indicates if requested data was found or not. The returned *info* array will contain a **PMIX\_QUERY\_RESULTS** element for each query of the *queries* array. If qualifiers were included in the query, then the first element of each results array shall contain the **PMIX\_QUERY\_QUALIFIERS** key with a **pmix\_data\_array\_t** containing the qualifiers. The remaining **pmix\_info\_t** shall contain the results of the query, one entry for each key that was found. Note that duplicate keys in the *queries* array shall result in duplicate responses within the constraints of the accompanying qualifiers. The caller is responsible for releasing the returned array.

#### Advice to PMIx library implementers –

Information returned from PMIx\_Query\_info shall be locally cached so that retrieval by subsequent calls to PMIx\_Get, PMIx\_Query\_info, or PMIx\_Query\_info\_nb can succeed with minimal overhead. The local cache shall be checked prior to querying the PMIx server and/or the host environment. Queries that include the PMIX\_QUERY\_REFRESH\_CACHE attribute shall bypass the local cache and retrieve a new value for the query, refreshing the values in the cache upon return.

# 5.4.4 PMIx Query info nb

#### Summary

Query information about the system in general.

# $^{10}$ PMIx v2.0

1

2

4

5

6

8 9

11

12

13

14

15 16

17

18

19 20

21 22

23

24

25 26

27

28

29

30

# Format

pmix status t

PMIx\_Query\_info\_nb(pmix\_query\_t queries[], size\_t nqueries,

pmix\_info\_cbfunc\_t cbfunc, void \*cbdata);

#### IN queries

Array of query structures (array of handles)

#### IN nqueries

Number of elements in the *queries* array (integer)

#### IN cbfunc

Callback function pmix\_info\_cbfunc\_t (function reference)

#### IN cbdata

Data to be passed to the callback function (memory reference)

A successful return indicates that the request has been accepted for processing. The provided callback function will only be executed upon successful return of the operation. Note that the library must not invoke the callback function prior to returning from the API.

Returns **PMIX\_SUCCESS** or a negative value indicating the error.

If executed, the status returned in the provided callback function will be one of the following constants:

- PMIX SUCCESS All data was found and has been returned.
- PMIX\_ERR\_NOT\_FOUND None of the requested data was available. The *info* array will be NULL and *ninfo* zero.

1 2	• PMIX_ERR_PARTIAL_SUCCESS Some of the requested data was found. The <i>info</i> array shall contain an element for each query key that returned a value.
3 4	• PMIX_ERR_NOT_SUPPORTED The host RM does not support this function. The <i>info</i> array will be NULL and <i>ninfo</i> zero.
5 6	• a non-zero PMIx error constant indicating a reason for the request's failure. The <i>info</i> array will be <b>NULL</b> and <i>ninfo</i> zero.
	▼ Required Attributes
7 8	PMIx libraries and host environments that support this API are required to support the following attributes:
9 0	PMIX_QUERY_REFRESH_CACHE "pmix.qry.rfsh" (bool) Retrieve updated information from server. NO QUALIFIERS.
1 2	PMIX_SESSION_INFO "pmix.ssn.info" (bool)  Return information regarding the session realm of the target process.
3 4 5	<pre>PMIX_JOB_INFO "pmix.job.info" (bool) Return information regarding the job realm corresponding to the namespace in the target process' identifier.</pre>
6 7 8 9 0 1	PMIX_APP_INFO "pmix.app.info" (bool)  Return information regarding the application realm to which the target process belongs - the namespace of the target process serves to identify the job containing the target application. If information about an application other than the one containing the target process is desired, then the attribute array must contain a PMIX_APPNUM attribute identifying the desired target application. This is useful in cases where there are multiple applications and the mapping of processes to applications is unclear.
3 4 5 6 7 8	PMIX_NODE_INFO "pmix.node.info" (bool)  Return information from the node realm regarding the node upon which the specified process is executing. If information about a node other than the one containing the specified process is desired, then the attribute array must also contain either the PMIX_NODEID or PMIX_HOSTNAME attribute identifying the desired target. This is useful for requesting information about a specific node even if the identity of processes running on that node are not known
0 1 2 3	PMIX_PROC_INFO "pmix.proc.info" (bool)  Return information regarding the target process. This attribute is technically not required as the PMIx_Get API specifically identifies the target process in its parameters. However, it is included here for completeness.
4	<pre>PMIX_PROCID "pmix.procid" (pmix_proc_t)</pre>

Process identifier. Used as a key in **PMIx\_Get** to retrieve the caller's own process identifier in a portion of the program that doesn't have access to the memory location in which it was originally stored (e.g., due to a call to **PMIx\_Init**). The process identifier in the **PMIx\_Get** call is ignored in this instance. In this context, specifies the process ID whose information is being requested - e.g., a query asking for the **pmix\_proc\_info\_t** of a specified process. Only required when the request is for information on a specific process.

#### PMIX NSPACE "pmix.nspace" (char\*)

Namespace of the job - may be a numerical value expressed as a string, but is often an alphanumeric string carrying information solely of use to the system. Required to be unique within the scope of the host environment. Specifies the namespace of the process whose information is being requested. Must be accompanied by the PMIX\_RANK attribute. Only required when the request is for information on a specific process.

#### PMIX\_RANK "pmix.rank" (pmix\_rank\_t)

Process rank within the job, starting from zero. Specifies the rank of the process whose information is being requested. Must be accompanied by the **PMIX\_NSPACE** attribute. Only required when the request is for information on a specific process.

#### PMIX\_QUERY\_ATTRIBUTE\_SUPPORT "pmix.qry.attrs" (bool)

Query list of supported attributes for specified APIs. REQUIRED QUALIFIERS: one or more of PMIX\_CLIENT\_FUNCTIONS, PMIX\_SERVER\_FUNCTIONS, PMIX\_TOOL\_FUNCTIONS, and PMIX\_HOST\_FUNCTIONS.

# PMIX\_CLIENT\_ATTRIBUTES "pmix.client.attrs" (bool)

Request attributes supported by the PMIx client library.

# PMIX\_SERVER\_ATTRIBUTES "pmix.srvr.attrs" (bool)

Request attributes supported by the PMIx server library.

#### PMIX\_HOST\_ATTRIBUTES "pmix.host.attrs" (bool)

Request attributes supported by the host environment.

#### PMIX\_TOOL\_ATTRIBUTES "pmix.setup.env" (bool)

Request attributes supported by the PMIx tool library functions.

Note that inclusion of both the PMIX\_PROCID directive and either the PMIX\_NSPACE or the PMIX\_RANK attribute will return a PMIX\_ERR\_BAD\_PARAM result, and that the inclusion of a process identifier must apply to all keys in that pmix\_query\_t. Queries for information on multiple specific processes therefore requires submitting multiple pmix\_query\_t structures, each referencing one process.

PMIx libraries are not required to directly support any other attributes for this function. However, all provided attributes must be passed to the host SMS daemon for processing. The PMIx library is required to add the PMIX\_USERID and the PMIX\_GRPID attributes of the client process making the request.

	→ Optional Attributes
1	The following attributes are optional for host environments that support this operation:
2	PMIX_QUERY_NAMESPACES "pmix.qry.ns" (char*) Request a comma-delimited list of active namespaces. NO QUALIFIERS.
4 5 6	<pre>PMIX_QUERY_JOB_STATUS "pmix.qry.jst" (pmix_status_t) Status of a specified, currently executing job. REQUIRED QUALIFIER: PMIX_NSPACE indicating the namespace whose status is being queried.</pre>
7 8	<pre>PMIX_QUERY_QUEUE_LIST "pmix.qry.qlst" (char*) Request a comma-delimited list of scheduler queues. NO QUALIFIERS.</pre>
9 10 11 12	<pre>PMIX_QUERY_QUEUE_STATUS "pmix.qry.qst" (char*) Returns status of a specified scheduler queue, expressed as a string. OPTIONAL QUALIFIERS: PMIX_ALLOC_QUEUE naming specific queue whose status is being requested.</pre>
13 14 15 16	PMIX_QUERY_PROC_TABLE "pmix.qry.ptable" (char*)  Returns a (pmix_data_array_t) array of pmix_proc_info_t, one entry for each process in the specified namespace, ordered by process job rank. REQUIRED QUALIFIER: PMIX_NSPACE indicating the namespace whose process table is being queried.
17 18 19 20 21 22 23	PMIX_QUERY_LOCAL_PROC_TABLE "pmix.qry.lptable" (char*)  Returns a (pmix_data_array_t) array of pmix_proc_info_t, one entry for each process in the specified namespace executing on the same node as the requester, ordered by process job rank. REQUIRED QUALIFIER: PMIX_NSPACE indicating the namespace whose local process table is being queried. OPTIONAL QUALIFIER: PMIX_HOSTNAME indicating the host whose local process table is being queried. By default, the query assumes that the host upon which the request was made is to be used.
24 25	<pre>PMIX_QUERY_SPAWN_SUPPORT "pmix.qry.spawn" (bool) Return a comma-delimited list of supported spawn attributes. NO QUALIFIERS.</pre>
26 27	<pre>PMIX_QUERY_DEBUG_SUPPORT "pmix.qry.debug" (bool) Return a comma-delimited list of supported debug attributes. NO QUALIFIERS.</pre>
28 29 30 31	PMIX_QUERY_MEMORY_USAGE "pmix.qry.mem" (bool)  Return information on memory usage for the processes indicated in the qualifiers.  OPTIONAL QUALIFIERS: PMIX_NSPACE and PMIX_RANK, or PMIX_PROCID of specific process(es) whose memory usage is being requested.
32 33	<pre>PMIX_QUERY_REPORT_AVG "pmix.qry.avg" (bool) Report only average values for sampled information. NO QUALIFIERS.</pre>
34 35	<pre>PMIX_QUERY_REPORT_MINMAX "pmix.qry.minmax" (bool) Report minimum and maximum values. NO QUALIFIERS.</pre>
36	<pre>PMIX_QUERY_ALLOC_STATUS "pmix.query.alloc" (char*)</pre>

1		String identifier of the allocation whose status is being requested. NO QUALIFIERS.
2 3 4 5		<pre>PMIX_TIME_REMAINING "pmix.time.remaining" (char*)     Query number of seconds (uint32_t) remaining in allocation for the specified namespace.     OPTIONAL QUALIFIERS: PMIX_NSPACE of the namespace whose info is being requested (defaults to allocation containing the caller).</pre>
6 7 8		PMIX_SERVER_URI "pmix.srvr.uri" (char*)  URI of the PMIx server to be contacted. Requests the URI of the specified PMIx server's PMIx connection. Defaults to requesting the information for the local PMIx server.
9 10 11		PMIX_CLIENT_AVG_MEMORY "pmix.cl.mem.avg" (float)  Average Megabytes of memory used by client processes on node. OPTIONAL  QUALIFERS: PMIX_HOSTNAME or PMIX_NODEID (defaults to caller's node).
12 13 14		PMIX_DAEMON_MEMORY "pmix.dmn.mem" (float)  Megabytes of memory currently used by the RM daemon on the node. OPTIONAL  QUALIFERS: PMIX_HOSTNAME or PMIX_NODEID (defaults to caller's node).
15 16		<pre>PMIX_QUERY_AUTHORIZATIONS "pmix.qry.auths" (bool) Return operations the PMIx tool is authorized to perform. NO QUALIFIERS.</pre>
17 18		PMIX_PROC_PID "pmix.ppid" (pid_t) Operating system PID of specified process.
19 20 21		PMIX_PROC_STATE_STATUS "pmix.proc.state" (pmix_proc_state_t)  State of the specified process as of the last report - may not be the actual current state based on update rate.
22 23		<b>Description</b> Non-blocking form of the <b>PMIx_Query_info</b> API.
24	5.4.5	Query-specific constants
25 26		<b>PMIX_QUERY_PARTIAL_SUCCESS</b> Some, but not all, of the requested information was returned.

# 1 5.4.6 Query attributes

2	Attributes used to direct behavior of the PMIx_Query_info APIs.
3	<pre>PMIX_QUERY_RESULTS "pmix.qry.res" (pmix_data_array_t)</pre>
4	Contains an array of query results for a given pmix_query_t passed to the
5	PMIx_Query_info APIs. If qualifiers were included in the query, then the first element
6	of the array shall be the PMIX_QUERY_QUALIFIERS attribute containing those qualifiers.
7	Each of the remaining elements of the array is a pmix_info_t containing the query key
8	and the corresponding value returned by the query. This attribute is solely for reporting
9	purposes and cannot be used in <b>PMIx_Get</b> or other query operations.
0	<pre>PMIX_QUERY_QUALIFIERS "pmix.qry.quals" (pmix_data_array_t)</pre>
1	Contains an array of qualifiers that were included in the query that produced the provided
2	results. This attribute is solely for reporting purposes and cannot be used in PMIx_Get or
3	other query operations.
4	<pre>PMIX_QUERY_SUPPORTED_KEYS "pmix.qry.keys" (char*)</pre>
5	Returns comma-delimited list of keys supported by the query function. NO QUALIFIERS.
6	<pre>PMIX_QUERY_SUPPORTED_QUALIFIERS "pmix.qry.quals" (char*)</pre>
7	Return comma-delimited list of qualifiers supported by a query on the provided key, instead
8	of actually performing the query on the key. NO QUALIFIERS.
9	<pre>PMIX_QUERY_REFRESH_CACHE "pmix.qry.rfsh" (bool)</pre>
0	Retrieve updated information from server. NO QUALIFIERS.
:1	<pre>PMIX_QUERY_NAMESPACES "pmix.qry.ns" (char*)</pre>
2	Request a comma-delimited list of active namespaces. NO QUALIFIERS.
3	<pre>PMIX_QUERY_NAMESPACE_INFO "pmix.qry.nsinfo" (pmix_data_array_t*)</pre>
4	Return an array of active namespace information - each element will itself contain an array
5	including the namespace plus the command line of the application executing within it.
6	OPTIONAL QUALIFIERS: PMIX_NSPACE of specific namespace whose info is being
7	requested.
8	<pre>PMIX_QUERY_JOB_STATUS "pmix.qry.jst" (pmix_status_t)</pre>
9	Status of a specified, currently executing job. REQUIRED QUALIFIER: PMIX_NSPACE
0	indicating the namespace whose status is being queried.
1	<pre>PMIX_QUERY_QUEUE_LIST "pmix.qry.qlst" (char*)</pre>
2	Request a comma-delimited list of scheduler queues. NO QUALIFIERS.
3	<pre>PMIX_QUERY_QUEUE_STATUS "pmix.qry.qst" (char*)</pre>
4	Returns status of a specified scheduler queue, expressed as a string. OPTIONAL
5	QUALIFIERS: PMIX_ALLOC_QUEUE naming specific queue whose status is being
6	requested.
7	<pre>PMIX_QUERY_PROC_TABLE "pmix.qry.ptable" (char*)</pre>
8	Returns a (pmix_data_array_t) array of pmix_proc_info_t, one entry for each
9	process in the specified namespace, ordered by process job rank. REQUIRED QUALIFIER:
.0	<b>PMIX_NSPACE</b> indicating the namespace whose process table is being queried.
1	<pre>PMIX_QUERY_LOCAL_PROC_TABLE "pmix.qry.lptable" (char*)</pre>

1 2 3 4 5 6	Returns a (pmix_data_array_t) array of pmix_proc_info_t, one entry for each process in the specified namespace executing on the same node as the requester, ordered by process job rank. REQUIRED QUALIFIER: pmix_nspace indicating the namespace whose local process table is being queried. OPTIONAL QUALIFIER: pmix_hostname indicating the host whose local process table is being queried. By default, the query assumes that the host upon which the request was made is to be used.
7	PMIX_QUERY_AUTHORIZATIONS "pmix.qry.auths" (bool)
8	Return operations the PMIx tool is authorized to perform. NO QUALIFIERS.
9	PMIX_QUERY_SPAWN_SUPPORT "pmix.qry.spawn" (bool)
10	Return a comma-delimited list of supported spawn attributes. NO QUALIFIERS.
11	PMIX_QUERY_DEBUG_SUPPORT "pmix.qry.debug" (bool)
12	Return a comma-delimited list of supported debug attributes. NO QUALIFIERS.
13	PMIX_QUERY_MEMORY_USAGE "pmix.qry.mem" (bool)
14	Return information on memory usage for the processes indicated in the qualifiers.
15	OPTIONAL QUALIFIERS: PMIX_NSPACE and PMIX_RANK, or PMIX_PROCID of
16	specific process(es) whose memory usage is being requested.
17	PMIX_QUERY_LOCAL_ONLY "pmix.qry.local" (bool)
18	Constrain the query to local information only. NO QUALIFIERS.
19	PMIX_QUERY_REPORT_AVG "pmix.qry.avg" (bool)
20	Report only average values for sampled information. NO QUALIFIERS.
21	PMIX_QUERY_REPORT_MINMAX "pmix.qry.minmax" (bool)
22	Report minimum and maximum values. NO QUALIFIERS.
23	PMIX_QUERY_ALLOC_STATUS "pmix.query.alloc" (char*)
24	String identifier of the allocation whose status is being requested. NO QUALIFIERS.
25	<pre>PMIX_TIME_REMAINING "pmix.time.remaining" (char*)</pre>
26	Query number of seconds (uint32_t) remaining in allocation for the specified namespace.
27	OPTIONAL QUALIFIERS: PMIX_NSPACE of the namespace whose info is being
28	requested (defaults to allocation containing the caller).
29	<pre>PMIX_QUERY_ATTRIBUTE_SUPPORT "pmix.qry.attrs" (bool)</pre>
30	Query list of supported attributes for specified APIs. REQUIRED QUALIFIERS: one or
31	more of PMIX_CLIENT_FUNCTIONS, PMIX_SERVER_FUNCTIONS,
32	PMIX_TOOL_FUNCTIONS, and PMIX_HOST_FUNCTIONS.
33	<pre>PMIX_QUERY_NUM_PSETS "pmix.qry.psetnum" (size_t)</pre>
34	Return the number of process sets defined in the specified range (defaults to
35	PMIX_RANGE_SESSION).
36	<pre>PMIX_QUERY_PSET_NAMES "pmix.qry.psets" (pmix_data_array_t*)</pre>
37	Return a pmix_data_array_t containing an array of strings of the process set names
38	defined in the specified range (defaults to PMIX_RANGE_SESSION).
39	<pre>PMIX_QUERY_PSET_MEMBERSHIP "pmix.qry.pmems" (pmix_data_array_t*)</pre>
40	Return an array of <b>pmix_proc_t</b> containing the members of the specified process set.
41	<pre>PMIX_QUERY_AVAIL_SERVERS "pmix.qry.asrvrs" (pmix_data_array_t*)</pre>

```
1
                    Return an array of pmix_info_t, each element itself containing a
 2
                    PMIX SERVER INFO ARRAY entry holding all available data for a server on this node to
                    which the caller might be able to connect.
 3
 4
               PMIX SERVER INFO_ARRAY "pmix.srv.arr" (pmix_data_array_t)
 5
                    Array of pmix info t about a given server, starting with its PMIX NSPACE and
6
                    including at least one of the rendezvous-required pieces of information.
7
               These attributes are used to query memory available and used in the system.
8
               PMIX AVAIL PHYS MEMORY "pmix.pmem" (uint64 t)
                    Total available physical memory on a node. OPTIONAL QUALIFERS: PMIX HOSTNAME
9
10
                    or PMIX NODEID (defaults to caller's node).
               PMIX DAEMON MEMORY "pmix.dmn.mem" (float)
11
                    Megabytes of memory currently used by the RM daemon on the node. OPTIONAL
12
                    QUALIFERS: PMIX HOSTNAME or PMIX NODEID (defaults to caller's node).
13
               PMIX CLIENT AVG MEMORY "pmix.cl.mem.avg" (float)
14
15
                    Average Megabytes of memory used by client processes on node. OPTIONAL
16
                    QUALIFERS: PMIX HOSTNAME or PMIX NODEID (defaults to caller's node).
17
               The following attributes are used as qualifiers in queries regarding attribute support within the
               PMIx implementation and/or the host environment:
18
19
               PMIX CLIENT FUNCTIONS "pmix.client.fns" (bool)
                    Request a list of functions supported by the PMIx client library.
20
               PMIX CLIENT ATTRIBUTES "pmix.client.attrs" (bool)
21
                    Request attributes supported by the PMIx client library.
22
23
               PMIX_SERVER_FUNCTIONS "pmix.srvr.fns" (bool)
                    Request a list of functions supported by the PMIx server library.
24
               PMIX SERVER ATTRIBUTES "pmix.srvr.attrs" (bool)
25
                    Request attributes supported by the PMIx server library.
26
               PMIX_HOST_FUNCTIONS "pmix.srvr.fns" (bool)
27
28
                    Request a list of functions supported by the host environment.
               PMIX_HOST_ATTRIBUTES "pmix.host.attrs" (bool)
29
                    Request attributes supported by the host environment.
30
               PMIX_TOOL_FUNCTIONS "pmix.tool.fns" (bool)
31
                    Request a list of functions supported by the PMIx tool library.
32
33
               PMIX_TOOL_ATTRIBUTES "pmix.setup.env" (bool)
34
                    Request attributes supported by the PMIx tool library functions.
             Query Structure
    5.4.7
36
               The pmix_query_t structure is used by the PMIx_Query_info APIs to describe a single
37
```

query operation.

PMIx v2.0

```
1
               typedef struct pmix query {
 2
                    char **keys;
 3
                    pmix_info_t *qualifiers;
 4
                    size_t nqual;
5
               } pmix_query_t;
               where:
6
7
               • keys is a NULL-terminated argv-style array of strings
               • qualifiers is an array of pmix info t describing constraints on the query
8
9
               • ngual is the number of elements in the qualifiers array
    5.4.7.1
              Query structure support macros
11
               The following macros are provided to support the pmix_query_t structure.
               Initialize the query structure
12
               Initialize the pmix_query_t fields
13
  PMIx v2.0
14
               PMIX_QUERY_CONSTRUCT (m)
15
               IN
                    m
                   Pointer to the structure to be initialized (pointer to pmix_query_t
16
               Destruct the query structure
17
               Destruct the pmix_query_t fields
18
  PMIx v2.0
19
               PMIX_QUERY_DESTRUCT (m)
               IN
20
21
                   Pointer to the structure to be destructed (pointer to pmix query t)
```

1 2	Create a query array Allocate and initialize an array of pmix_query_t structures
3	PMIX_QUERY_CREATE (m, n)
4 5 6 7	<pre>INOUT m</pre>
8 9 <i>PMIx v4.0</i>	Free a query structure Release a pmix_query_t structure  C
10	PMIX_QUERY_RELEASE (m)
11 12	IN m Pointer to a pmix_query_t structure (handle)
13 14 <i>PMIx v2.0</i>	Free a query array Release an array of pmix_query_t structures C
15	PMIX_QUERY_FREE (m, n)
16 17 18 19	<pre>IN m     Pointer to the array of pmix_query_t structures (handle) IN n     Number of structures in the array (size_t)</pre>
20 21 22 <i>PMIx v2.2</i>	Create the info array of query qualifiers  Create an array of pmix_info_t structures for passing query qualifiers, updating the nqual field of the pmix_query_t structure.
23	PMIX_QUERY_QUALIFIERS_CREATE (m, n) C
24 25 26 27	IN m Pointer to the pmix_query_t structure (handle) IN n Number of qualifiers to be allocated (size_t)

# 5.5 Using Get vs Query

Both **PMIx\_Get** and **PMIx\_Query\_info** can be used to retrieve information about the system. In general, the *get* operation should be used to retrieve:

- information provided by the host environment at time of job start. This includes information on the number of processes in the job, their location, and possibly their communication endpoints.
- information posted by processes via the **PMIx\_Put** function.

This information is largely considered to be *static*, although this will not necessarily be true for environments supporting dynamic programming models or fault tolerance. Note that the **PMIx\_Get** function only accesses information about execution environments - i.e., its scope is limited to values pertaining to a specific *session*, *job*, *application*, *process*, or *node*. It cannot be used to obtain information about areas such as the status of queues in the WLM.

In contrast, the *query* option should be used to access:

- system-level information (such as the available WLM queues) that would generally not be included in job-level information provided at job start.
- dynamic information such as application and queue status, and resource utilization statistics.
   Note that the PMIX\_QUERY\_REFRESH\_CACHE attribute must be provided on each query to ensure current data is returned.
- information created post job start, such as process tables.
- information requiring more complex search criteria than supported by the simpler PMIx\_Get API.
- queries focused on retrieving multi-attribute blocks of data with a single request, thus bypassing the single-key limitation of the **PMIx\_Get** API.

In theory, all information can be accessed via PMIx\_Query\_info as the local cache is typically the same datastore searched by PMIx\_Get. However, in practice, the overhead associated with the query operation may (depending upon implementation) be higher than the simpler get operation due to the need to construct and process the more complex pmix\_query\_t structure. Thus, requests for a single key value are likely to be accomplished faster with PMIx\_Get versus the query operation.

# 5.6 Accessing attribute support information

Information as to which attributes are supported by either the PMIx implementation or its host environment can be obtained via the PMIx\_Query\_info APIs. The PMIX\_QUERY\_ATTRIBUTE\_SUPPORT attribute must be listed as the first entry in the *keys* field of the pmix\_query\_t structure, followed by the name of the function whose attribute support is being requested - support for multiple functions can be requested simultaneously by simply adding

the function names to the array of *keys*. Function names *must* be given as user-level API names - e.g., "PMIx\_Get", "PMIx\_server\_setup\_application", or "PMIx\_tool\_attach\_to\_server".

The desired levels of attribute support are provided as qualifiers. Multiple levels can be requested simultaneously by simply adding elements to the *qualifiers* array. Each qualifier should contain the desired level attribute with the boolean value set to indicate whether or not that level is to be included in the returned information. Failure to provide any levels is equivalent to a request for all levels. Supported levels include:

• PMIX\_CLIENT\_FUNCTIONS "pmix.client.fns" (bool)

Request a list of functions supported by the PMIx client library.

- PMIX\_CLIENT\_ATTRIBUTES "pmix.client.attrs" (bool)

  Request attributes supported by the PMIx client library.
- PMIX\_SERVER\_FUNCTIONS "pmix.srvr.fns" (bool)

  Request a list of functions supported by the PMIx server library.
- PMIX\_SERVER\_ATTRIBUTES "pmix.srvr.attrs" (bool)
  Request attributes supported by the PMIx server library.
- PMIX\_HOST\_FUNCTIONS "pmix.srvr.fns" (bool)

  Request a list of functions supported by the host environment.
- PMIX\_HOST\_ATTRIBUTES "pmix.host.attrs" (bool)

  Request attributes supported by the host environment.
- PMIX\_TOOL\_FUNCTIONS "pmix.tool.fns" (bool)

  Request a list of functions supported by the PMIx tool library.
- PMIX\_TOOL\_ATTRIBUTES "pmix.setup.env" (bool)

  Request attributes supported by the PMIx tool library functions.

Unlike other queries, queries for attribute support can result in the number of returned <code>pmix\_info\_t</code> structures being different from the number of queries. Each element in the returned array will correspond to a pair of specified attribute level and function in the query, where the <code>key</code> is the function and the <code>value</code> contains a <code>pmix\_data\_array\_t</code> of <code>pmix\_info\_t</code>. Each element of the array is marked by a <code>key</code> indicating the requested attribute <code>level</code> with a <code>value</code> composed of a <code>pmix\_data\_array\_t</code> of <code>pmix\_regattr\_t</code>, each describing a supported attribute for that function, as illustrated in Fig. 5.1 below where the requestor asked for supported attributes of <code>PMIx\_Get</code> at the <code>client</code> and <code>server</code> levels, plus attributes of <code>PMIx\_Allocation\_request</code> at all levels.

The array of returned structures, and their child arrays, are subject to the return rules for the **PMIx\_Query\_info\_nb** API. For example, a request for supported attributes of the **PMIx\_Get** function that includes the *host* level will return values for the *client* and *server* levels, plus an array element with a *key* of **PMIX\_HOST\_ATTRIBUTES** and a value type of **PMIX\_UNDEF** indicating that no attributes are supported at that level.




Figure 5.1.: Returned information hierarchy for attribute support request

#### **CHAPTER 6**

# **Reserved Keys**

Reserved keys are keys whose string representation begin with a prefix of "pmix". By definition, reserved keys are provided by the host environment and the PMIx server, and are required to be available at client start of execution. PMIx clients and tools are therefore prohibited from posting reserved keys using the PMIx\_Put API.

PMIx implementations may choose to define their own custom-prefixed keys which may adhere to either the *reserved* or the *non-reserved* retrieval rules at the discretion of the implementation. Implementations may choose to provide such custom keys at client start of execution, but this is not required.

Host environments may also opt to define their own custom keys. However, PMIx implementations are unlikely to recognize such host-defined keys and will therefore treat them according to the *non-reserved* rules described in Chapter 7. Users are advised to check both the local PMIx implementation and host environment documentation for a list of any custom prefixes they must avoid, and to learn of any non-standard keys that may require special handling.

# 4 6.1 Data realms

PMIx information spans a wide range of sources. In some cases, there are multiple overlapping sources for the same type of data - e.g., the session, job, and application can each provide information on the number of nodes involved in their respective area. In order to resolve the ambiguity, a *data realm* is used to identify the scope to which the referenced data applies. Thus, a reference to an attribute that isn't specific to a realm (e.g., the PMIX\_NUM\_NODES attribute) must be accompanied by a corresponding attribute identifying the realm to which the request pertains if it differs from the default.

PMIx defines five *data realms* to resolve the ambiguities, as captured in the following attributes used in **PMIx\_Get** for retrieving information from each of the realms:

PMIX\_SESSION\_INFO "pmix.ssn.info" (bool)

Return information regarding the session realm of the target process.

PMIX\_JOB\_INFO "pmix.job.info" (bool)

Return information regarding the job realm corresponding to the namespace in the target process' identifier.

PMIX\_APP\_INFO "pmix.app.info" (bool)

Return information regarding the application realm to which the target process belongs - the namespace of the target process serves to identify the job containing the target application. If information about an application other than the one containing the target process is desired, then the attribute array must contain a PMIX\_APPNUM attribute identifying the desired target application. This is useful in cases where there are multiple applications and the mapping of processes to applications is unclear.

#### PMIX PROC INFO "pmix.proc.info" (bool)

Return information regarding the target process. This attribute is technically not required as the **PMIx\_Get** API specifically identifies the target process in its parameters. However, it is included here for completeness.

#### PMIX NODE INFO "pmix.node.info" (bool)

Return information from the node realm regarding the node upon which the specified process is executing. If information about a node other than the one containing the specified process is desired, then the attribute array must also contain either the **PMIX\_NODEID** or **PMIX\_HOSTNAME** attribute identifying the desired target. This is useful for requesting information about a specific node even if the identity of processes running on that node are not known.

#### Advice to users

If information about a session other than the one containing the requesting process is desired, then the attribute array must contain a **PMIX\_SESSION\_ID** attribute identifying the desired target session. This is required as many environments only guarantee unique namespaces within a session, and not across sessions.

The PMIx server has corresponding attributes the host can use to specify the realm of information that it provides during namespace registration (see Section 16.2.3.2).

# 6.1.1 Session realm attributes

If information about a session other than the one containing the requesting process is desired, then the *info* array passed to **PMIx\_Get** must contain a **PMIX\_SESSION\_ID** attribute identifying the desired target session. This is required as many environments only guarantee unique namespaces within a session, and not across sessions.

Note that the *proc* argument of **PMIx\_Get** is ignored when referencing session-related information.

Session-level information includes the following attributes:

```
PMIX_SESSION_ID "pmix.session.id" (uint32_t)
Session identifier assigned by the scheduler.

PMIX_CLUSTER_ID "pmix.clid" (char*)
A string name for the cluster this allocation is on.

PMIX_UNIV_SIZE "pmix.univ.size" (uint32_t)
```

1	Maximum number of process that can be simultaneously executing in a session. Note that
2	this attribute is equivalent to the <b>PMIX_MAX_PROCS</b> attribute for the <i>session</i> realm - it is
3	included in the PMIx Standard for historical reasons.
4	PMIX_TMPDIR "pmix.tmpdir" (char*)
5	Full path to the top-level temporary directory assigned to the session.
6	PMIX_TDIR_RMCLEAN "pmix.tdir.rmclean" (bool)
7	Resource Manager will cleanup assigned temporary directory trees.
8	PMIX_HOSTNAME_KEEP_FQDN "pmix.fqdn" (bool)
9	Fully Qualified Domain Names (FQDNs) are being retained by the PMIx library.
0	The following attributes are used to describe the RM - these are values assigned by the host
1	environment to the session:
2	PMIX_RM_NAME "pmix.rm.name" (char*)
3	String name of the RM.
4	PMIX_RM_VERSION "pmix.rm.version" (char*)
5	RM version string.
6	The remaining session-related information can only be retrieved by including the
7	PMIX_SESSION_INFO attribute in the <i>info</i> array passed to PMIx_Get:
8	PMIX_ALLOCATED_NODELIST "pmix.alist" (char*)
9	Comma-delimited list or regular expression of all nodes in the specified realm regardless of
20	whether or not they currently host processes. Defaults to the <i>job</i> realm.
21	<pre>PMIX_NUM_ALLOCATED_NODES "pmix.num.anodes" (uint32_t)</pre>
22	Number of nodes in the specified realm regardless of whether or not they currently host
23	processes. Defaults to the <i>job</i> realm.
24	<pre>PMIX_MAX_PROCS "pmix.max.size" (uint32_t)</pre>
25	Maximum number of processes that can be executed in the specified realm. Typically, this is
26	a constraint imposed by a scheduler or by user settings in a hostfile or other resource
27	description. Defaults to the <i>job</i> realm.
28	<pre>PMIX_NODE_LIST "pmix.nlist" (char*)</pre>
29	Comma-delimited list of nodes currently hosting processes in the specified realm. Defaults
80	to the <i>job</i> realm.
81	<pre>PMIX_NUM_SLOTS "pmix.num.slots" (uint32_t)</pre>
32	Maximum number of processes that can simultaneously be executing in the specified realm.
3	Note that this attribute is the equivalent to <b>PMIX_MAX_PROCS</b> - it is included in the PMIx
34	Standard for historical reasons. Defaults to the <i>job</i> realm.
35	PMIX_NUM_NODES "pmix.num.nodes" (uint32_t)
16	Number of nodes currently hosting processes in the specified realm. Defaults to the <i>job</i>
37	realm.
8	<pre>PMIX_NODE_MAP "pmix.nmap" (char*)</pre>
9	Regular expression of nodes currently hosting processes in the specified realm - see 16.2.3.2
-0	for an explanation of its generation. Defaults to the <i>job</i> realm.

#### 1 PMIX\_NODE\_MAP\_RAW "pmix.nmap.raw" (char\*)

Comma-delimited list of nodes containing procs within the specified realm. Defaults to the *job* realm.

#### PMIX\_PROC\_MAP "pmix.pmap" (char\*)

Regular expression describing processes on each node in the specified realm - see 16.2.3.2 for an explanation of its generation. Defaults to the *job* realm.

#### PMIX PROC MAP RAW "pmix.pmap.raw" (char\*)

Semi-colon delimited list of strings, each string containing a comma-delimited list of ranks on the corresponding node within the specified realm. Defaults to the *job* realm.

#### PMIX\_ANL\_MAP "pmix.anlmap" (char\*)

Process map equivalent to **PMIX\_PROC\_MAP** expressed in Argonne National Laboratory's PMI-1/PMI-2 notation. Defaults to the *job* realm.

## 6.1.2 Job realm attributes

Job-related information is retrieved by including the namespace of the target job and a rank of **PMIX\_RANK\_WILDCARD** in the *proc* argument passed to **PMIX\_Get**. If desired for code clarity, the caller can also include the **PMIX\_JOB\_INFO** attribute in the *info* array, though this is not required. If information is requested about a namespace in a session other than the one containing the requesting process, then the *info* array must contain a **PMIX\_SESSION\_ID** attribute identifying the desired target session. This is required as many environments only guarantee unique namespaces within a session, and not across sessions.

Job-level information includes the following attributes:

#### PMIX NSPACE "pmix.nspace" (char\*)

Namespace of the job - may be a numerical value expressed as a string, but is often an alphanumeric string carrying information solely of use to the system. Required to be unique within the scope of the host environment.

#### PMIX\_JOBID "pmix.jobid" (char\*)

Job identifier assigned by the scheduler to the specified job - may be identical to the namespace, but is often a numerical value expressed as a string (e.g., "12345.3").

PMIX\_NPROC\_OFFSET "pmix.offset" (pmix\_rank\_t)

Starting global rank of the specified job.

#### PMIX MAX PROCS "pmix.max.size" (uint32 t)

Maximum number of processes that can be executed in the specified realm. Typically, this is a constraint imposed by a scheduler or by user settings in a hostfile or other resource description. Defaults to the *job* realm. In this context, this is the maximum number of processes that can be simultaneously executed in the specified job, which may be a subset of the number allocated to the overall session.

#### PMIX NUM SLOTS "pmix.num.slots" (uint32 t)

Maximum number of processes that can simultaneously be executing in the specified realm. Note that this attribute is the equivalent to **PMIX\_MAX\_PROCS** - it is included in the PMIx Standard for historical reasons. Defaults to the *job* realm. In this context, this is the

maximum number of process that can be simultaneously executing within the specified job, which may be a subset of the number allocated to the overall session. Jobs may reserve a subset of their assigned maximum processes for dynamic operations such as **PMIx\_Spawn**.

#### PMIX NUM NODES "pmix.num.nodes" (uint32 t)

Number of nodes currently hosting processes in the specified realm. Defaults to the *job* realm. In this context, this is the number of nodes currently hosting processes in the specified job, which may be a subset of the nodes allocated to the overall session. Jobs may reserve a subset of their assigned nodes for dynamic operations such as **PMIx\_Spawn** - i.e., not all nodes may have executing processes from this job at a given point in time.

#### PMIX NODE MAP "pmix.nmap" (char\*)

Regular expression of nodes currently hosting processes in the specified realm - see 16.2.3.2 for an explanation of its generation. Defaults to the *job* realm. In this context, this is the regular expression of nodes currently hosting processes in the specified job.

#### PMIX\_NODE\_LIST "pmix.nlist" (char\*)

Comma-delimited list of nodes currently hosting processes in the specified realm. Defaults to the *job* realm. In this context, this is the comma-delimited list of nodes currently hosting processes in the specified job.

#### PMIX\_PROC\_MAP "pmix.pmap" (char\*)

Regular expression describing processes on each node in the specified realm - see 16.2.3.2 for an explanation of its generation. Defaults to the *job* realm. In this context, this is the regular expression describing processes on each node in the specified job.

#### PMIX\_ANL\_MAP "pmix.anlmap" (char\*)

Process map equivalent to **PMIX\_PROC\_MAP** expressed in Argonne National Laboratory's PMI-1/PMI-2 notation. Defaults to the *job* realm. In this context, this is the process mapping in Argonne National Laboratory's PMI-1/PMI-2 notation of the processes in the specified job.

#### PMIX\_CMD\_LINE "pmix.cmd.line" (char\*)

Command line used to execute the specified job (e.g., "mpirun -n 2 –map-by foo ./myapp: -n 4 ./myapp2").

#### PMIX\_NSDIR "pmix.nsdir" (char\*)

Full path to the temporary directory assigned to the specified job, under PMIX\_TMPDIR.

#### PMIX\_JOB\_SIZE "pmix.job.size" (uint32\_t)

Total number of processes in the specified job across all contained applications. Note that this value can be different from PMIX\_MAX\_PROCS. For example, users may choose to subdivide an allocation (running several jobs in parallel within it), and dynamic programming models may support adding and removing processes from a running *job* on-the-fly. In the latter case, PMIx events may be used to notify processes within the job that the job size has changed.

## PMIX\_JOB\_NUM\_APPS "pmix.job.napps" (uint32\_t)

Number of applications in the specified job.

# 6.1.3 Application realm attributes

Application-related information can only be retrieved by including the PMIX\_APP\_INFO attribute in the *info* array passed to PMIx\_Get. If the PMIX\_APPNUM qualifier is given, then the query shall return the corresponding value for the given application within the namespace specified in the *proc* argument of the query (a NULL value for the *proc* argument equates to the namespace of the caller). If the PMIX\_APPNUM qualifier is not included, then the retrieval shall default to the application containing the specified process. If the rank of the specified process is PMIX\_RANK\_WILDCARD, then the application number shall default to that of the calling process if the namespace is its own job, or a value of zero if the namespace is that of a different job.

Application-level information includes the following attributes:

#### PMIX\_APPNUM "pmix.appnum" (uint32\_t)

The application number within the job in which the specified process is a member.

#### PMIX\_NUM\_NODES "pmix.num.nodes" (uint32\_t)

Number of nodes currently hosting processes in the specified realm. Defaults to the *job* realm. In this context, this is the number of nodes currently hosting processes in the specified application, which may be a subset of the nodes allocated to the overall session.

#### PMIX\_APPLDR "pmix.aldr" (pmix\_rank\_t)

Lowest rank in the specified application.

#### PMIX\_APP\_SIZE "pmix.app.size" (uint32\_t)

Number of processes in the specified application, regardless of their execution state - i.e., this number may include processes that either failed to start or have already terminated.

#### PMIX APP ARGV "pmix.app.argv" (char\*)

Consolidated argy passed to the spawn command for the given application (e.g., "./myapp arg1 arg2 arg3").

#### PMIX MAX PROCS "pmix.max.size" (uint32 t)

Maximum number of processes that can be executed in the specified realm. Typically, this is a constraint imposed by a scheduler or by user settings in a hostfile or other resource description. Defaults to the *job* realm. In this context, this is the maximum number of processes that can be executed in the specified application, which may be a subset of the number allocated to the overall session and job.

#### PMIX NUM SLOTS "pmix.num.slots" (uint32 t)

Maximum number of processes that can simultaneously be executing in the specified realm. Note that this attribute is the equivalent to **PMIX\_MAX\_PROCS** - it is included in the PMIx Standard for historical reasons. Defaults to the *job* realm. In this context, this is the number of slots assigned to the specified application, which may be a subset of the slots allocated to the overall session and job.

#### PMIX\_NODE\_MAP "pmix.nmap" (char\*)

Regular expression of nodes currently hosting processes in the specified realm - see 16.2.3.2 for an explanation of its generation. Defaults to the *job* realm. In this context, this is the regular expression of nodes currently hosting processes in the specified application.

#### 1 PMIX\_NODE\_LIST "pmix.nlist" (char\*) 2 Comma-delimited list of nodes currently hosting processes in the specified realm. Defaults 3 to the job realm. In this context, this is the comma-delimited list of nodes currently hosting processes in the specified application. 4 5 PMIX PROC MAP "pmix.pmap" (char\*) 6 Regular expression describing processes on each node in the specified realm - see 16,2.3.2 for an explanation of its generation. Defaults to the job realm. In this context, this is the 7 8 regular expression describing processes on each node in the specified application. 9 PMIX\_APP\_MAP\_TYPE "pmix.apmap.type" (char\*) Type of mapping used to layout the application (e.g., cyclic). 10 PMIX APP MAP REGEX "pmix.apmap.regex" (char\*) 11 Regular expression describing the result of the process mapping. 12 6.1.4 Process realm attributes 13 14 Process-related information is retrieved by referencing the namespace and rank of the target process in the call to **PMIx** Get. If information is requested about a process in a session other than the one 15 containing the requesting process, then an attribute identifying the target session must be provided. 16 17 This is required as many environments only guarantee unique namespaces within a session, and not across sessions. 18 19 Process-level information includes the following attributes: PMIX APPNUM "pmix.appnum" (uint32 t) 20 The application number within the job in which the specified process is a member. 21 22 PMIX RANK "pmix.rank" (pmix rank t) 23 Process rank within the job, starting from zero. PMIX GLOBAL RANK "pmix.grank" (pmix rank t) 24 Rank of the specified process spanning across all jobs in this session, starting with zero. 25 Note that no ordering of the jobs is implied when computing this value. As jobs can start and 26 27 end at random times, this is defined as a continually growing number - i.e., it is not 28 dynamically adjusted as individual jobs and processes are started or terminated. PMIX APP RANK "pmix.apprank" (pmix rank t) 29 Rank of the specified process within its application. 30 31 PMIX PARENT ID "pmix.parent" (pmix proc t) 32 Process identifier of the parent process of the specified process - typically used to identify the application process that caused the job containing the specified process to be spawned 33 (e.g., the process that called **PMIx\_Spawn**). 34 PMIX EXIT CODE "pmix.exit.code" (int) 35 36 Exit code returned when the specified process terminated. 37 PMIX PROCID "pmix.procid" (pmix proc t) Process identifier. Used as a key in **PMIx** Get to retrieve the caller's own process identifier 38 in a portion of the program that doesn't have access to the memory location in which it was 39

originally stored (e.g., due to a call to **PMIx Init**). The process identifier in the

**PMIx** Get call is ignored in this instance.

#### PMIX\_LOCAL\_RANK "pmix.lrank" (uint16\_t)

Rank of the specified process on its node - refers to the numerical location (starting from zero) of the process on its node when counting only those processes from the same job that share the node, ordered by their overall rank within that job.

#### PMIX\_NODE\_RANK "pmix.nrank" (uint16\_t)

Rank of the specified process on its node spanning all jobs- refers to the numerical location (starting from zero) of the process on its node when counting all processes (regardless of job) that share the node, ordered by their overall rank within the job. The value represents a snapshot in time when the specified process was started on its node and is not dynamically adjusted as processes from other jobs are started or terminated on the node.

#### PMIX\_PACKAGE\_RANK "pmix.pkgrank" (uint16\_t)

Rank of the specified process on the *package* where this process resides - refers to the numerical location (starting from zero) of the process on its package when counting only those processes from the same job that share the package, ordered by their overall rank within that job. Note that processes that are not bound to Processing Units (PUs) within a single specific package cannot have a package rank.

#### PMIX\_PROC\_PID "pmix.ppid" (pid\_t)

Operating system PID of specified process.

#### PMIX\_PROCDIR "pmix.pdir" (char\*)

Full path to the subdirectory under **PMIX\_NSDIR** assigned to the specified process.

#### PMIX\_CPUSET "pmix.cpuset" (char\*)

A string representation of the PU binding bitmap applied to the process upon launch. The string shall begin with the name of the library that generated it (e.g., "hwloc") followed by a colon and the bitmap string itself.

#### PMIX CPUSET BITMAP "pmix.bitmap" (pmix cpuset t\*)

Bitmap applied to the process upon launch.

#### PMIX CREDENTIAL "pmix.cred" (char\*)

Security credential assigned to the process.

#### PMIX\_SPAWNED "pmix.spawned" (bool)

**true** if this process resulted from a call to **PMIx\_Spawn**. Lack of inclusion (i.e., a return status of **PMIX\_ERR\_NOT\_FOUND**) corresponds to a value of **false** for this attribute.

#### PMIX\_REINCARNATION "pmix.reinc" (uint32\_t)

Number of times this process has been re-instantiated - i.e, a value of zero indicates that the process has never been restarted. 5

In addition, process-level information includes functional attributes directly associated with a process - for example, the process-related fabric attributes included in Section 14.3 or the distance attributes of Section 11.4.11.

# 6.1.5 Node realm keys

Information regarding the local node can be retrieved by directly requesting the node realm key in the call to **PMIx\_Get** - the keys for node-related information are not shared across other realms.

The target process identifier will be ignored for keys that are not dependent upon it. Information 1 about a node other than the local node can be retrieved by specifying the PMIX NODE INFO 2 attribute in the info array along with either the PMIX HOSTNAME or PMIX NODEID qualifiers for 3 the node of interest. 4 5 Node-level information includes the following keys: PMIX HOSTNAME "pmix.hname" (char\*) 6 Name of the host, as returned by the **gethostname** utility or its equivalent. 7 PMIX HOSTNAME ALIASES "pmix.alias" (char\*) 8 9 Comma-delimited list of names by which the target node is known. PMIX NODEID "pmix.nodeid" (uint32 t) 10 Node identifier expressed as the node's index (beginning at zero) in an array of nodes within 11 the active session. The value must be unique and directly correlate to the PMIX HOSTNAME 12 of the node - i.e., users can interchangeably reference the same location using either the 13 14 PMIX HOSTNAME or corresponding PMIX NODELD. PMIX NODE SIZE "pmix.node.size" (uint32 t) 15 Number of processes across all jobs that are executing upon the node. 16 17 PMIX AVAIL PHYS MEMORY "pmix.pmem" (uint64 t) Total available physical memory on a node. 18 The following attributes only return information regarding the caller's node - any node-related 19 qualifiers shall be ignored. In addition, these attributes require specification of the namespace in the 20 target process identifier except where noted - the value of the rank is ignored in all cases. 21 22 PMIX LOCAL PEERS "pmix.lpeers" (char\*) Comma-delimited list of ranks that are executing on the local node within the specified 23 namespace – shortcut for **PMIx Resolve peers** for the local node. 24 25 PMIX LOCAL PROCS "pmix.lprocs" (pmix proc t array) Array of pmix proc t of all processes executing on the local node – shortcut for 26 PMIx Resolve peers for the local node and a NULL namespace argument. The process 27 identifier is ignored for this attribute. 28 29 PMIX LOCALLDR "pmix.lldr" (pmix rank t) Lowest rank within the specified job on the node (defaults to current node in absence of 30 PMIX\_HOSTNAME or PMIX\_NODEID qualifier). 31 PMIX LOCAL CPUSETS "pmix.lcpus" (pmix data array t) 32 A pmix data array t array of string representations of the PU binding bitmaps 33 applied to each local *peer* on the caller's node upon launch. Each string shall begin with the 34 35 name of the library that generated it (e.g., "hwloc") followed by a colon and the bitmap string itself. The array shall be in the same order as the processes returned by 36 PMIX\_LOCAL\_PEERS for that namespace. 37 PMIX\_LOCAL\_SIZE "pmix.local.size" (uint32\_t) 38

Number of processes in the specified job or application realm on the caller's node. Defaults

to job realm unless the PMIX\_APP\_INFO and the PMIX\_APPNUM qualifiers are given.

39

# 6.2 Retrieval rules for reserved keys

The retrieval rules for reserved keys are relatively simple as the keys are required, by definition, to be available when the client begins execution. Accordingly, **PMIx\_Get** for a reserved key first checks the local PMIx Client cache (per the data realm rules of the prior section) for the target key. If the information is not found, then the **PMIX\_ERR\_NOT\_FOUND** error constant is returned unless the target process belongs to a different namespace from that of the requester.

In the case where the target and requester's namespaces differ, then the request is forwarded to the local PMIx server. Upon receiving the request, the server shall check its data storage for the specified namespace. If it already knows about this namespace, then it shall attempt to lookup the specified key, returning the value if it is found or the PMIX\_ERR\_NOT\_FOUND error constant.

If the server does not have a copy of the information for the specified namespace, then the server shall take one of the following actions:

- 1. If the request included the **PMIX\_IMMEDIATE** attribute, then the server will respond to the client with the **PMIX\_ERR\_NOT\_FOUND** status.
- 2. If the host has provided the Direct Business Card Exchange (DBCX) module function interface (pmix\_server\_dmodex\_req\_fn\_t), then the server shall pass the request to its host for servicing. The host is responsible for identifying a source of information on the specified namespace and retrieving it. The host is required to retrieve all of the information regarding the target namespace and return it to the requesting server in anticipation of follow-on requests. If the host cannot retrieve the namespace information, then it must respond with the PMIX\_ERR\_NOT\_FOUND error constant unless the PMIX\_TIMEOUT is given and reached (in which case, the host must respond with the PMIX\_ERR\_TIMEOUT constant).

Once the the PMIx server receives the namespace information, the server shall search it (again adhering to the prior data realm rules) for the requested key, returning the value if it is found or the PMIX\_ERR\_NOT\_FOUND error constant.

3. If the host does not support the DBCX interface, then the server will respond to the client with the PMIX ERR NOT FOUND status

# 6.2.1 Accessing information: examples

This section provides examples illustrating methods for accessing information from the various realms. The intent of the examples is not to provide comprehensive coding guidance, but rather to further illustrate the use of **PMIx\_Get** for obtaining information on a *session*, *job*, *application*, *process*, and *node*.

#### 6.2.1.1 Session-level information

 The **PMIx\_Get** API does not include an argument for specifying the *session* associated with the information being requested. Thus, requests for keys that are not specifically for session-level information must be accompanied by the **PMIX\_SESSION\_INFO** qualifier.

Example requests are shown below:

```
pmix_info_t info;
pmix_value_t *value;
pmix_status_t rc;
pmix_proc_t myproc, wildcard;

/* initialize the client library */
PMIx_Init(&myproc, NULL, 0);

/* get the #slots in our session */
PMIX_PROC_LOAD(&wildcard, myproc.nspace, PMIX_RANK_WILDCARD);
rc = PMIx_Get(&wildcard, PMIX_UNIV_SIZE, NULL, 0, &value);

/* get the #nodes in our session */
PMIX_INFO_LOAD(&info, PMIX_SESSION_INFO, NULL, PMIX_BOOL);
rc = PMIx_Get(&wildcard, PMIX_NUM_NODES, &info, 1, &value);
```

Information regarding a different session can be requested by adding the **PMIX\_SESSION\_ID** attribute identifying the target session. In this case, the *proc* argument to **PMIx\_Get** will be ignored:

```
pmix_info_t info[2];
pmix_value_t *value;
pmix_status_t rc;
pmix_proc_t myproc;
uint32_t sid;

/* initialize the client library */
PMIx_Init(&myproc, NULL, 0);

/* get the #nodes in a different session */
sid = 12345;
PMIX_INFO_LOAD(&info[0], PMIX_SESSION_INFO, NULL, PMIX_BOOL);
PMIX_INFO_LOAD(&info[1], PMIX_SESSION_ID, &sid, PMIX_UINT32);
rc = PMIx_Get(NULL, PMIX_NUM_NODES, info, 2, &value);
```

С

#### 6.2.1.2 Job-level information

2

3

20 21 Information regarding a job can be obtained by the methods detailed in Section 6.1.2. Example requests are shown below:

```
4
            pmix_info_t info;
5
            pmix value t *value;
6
            pmix status t rc;
7
            pmix proc t myproc, wildcard;
8
9
            /* initialize the client library */
10
            PMIx Init(&myproc, NULL, 0);
11
12
            /* get the #apps in our job */
            PMIX_PROC_LOAD(&wildcard, myproc.nspace, PMIX_RANK_WILDCARD);
13
            rc = PMIx_Get(&wildcard, PMIX_JOB_NUM_APPS, NULL, 0, &value);
14
15
16
            /* get the #nodes in our job */
17
            PMIX_INFO_LOAD(&info, PMIX_JOB_INFO, NULL, PMIX_BOOL);
            rc = PMIx_Get(&wildcard, PMIX_NUM_NODES, &info, 1, &value);
18
```

## 6.2.1.3 Application-level information

Information regarding an application can be obtained by the methods described in Section 6.1.3. Example requests are shown below:

```
22
            pmix info t info;
23
            pmix_value_t *value;
            pmix_status_t rc;
24
25
            pmix_proc_t myproc, otherproc;
            uint32_t appsize, appnum;
26
27
            /* initialize the client library */
28
29
            PMIx_Init(&myproc, NULL, 0);
30
            /* get the #processes in our application */
31
32
            rc = PMIx Get(&myproc, PMIX APP SIZE, NULL, 0, &value);
33
            appsize = value->data.uint32;
34
35
            /* get the #nodes in an application containing "otherproc".
```

```
* For this use-case, assume that we are in the first application
1
2
             * and we want the #nodes in the second application - use the
             * rank of the first process in that application, remembering
3
4
             * that ranks start at zero */
5
            PMIX PROC LOAD (&otherproc, myproc.nspace, appsize);
6
7
            /* Since "otherproc" refers to a process in the second application,
8
             * we can simply mark that we want the info for this key from the
9
             * application realm */
            PMIX_INFO_LOAD(&info, PMIX_APP_INFO, NULL, PMIX_BOOL);
10
            rc = PMIx_Get(&otherproc, PMIX_NUM_NODES, &info, 1, &value);
11
12
13
            /* alternatively, we can directly ask for the #nodes in
14
             * the second application in our job, again remembering that
15
             * application numbers start with zero. Since we are asking
             * for application realm information about a specific appnum
16
17
             * within our own namespace, the process identifier can be NULL */
18
            appnum = 1;
            PMIX INFO LOAD (&appinfo[0], PMIX APP INFO, NULL, PMIX BOOL);
19
20
            PMIX_INFO_LOAD(&appinfo[1], PMIX_APPNUM, &appnum, PMIX_UINT32);
            rc = PMIx_Get(NULL, PMIX_NUM_NODES, appinfo, 2, &value);
21
```

#### 6.2.1.4 Process-level information

Process-level information is accessed by providing the namespace and rank of the target process. In the absence of any directive as to the level of information being requested, the PMIx library will always return the process-level value. See Section 6.1.4 for details.

#### 26 6.2.1.5 Node-level information

23 24

25

27

28

Information regarding a node within the system can be obtained by the methods described in Section 6.1.5. Example requests are shown below:

```
29
            pmix_info_t info[2];
30
            pmix value t *value;
            pmix status t rc;
31
32
            pmix proc t myproc, otherproc;
33
            uint32_t nodeid;
34
35
            /* initialize the client library */
36
            PMIx_Init(&myproc, NULL, 0);
37
38
            /* get the #procs on our node */
```

```
1
           rc = PMIx_Get(&myproc, PMIX_NODE_SIZE, NULL, 0, &value);
2
           /* get the #slots on another node */
3
4
           PMIX_INFO_LOAD(&info[0], PMIX_NODE_INFO, NULL, PMIX_BOOL);
5
           PMIX_INFO_LOAD(&info[1], PMIX_HOSTNAME, "remotehost", PMIX_STRING);
6
           rc = PMIx_Get(NULL, PMIX_MAX_PROCS, info, 2, &value);
7
8
           /* get the total #procs on the remote node - note that we don't
9
             * actually need to include the "PMIX_NODE_INFO" attribute here,
10
             * but (a) it does no harm and (b) it allowed us to simply reuse
11
             * the prior info array
           rc = PMIx_Get(NULL, PMIX_NODE_SIZE, info, 2, &value);
12
```

#### **CHAPTER 7**

# **Process-Related Non-Reserved Keys**

Non-reserved keys are keys whose string representation begin with a prefix other than "pmix". Such keys are typically defined by an application when information needs to be exchanged between processes (e.g., where connection information is required and the host environment does not support the *instant on* option) or where the host environment does not provide a required piece of data. Beyond the restriction on name prefix, non-reserved keys are required to be unique across conflicting *scopes* as defined in Section 7.1.1.1 - e,g., a non-reserved key cannot be posted by the same process in both the PMIX\_LOCAL and PMIX\_REMOTE scopes (note that posting the key in the PMIX\_GLOBAL scope would have met the desired objective).

PMIx provides support for two methods of exchanging non-reserved keys:

- Global, collective exchange of the information prior to retrieval. This is accomplished by
  executing a barrier operation that includes collection and exchange of the data provided by each
  process such that each process has access to the full set of data from all participants once the
  operation has completed. PMIx provides the PMIx\_Fence function (or its non-blocking
  equivalent) for this purpose, accompanied by the PMIX\_COLLECT\_DATA qualifier.
- Direct, on-demand retrieval of the information. No barrier or global exchange is conducted in this case. Instead, information is retrieved from the host where that process is executing upon request i.e., a call to PMIx\_Get results in a data exchange with the PMIx server on the remote host. Various caching strategies may be employed by the host environment and/or PMIx implementation to reduce the number of retrievals. Note that this method requires that the host environment both know the location of the posting process and support direct information retrieval.

Both of the above methods are based on retrieval from a specific process - i.e., the *proc* argument to <code>PMIx\_Get</code> must include both the namespace and the rank of the process that posted the information. However, in some cases, non-reserved keys are provided on a globally unique basis and the retrieving process has no knowledge of the identity of the process posting the key. This is typically found in legacy applications (where the originating process identifier is often embedded in the key itself) and in unstructured applications that lack rank-related behavior. In these cases, the key remains associated with the namespace of the process that posted it, but is retrieved by use of the <code>PMIX\_RANK\_UNDEF</code> rank. In addition, the keys must be globally exchanged prior to retrieval as there is no way for the host to otherwise locate the source for the information.

Note that the retrieval rules for non-reserved keys (detailed in Section 7.2) differ significantly from those used for reserved keys.

#### 7.1 **Posting Key/Value Pairs**

PMIx clients can post non-reserved key-value pairs associated with themselves by using 2 3 PMIx Put. Alternatively, PMIx clients can cache arbitrary key-value pairs accessible only by the 4 caller via the PMIx Store internal API.

#### 7.1.1 PMIx Put

6 7

13

14

15

16 17

18

19

20

21 22

23 24

25

26 27

28

29 30

31

32

#### Summary

**Format** 

Post a key/value pair for distribution.

```
8 PMIx v1.0
9
            pmix status t
10
            PMIx_Put(pmix_scope_t scope,
                      const pmix key t key,
11
                      pmix value t *val);
12
```

IN scope

Distribution scope of the provided value (handle)

IN key (pmix\_key\_t)

IN value

Reference to a **pmix\_value\_t** structure (handle)

Returns PMIX\_SUCCESS or one of the following error codes when the condition described occurs:

• PMIX\_ERR\_BAD\_PARAM indicating a reserved key is provided in the key argument.

If none of the above return codes are appropriate, then an implementation must return either a general PMIx error code or an implementation defined error code as described in Section 3.1.1.

#### **Description**

Post a key-value pair for distribution. Depending upon the PMIx implementation, the posted value may be locally cached in the client's PMIx library until PMIx Commit is called.

The provided *scope* determines the ability of other processes to access the posted data, as defined in Section 7.1.1.1 on page 113. Specific implementations may support different scope values, but all implementations must support at least **PMIX GLOBAL**.

The pmix\_value\_t structure supports both string and binary values. PMIx implementations are required to support heterogeneous environments by properly converting binary values between host architectures, and will copy the provided *value* into internal memory prior to returning from PMIx Put.

#### Advice to users

Note that keys starting with a string of "**pmix**" must not be used in calls to **PMIx\_Put**. Thus, applications should never use a defined "PMIX" attribute as the key in a call to **PMIx\_Put**.

# 7.1.1.1 Scope of Put Data

7

8

10

11

12

13

14 15

16

17

19

20

23

18 *PMIx* v2.0

The pmix\_scope\_t structure is a uint8\_t type that defines the availability of data passed to pmix\_put. The following constants can be used to set a variable of the type pmix\_scope\_t.

All definitions were introduced in version 1 of the standard unless otherwise marked.

Specific implementations may support different scope values, but all implementations must support at least PMIX\_GLOBAL. If a specified scope value is not supported, then the PMIX\_Put call must return PMIX\_ERR\_NOT\_SUPPORTED.

**PMIX\_SCOPE\_UNDEF** Undefined scope.

**PMIX\_LOCAL** The data is intended only for other application processes on the same node. Data marked in this way will not be included in data packages sent to remote requesters - i.e., it is only available to processes on the local node.

**PMIX\_REMOTE** The data is intended solely for applications processes on remote nodes. Data marked in this way will not be shared with other processes on the same node - i.e., it is only available to processes on remote nodes.

**PMIX\_GLOBAL** The data is to be shared with all other requesting processes, regardless of location.

**PMIX\_INTERNAL** The data is intended solely for this process and is not shared with other processes.

# 7.1.2 PMIx\_Store\_internal

## 22 Summary

Store some data locally for retrieval by other areas of the process.

# $_{PMIx,v1.0}$ Format

1 IN proc 2 process

3

4

5

6

7

8

10

11 12

13

14

16

17

19

20

21

22

23 24

25

26

27

28 29

30

process reference (handle)

IN key

key to retrieve (string)

IN val

Value to store (handle)

Returns PMIX\_SUCCESS or one of the following error codes when the condition described occurs:

• PMIX ERR BAD PARAM indicating a reserved key is provided in the key argument.

If none of the above return codes are appropriate, then an implementation must return either a general PMIx error code or an implementation defined error code as described in Section 3.1.1.

#### **Description**

Store some data locally for retrieval by other areas of the process. This is data that has only internal scope - it will never be posted externally. Typically used to cache data obtained by means outside of PMIx so that it can be accessed by various areas of the process.

#### 15 7.1.3 PMIx Commit

#### Summary

Post all previously **PMIx\_Put** values for distribution.

# 18 *PMIx v1.0*

# Format

pmix\_status\_t PMIx\_Commit(void);

Returns **PMIX\_SUCCESS** or a negative value indicating the error.

## Description

PMIx implementations may choose to locally cache non-reserved keys prior to submitting them for distribution. Accordingly, PMIx provides a second API specifically to stage all previously posted data for distribution - e.g., by transmitting the entire collection of data posted by the process to a server in one operation. This is an asynchronous operation that will immediately return to the caller while the data is staged in the background.

#### Advice to users

Users are advised to always include the call to **PMIx\_Commit** in case the local implementation requires it. Note that posted data will not be circulated during **PMIx\_Commit**. Availability of the data by other processes upon completion of **PMIx\_Commit** therefore still relies upon the exchange mechanisms described at the beginning of this chapter.

# 7.2 Retrieval rules for non-reserved keys

Since non-reserved keys cannot, by definition, have been provided by the host environment, their retrieval follows significantly different rules than those defined for reserved keys (as detailed in Section 6.2). **PMIx\_Get** for a non-reserved key will obey the following precedence search:

- 1. If the **PMIX\_GET\_REFRESH\_CACHE** attribute is given, then the request is first forwarded to the local PMIx server which will then update the client's cache. Note that this may not, depending upon implementation details, result in any action.
- 2. Check the local PMIx client cache for the requested key if not found and either the PMIX\_OPTIONAL or PMIX\_GET\_REFRESH\_CACHE attribute was given, the search will stop at this point and return the PMIX\_ERR\_NOT\_FOUND status.
- 3. Request the information from the local PMIx server. The server will check its cache for the specified key within the appropriate scope as defined by the process that originally posted the key. If the value exists in a scope that contains the requesting process, then the value shall be returned. If the value exists, but in a scope that excludes the requesting process, then the server shall immediately return the PMIX ERR EXISTS OUTSIDE SCOPE.

If the value still isn't found and the **PMIX\_IMMEDIATE** attribute was given, then the library shall return the **PMIX\_ERR\_NOT\_FOUND** error constant to the requester. Otherwise, the PMIx server library will take one of the following actions:

- If the target process has a rank of PMIX\_RANK\_UNDEF, then this indicates that the key being requested is globally unique and *not* associated with a specific process. In this case, the server shall hold the request until either the data appears at the server or, if given, the PMIX\_TIMEOUT is reached. In the latter case, the server will return the PMIX\_ERR\_TIMEOUT status. Note that the server may, depending on PMIx implementation, never respond if the caller failed to specify a PMIX\_TIMEOUT and the requested key fails to arrive at the server.
- If the target process is *local* (i.e., attached to the same PMIx server), then the server will hold the request until either the target process provides the data or, if given, the PMIX\_TIMEOUT is reached. In the latter case, the server will return the PMIX\_ERR\_TIMEOUT status. Note that data which is posted via PMIx\_Put but not staged with PMIx\_Commit may, depending upon implementation, never appear at the server.
- If the target process is *remote* (i.e., not attached to the same PMIx server), the server will either:
  - If the host has provided the **pmix\_server\_dmodex\_req\_fn\_t** module function interface, then the server shall pass the request to its host for servicing. The host is responsible for determining the location of the target process and passing the request to the PMIx server at that location.

When the remote data request is received, the target PMIx server will check its cache for the specified key. If the key is not present, the request shall be held until either the target process provides the data or, if given, the **PMIX\_TIMEOUT** is reached. In the latter case,

1 the server will return the PMIX\_ERR\_TIMEOUT status. The host shall convey the result 2 back to the originating PMIx server, which will reply to the requesting client with the result of the request when the host provides it. 3 4 Note that the target server may, depending on PMIx implementation, never respond if the 5 caller failed to specify a PMIX\_TIMEOUT and the target process fails to post the requested 6 key. 7 - if the host does not support the **pmix\_server\_dmodex\_req\_fn\_t** interface, then the 8 server will immediately respond to the client with the PMIX\_ERR\_NOT\_FOUND status Advice to PMIx library implementers – 9 While there is no requirement that all PMIx implementations follow the client-server paradigm 10 used in the above description, implementers are required to provide behaviors consistent with the described search pattern. 11 Advice to users Users are advised to always specify the PMIX\_TIMEOUT value when retrieving non-reserved keys 12 to avoid potential deadlocks should the specified key not become available. 13

#### **CHAPTER 8**

1

2

3

4

5

6 7

8

9 10

11 12

13

14

# **Publish/Lookup Operations**

Chapter 6 and Chapter 7 discussed how reserved and non-reserved keys dealt with information that either was associated with a specific process (i.e., the retrieving process knew the identifier of the process that posted it) or required a synchronization operation prior to retrieval (e.g., the case of globally unique non-reserved keys). However, another requirement exists for an asynchronous exchange of data where neither the posting nor the retrieving process is known in advance. For example, two separate namespaces may need to rendezvous with each other without knowing in advance the identity of the other namespace or when that namespace might become active.

The APIs defined in this section focus on resolving that specific situation by allowing processes to publish data that can subsequently be retrieved solely by referral to its key. Mechanisms for constraining availability of the information are also provided as a means for better targeting of the eventual recipient(s).

Note that no presumption is made regarding how the published information is to be stored, nor as to the entity (host environment or PMIx implementation) that shall act as the datastore. The descriptions in the remainder of this chapter shall simply refer to that entity as the *datastore*.

# 5 8.1 PMIx\_Publish

#### Summary 16 Publish data for later access via PMIx\_Lookup. 17 **Format** PMIx v1.0 19 pmix status t 20 PMIx Publish(const pmix info t info[], size t ninfo); IN 21 info Array of info structures containing both data to be published and directives (array of handles) 22 23 24 Number of elements in the *info* array (integer) 25 Returns **PMIX\_SUCCESS** or a negative value indicating the error.

# ----- Required Attributes

There are no required attributes for this API. PMIx implementations that do not directly support the operation but are hosted by environments that do support it must pass any attributes that are provided by the client to the host environment for processing. In addition, the PMIx library is required to add the PMIX\_USERID and the PMIX\_GRPID attributes of the client process that published the information to the *info* array passed to the host environment.

## Optional Attributes

The following attributes are optional for host environments that support this operation:

#### PMIX TIMEOUT "pmix.timeout" (int)

Time in seconds before the specified operation should time out (zero indicating infinite) and return the **PMIX\_ERR\_TIMEOUT** error. Care should be taken to avoid race conditions caused by multiple layers (client, server, and host) simultaneously timing the operation.

#### PMIX\_RANGE "pmix.range" (pmix\_data\_range\_t)

Define constraints on the processes that can access the provided data. Only processes that meet the constraints are allowed to access it.

#### PMIX PERSISTENCE "pmix.persist" (pmix persistence t)

Declare how long the datastore shall retain the provided data. The datastore is to delete the data upon reaching the persistence criterion.

#### PMIX ACCESS PERMISSIONS "pmix.aperms" (pmix data array t)

Define access permissions for the published data. The value shall contain an array of **pmix\_info\_t** structs containing the specified permissions.

#### **Description**

Publish the data in the *info* array for subsequent lookup. By default, the data will be published into the PMIX\_RANGE\_SESSION range and with PMIX\_PERSIST\_APP persistence. Changes to those values, and any additional directives, can be included in the pmix\_info\_t array. Attempts to access the data by processes outside of the provided data range shall be rejected. The PMIX\_PERSISTENCE attribute instructs the datastore holding the published information as to how long that information is to be retained.

The blocking form of this call will block until it has obtained confirmation from the datastore that the data is available for lookup. The *info* array can be released upon return from the blocking function call.

Publishing duplicate keys is permitted provided they are published to different ranges. Duplicate keys being published on the same data range shall return the **PMIX ERR DUPLICATE KEY** error.

# 1 8.2 PMIx\_Publish\_nb

2	Summary Nonblocking PMIx_Publish routine.
4 <i>PMIx v1.0</i>	Format C
5 6 7 8 9 0	<pre>pmix_status_t PMIx_Publish_nb(const pmix_info_t info[], size_t ninfo,</pre>
1 2 3 4 5	Number of elements in the <i>info</i> array (integer)  IN cbfunc Callback function pmix_op_cbfunc_t (function reference)  IN cbdata Data to be passed to the callback function (memory reference)
6 7 8	A successful return indicates that the request is being processed by the host environment and the result will be returned in the provided <i>cbfunc</i> . Note that the library must not invoke the callback function prior to returning from the API. In all other cases, the <i>cbfunc</i> will <i>not</i> be called.
9 20 21	Returns PMIX_SUCCESS or one of the following error codes when the condition described occurs:  • PMIX_OPERATION_SUCCEEDED, indicating that the request was immediately processed and returned <i>success</i> - the <i>cbfunc</i> will <i>not</i> be called.
22 23	If none of the above return codes are appropriate, then an implementation must return either a general PMIx error code or an implementation defined error code as described in Section 3.1.1.  Required Attributes
24 25 26 27 28	There are no required attributes for this API. PMIx implementations that do not directly support the operation but are hosted by environments that do support it must pass any attributes that are provided by the client to the host environment for processing. In addition, the PMIx library is required to add the PMIX_USERID and the PMIX_GRPID attributes of the client process that published the information to the <i>info</i> array passed to the host environment.

#### Optional Attributes The following attributes are optional for host environments that support this operation: 1 2 PMIX TIMEOUT "pmix.timeout" (int) 3 Time in seconds before the specified operation should time out (zero indicating infinite) and return the PMIX ERR TIMEOUT error. Care should be taken to avoid race conditions caused by multiple layers (client, server, and host) simultaneously timing the operation. 5 6 PMIX RANGE "pmix.range" (pmix data range t) 7 Define constraints on the processes that can access the provided data. Only processes that meet the constraints are allowed to access it. 8 PMIX\_PERSISTENCE "pmix.persist" (pmix\_persistence\_t) 9 10 Declare how long the datastore shall retain the provided data. The datastore is to delete the data upon reaching the persistence criterion. 12 PMIX\_ACCESS\_PERMISSIONS "pmix.aperms" (pmix\_data\_array\_t) Define access permissions for the published data. The value shall contain an array of 13 14 pmix info t structs containing the specified permissions. **Description** 15 Nonblocking **PMIx\_Publish** routine. 16 8.3 Publish-specific constants The following constants are defined for use with the **PMIx Publish** APIs: 18 19 PMIX ERR DUPLICATE KEY The provided key has already been published on the same 20 data range. **Publish-specific attributes** 8.4 22 The following attributes are defined for use with the **PMIx\_Publish** APIs: 23 PMIX RANGE "pmix.range" (pmix data range t) Define constraints on the processes that can access the provided data. Only processes that 24 meet the constraints are allowed to access it. 25 26 PMIX\_PERSISTENCE "pmix.persist" (pmix\_persistence\_t) Declare how long the datastore shall retain the provided data. The datastore is to delete the 27 28 data upon reaching the persistence criterion.

PMIX\_ACCESS\_PERMISSIONS "pmix.aperms" (pmix\_data\_array\_t)

pmix\_info\_t structs containing the specified permissions.

Define access permissions for the published data. The value shall contain an array of

29

```
1 PMIX_ACCESS_USERIDS "pmix.auids" (pmix_data_array_t)
2 Array of effective User IDs (UIDs) that are allowed to access the published data.
3 PMIX_ACCESS_GRPIDS "pmix.agids" (pmix_data_array_t)
4 Array of effective Group IDs (GIDs) that are allowed to access the published data.
```

# 8.5 Publish-Lookup Datatypes

The following data types are defined for use with the **PMIx\_Publish** APIs.

# 8.5.1 Range of Published Data

6

11

12

13

14 15

16

17

18

19

20 21

22

23 24

25

26

27

28

29

33

34

35

36 37

38

39

8 PMIx v1.0 The pmix\_data\_range\_t structure is a uint8\_t type that defines a range for both data published via the PMIx\_Publish API and generated events. The following constants can be used to set a variable of the type pmix\_data\_range\_t.

**PMIX\_RANGE\_UNDEF** Undefined range.

**PMIX\_RANGE\_RM** Data is intended for the host environment, or lookup is restricted to data published by the host environment.

**PMIX\_RANGE\_LOCAL** Data is only available to processes on the local node, or lookup is restricted to data published by processes on the local node of the requester.

**PMIX\_RANGE\_NAMESPACE** Data is only available to processes in the same namespace, or lookup is restricted to data published by processes in the same namespace as the requester.

**PMIX\_RANGE\_SESSION** Data is only available to all processes in the session, or lookup is restricted to data published by other processes in the same session as the requester.

**PMIX\_RANGE\_GLOBAL** Data is available to all processes, or lookup is open to data published by anyone.

**PMIX\_RANGE\_CUSTOM** Data is available only to processes as specified in the **pmix\_info\_t** associated with this call, or lookup is restricted to data published by processes as specified in the **pmix\_info\_t**.

**PMIX\_RANGE\_PROC\_LOCAL** Data is only available to this process, or lookup is restricted to data published by this process.

**PMIX\_RANGE\_INVALID** Invalid value - typically used to indicate that a range has not yet been set.

# 8.5.2 Data Persistence Structure

The pmix\_persistence\_t structure is a uint8\_t type that defines the policy for data published by clients via the PMIx\_Publish API. The following constants can be used to set a variable of the type pmix\_persistence\_t.

**PMIX\_PERSIST\_INDEF** Retain data until specifically deleted.

**PMIX PERSIST\_FIRST\_READ** Retain data until the first access, then the data is deleted.

**PMIX\_PERSIST\_PROC** Retain data until the publishing process terminates.

**PMIX PERSIST APP** Retain data until the application terminates.

**PMIX PERSIST SESSION** Retain data until the session/allocation terminates.

**PMIX\_PERSIST\_INVALID** Invalid value - typically used to indicate that a persistence has not yet been set.

# 1 8.6 PMIx\_Lookup

2 3 4	Summary Lookup information published by this or another process with PMIx_Publish or PMIx_Publish_nb.
5 <sub>PMIx v1.0</sub>	Format C
6 7 8	<pre>pmix_status_t PMIx_Lookup(pmix_pdata_t data[], size_t ndata,</pre>
9 10 11 12 13 14 15	INOUT data Array of publishable data structures (array of pmix_pdata_t)  IN ndata Number of elements in the data array (integer)  IN info Array of info structures (array of pmix_info_t)  IN ninfo Number of elements in the info array (integer)
17 18 19	Returns PMIX_SUCCESS or one of the following error codes when the condition described occurs:  • PMIX_ERR_NOT_FOUND None of the requested data could be found within the requester's range.
20 21 22 23	• PMIX_ERR_PARTIAL_SUCCESS Some of the requested data was found. Any key that cannot be found will return with a data type of PMIX_UNDEF in the associated <i>value</i> struct. Note that the specific reason for a particular piece of missing information (e.g., lack of permissions) cannot be communicated back to the requester in this situation.
24 25 26	• PMIX_ERR_NO_PERMISSIONS All of the requested data was found and range restrictions were met for each specified key, but none of the matching data could be returned due to lack of access permissions.
27 28	If none of the above return codes are appropriate, then an implementation must return either a general PMIx error code or an implementation defined error code as described in Section 3.1.1.  Required Attributes
29 30 31 32	PMIx libraries are not required to directly support any attributes for this function. However, any provided attributes must be passed to the host environment for processing, and the PMIx library is required to add the PMIX_USERID and the PMIX_GRPID attributes of the client process that is requesting the info.

### Optional Attributes

The following attributes are optional for host environments that support this operation:

#### PMIX\_TIMEOUT "pmix.timeout" (int)

Time in seconds before the specified operation should time out (zero indicating infinite) and return the **PMIX\_ERR\_TIMEOUT** error. Care should be taken to avoid race conditions caused by multiple layers (client, server, and host) simultaneously timing the operation.

#### PMIX RANGE "pmix.range" (pmix data range t)

Define constraints on the processes that can access the provided data. Only processes that meet the constraints are allowed to access it.

#### PMIX WAIT "pmix.wait" (int)

Caller requests that the PMIx server wait until at least the specified number of values are found (a value of zero indicates *all* and is the default).

#### **Description**

Lookup information published by this or another process. By default, the search will be constrained to publishers that fall within the **PMIX\_RANGE\_SESSION** range in case duplicate keys exist on different ranges. Changes to the range (e.g., expanding the search to all potential publishers via the **PMIX\_RANGE\_GLOBAL** constant), and any additional directives, can be provided in the **pmix\_info\_t** array. Data is returned per the retrieval rules of Section 8.8.

The *data* parameter consists of an array of **pmix\_pdata\_t** structures with the keys specifying the requested information. Data will be returned for each **key** field in the associated **value** field of this structure as per the above description of return values. The **proc** field in each **pmix\_pdata\_t** structure will contain the namespace/rank of the process that published the data.

#### Advice to users ——

Although this is a blocking function, it will not wait by default for the requested data to be published. Instead, it will block for the time required by the datastore to lookup its current data and return any found items. Thus, the caller is responsible for either ensuring that data is published prior to executing a lookup, using **PMIX\_WAIT** to instruct the datastore to wait for the data to be published, or retrying until the requested data is found.

# 8.7 PMIx\_Lookup\_nb

#### Summary

Nonblocking version of **PMIx** Lookup.

IN keys
 NULL-terminated array of keys (array of strings)
 IN info
 Array of info structures (array of handles)
 IN ninfo

Number of elements in the *info* array (integer)

IN cbfunc
Callback function (handle)

IN cbdata
Callback data to be provided to the callback function (pointer)

Returns **PMIX\_SUCCESS** or a negative value indicating the error.

If executed, the status returned in the provided callback function will be one of the following constants:

- PMIX SUCCESS All data was found and has been returned.
- PMIX\_ERR\_NOT\_FOUND None of the requested data was available within the requester's range. The *pdata* array in the callback function shall be **NULL** and the *npdata* parameter set to zero.
- PMIX\_ERR\_PARTIAL\_SUCCESS Some of the requested data was found. Only found data will be included in the returned *pdata* array. Note that the specific reason for a particular piece of missing information (e.g., lack of permissions) cannot be communicated back to the requester in this situation.
- PMIX\_ERR\_NOT\_SUPPORTED There is no available datastore (either at the host environment or PMIx implementation level) on this system that supports this function.
- PMIX\_ERR\_NO\_PERMISSIONS All of the requested data was found and range restrictions
  were met for each specified key, but none of the matching data could be returned due to lack of
  access permissions.
- a non-zero PMIx error constant indicating a reason for the request's failure.

#### Required Attributes 1 PMIx libraries are not required to directly support any attributes for this function. However, any 2 provided attributes must be passed to the host environment for processing, and the PMIx library is 3 required to add the PMIX USERID and the PMIX GRPID attributes of the client process that is 4 requesting the info. Optional Attributes The following attributes are optional for host environments that support this operation: 5 6 PMIX TIMEOUT "pmix.timeout" (int) 7 Time in seconds before the specified operation should time out (zero indicating infinite) and 8 return the PMIX ERR TIMEOUT error. Care should be taken to avoid race conditions caused by multiple layers (client, server, and host) simultaneously timing the operation. 9 PMIX\_RANGE "pmix.range" (pmix\_data\_range\_t) 10 Define constraints on the processes that can access the provided data. Only processes that 11 meet the constraints are allowed to access it. 12 PMIX\_WAIT "pmix.wait" (int) 13 Caller requests that the PMIx server wait until at least the specified number of values are 14 15 found (a value of zero indicates *all* and is the default). **Description** 16 17 Non-blocking form of the **PMIx** Lookup function. **Lookup Returned Data Structure** 8.7.1 19 The pmix\_pdata\_t structure is used by PMIx\_Lookup to describe the data being accessed. PMIx v1.0 20 typedef struct pmix\_pdata { 21 pmix\_proc\_t proc; 22 pmix\_key\_t key; 23 pmix\_value\_t value; 24 pmix\_pdata\_t; 25 where: 26 • proc is the process identifier of the data publisher. 27 • key is the string key of the published data. 28 • *value* is the value associated with the *key*.

#### 8.7.1.1 Lookup data structure support macros 2 The following macros are provided to support the **pmix\_pdata\_t** structure. Initialize the pdata structure 3 Initialize the pmix\_pdata\_t fields *PMIx v1.0* 5 PMIX PDATA CONSTRUCT (m) IN 6 Pointer to the structure to be initialized (pointer to pmix\_pdata\_t) 7 8 Destruct the pdata structure Destruct the pmix\_pdata\_t fields PMIx v1.0 10 PMIX PDATA DESTRUCT (m) 11 IN m 12 Pointer to the structure to be destructed (pointer to pmix\_pdata\_t) 13 Create a pdata array 14 Allocate and initialize an array of pmix\_pdata\_t structures PMIx v1.0 15 PMIX PDATA CREATE (m, n) 16 INOUT m Address where the pointer to the array of **pmix\_pdata\_t** structures shall be stored (handle) 17 IN 18 Number of structures to be allocated (size t) 19 Free a pdata structure 20 21 Release a pmix pdata t structure PMIx v4.0 22 PMIX PDATA RELEASE (m) IN 23 24 Pointer to a pmix\_pdata\_t structure (handle)

1 2	Free a pdata array Release an array of pmix_pdata_t structures
	C
3	PMIX_PDATA_FREE(m, n)
4	IN m
5	Pointer to the array of pmix_pdata_t structures (handle)
6	IN n
7	Number of structures in the array (size_t)
8	Load a lookup data structure
9	This macro simplifies the loading of key, process identifier, and data into a pmix_pdata_t by
10	correctly assigning values to the structure's fields.
PMIx v1.0	C
11	PMIX_PDATA_LOAD(m, p, k, d, t);
11	PMIX_FDATA_HOAD (M, p, k, d, t),
12	IN m
13	Pointer to the pmix_pdata_t structure into which the key and data are to be loaded
14	(pointer to pmix_pdata_t)
15	IN p
16	Pointer to the <pre>pmix_proc_t</pre> structure containing the identifier of the process being
17	referenced (pointer to pmix_proc_t)
18	IN k
19	String key to be loaded - must be less than or equal to PMIX_MAX_KEYLEN in length
20	(handle)
21	IN d
22	Pointer to the data value to be loaded (handle)
23	IN t
24	Type of the provided data value (pmix_data_type_t)
	Advice to users
25	Key, process identifier, and data will all be copied into the <b>pmix_pdata_t</b> - thus, the source
26	information can be modified or free'd without affecting the copied data once the macro has
27	completed.

```
Transfer a lookup data structure
 1
2
              This macro simplifies the transfer of key, process identifier, and data value between
              twopmix pdata t structures.
 3
 4
              PMIX_PDATA_XFER(d, s);
              IN
5
                   d
                   Pointer to the destination pmix_pdata_t (pointer to pmix_pdata_t)
 6
 7
              IN
                   Pointer to the source pmix_pdata_t (pointer to pmix_pdata_t)
8
                                               Advice to users
9
              Key, process identifier, and data will all be copied into the destination pmix pdata t - thus, the
10
              source pmix pdata t may free'd without affecting the copied data once the macro has
              completed.
11
             Lookup Callback Function
12 8.7.2
              Summary
13
              The pmix lookup cbfunc t is used by PMIx Lookup nb to return data.
14
  PMIx v1.0
15
              typedef void (*pmix_lookup_cbfunc_t)
16
                    (pmix_status_t status,
                     pmix_pdata_t data[], size_t ndata,
17
                     void *cbdata);
18
19
              IN
                   status
20
                   Status associated with the operation (handle)
              IN
                   data
21
22
                   Array of data returned (pmix pdata t)
              IN
                   ndata
23
24
                   Number of elements in the data array (size t)
              IN
                   cbdata
25
26
                   Callback data passed to original API call (memory reference)
```

### Description

A callback function for calls to **PMIx\_Lookup\_nb**. The function will be called upon completion of the **PMIx\_Lookup\_nb** API with the *status* indicating the success or failure of the request. Any retrieved data will be returned in an array of **pmix\_pdata\_t** structs. The namespace and rank of the process that provided each data element is also returned.

Note that the <code>pmix\_pdata\_t</code> structures will be released upon return from the callback function, so the receiver must copy/protect the data prior to returning if it needs to be retained.

# 8.8 Retrieval rules for published data

The retrieval rules for published data primarily revolve around enforcing data access permissions and range constraints. The datastore shall search its stored information for each specified key according to the following precedence logic:

- 1. If the requester specified the range, then the search shall be constrained to data where the publishing process falls within the specified range.
- If the key of the stored information does not match the specified key, then the search will continue.
- 3. If the requester's identifier does not fall within the range specified by the publisher, then the search will continue.
- 4. If the publisher specified access permissions, the effective UID and GID of the requester shall be checked against those permissions, with the datastore rejecting the match if the requester fails to meet the requirements.
- 5. If all of the above checks pass, then the value is added to the information that is to be returned.
- The status returned by the datastore shall be set to:
- PMIX SUCCESS All data was found and is included in the returned information.
- PMIX ERR NOT FOUND None of the requested data could be found within a requester's range.
- PMIX\_ERR\_PARTIAL\_SUCCESS Some of the requested data was found. Only found data will be included in the returned information. Note that the specific reason for a particular piece of missing information (e.g., lack of permissions) cannot be communicated back to the requester in this situation.
- a non-zero PMIx error constant indicating a reason for the request's failure.

In the case where data was found and range restrictions were met for each specified key, but none of the matching data could be returned due to lack of access permissions, the datastore must return the **PMIX\_ERR\_NO\_PERMISSIONS** error.

#### Advice to users

Note that duplicate keys are allowed to exist on different ranges, and that ranges do overlap each other. Thus, if duplicate keys are published on overlapping ranges, it is possible for the datastore to successfully find multiple responses for a given key should publisher and requester specify sufficiently broad ranges. In this situation, the choice of resolving the duplication is left to the datastore implementation - e.g., it may return the first value found in its search, or the value corresponding to the most limited range of the found values, or it may choose to simply return an error.

Users are advised to avoid this ambiguity by careful selection of key values and ranges - e.g., by creating range-specific keys where necessary.

# 8.9 PMIx\_Unpublish

```
Summary
```

1

2

4

5

6

7

8

9

11 12

14

15

16

18

19

20

21

22 23

24 25

26 27 Unpublish data posted by this process using the given keys.

```
PMIx v1.0 Format
```

```
pmix status t
```

PMIx\_Unpublish(char \*\*keys,

const pmix\_info\_t info[], size\_t ninfo);

17 **IN** key:

**NULL**-terminated array of keys (array of strings)

IN info

Array of info structures (array of handles)

IN ninfo

Number of elements in the *info* array (integer)

Returns **PMIX SUCCESS** or a negative value indicating the error.

#### Required Attributes

PMIx libraries are not required to directly support any attributes for this function. However, any provided attributes must be passed to the host environment for processing, and the PMIx library is required to add the PMIX\_USERID and the PMIX\_GRPID attributes of the client process that is requesting the operation.

```
Optional Attributes
               The following attributes are optional for host environments that support this operation:
 1
 2
               PMIX TIMEOUT "pmix.timeout" (int)
 3
                      Time in seconds before the specified operation should time out (zero indicating infinite) and
                      return the PMIX ERR TIMEOUT error. Care should be taken to avoid race conditions
 4
                      caused by multiple layers (client, server, and host) simultaneously timing the operation.
 5
 6
               PMIX RANGE "pmix.range" (pmix data range t)
                      Define constraints on the processes that can access the provided data. Only processes that
 7
 8
                      meet the constraints are allowed to access it.
               Description
 9
               Unpublish data posted by this process using the given keys. The function will block until the data
10
               has been removed by the server (i.e., it is safe to publish that key again within the specified range).
11
               A value of NULL for the keys parameter instructs the server to remove all data published by this
12
13
               process.
               By default, the range is assumed to be PMIX RANGE SESSION. Changes to the range, and any
14
15
               additional directives, can be provided in the info array.
    8.10
              PMIx_Unpublish_nb
               Summary
17
18
               Nonblocking version of PMIx_Unpublish.
               Format
   PMIx v1.0
               pmix_status_t
20
21
               PMIx Unpublish nb (char **keys,
22
                                        const pmix_info_t info[], size_t ninfo,
23
                                        pmix op cbfunc t cbfunc, void *cbdata);
               IN
24
                     keys
                    NULL-terminated array of keys (array of strings)
25
26
                     info
27
                     Array of info structures (array of handles)
               IN
                     ninfo
28
29
                    Number of elements in the info array (integer)
30
               IN
                     cbfunc
31
                    Callback function pmix op cbfunc t (function reference)
```

#### IN chdata 1 2 Data to be passed to the callback function (memory reference) 3 A successful return indicates that the request is being processed by the host environment and the 4 result will be returned in the provided cbfunc. Note that the library must not invoke the callback function prior to returning from the API. In all other cases, the *cbfunc* will *not* be called. 5 Returns PMIX SUCCESS or one of the following error codes when the condition described occurs: 6 7 • PMIX OPERATION SUCCEEDED, indicating that the request was immediately processed and returned success - the cbfunc will not be called. 8 If none of the above return codes are appropriate, then an implementation must return either a 9 general PMIx error code or an implementation defined error code as described in Section 3.1.1. 10 Required Attributes PMIx libraries are not required to directly support any attributes for this function. However, any 11 provided attributes must be passed to the host environment for processing, and the PMIx library is 12 13 required to add the PMIX USERID and the PMIX GRPID attributes of the client process that is 14 requesting the operation. Optional Attributes -----15 The following attributes are optional for host environments that support this operation: PMIX TIMEOUT "pmix.timeout" (int) 16 Time in seconds before the specified operation should time out (zero indicating infinite) and 17 return the PMIX ERR TIMEOUT error. Care should be taken to avoid race conditions 18 19 caused by multiple layers (client, server, and host) simultaneously timing the operation. 20 PMIX\_RANGE "pmix.range" (pmix\_data\_range\_t) 21 Define constraints on the processes that can access the provided data. Only processes that 22 meet the constraints are allowed to access it. Description 23 24 Non-blocking form of the PMIx\_Unpublish function. The callback function will be executed 25 once the server confirms removal of the specified data. The info array must be maintained until the

callback is provided.

26

#### **CHAPTER 9**

# **Event Notification**

This chapter defines the PMIx event notification system. These interfaces are designed to support the reporting of events to/from clients and servers, and between library layers within a single process.

# 9.1 Notification and Management

PMIx event notification provides an asynchronous out-of-band mechanism for communicating events between application processes and/or elements of the SMS. Its uses span a wide range including fault notification, coordination between multiple programming libraries within a single process, and workflow orchestration for non-synchronous programming models. Events can be divided into two distinct classes:

- *Job-specific events* directly relate to a job executing within the session, such as a debugger attachment, process failure within a related job, or events generated by an application process. Events in this category are to be immediately delivered to the PMIx server library for relay to the related local processes.
- Environment events indirectly relate to a job but do not specifically target the job itself. This category includes SMS-generated events such as Error Check and Correction (ECC) errors, temperature excursions, and other non-job conditions that might directly affect a session's resources, but would never include an event generated by an application process. Note that although these do potentially impact the session's jobs, they are not directly tied to those jobs. Thus, events in this category are to be delivered to the PMIx server library only upon request.

Both SMS elements and applications can register for events of either type.

## Advice to PMIx library implementers

Race conditions can cause the registration to come after events of possible interest (e.g., a memory ECC event that occurs after start of execution but prior to registration, or an application process generating an event prior to another process registering to receive it). SMS vendors are *requested* to cache environment events for some time to mitigate this situation, but are not *required* to do so. However, PMIx implementers are *required* to cache all events received by the PMIx server library and to deliver them to registering clients in the same order in which they were received

Applications must be aware that they may not receive environment events that occur prior to registration, depending upon the capabilities of the host SMS.

The generator of an event can specify the *target range* for delivery of that event. Thus, the generator can choose to limit notification to processes on the local node, processes within the same job as the generator, processes within the same allocation, other threads within the same process, only the SMS (i.e., not to any application processes), all application processes, or to a custom range based on specific process identifiers. Only processes within the given range that register for the provided event code will be notified. In addition, the generator can use attributes to direct that the event not be delivered to any default event handlers, or to any multi-code handler (as defined below).

Event notifications provide the process identifier of the source of the event plus the event code and any additional information provided by the generator. When an event notification is received by a process, the registered handlers are scanned for their event code(s), with matching handlers assembled into an *event chain* for servicing. Note that users can also specify a *source range* when registering an event (using the same range designators described above) to further limit when they are to be invoked. When assembled, PMIx event chains are ordered based on both the specificity of the event handler and user directives at time of handler registration. By default, handlers are grouped into three categories based on the number of event codes that can trigger the callback:

- *single-code* handlers are serviced first as they are the most specific. These are handlers that are registered against one specific event code.
- *multi-code* handlers are serviced once all single-code handlers have completed. The handler will be included in the chain upon receipt of an event matching any of the provided codes.
- *default* handlers are serviced once all multi-code handlers have completed. These handlers are always included in the chain unless the generator specifically excludes them.

Users can specify the callback order of a handler within its category at the time of registration. Ordering can be specified either by providing the relevant returned event handler registration ID or using event handler names, if the user specified an event handler name when registering the corresponding event. Thus, users can specify that a given handler be executed before or after another handler should both handlers appear in an event chain (the ordering is ignored if the other handler isn't included). Note that ordering does not imply immediate relationships. For example, multiple handlers registered to be serviced after event handler *A* will all be executed after *A*, but are not guaranteed to be executed in any particular order amongst themselves.

In addition, one event handler can be declared as the *first* handler to be executed in the chain. This handler will *always* be called prior to any other handler, regardless of category, provided the incoming event matches both the specified range and event code. Only one handler can be so designated — attempts to designate additional handlers as *first* will return an error. Deregistration of the declared *first* handler will re-open the position for subsequent assignment.

Similarly, one event handler can be declared as the *last* handler to be executed in the chain. This handler will *always* be called after all other handlers have executed, regardless of category, provided the incoming event matches both the specified range and event code. Note that this handler will not be called if the chain is terminated by an earlier handler. Only one handler can be designated as *last* — attempts to designate additional handlers as *last* will return an error. Deregistration of the declared *last* handler will re-open the position for subsequent assignment.

#### Advice to users

Note that the *last* handler is called *after* all registered default handlers that match the specified range of the incoming event unless a handler prior to it terminates the chain. Thus, if the application intends to define a *last* handler, it should ensure that no default handler aborts the process before it.

Upon completing its work and prior to returning, each handler *must* call the event handler completion function provided when it was invoked (including a status code plus any information to be passed to later handlers) so that the chain can continue being progressed. PMIx automatically aggregates the status and any results of each handler (as provided in the completion callback) with status from all prior handlers so that each step in the chain has full knowledge of what preceded it. An event handler can terminate all further progress along the chain by passing the PMIX EVENT ACTION COMPLETE status to the completion callback function.

## 17 9.1.1 Events versus status constants

Return status constants (see Section 3.1.1) represent values that can be returned from or passed into PMIx APIs. These are distinct from PMIx *events* in that they are not values that can be registered against event handlers. In general, the two types of constants are distinguished by inclusion of an "ERR" in the name of error constants versus an "EVENT" in events, though there are exceptions (e.g., the PMIX\_SUCCESS constant).

# 3 9.1.2 PMIx\_Register\_event\_handler

#### **Summary** 25 Register an e

Register an event handler.

mix_status_t
<pre>MIx_Register_event_handler(pmix_status_t codes[], size_t ncodes,</pre>
<pre>pmix_info_t info[], size_t ninfo,</pre>
<pre>pmix_notification_fn_t evhdlr,</pre>
pmix_hdlr_reg_cbfunc_t cbfunc,
<pre>void *cbdata);</pre>

IN codes

Array of status codes (array of pmix\_status\_t)

N ncodes

Number of elements in the *codes* array (size\_t)

IN info

Array of info structures (array of handles)

IN ninfo

Number of elements in the *info* array (size t)

IN evhdlr

Event handler to be called **pmix notification fn t** (function reference)

IN cbfunc

Callback function pmix\_hdlr\_reg\_cbfunc\_t (function reference)

IN cbdata

Data to be passed to the cbfunc callback function (memory reference)

If *cbfunc* is **NULL**, the function call will be treated as a *blocking* call. In this case, the returned status will be either (a) the event handler reference identifier if the value is greater than or equal to zero, or (b) a negative error code indicative of the reason for the failure.

If the *cbfunc* is non-**NULL**, the function call will be treated as a *non-blocking* call and will return the following:

A successful return indicates that the request is being processed by the host environment and the result will be returned in the provided *cbfunc*. Note that the library must not invoke the callback function prior to returning from the API. In all other cases, the *cbfunc* will *not* be called. The result of the registration operation shall be returned in the provided callback function along with the assigned event handler identifier.

Returns PMIX\_SUCCESS or one of the following error codes when the condition described occurs:

PMIX\_ERR\_EVENT\_REGISTRATION indicating that the registration has failed for an
undetermined reason.

If none of the above return codes are appropriate, then an implementation must return either a general PMIx error code or an implementation defined error code as described in Section 3.1.1.

1 2 3	The callback function must not be executed prior to returning from the API, and no events corresponding to this registration may be delivered prior to the completion of the registration callback function ( <i>cbfunc</i> ).
	Required Attributes
4	The following attributes are required to be supported by all PMIx libraries:
5 6	PMIX_EVENT_HDLR_NAME "pmix.evname" (char*) String name identifying this handler.
7 8	PMIX_EVENT_HDLR_FIRST "pmix.evfirst" (bool) Invoke this event handler before any other handlers.
9 10	PMIX_EVENT_HDLR_LAST "pmix.evlast" (bool)  Invoke this event handler after all other handlers have been called.
11 12	<pre>PMIX_EVENT_HDLR_FIRST_IN_CATEGORY "pmix.evfirstcat" (bool) Invoke this event handler before any other handlers in this category.</pre>
13 14	<pre>PMIX_EVENT_HDLR_LAST_IN_CATEGORY "pmix.evlastcat" (bool)</pre> Invoke this event handler after all other handlers in this category have been called.
15 16	<pre>PMIX_EVENT_HDLR_BEFORE "pmix.evbefore" (char*) Put this event handler immediately before the one specified in the (char*) value.</pre>
17 18	<pre>PMIX_EVENT_HDLR_AFTER "pmix.evafter" (char*) Put this event handler immediately after the one specified in the (char*) value.</pre>
19 20	PMIX_EVENT_HDLR_PREPEND "pmix.evprepend" (bool)  Prepend this handler to the precedence list within its category.
21 22	PMIX_EVENT_HDLR_APPEND "pmix.evappend" (bool) Append this handler to the precedence list within its category.
23 24	<pre>PMIX_EVENT_CUSTOM_RANGE "pmix.evrange" (pmix_data_array_t*) Array of pmix_proc_t defining range of event notification.</pre>
25 26 27	<pre>PMIX_RANGE "pmix.range" (pmix_data_range_t) Define constraints on the processes that can access the provided data. Only processes that meet the constraints are allowed to access it.</pre>
28 29 30	PMIX_EVENT_RETURN_OBJECT "pmix.evobject" (void *)  Object to be returned whenever the registered callback function cbfunc is invoked. The object will only be returned to the process that registered it

Host environments that implement support for PMIx event notification are required to support the following attributes when registering handlers - these attributes are used to direct that the handler should be invoked only when the event affects the indicated process(es):

should be invoked only when the event affects the indicated process(es):

PMIX\_EVENT\_AFFECTED\_PROC "pmix.evproc" (pmix\_proc\_t)

The single process that was affected.

Description

Register an event handler to report events. Note that the codes being registered do *not* need to be PMIx error constants — any integer value can be registered. This allows for registration of non-PMIx events such as those defined by a particular SMS vendor or by an application itself.

Advice to users

In order to avoid potential conflicts, users are advised to only define codes that lie outside the range of the PMIx standard's error codes. Thus, SMS vendors and application developers should constrain their definitions to positive values or negative values beyond the PMIX EXTERNAL ERR BASE boundary.

## Advice to users -

As previously stated, upon completing its work, and prior to returning, each handler *must* call the event handler completion function provided when it was invoked (including a status code plus any information to be passed to later handlers) so that the chain can continue being progressed. An event handler can terminate all further progress along the chain by passing the <code>PMIX\_EVENT\_ACTION\_COMPLETE</code> status to the completion callback function. Note that the parameters passed to the event handler (e.g., the *info* and *results* arrays) will cease to be valid once the completion function has been called - thus, any information in the incoming parameters that will be referenced following the call to the completion function must be copied.

# 9.1.3 Event registration constants

**PMIX ERR EVENT REGISTRATION** Error in event registration.

# 1 9.1.4 System events

2 3 4 5 6 7 8 9	<ul> <li>PMIX_EVENT_SYS_BASE</li></ul>
10 11 12 <i>PMIx v2.</i>	Detect system event constant  Test a given event constant to see if it falls within the dedicated range of constants for system event reporting.  C
13	PMIX_SYSTEM_EVENT(a)
14 15	IN a Error constant to be checked (pmix_status_t)
16 17	Returns <b>true</b> if the provided values falls within the dedicated range of events for system event reporting.
18 9.1.5	Event handler registration and notification attributes
19	Attributes to support event registration and notification.
20 21 22 23 24 25 26 27 28 29 30 31 32 33	PMIX_EVENT_HDLR_NAME "pmix.evname" (char*) String name identifying this handler.  PMIX_EVENT_HDLR_FIRST "pmix.evfirst" (bool) Invoke this event handler before any other handlers.  PMIX_EVENT_HDLR_LAST "pmix.evlast" (bool) Invoke this event handler after all other handlers have been called.  PMIX_EVENT_HDLR_FIRST_IN_CATEGORY "pmix.evfirstcat" (bool) Invoke this event handler before any other handlers in this category.  PMIX_EVENT_HDLR_LAST_IN_CATEGORY "pmix.evlastcat" (bool) Invoke this event handler after all other handlers in this category have been called.  PMIX_EVENT_HDLR_BEFORE "pmix.evbefore" (char*) Put this event handler immediately before the one specified in the (char*) value.  PMIX_EVENT_HDLR_AFTER "pmix.evafter" (char*)
<del>-</del>	Put this event handler immediately after the one specified in the (char*) value.  PMIX_EVENT_HDLR_PREPEND "pmix.evprepend" (bool)  Prepend this handler to the precedence list within its category.

```
1
              PMIX_EVENT_HDLR_APPEND "pmix.evappend" (bool)
2
                    Append this handler to the precedence list within its category.
              PMIX EVENT_CUSTOM_RANGE "pmix.evrange" (pmix_data_array_t*)
 3
 4
                    Array of pmix proc t defining range of event notification.
              PMIX_EVENT_AFFECTED_PROC "pmix.evproc" (pmix_proc_t)
5
6
                    The single process that was affected.
              PMIX EVENT_AFFECTED_PROCS "pmix.evaffected" (pmix_data_array_t*)
7
                    Array of pmix_proc_t defining affected processes.
8
9
              PMIX_EVENT_NON_DEFAULT "pmix.evnondef" (bool)
10
                    Event is not to be delivered to default event handlers.
11
              PMIX_EVENT_RETURN_OBJECT "pmix.evobject" (void *)
                    Object to be returned whenever the registered callback function cbfunc is invoked. The
12
                    object will only be returned to the process that registered it.
13
14
              PMIX_EVENT_DO_NOT_CACHE "pmix.evnocache" (bool)
                    Instruct the PMIx server not to cache the event.
15
16
              PMIX EVENT PROXY "pmix.evproxy" (pmix proc t*)
                    PMIx server that sourced the event.
17
18
              PMIX EVENT TEXT MESSAGE "pmix.evtext" (char*)
                    Text message suitable for output by recipient - e.g., describing the cause of the event.
19
20
              PMIX EVENT TIMESTAMP "pmix.evtstamp" (time t)
21
                    System time when the associated event occurred.
    9.1.5.1
22
              Fault tolerance event attributes
              The following attributes may be used by the host environment when providing an event notification
23
              as qualifiers indicating the action it intends to take in response to the event:
24
              PMIX_EVENT_TERMINATE_SESSION "pmix.evterm.sess" (bool)
25
                    The RM intends to terminate this session.
26
27
              PMIX_EVENT_TERMINATE_JOB "pmix.evterm.job" (bool)
                    The RM intends to terminate this job.
28
29
              PMIX_EVENT_TERMINATE_NODE "pmix.evterm.node" (bool)
30
                    The RM intends to terminate all processes on this node.
31
              PMIX_EVENT_TERMINATE_PROC "pmix.evterm.proc" (bool)
                    The RM intends to terminate just this process.
32
              PMIX_EVENT_ACTION_TIMEOUT "pmix.evtimeout" (int)
33
34
                    The time in seconds before the RM will execute the indicated operation.
              Hybrid programming event attributes
    9.1.5.2
35
              The following attributes may be used by programming models to coordinate their use of common
36
37
              resources within a process in conjunction with the PMIX OPENMP PARALLEL ENTERED event:
              PMIX MODEL PHASE NAME "pmix.mdl.phase" (char*)
38
                    User-assigned name for a phase in the application execution (e.g., "cfd reduction").
39
40
              PMIX MODEL PHASE TYPE "pmix.mdl.ptype" (char*)
                    Type of phase being executed (e.g., "matrix multiply").
41
```

## 9.1.6 Notification Function

#### Summary 2 The **pmix\_notification\_fn\_t** is called by PMIx to deliver notification of an event. 3 Advice to users 4 The PMIx ad hoc v1.0 Standard defined an error notification function with an identical name, but different signature than the v2.0 Standard described below. The ad hoc v1.0 version was removed 5 6 from the v2.0 Standard is not included in this document to avoid confusion. PMIx v2.0 7 typedef void (\*pmix\_notification\_fn\_t) (size\_t evhdlr\_registration\_id, 8 pmix\_status\_t status, 9 10 const pmix\_proc\_t \*source, pmix\_info\_t info[], size\_t ninfo, 11 pmix\_info\_t results[], size\_t nresults, 12 pmix\_event\_notification\_cbfunc\_fn\_t cbfunc, 13 14 void \*cbdata); 15 IN evhdlr\_registration\_id Registration number of the handler being called (size\_t) 16 IN 17 status Status associated with the operation (pmix\_status\_t) 18 19 IN source Identifier of the process that generated the event (pmix\_proc\_t). If the source is the SMS, 20 then the nspace will be empty and the rank will be PMIX\_RANK\_UNDEF 21 IN 22 info Information describing the event (pmix\_info\_t). This argument will be NULL if no 23 24 additional information was provided by the event generator. IN ninfo 25 Number of elements in the info array (size\_t) 26 IN 27 28 Aggregated results from prior event handlers servicing this event (pmix\_info\_t). This 29 argument will be **NULL** if this is the first handler servicing the event, or if no prior handlers 30 provided results. IN nresults 31 32 Number of elements in the results array (size\_t) 33 IN cbfunc pmix\_event\_notification\_cbfunc\_fn\_t callback function to be executed upon 34 completion of the handler's operation and prior to handler return (function reference). 35

#### IN chdata

Callback data to be passed to cbfunc (memory reference)

### Description

Note that different RMs may provide differing levels of support for event notification to application processes. Thus, the *info* array may be **NULL** or may contain detailed information of the event. It is the responsibility of the application to parse any provided info array for defined key-values if it so desires.

#### Advice to users

Possible uses of the info array include:

- for the host RM to alert the process as to planned actions, such as aborting the session, in response to the reported event
- provide a timeout for alternative action to occur, such as for the application to request an alternate response to the event

For example, the RM might alert the application to the failure of a node that resulted in termination of several processes, and indicate that the overall session will be aborted unless the application requests an alternative behavior in the next 5 seconds. The application then has time to respond with a checkpoint request, or a request to recover from the failure by obtaining replacement nodes and restarting from some earlier checkpoint.

Support for these options is left to the discretion of the host RM. Info keys are included in the common definitions above but may be augmented by environment vendors.

## Advice to PMIx server hosts -

On the server side, the notification function is used to inform the PMIx server library's host of a detected event in the PMIx server library. Events generated by PMIx clients are communicated to the PMIx server library, but will be relayed to the host via the pmix\_server\_notify\_event\_fn\_t function pointer, if provided.

# 9.1.7 PMIx\_Deregister\_event\_handler

### Summary

Deregister an event handler.

1	Format C
2	pmix_status_t
3	PMIx_Deregister_event_handler(size_t evhdlr_ref,
4	pmix_op_cbfunc_t cbfunc,
5	void *cbdata);
	C
6	IN evhdlr_ref
7 8	Event handler ID returned by registration (size_t)  IN cbfunc
9	Callback function to be executed upon completion of operation pmix_op_cbfunc_t
10	(function reference)
11	IN cbdata
12	Data to be passed to the cbfunc callback function (memory reference)
13	If <i>cbfunc</i> is <b>NULL</b> , the function will be treated as a <i>blocking</i> call and the result of the operation
14	returned in the status code.
15	If <i>cbfunc</i> is non- <b>NULL</b> , the function will be treated as a <i>non-blocking</i> call.
16 17 18	A successful return indicates that the request is being processed by the host environment and the result will be returned in the provided <i>cbfunc</i> . Note that the library must not invoke the callback function prior to returning from the API. In all other cases, the <i>cbfunc</i> will <i>not</i> be called.
19 20	<ul> <li>PMIX_OPERATION_SUCCEEDED, returned only when cbfunc is non-NULL and the request was immediately processed successfully - the cbfunc will not be called</li> </ul>
21	The returned status code of <i>cbfunc</i> will be one of the following:
22	• PMIX_SUCCESS The event handler was successfully deregistered.
23	• PMIX_ERR_BAD_PARAM The provided <i>evhdlr_ref</i> was unrecognized.
24	• PMIX_ERR_NOT_SUPPORTED The PMIx implementation does not support event notification.
25	Description
26	Deregister an event handler. Note that no events corresponding to the referenced registration may
27	be delivered following completion of the deregistration operation (either return from the API with
28	<b>PMIX_OPERATION_SUCCEEDED</b> or execution of the <i>cbfunc</i> ).
29	9.1.8 PMIx_Notify_event

Report an event for notification via any registered event handler.

Summary

30

31

pmix status t

1

2

7

10

14 15 16

17 18 19

20 21 22

23

24 25

262728

30

29

32 33

35 36

34

36 37

P	
PMIx_Notify_eve	ent(pmix_status_t status,
	<pre>const pmix_proc_t *source,</pre>
	<pre>pmix_data_range_t range,</pre>
	<pre>pmix_info_t info[], size_t ninfo,</pre>
	<pre>pmix_op_cbfunc_t cbfunc, void *cbdata);</pre>
	•

IN status

Status code of the event (pmix\_status\_t)

IN source

Pointer to a pmix\_proc\_t identifying the original reporter of the event (handle)

IN range

Range across which this notification shall be delivered (pmix\_data\_range\_t)

IN info

Array of **pmix\_info\_t** structures containing any further info provided by the originator of the event (array of handles)

IN ninfo

Number of elements in the *info* array (size\_t)

IN cbfunc

Callback function to be executed upon completion of operation  ${\tt pmix\_op\_cbfunc\_t}$  (function reference)

IN cbdata

Data to be passed to the cbfunc callback function (memory reference)

If *cbfunc* is **NULL**, the function will be treated as a *blocking* call and the result of the operation returned in the status code.

If *cbfunc* is non-**NULL**, the function will be treated as a *non-blocking* call.

A successful return indicates that the request is being processed by the host environment and the result will be returned in the provided *cbfunc*. Note that the library must not invoke the callback function prior to returning from the API. In all other cases, the *cbfunc* will *not* be called.Note that a successful call does *not* reflect the success or failure of delivering the event to any recipients.

Returns PMIX\_SUCCESS or one of the following error codes when the condition described occurs:

- PMIX\_OPERATION\_SUCCEEDED, returned only when *cbfunc* is non-NULL and the request was immediately processed successfully the *cbfunc* will *not* be called
- PMIX\_ERR\_BAD\_PARAM The request contains at least one incorrect entry that prevents it from being processed. The callback function will *not* be called.

If none of the above return codes are appropriate, then an implementation must return either a general PMIx error code or an implementation defined error code as described in Section 3.1.1.

•	Required Attributes
T	The following attributes are required to be supported by all PMIx libraries:
P	Event is not to be delivered to default event handlers.
P	MIX_EVENT_CUSTOM_RANGE "pmix.evrange" (pmix_data_array_t*) Array of pmix_proc_t defining range of event notification.
P	Instruct the PMIx server not to cache the event.
P	PMIX_EVENT_PROXY "pmix.evproxy" (pmix_proc_t*) PMIx server that sourced the event.
P	Text message suitable for output by recipient - e.g., describing the cause of the event.
	Host environments that implement support for PMIx event notification are required to provide the ollowing attributes for all events generated by the environment:
P	MIX_EVENT_AFFECTED_PROC "pmix.evproc" (pmix_proc_t) The single process that was affected.
P	MIX_EVENT_AFFECTED_PROCS "pmix.evaffected" (pmix_data_array_t*) Array of pmix_proc_t defining affected processes.
•	Optional Attributes
e	Host environments that support PMIx event notification may offer notifications for environmental vents impacting the job and for SMS events relating to the job. The following attributes may ptionally be included to indicate the host environment's intended response to the event:
P	MIX_EVENT_TERMINATE_SESSION "pmix.evterm.sess" (bool) The RM intends to terminate this session.
P	The RM intends to terminate this job.  "pmix.evterm.job" (bool)
P	MIX_EVENT_TERMINATE_NODE "pmix.evterm.node" (bool) The RM intends to terminate all processes on this node.
P	The RM intends to terminate just this process. (bool)
P	MIX_EVENT_ACTION_TIMEOUT "pmix.evtimeout" (int)  The time in seconds before the RM will execute the indicated operation.

### Description

Report an event for notification via any registered event handler. This function can be called by any PMIx process, including application processes, PMIx servers, and SMS elements. The PMIx server calls this API to report events it detected itself so that the host SMS daemon distribute and handle them, and to pass events given to it by its host down to any attached client processes for processing. Examples might include notification of the failure of another process, detection of an impending node failure due to rising temperatures, or an intent to preempt the application. Events may be locally generated or come from anywhere in the system.

Host SMS daemons call the API to pass events down to its embedded PMIx server both for transmittal to local client processes and for the host's own internal processing where the host has registered its own event handlers. The PMIx server library is not allowed to echo any event given to it by its host via this API back to the host through the <code>pmix\_server\_notify\_event\_fn\_t</code> server module function. The host is required to deliver the event to all PMIx servers where the targeted processes either are currently running, or (if they haven't started yet) might be running at some point in the future as the events are required to be cached by the PMIx server library.

Client application processes can call this function to notify the SMS and/or other application processes of an event it encountered. Note that processes are not constrained to report status values defined in the official PMIx standard — any integer value can be used. Thus, applications are free to define their own internal events and use the notification system for their own internal purposes.

### Advice to users -

The callback function will be called upon completion of the **notify\_event** function's actions. At that time, any messages required for executing the operation (e.g., to send the notification to the local PMIx server) will have been queued, but may not yet have been transmitted. The caller is required to maintain the input data until the callback function has been executed — the sole purpose of the callback function is to indicate when the input data is no longer required.

# 9.1.9 Notification Handler Completion Callback Function

#### Summary 2 3 The pmix\_event\_notification\_cbfunc\_fn\_t is called by event handlers to indicate completion of their operations. 4 typedef void (\*pmix event notification cbfunc fn t) 5 (pmix status t status, 6 7 pmix\_info\_t \*results, size\_t nresults, pmix op cbfunc t cbfunc, void \*thiscbdata, 8 9 void \*notification cbdata); IN status 10 11 Status returned by the event handler's operation (pmix\_status\_t) IN results 12 Results from this event handler's operation on the event (pmix\_info\_t) 13 14 IN nresults Number of elements in the results array (size t) 15 IN cbfunc 16 pmix op cbfunc t function to be executed when PMIx completes processing the 17 18 callback (function reference) thiscbdata 19 Callback data that was passed in to the handler (memory reference) 20 IN cbdata 21 Callback data to be returned when PMIx executes cbfunc (memory reference) 22 23 Description Define a callback by which an event handler can notify the PMIx library that it has completed its 24 response to the notification. The handler is required to execute this callback so the library can 25 determine if additional handlers need to be called. The handler shall return 26 27 PMIX EVENT ACTION COMPLETE if no further action is required. The return status of each 28 event handler and any returned **pmix info** t structures will be added to the results array of pmix info t passed to any subsequent event handlers to help guide their operation. 29 If non-NULL, the provided callback function will be called to allow the event handler to release the 30 provided info array and execute any other required cleanup operations. 31 9.1.9.1 **Completion Callback Function Status Codes** 33 The following status code may be returned indicating various actions taken by other event handlers. PMIX EVENT NO ACTION TAKEN Event handler: No action taken. 34 PMIX EVENT PARTIAL ACTION TAKEN Event handler: Partial action taken. 35 PMIX EVENT ACTION DEFERRED Event handler: Action deferred. 36

PMIX EVENT ACTION COMPLETE

37

Event handler: Action complete.

#### **CHAPTER 10**

2

3

4 5

6

7

# **Data Packing and Unpacking**

PMIx intentionally does not include support for internode communications in the standard, instead relying on its host SMS environment to transfer any needed data and/or requests between nodes. These operations frequently involve PMIx-defined public data structures that include binary data. Many HPC clusters are homogeneous, and so transferring the structures can be done rather simply. However, greater effort is required in heterogeneous environments to ensure binary data is correctly transferred. PMIx buffer manipulation functions are provided for this purpose via standardized interfaces to ease adoption.

# 10.1 Data Buffer Type

```
The pmix data buffer t structure describes a data buffer used for packing and unpacking.
  PMIx v2.0
            typedef struct pmix_data_buffer {
10
                 /** Start of my memory */
11
12
                 char *base ptr;
                 /** Where the next data will be packed to
13
14
                     (within the allocated memory starting
                     at base_ptr) */
15
16
                 char *pack_ptr;
17
                 /** Where the next data will be unpacked
18
                     from (within the allocated memory
19
                     starting as base_ptr) */
20
                 char *unpack_ptr;
                 /** Number of bytes allocated (starting
21
22
                     at base_ptr) */
23
                 size_t bytes_allocated;
                 /** Number of bytes used by the buffer
24
25
                     (i.e., amount of data -- including
                     overhead -- packed in the buffer) */
26
27
                 size t bytes used;
28
             } pmix data buffer t;
```

# 1 10.2 Support Macros

2		PMIx provides a set of convenience macros for creating, initiating, and releasing data buffers.
3 4 5	PMIx v2.0	PMIX_DATA_BUFFER_CREATE Allocate memory for a pmix_data_buffer_t object and initialize it. This macro uses calloc to allocate memory for the buffer and initialize all fields in it  C
6		PMIX_DATA_BUFFER_CREATE (buffer);
7 8		OUT buffer Variable to be assigned the pointer to the allocated pmix_data_buffer_t (handle)
9		PMIX DATA BUFFER RELEASE
10		Free a pmix_data_buffer_t object and the data it contains. Free's the data contained in the
11		buffer, and then free's the buffer itself
	PMIx v2.0	C
	11,11,7,10	
12		PMIX_DATA_BUFFER_RELEASE (buffer);
		C
		IN 1 CC
13		IN buffer
14		Pointer to the <b>pmix_data_buffer_t</b> to be released (handle)
15		PMIX_DATA_BUFFER_CONSTRUCT
16		Initialize a statically declared pmix_data_buffer_t object.
10	PMIx v2.0	initialize a statically declared pinta_data_buffer_c object.
	I WIIX V2.0	
17		<pre>PMIX_DATA_BUFFER_CONSTRUCT(buffer);</pre>
		C
8		IN buffer
19		Pointer to the allocated <pre>pmix_data_buffer_t</pre> that is to be initialized (handle)
		DATA DATA DURANG DEGEDUGE
20		PMIX_DATA_BUFFER_DESTRUCT
21	D144 2 0	Release the data contained in a pmix_data_buffer_t object.
	PMIx v2.0	<u> </u>
22		<pre>PMIX_DATA_BUFFER_DESTRUCT(buffer);</pre>
		C
23		IN buffer
24		Pointer to the pmix_data_buffer_t whose data is to be released (handle)

```
1
               PMIX_DATA_BUFFER_LOAD
               Load a blob into a pmix_data_buffer_t object. Load the given data into the provided
 2
               pmix data buffer t object, usually done in preparation for unpacking the provided data.
 3
 4
               Note that the data is not copied into the buffer - thus, the blob must not be released until after
               operations on the buffer have completed.
  PMIx v2.0
 6
               PMIX DATA BUFFER LOAD (buffer, data, size);
 7
               IN
                     buffer
                    Pointer to a pre-allocated pmix_data_buffer_t (handle)
 8
               IN
 9
                     data
10
                    Pointer to a blob (char*)
11
               IN
                     size
12
                    Number of bytes in the blob size_t
13
               PMIX DATA BUFFER UNLOAD
               Unload the data from a pmix_data_buffer_t object. Extract the data in a buffer, assigning the
14
15
               pointer to the data (and the number of bytes in the blob) to the provided variables, usually done to
               transmit the blob to a remote process for unpacking. The buffer's internal pointer will be set to
16
               NULL to protect the data upon buffer destruct or release - thus, the user is responsible for releasing
17
18
               the blob when done with it.
  PMIx v2.0
19
               PMIX DATA BUFFER UNLOAD (buffer,
                                                           data, size);
20
               IN
                   buffer
21
                    Pointer to the pmix_data_buffer_t whose data is to be extracted (handle)
22
               OUT data
23
                    Variable to be assigned the pointer to the extracted blob (void*)
24
               OUT size
25
                     Variable to be assigned the number of bytes in the blob size_t
    10.3
               General Routines
27
                The following routines are provided to support internode transfers in heterogeneous environments.
```

# 8 10.3.1 PMIx Data pack

### Summary

Pack one or more values of a specified type into a buffer, usually for transmission to another process.

29

30

### IN target

Pointer to a <code>pmix\_proc\_t</code> containing the nspace/rank of the process that will be unpacking the final buffer. A NULL value may be used to indicate that the target is based on the same PMIx version as the caller. Note that only the target's nspace is relevant. (handle)

#### IN buffer

Pointer to a pmix\_data\_buffer\_t where the packed data is to be stored (handle)

#### IN src

Pointer to a location where the data resides. Strings are to be passed as (char \*\*) — i.e., the caller must pass the address of the pointer to the string as the (void\*). This allows the caller to pass multiple strings in a single call. (memory reference)

#### IN num\_vals

Number of elements pointed to by the *src* pointer. A string value is counted as a single value regardless of length. The values must be contiguous in memory. Arrays of pointers (e.g., string arrays) should be contiguous, although the data pointed to need not be contiguous across array entries.(int32\_t)

### IN type

The type of the data to be packed (pmix data type t)

Returns PMIX SUCCESS or one of the following error codes when the condition described occurs:

```
PMIX_ERR_BAD_PARAM The provided buffer or src is NULL
PMIX_ERR_UNKNOWN_DATA_TYPE The specified data type is not known to this implementation
```

PMIX\_ERR\_OUT\_OF\_RESOURCE Not enough memory to support the operation

If none of the above return codes are appropriate, then an implementation must return either a general PMIx error code or an implementation defined error code as described in Section 3.1.1.

# Description

The pack function packs one or more values of a specified type into the specified buffer. The buffer must have already been initialized via the **PMIX\_DATA\_BUFFER\_CREATE** or **PMIX\_DATA\_BUFFER\_CONSTRUCT** macros — otherwise, **PMIx\_Data\_pack** will return an error. Providing an unsupported type flag will likewise be reported as an error.

Note that any data to be packed that is not hard type cast (i.e., not type cast to a specific size) may lose precision when unpacked by a non-homogeneous recipient. The PMIx\_Data\_pack function will do its best to deal with heterogeneity issues between the packer and unpacker in such cases.

Sending a number larger than can be handled by the recipient will return an error code (generated upon unpacking) — the error cannot be detected during packing.

The namespace of the intended recipient of the packed buffer (i.e., the process that will be unpacking it) is used solely to resolve any data type differences between PMIx versions. The recipient must, therefore, be known to the user prior to calling the pack function so that the PMIx library is aware of the version the recipient is using. Note that all processes in a given namespace are *required* to use the same PMIx version — thus, the caller must only know at least one process from the target's namespace.

# 10.3.2 PMIx Data unpack

#### Summary

Unpack values from a pmix\_data\_buffer\_t

# $^{12}$ *PMIx* v2.0

# Format

pmix status t

#### IN source

Pointer to a pmix\_proc\_t structure containing the nspace/rank of the process that packed the provided buffer. A NULL value may be used to indicate that the source is based on the same PMIx version as the caller. Note that only the source's nspace is relevant. (handle)

#### IN buffer

A pointer to the buffer from which the value will be extracted. (handle)

#### INOUT dest

A pointer to the memory location into which the data is to be stored. Note that these values will be stored contiguously in memory. For strings, this pointer must be to (char\*\*) to provide a means of supporting multiple string operations. The unpack function will allocate memory for each string in the array - the caller must only provide adequate memory for the array of pointers. (void\*)

#### INOUT max num values

The number of values to be unpacked — upon completion, the parameter will be set to the actual number of values unpacked. In most cases, this should match the maximum number provided in the parameters — but in no case will it exceed the value of this parameter. Note that unpacking fewer values than are actually available will leave the buffer in an unpackable state — the function will return an error code to warn of this condition.(int32 t)

#### IN type

The type of the data to be unpacked — must be one of the PMIx defined data types (pmix\_data\_type\_t)

Returns PMIX SUCCESS or one of the following error codes when the condition described occurs:

PMIX\_ERR\_BAD\_PARAM The provided buffer or dest is NULL
PMIX\_ERR\_UNKNOWN\_DATA\_TYPE The specified data type is not known to this implementation

PMIX\_ERR\_OUT\_OF\_RESOURCE Not enough memory to support the operation

If none of the above return codes are appropriate, then an implementation must return either a general PMIx error code or an implementation defined error code as described in Section 3.1.1.

#### **Description**

The unpack function unpacks the next value (or values) of a specified type from the given buffer. The buffer must have already been initialized via an PMIX\_DATA\_BUFFER\_CREATE or PMIX\_DATA\_BUFFER\_CONSTRUCT call (and assumedly filled with some data) — otherwise, the unpack\_value function will return an error. Providing an unsupported type flag will likewise be reported as an error, as will specifying a data type that *does not* match the type of the next item in the buffer. An attempt to read beyond the end of the stored data held in the buffer will also return an error.

Note that it is possible for the buffer to be corrupted and that PMIx will *think* there is a proper variable type at the beginning of an unpack region — but that the value is bogus (e.g., just a byte field in a string array that so happens to have a value that matches the specified data type flag). Therefore, the data type error check is *not* completely safe.

Unpacking values is a "nondestructive" process — i.e., the values are not removed from the buffer. It is therefore possible for the caller to re-unpack a value from the same buffer by resetting the unpack\_ptr.

Warning: The caller is responsible for providing adequate memory storage for the requested data. The user must provide a parameter indicating the maximum number of values that can be unpacked into the allocated memory. If more values exist in the buffer than can fit into the memory storage, then the function will unpack what it can fit into that location and return an error code indicating that the buffer was only partially unpacked.

Note that any data that was not hard type cast (i.e., not type cast to a specific size) when packed may lose precision when unpacked by a non-homogeneous recipient. PMIx will do its best to deal with heterogeneity issues between the packer and unpacker in such cases. Sending a number larger than can be handled by the recipient will return an error code generated upon unpacking — these errors cannot be detected during packing.

The namespace of the process that packed the buffer is used solely to resolve any data type differences between PMIx versions. The packer must, therefore, be known to the user prior to calling the pack function so that the PMIx library is aware of the version the packer is using. Note

that all processes in a given namespace are *required* to use the same PMIx version — thus, the caller must only know at least one process from the packer's namespace.

## 10.3.3 PMIx Data copy

#### Summary

Copy a data value from one location to another.

# 6 PMIx v2.0 Format

1

5

7

8

9

11 12

13 14

15

16

17 18

19

20 21

22

23

24

25

26 27

28

29

30 31 C

10 IN dest

The address of a pointer into which the address of the resulting data is to be stored. (void\*\*)

IN src

A pointer to the memory location from which the data is to be copied (handle)

IN type

The type of the data to be copied — must be one of the PMIx defined data types.

(pmix\_data\_type\_t)

Returns PMIX\_SUCCESS or one of the following error codes when the condition described occurs:

PMIX ERR BAD PARAM The provided src or dest is NULL

**PMIX\_ERR\_UNKNOWN\_DATA\_TYPE** The specified data type is not known to this implementation

PMIX ERR OUT OF RESOURCE Not enough memory to support the operation

If none of the above return codes are appropriate, then an implementation must return either a general PMIx error code or an implementation defined error code as described in Section 3.1.1.

## **Description**

Since registered data types can be complex structures, the system needs some way to know how to copy the data from one location to another (e.g., for storage in the registry). This function, which can call other copy functions to build up complex data types, defines the method for making a copy of the specified data type.

# 10.3.4 PMIx\_Data\_print

## Summary

Pretty-print a data value.

```
Format
 1
 2
               pmix status t
 3
               PMIx Data print(char **output, char *prefix,
 4
                                    void *src, pmix_data_type_t type);
               IN
 5
                    output
 6
                    The address of a pointer into which the address of the resulting output is to be stored.
 7
               IN
 8
                    prefix
 9
                    String to be prepended to the resulting output (char*)
10
               IN
                    A pointer to the memory location of the data value to be printed (handle)
11
               IN
                    type
12
                    The type of the data value to be printed — must be one of the PMIx defined data types.
13
14
                    (pmix_data_type_t)
               Returns PMIX_SUCCESS or one of the following error codes when the condition described occurs:
15
                PMIX_ERR_BAD_PARAM The provided data type is not recognized.
16
               If none of the above return codes are appropriate, then an implementation must return either a
17
               general PMIx error code or an implementation defined error code as described in Section 3.1.1.
18
               Description
19
               Since registered data types can be complex structures, the system needs some way to know how to
20
               print them (i.e., convert them to a string representation). Primarily for debug purposes.
21
    10.3.5
               PMIx_Data_copy_payload
               Summary
23
24
               Copy a payload from one buffer to another
               Format
   PMIx v2.0
26
               pmix_status t
27
               PMIx_Data_copy_payload(pmix_data_buffer_t *dest,
28
                                              pmix data buffer t *src);
               IN
29
                    Pointer to the destination pmix_data_buffer_t (handle)
30
31
               IN
                    src
32
                    Pointer to the source pmix data buffer t (handle)
```

Returns PMIX\_SUCCESS or one of the following error codes when the condition described occurs:

PMIX\_ERR\_BAD\_PARAM The src and dest pmix\_data\_buffer\_t types do not match

If none of the above return codes are appropriate, then an implementation must return either a general PMIx error code or an implementation defined error code as described in Section 3.1.1.

### **Description**

1

3

4

5

6 7

8

This function will append a copy of the payload in one buffer into another buffer. Note that this is *not* a destructive procedure — the source buffer's payload will remain intact, as will any pre-existing payload in the destination's buffer. Only the unpacked portion of the source payload will be copied.

#### **CHAPTER 11**

22 23

# **Process Management**

This chapter defines functionality processes can use to abort processes, spawn processes, and 2 determine the relative locality of local processes. 11.1 **Abort** PMIx provides a dedicated API by which an application can request that specified processes be 5 aborted by the system. 11.1.1 PMIx Abort Summary 8 Abort the specified processes **Format** PMIx v1.0 10 pmix status t PMIx Abort (int status, const char msg[], 11 12 pmix proc t procs[], size t nprocs) IN 13 status Error code to return to invoking environment (integer) 14 15 IN 16 String message to be returned to user (string) IN 17 procs Array of pmix\_proc\_t structures (array of handles) 18 IN 19 nprocs 20 Number of elements in the *procs* array (integer) A successful return indicates that the requested processes are in a terminated state. Note that the 21

function shall not return in this situation if the caller's own process was included in the request.

Returns PMIX\_SUCCESS or one of the following error codes when the condition described occurs:

• PMIX\_ERR\_PARAM\_VALUE\_NOT\_SUPPORTED if the PMIx implementation and host environment support this API, but the request includes processes that the host environment cannot abort - e.g., if the request is to abort subsets of processes from a namespace, or processes outside of the caller's own namespace, and the host environment does not permit such operations. In this case, none of the specified processes will be terminated.

If none of the above return codes are appropriate, then an implementation must return either a general PMIx error code or an implementation defined error code as described in Section 3.1.1.

## **Description**

Request that the host resource manager print the provided message and abort the provided array of procs. A Unix or POSIX environment should handle the provided status as a return error code from the main program that launched the application. A NULL for the procs array indicates that all processes in the caller's namespace are to be aborted, including itself - this is the equivalent of passing a pmix\_proc\_t array element containing the caller's namespace and a rank value of PMIX\_RANK\_WILDCARD. While it is permitted for a caller to request abort of processes from namespaces other than its own, not all environments will support such requests. Passing a NULL msg parameter is allowed.

The function shall not return until the host environment has carried out the operation on the specified processes. If the caller is included in the array of targets, then the function will not return unless the host is unable to execute the operation.

### Advice to users

The response to this request is somewhat dependent on the specific RM and its configuration (e.g., some resource managers will not abort the application if the provided status is zero unless specifically configured to do so, some cannot abort subsets of processes in an application, and some may not permit termination of processes outside of the caller's own namespace), and thus lies outside the control of PMIx itself. However, the PMIx client library shall inform the RM of the request that the specified *procs* be aborted, regardless of the value of the provided status.

Note that race conditions caused by multiple processes calling **PMIx\_Abort** are left to the server implementation to resolve with regard to which status is returned and what messages (if any) are printed.

# 11.2 Process Creation

The **PMIx\_Spawn** commands spawn new processes and/or applications in the PMIx universe. This may include requests to extend the existing resource allocation or obtain a new one, depending upon provided and supported attributes.

#### Summary 3 Spawn a new job. Format PMIx v1.0 5 pmix\_status\_t 6 PMIx\_Spawn(const pmix\_info\_t job\_info[], size\_t ninfo, 7 const pmix\_app\_t apps[], size\_t napps, 8 char nspace[]) IN 9 job info Array of info structures (array of handles) 10 11 IN ninfo Number of elements in the *job info* array (integer) 12 IN 13 14 Array of pmix app t structures (array of handles) 15 IN napps Number of elements in the apps array (integer) 16 17 OUT nspace Namespace of the new job (string) 18 19 Returns **PMIX SUCCESS** or a negative value indicating the error. Required Attributes 20 PMIx libraries are not required to directly support any attributes for this function. However, any provided attributes must be passed to the host environment for processing. 21 Host environments are required to support the following attributes when present in either the 22 *job\_info* or the *info* array of an element of the *apps* array: 23 24 PMIX WDIR "pmix.wdir" (char\*) 25 Working directory for spawned processes. 26 PMIX\_SET\_SESSION\_CWD "pmix.ssncwd" (bool) 27 Set the current working directory to the session working directory assigned by the RM - can be assigned to the entire job (by including attribute in the job info array) or on a 28 per-application basis in the *info* array for each pmix\_app\_t. 29 30 PMIX PREFIX "pmix.prefix" (char\*) 31 Prefix to use for starting spawned processes - i.e., the directory where the executables can be 32 found. 33 PMIX HOST "pmix.host" (char\*) Comma-delimited list of hosts to use for spawned processes. 34

11.2.1

PMIx\_Spawn

1 2	PMIX_HOSTFILE "pmix.hostfile" (char*)  Hostfile to use for spawned processes.
	▼ Optional Attributes
3	The following attributes are optional for host environments that support this operation:
4 5	PMIX_ADD_HOSTFILE "pmix.addhostfile" (char*) Hostfile containing hosts to add to existing allocation.
6 7	PMIX_ADD_HOST "pmix.addhost" (char*)  Comma-delimited list of hosts to add to the allocation.
8 9	<pre>PMIX_PRELOAD_BIN "pmix.preloadbin" (bool) Preload executables onto nodes prior to executing launch procedure.</pre>
10 11	<pre>PMIX_PRELOAD_FILES "pmix.preloadfiles" (char*) Comma-delimited list of files to pre-position on nodes prior to executing launch procedure.</pre>
12 13 14	PMIX_PERSONALITY "pmix.pers" (char*)  Name of personality corresponding to programming model used by application - supported values depend upon PMIx implementation.
15 16	PMIX_DISPLAY_MAP "pmix.dispmap" (bool) Display process mapping upon spawn.
17 18	<pre>PMIX_PPR "pmix.ppr" (char*) Number of processes to spawn on each identified resource.</pre>
19 20 21 22	<pre>PMIX_MAPBY "pmix.mapby" (char*) Process mapping policy - when accessed using PMIx_Get, use the PMIX_RANK_WILDCARD value for the rank to discover the mapping policy used for the provided namespace. Supported values are launcher specific.</pre>
23 24 25 26	<pre>PMIX_RANKBY "pmix.rankby" (char*) Process ranking policy - when accessed using PMIx_Get, use the PMIX_RANK_WILDCARD value for the rank to discover the ranking algorithm used for the provided namespace. Supported values are launcher specific.</pre>
27 28 29 30	PMIX_BINDTO "pmix.bindto" (char*)  Process binding policy - when accessed using PMIx_Get, use the  PMIX_RANK_WILDCARD value for the rank to discover the binding policy used for the provided namespace. Supported values are launcher specific.
31 32	PMIX_STDIN_TGT "pmix.stdin" (uint32_t) Spawned process rank that is to receive any forwarded stdin.
33	<pre>PMIX_TAG_OUTPUT "pmix.tagout" (bool)</pre>

1 2 3	Tag <b>stdout/stderr</b> with the identity of the source process - can be assigned to the entire job (by including attribute in the <i>job_info</i> array) or on a per-application basis in the <i>info</i> array for each <b>pmix_app_t</b> .
4 5 6	PMIX_TIMESTAMP_OUTPUT "pmix.tsout" (bool)  Timestamp output - can be assigned to the entire job (by including attribute in the job_info array) or on a per-application basis in the info array for each pmix_app_t.
7 8 9 0	<pre>PMIX_MERGE_STDERR_STDOUT "pmix.mergeerrout" (bool)     Merge stdout and stderr streams - can be assigned to the entire job (by including attribute in the job_info array) or on a per-application basis in the info array for each pmix_app_t.</pre>
1 2 3 4	<pre>PMIX_OUTPUT_TO_FILE "pmix.outfile" (char*) Direct output (both stdout and stderr) into files of form "<filename>.rank" - can be assigned to the entire job (by including attribute in the job_info array) or on a per-application basis in the info array for each pmix_app_t.</filename></pre>
5 6	PMIX_INDEX_ARGV "pmix.indxargv" (bool)  Mark the argv with the rank of the process.
7 8 9	<pre>PMIX_CPUS_PER_PROC "pmix.cpuperproc" (uint32_t) Number of PUs to assign to each rank - when accessed using PMIx_Get, use the PMIX_RANK_WILDCARD value for the rank to discover the PUs/process assigned to the provided namespace.</pre>
?1 ?2	<pre>PMIX_NO_PROCS_ON_HEAD "pmix.nolocal" (bool) Do not place processes on the head node.</pre>
23 24 25	<pre>PMIX_NO_OVERSUBSCRIBE "pmix.noover" (bool) Do not oversubscribe the nodes - i.e., do not place more processes than allocated slots on a node.</pre>
26 27	<pre>PMIX_REPORT_BINDINGS "pmix.repbind" (bool) Report bindings of the individual processes.</pre>
28 29 30 31	<pre>PMIX_CPU_LIST "pmix.cpulist" (char*) List of PUs to use for this job - when accessed using PMIx_Get, use the PMIX_RANK_WILDCARD value for the rank to discover the PU list used for the provided namespace.</pre>
32 33	PMIX_JOB_RECOVERABLE "pmix.recover" (bool) Application supports recoverable operations.
34 35	PMIX_JOB_CONTINUOUS "pmix.continuous" (bool) Application is continuous, all failed processes should be immediately restarted.
86	<pre>PMIX_MAX_RESTARTS "pmix.maxrestarts" (uint32_t)</pre>

1 2 3	Maximum number of times to restart a process - when accessed using <b>PMIx_Get</b> , use the <b>PMIX_RANK_WILDCARD</b> value for the rank to discover the max restarts for the provided namespace.
4 5	<pre>PMIX_SET_ENVAR "pmix.envar.set" (pmix_envar_t*) Set the envar to the given value, overwriting any pre-existing one</pre>
6 7	<pre>PMIX_UNSET_ENVAR "pmix.envar.unset" (char*) Unset the environment variable specified in the string.</pre>
8 9	PMIX_ADD_ENVAR "pmix.envar.add" (pmix_envar_t*)  Add the environment variable, but do not overwrite any pre-existing one
10 11 12	<pre>PMIX_PREPEND_ENVAR "pmix.envar.prepnd" (pmix_envar_t*) Prepend the given value to the specified environmental value using the given separator character, creating the variable if it doesn't already exist</pre>
13 14 15	<pre>PMIX_APPEND_ENVAR "pmix.envar.appnd" (pmix_envar_t*) Append the given value to the specified environmental value using the given separator character, creating the variable if it doesn't already exist</pre>
16 17 18	<pre>PMIX_FIRST_ENVAR "pmix.envar.first" (pmix_envar_t*) Ensure the given value appears first in the specified envar using the separator character, creating the envar if it doesn't already exist</pre>
19 20 21	<pre>PMIX_ALLOC_QUEUE "pmix.alloc.queue" (char*) Name of the WLM queue to which the allocation request is to be directed, or the queue being referenced in a query.</pre>
22 23	<pre>PMIX_ALLOC_TIME "pmix.alloc.time" (uint32_t) Total session time (in seconds) being requested in an allocation request.</pre>
24 25	<pre>PMIX_ALLOC_NUM_NODES "pmix.alloc.nnodes" (uint64_t) The number of nodes being requested in an allocation request.</pre>
26 27	<pre>PMIX_ALLOC_NODE_LIST "pmix.alloc.nlist" (char*) Regular expression of the specific nodes being requested in an allocation request.</pre>
28 29	<pre>PMIX_ALLOC_NUM_CPUS "pmix.alloc.ncpus" (uint64_t) Number of PUs being requested in an allocation request.</pre>
30 31 32	<pre>PMIX_ALLOC_NUM_CPU_LIST "pmix.alloc.ncpulist" (char*) Regular expression of the number of PUs for each node being requested in an allocation request.</pre>
33 34	PMIX_ALLOC_CPU_LIST "pmix.alloc.cpulist" (char*)  Regular expression of the specific PUs being requested in an allocation request.
35	<pre>PMIX_ALLOC_MEM_SIZE "pmix.alloc.msize" (float)</pre>

Number of Megabytes[base2] of memory (per process) being requested in an allocation 1 2 request. 3 PMIX ALLOC BANDWIDTH "pmix.alloc.bw" (float) Fabric bandwidth (in Megabits[base2]/sec) for the job being requested in an allocation 4 5 request. PMIX ALLOC FABRIC QOS "pmix.alloc.netgos" (char\*) 6 Fabric quality of service level for the job being requested in an allocation request. 7 8 PMIX ALLOC FABRIC TYPE "pmix.alloc.nettype" (char\*) Type of desired transport (e.g., "tcp", "udp") being requested in an allocation request. 9 PMIX ALLOC FABRIC PLANE "pmix.alloc.netplane" (char\*) 10 ID string for the *fabric plane* to be used for the requested allocation. 11 PMIX\_ALLOC\_FABRIC\_ENDPTS "pmix.alloc.endpts" (size\_t) 12 13 Number of endpoints to allocate per *process* in the job. PMIX\_ALLOC\_FABRIC\_ENDPTS\_NODE "pmix.alloc.endpts.nd" (size\_t) 14 Number of endpoints to allocate per *node* for the job. 15 16 PMIX\_COSPAWN\_APP "pmix.cospawn" (bool) Designated application is to be spawned as a disconnected job - i.e., the launcher shall not 17 18 include the application in any of the job-level values (e.g., PMIX\_RANK within the job) provided to any other application process generated by the same spawn request. Typically 19 used to cospawn debugger daemons alongside an application. 20 PMIX SPAWN TOOL "pmix.spwn.tool" (bool) 21 Indicate that the job being spawned is a tool. 22 PMIX\_EVENT\_SILENT\_TERMINATION "pmix.evsilentterm" (bool) 23 Do not generate an event when this job normally terminates. 24

# **Description**

25

26

27

28 29

30

31

32 33

34

Spawn a new job. The assigned namespace of the spawned applications is returned in the *nspace* parameter. A **NULL** value in that location indicates that the caller doesn't wish to have the namespace returned. The *nspace* array must be at least of size one more than **PMIX MAX NSLEN**.

By default, the spawned processes will be PMIx "connected" to the parent process upon successful launch (see Section 11.3 for details). This includes that (a) the parent process will be given a copy of the new job's information so it can query job-level info without incurring any communication penalties, (b) newly spawned child processes will receive a copy of the parent processes job-level info, and (c) both the parent process and members of the child job will receive notification of errors from processes in their combined assemblage.

### Advice to users

Behavior of individual resource managers may differ, but it is expected that failure of any application process to start will result in termination/cleanup of all processes in the newly spawned job and return of an error code to the caller.

# Advice to PMIx library implementers -

Tools may utilize **PMIx\_Spawn** to start intermediate launchers as described in Section 17.2.2. For times where the tool is not attached to a PMIx server, internal support for fork/exec of the specified applications would allow the tool to maintain a single code path for both the connected and disconnected cases. Inclusion of such support is recommended, but not required.

# 11.2.2 PMIx\_Spawn\_nb

### Summary

Nonblocking version of the **PMIx\_Spawn** routine.

# PMIx v1.0 Format

1

2

3

4 5

6 7

9

10

12

13 14

15

16 17

18

19

20

21 22

23

24 25

26

27

28 29

IN job\_info

Array of info structures (array of handles)

IN ninfo

Number of elements in the *job\_info* array (integer)

IN apps

Array of pmix\_app\_t structures (array of handles)

IN cbfund

Callback function **pmix\_spawn\_cbfunc\_t** (function reference)

IN cbdata

Data to be passed to the callback function (memory reference)

A successful return indicates that the request is being processed by the host environment and the result will be returned in the provided *cbfunc*. Note that the library must not invoke the callback function prior to returning from the API. In all other cases, the *cbfunc* will *not* be called.

Returns PMIX\_SUCCESS or one of the following error codes when the condition described occurs:

1 2	<ul> <li>PMIX_OPERATION_SUCCEEDED, indicating that the request was immediately processed and returned success - the cbfunc will not be called</li> </ul>
3 4	If none of the above return codes are appropriate, then an implementation must return either a general PMIx error code or an implementation defined error code as described in Section 3.1.1.
	▼
5 6	PMIx libraries are not required to directly support any attributes for this function. However, any provided attributes must be passed to the host SMS daemon for processing.
7 8	Host environments are required to support the following attributes when present in either the <i>job_info</i> or the <i>info</i> array of an element of the <i>apps</i> array:
9 10	PMIX_WDIR "pmix.wdir" (char*) Working directory for spawned processes.
11 12 13 14	PMIX_SET_SESSION_CWD "pmix.ssncwd" (bool)  Set the current working directory to the session working directory assigned by the RM - can be assigned to the entire job (by including attribute in the job_info array) or on a per-application basis in the info array for each pmix_app_t.
15 16 17	<pre>PMIX_PREFIX "pmix.prefix" (char*)     Prefix to use for starting spawned processes - i.e., the directory where the executables can be found.</pre>
18 19	<pre>PMIX_HOST "pmix.host" (char*) Comma-delimited list of hosts to use for spawned processes.</pre>
20 21	PMIX_HOSTFILE "pmix.hostfile" (char*)  Hostfile to use for spawned processes.
	▼
22	The following attributes are optional for host environments that support this operation:
23 24	<pre>PMIX_ADD_HOSTFILE "pmix.addhostfile" (char*) Hostfile containing hosts to add to existing allocation.</pre>
25 26	PMIX_ADD_HOST "pmix.addhost" (char*)  Comma-delimited list of hosts to add to the allocation.
27 28	<pre>PMIX_PRELOAD_BIN "pmix.preloadbin" (bool) Preload executables onto nodes prior to executing launch procedure.</pre>
29 30	<pre>PMIX_PRELOAD_FILES "pmix.preloadfiles" (char*) Comma-delimited list of files to pre-position on nodes prior to executing launch procedure.</pre>
31	<pre>PMIX_PERSONALITY "pmix.pers" (char*)</pre>

1 2	Name of personality corresponding to programming model used by application - supported values depend upon PMIx implementation.
3 4	PMIX_DISPLAY_MAP "pmix.dispmap" (bool) Display process mapping upon spawn.
5 6	PMIX_PPR "pmix.ppr" (char*)  Number of processes to spawn on each identified resource.
7 8 9 0	PMIX_MAPBY "pmix.mapby" (char*)  Process mapping policy - when accessed using PMIx_Get, use the  PMIX_RANK_WILDCARD value for the rank to discover the mapping policy used for the provided namespace. Supported values are launcher specific.
1 2 3 4	PMIX_RANKBY "pmix.rankby" (char*)  Process ranking policy - when accessed using PMIx_Get, use the  PMIX_RANK_WILDCARD value for the rank to discover the ranking algorithm used for the provided namespace. Supported values are launcher specific.
5 6 7 8	PMIX_BINDTO "pmix.bindto" (char*)  Process binding policy - when accessed using PMIx_Get, use the  PMIX_RANK_WILDCARD value for the rank to discover the binding policy used for the provided namespace. Supported values are launcher specific.
9	PMIX_STDIN_TGT "pmix.stdin" (uint32_t) Spawned process rank that is to receive any forwarded stdin.
21 22 23 24	PMIX_TAG_OUTPUT "pmix.tagout" (bool)  Tag stdout/stderr with the identity of the source process - can be assigned to the entire job (by including attribute in the job_info array) or on a per-application basis in the info array for each pmix_app_t.
25 26 27	PMIX_TIMESTAMP_OUTPUT "pmix.tsout" (bool)  Timestamp output - can be assigned to the entire job (by including attribute in the <i>job_info</i> array) or on a per-application basis in the <i>info</i> array for each pmix_app_t.
28 29 30 31	PMIX_MERGE_STDERR_STDOUT "pmix.mergeerrout" (bool)  Merge stdout and stderr streams - can be assigned to the entire job (by including attribute in the job_info array) or on a per-application basis in the info array for each pmix_app_t.
33 34 35	<pre>PMIX_OUTPUT_TO_FILE "pmix.outfile" (char*)     Direct output (both stdout and stderr) into files of form "<filename>.rank" - can be     assigned to the entire job (by including attribute in the job_info array) or on a per-application     basis in the info array for each pmix_app_t.</filename></pre>
36 37	PMIX_INDEX_ARGV "pmix.indxargv" (bool)  Mark the argv with the rank of the process.

1 2 3 4	PMIX_CPUS_PER_PROC "pmix.cpuperproc" (uint32_t)  Number of PUs to assign to each rank - when accessed using PMIx_Get, use the  PMIX_RANK_WILDCARD value for the rank to discover the PUs/process assigned to the  provided namespace.
5 6	PMIX_NO_PROCS_ON_HEAD "pmix.nolocal" (bool)  Do not place processes on the head node.
7 8 9	<pre>PMIX_NO_OVERSUBSCRIBE "pmix.noover" (bool)     Do not oversubscribe the nodes - i.e., do not place more processes than allocated slots on a node.</pre>
10 11	PMIX_REPORT_BINDINGS "pmix.repbind" (bool) Report bindings of the individual processes.
12 13 14 15	<pre>PMIX_CPU_LIST "pmix.cpulist" (char*) List of PUs to use for this job - when accessed using PMIx_Get, use the PMIX_RANK_WILDCARD value for the rank to discover the PU list used for the provided namespace.</pre>
16 17	PMIX_JOB_RECOVERABLE "pmix.recover" (bool) Application supports recoverable operations.
18 19	PMIX_JOB_CONTINUOUS "pmix.continuous" (bool) Application is continuous, all failed processes should be immediately restarted.
20 21 22 23	<pre>PMIX_MAX_RESTARTS "pmix.maxrestarts" (uint32_t)     Maximum number of times to restart a process - when accessed using PMIx_Get, use the     PMIX_RANK_WILDCARD value for the rank to discover the max restarts for the provided     namespace.</pre>
24 25	<pre>PMIX_SET_ENVAR "pmix.envar.set" (pmix_envar_t*) Set the envar to the given value, overwriting any pre-existing one</pre>
26 27	<pre>PMIX_UNSET_ENVAR "pmix.envar.unset" (char*) Unset the environment variable specified in the string.</pre>
28 29	<pre>PMIX_ADD_ENVAR "pmix.envar.add" (pmix_envar_t*) Add the environment variable, but do not overwrite any pre-existing one</pre>
30 31 32	<pre>PMIX_PREPEND_ENVAR "pmix.envar.prepnd" (pmix_envar_t*) Prepend the given value to the specified environmental value using the given separator character, creating the variable if it doesn't already exist</pre>
33 34 35	<pre>PMIX_APPEND_ENVAR "pmix.envar.appnd" (pmix_envar_t*) Append the given value to the specified environmental value using the given separator character, creating the variable if it doesn't already exist</pre>
36	<pre>PMIX_FIRST_ENVAR "pmix.envar.first" (pmix_envar_t*)</pre>

1 2	Ensure the given value appears first in the specified envar using the separator character, creating the envar if it doesn't already exist
3 4 5	PMIX_ALLOC_QUEUE "pmix.alloc.queue" (char*)  Name of the WLM queue to which the allocation request is to be directed, or the queue being referenced in a query.
6 7	PMIX_ALLOC_TIME "pmix.alloc.time" (uint32_t)  Total session time (in seconds) being requested in an allocation request.
8 9	<pre>PMIX_ALLOC_NUM_NODES "pmix.alloc.nnodes" (uint64_t) The number of nodes being requested in an allocation request.</pre>
10 11	<pre>PMIX_ALLOC_NODE_LIST "pmix.alloc.nlist" (char*) Regular expression of the specific nodes being requested in an allocation request.</pre>
12 13	<pre>PMIX_ALLOC_NUM_CPUS "pmix.alloc.ncpus" (uint64_t) Number of PUs being requested in an allocation request.</pre>
14 15 16	<pre>PMIX_ALLOC_NUM_CPU_LIST "pmix.alloc.ncpulist" (char*) Regular expression of the number of PUs for each node being requested in an allocation request.</pre>
17 18	<pre>PMIX_ALLOC_CPU_LIST "pmix.alloc.cpulist" (char*) Regular expression of the specific PUs being requested in an allocation request.</pre>
19 20 21	<pre>PMIX_ALLOC_MEM_SIZE "pmix.alloc.msize" (float)     Number of Megabytes[base2] of memory (per process) being requested in an allocation request.</pre>
22 23 24	<pre>PMIX_ALLOC_BANDWIDTH "pmix.alloc.bw" (float) Fabric bandwidth (in Megabits[base2]/sec) for the job being requested in an allocation request.</pre>
25 26	<pre>PMIX_ALLOC_FABRIC_QOS "pmix.alloc.netqos" (char*) Fabric quality of service level for the job being requested in an allocation request.</pre>
27 28	<pre>PMIX_ALLOC_FABRIC_TYPE "pmix.alloc.nettype" (char*) Type of desired transport (e.g., "tcp", "udp") being requested in an allocation request.</pre>
29 30	<pre>PMIX_ALLOC_FABRIC_PLANE "pmix.alloc.netplane" (char*) ID string for the fabric plane to be used for the requested allocation.</pre>
31 32	<pre>PMIX_ALLOC_FABRIC_ENDPTS "pmix.alloc.endpts" (size_t) Number of endpoints to allocate per process in the job.</pre>
33 34	<pre>PMIX_ALLOC_FABRIC_ENDPTS_NODE "pmix.alloc.endpts.nd" (size_t) Number of endpoints to allocate per node for the job.</pre>
35	PMIX_COSPAWN_APP "pmix.cospawn" (bool)

Designated application is to be spawned as a disconnected job - i.e., the launcher shall not 1 2 include the application in any of the job-level values (e.g., PMIX RANK within the job) provided to any other application process generated by the same spawn request. Typically 3 4 used to cospawn debugger daemons alongside an application. PMIX\_SPAWN\_TOOL "pmix.spwn.tool" (bool) 5 6 Indicate that the job being spawned is a tool. 7 PMIX EVENT SILENT TERMINATION "pmix.evsilentterm" (bool) 8 Do not generate an event when this job normally terminates. **Description** 9 10 Nonblocking version of the PMIx\_Spawn routine. The provided callback function will be 11 executed upon successful start of all specified application processes. Advice to users 12 Behavior of individual resource managers may differ, but it is expected that failure of any 13 application process to start will result in termination/cleanup of all processes in the newly spawned

# 5 11.2.3 Spawn-specific constants

job and return of an error code to the caller.

14

16 17

18

19

20 21

22

23

24 25

26

In addition to the generic error constants, the following spawn-specific error constants may be returned by the spawn APIs:

PMIX\_ERR\_JOB\_ALLOC\_FAILED The job request could not be executed due to failure to obtain the specified allocation

**PMIX\_ERR\_JOB\_APP\_NOT\_EXECUTABLE** The specified application executable either could not be found, or lacks execution privileges.

PMIX\_ERR\_JOB\_NO\_EXE\_SPECIFIED The job request did not specify an executable.

**PMIX\_ERR\_JOB\_FAILED\_TO\_MAP** The launcher was unable to map the processes for the specified job request.

PMIX\_ERR\_JOB\_FAILED\_TO\_LAUNCH One or more processes in the job request failed to launch

# 11.2.4 Spawn attributes

2

3

5 6

7 8

9

10

11

12

13

14

15 16

17

18

19

20 21

22

23

24 25

26

27

28 29

30 31

32

33

34

35

36

37

38 39

40

41

42

Attributes used to describe PMIx\_Spawn behavior - they are values passed to the PMIx\_Spawn API and therefore are not accessed using the PMIx\_Get APIs when used in that context. However, some of the attributes defined in this section can be provided by the host environment for other purposes - e.g., the host might provide the PMIX\_MAPBY attribute in the job-related information so that an application can use PMIx\_Get to discover the mapping used for determining process locations. Multi-use attributes and their respective access reference rank are denoted below.

### PMIX PERSONALITY "pmix.pers" (char\*)

Name of personality corresponding to programming model used by application - supported values depend upon PMIx implementation.

# PMIX\_HOST "pmix.host" (char\*)

Comma-delimited list of hosts to use for spawned processes.

# PMIX\_HOSTFILE "pmix.hostfile" (char\*)

Hostfile to use for spawned processes.

PMIX\_ADD\_HOST "pmix.addhost" (char\*)

Comma-delimited list of hosts to add to the allocation.

# PMIX\_ADD\_HOSTFILE "pmix.addhostfile" (char\*)

Hostfile containing hosts to add to existing allocation.

# PMIX\_PREFIX "pmix.prefix" (char\*)

Prefix to use for starting spawned processes - i.e., the directory where the executables can be found.

### PMIX\_WDIR "pmix.wdir" (char\*)

Working directory for spawned processes.

### PMIX\_DISPLAY\_MAP "pmix.dispmap" (bool)

Display process mapping upon spawn.

### PMIX\_PPR "pmix.ppr" (char\*)

Number of processes to spawn on each identified resource.

### PMIX\_MAPBY "pmix.mapby" (char\*)

Process mapping policy - when accessed using **PMIx** Get, use the

**PMIX\_RANK\_WILDCARD** value for the rank to discover the mapping policy used for the provided namespace. Supported values are launcher specific.

### PMIX\_RANKBY "pmix.rankby" (char\*)

Process ranking policy - when accessed using PMIx\_Get, use the

**PMIX\_RANK\_WILDCARD** value for the rank to discover the ranking algorithm used for the provided namespace. Supported values are launcher specific.

### PMIX\_BINDTO "pmix.bindto" (char\*)

Process binding policy - when accessed using  ${\tt PMIx\_Get},$  use the

**PMIX\_RANK\_WILDCARD** value for the rank to discover the binding policy used for the provided namespace. Supported values are launcher specific.

# PMIX PRELOAD\_BIN "pmix.preloadbin" (bool)

Preload executables onto nodes prior to executing launch procedure.

PMIX\_PRELOAD\_FILES "pmix.preloadfiles" (char\*)

1	Comma-delimited list of files to pre-position on nodes prior to executing launch procedure.
2	<pre>PMIX_STDIN_TGT "pmix.stdin" (uint32_t)</pre>
3	Spawned process rank that is to receive any forwarded <b>stdin</b> .
4	PMIX_SET_SESSION_CWD "pmix.ssncwd" (bool)
5	Set the current working directory to the session working directory assigned by the RM - can
6	be assigned to the entire job (by including attribute in the <i>job_info</i> array) or on a
7	per-application basis in the <i>info</i> array for each <b>pmix_app_t</b> .
8	PMIX_TAG_OUTPUT "pmix.tagout" (bool)
9	Tag stdout/stderr with the identity of the source process - can be assigned to the entire
10	job (by including attribute in the <i>job_info</i> array) or on a per-application basis in the <i>info</i>
11	array for each pmix_app_t.
12	PMIX_TIMESTAMP_OUTPUT "pmix.tsout" (bool)
13	Timestamp output - can be assigned to the entire job (by including attribute in the job_info
14	array) or on a per-application basis in the <i>info</i> array for each <b>pmix_app_t</b> .
15	PMIX_MERGE_STDERR_STDOUT "pmix.mergeerrout" (bool)
16	Merge <b>stdout</b> and <b>stderr</b> streams - can be assigned to the entire job (by including
17	attribute in the <i>job_info</i> array) or on a per-application basis in the <i>info</i> array for each
18	pmix_app_t.
19	PMIX_OUTPUT_TO_FILE "pmix.outfile" (char*)
20	Direct output (both stdout and stderr) into files of form " <filename>.rank" - can be</filename>
21	assigned to the entire job (by including attribute in the job_info array) or on a per-application
22	basis in the <i>info</i> array for each <b>pmix_app_t</b> .
23	<pre>PMIX_OUTPUT_TO_DIRECTORY "pmix.outdir" (char*)</pre>
24	Direct output into files of form " <directory>/<jobid>/rank.<rank>/</rank></jobid></directory>
25	<b>stdout[err]</b> " - can be assigned to the entire job (by including attribute in the <i>job_info</i>
26	array) or on a per-application basis in the <i>info</i> array for each <b>pmix_app_t</b> .
27	PMIX_INDEX_ARGV "pmix.indxargv" (bool)
28	Mark the <b>argv</b> with the rank of the process.
29	PMIX_CPUS_PER_PROC "pmix.cpuperproc" (uint32_t)
30	Number of PUs to assign to each rank - when accessed using <b>PMIx_Get</b> , use the
31	PMIX_RANK_WILDCARD value for the rank to discover the PUs/process assigned to the
32	provided namespace.
33	PMIX_NO_PROCS_ON_HEAD "pmix.nolocal" (bool)
34	Do not place processes on the head node.
35	PMIX_NO_OVERSUBSCRIBE "pmix.noover" (bool)
36	Do not oversubscribe the nodes - i.e., do not place more processes than allocated slots on a
37	node.
38	PMIX_REPORT_BINDINGS "pmix.repbind" (bool)
39	Report bindings of the individual processes.
40	PMIX_CPU_LIST "pmix.cpulist" (char*)
41	List of PUs to use for this job - when accessed using PMIx_Get, use the
42	PMIX_RANK_WILDCARD value for the rank to discover the PU list used for the provided
	•
43	namespace.

```
PMIX_JOB_RECOVERABLE "pmix.recover" (bool)
1
2
                     Application supports recoverable operations.
               PMIX JOB CONTINUOUS "pmix.continuous" (bool)
 3
 4
                     Application is continuous, all failed processes should be immediately restarted.
               PMIX_MAX_RESTARTS "pmix.maxrestarts" (uint32_t)
5
6
                     Maximum number of times to restart a process - when accessed using PMIx_Get, use the
                     PMIX RANK WILDCARD value for the rank to discover the max restarts for the provided
7
8
                     namespace.
9
               PMIX_SPAWN_TOOL "pmix.spwn.tool" (bool)
                     Indicate that the job being spawned is a tool.
10
               PMIX_TIMEOUT_STACKTRACES "pmix.tim.stack" (bool)
11
12
                     Include process stacktraces in timeout report from a job.
               PMIX_TIMEOUT_REPORT_STATE "pmix.tim.state" (bool)
13
14
                     Report process states in timeout report from a job.
               PMIX_NOTIFY_JOB_EVENTS "pmix.note.jev" (bool)
15
                     Requests that the launcher generate the PMIX EVENT JOB START,
16
                     PMIX LAUNCH_COMPLETE, and PMIX_EVENT_JOB_END events. Each event is to
17
                     include at least the namespace of the corresponding job and a PMIX_EVENT_TIMESTAMP
18
                     indicating the time the event occurred. Note that the requester must register for these
19
                     individual events, or capture and process them by registering a default event handler instead
20
21
                     of individual handlers and then process the events based on the returned status code.
22
                     Another common method is to register one event handler for all job-related events, with a
23
                     separate handler for non-job events - see PMIx_Register_event_handler for details.
24
               PMIX_NOTIFY_COMPLETION "pmix.notecomp" (bool)
                     Requests that the launcher generate the PMIX EVENT JOB END event for normal or
25
26
                     abnormal termination of the spawned job. The event shall include the returned status code
27
                     (PMIX JOB TERM STATUS) for the corresponding job; the identity (PMIX PROCID)
                     and exit status (PMIX EXIT CODE) of the first failed process, if applicable; and a
28
29
                     PMIX EVENT TIMESTAMP indicating the time the termination occurred. Note that the
                     requester must register for the event or capture and process it within a default event handler.
30
31
               PMIX NOTIFY PROC TERMINATION "pmix.noteproc" (bool)
                     Requests that the launcher generate the PMIX EVENT PROC TERMINATED event
32
                     whenever a process either normally or abnormally terminates.
33
               PMIX NOTIFY PROC ABNORMAL TERMINATION "pmix.noteabproc" (bool)
34
35
                     Requests that the launcher generate the PMIX EVENT PROC TERMINATED event only
36
                     when a process abnormally terminates.
               PMIX_LOG_PROC_TERMINATION "pmix.logproc" (bool)
37
                     Requests that the launcher log the PMIX EVENT PROC TERMINATED event whenever a
38
39
                     process either normally or abnormally terminates.
40
               PMIX LOG PROC ABNORMAL TERMINATION "pmix.logabproc" (bool)
                     Requests that the launcher log the PMIX EVENT PROC TERMINATED event only when a
41
42
                     process abnormally terminates.
               PMIX_LOG_JOB_EVENTS "pmix.log.jev" (bool)
43
```

1		Requests that the launcher log the PMIX_EVENT_JOB_START,
2		PMIX_LAUNCH_COMPLETE, and PMIX_EVENT_JOB_END events using PMIx_Log,
3		subject to the logging attributes of Section 12.4.3.
4		PMIX_LOG_COMPLETION "pmix.logcomp" (bool)
5		Requests that the launcher log the PMIX_EVENT_JOB_END event for normal or abnormal
6		termination of the spawned job using <b>PMIx_Log</b> , subject to the logging attributes of
7		Section 12.4.3. The event shall include the returned status code
8		(PMIX_JOB_TERM_STATUS) for the corresponding job; the identity (PMIX_PROCID)
9		and exit status (PMIX_EXIT_CODE) of the first failed process, if applicable; and a
0		PMIX_EVENT_TIMESTAMP indicating the time the termination occurred.
1		PMIX_EVENT_SILENT_TERMINATION "pmix.evsilentterm" (bool)
2		Do not generate an event when this job normally terminates.
3		Attributes used to adjust remote environment variables prior to spawning the specified application
4		processes.
5		PMIX_SET_ENVAR "pmix.envar.set" (pmix_envar_t*)
6		Set the envar to the given value, overwriting any pre-existing one
7		PMIX_UNSET_ENVAR "pmix.envar.unset" (char*)
8		Unset the environment variable specified in the string.
9		<pre>PMIX_ADD_ENVAR "pmix.envar.add" (pmix_envar_t*)</pre>
20		Add the environment variable, but do not overwrite any pre-existing one
21		PMIX_PREPEND_ENVAR "pmix.envar.prepnd" (pmix_envar_t*)
2		Prepend the given value to the specified environmental value using the given separator
23		character, creating the variable if it doesn't already exist
24		<pre>PMIX_APPEND_ENVAR "pmix.envar.appnd" (pmix_envar_t*)</pre>
25		Append the given value to the specified environmental value using the given separator
26		character, creating the variable if it doesn't already exist
27		<pre>PMIX_FIRST_ENVAR "pmix.envar.first" (pmix_envar_t*)</pre>
28		Ensure the given value appears first in the specified envar using the separator character,
9		creating the envar if it doesn't already exist
80	11.2.5	Application Structure
1		The pmix_app_t structure describes the application context for the PMIx_Spawn and
2		PMIx_Spawn_nb operations.
	<i>PMIx v1.0</i>	

```
1
             typedef struct pmix_app {
 2
                  /** Executable */
 3
                  char *cmd;
                  /** Argument set, NULL terminated */
 4
 5
                  char **argv;
 6
                  /** Environment set, NULL terminated */
 7
                  char **env;
 8
                  /** Current working directory */
 9
                  char *cwd;
10
                  /** Maximum processes with this profile */
                  int maxprocs;
11
                  /** Array of info keys describing this application*/
12
13
                  pmix info t *info;
                  /** Number of info keys in 'info' array */
14
15
                  size t ninfo;
16
              } pmix app t;
    11.2.5.1
              App structure support macros
17
18
             The following macros are provided to support the pmix_app_t structure.
             Initialize the app structure
19
20
             Initialize the pmix app t fields
  PMIx v1.0
21
             PMIX APP CONSTRUCT (m)
             IN
22
23
                  Pointer to the structure to be initialized (pointer to pmix_app_t)
             Destruct the app structure
24
             Destruct the pmix_app_t fields
25
  PMIx v1.0
             PMIX APP DESTRUCT (m)
26
             IN
27
28
                  Pointer to the structure to be destructed (pointer to pmix_app_t)
```

1	Create an app array
2	Allocate and initialize an array of pmix_app_t structures  C
3	PMIX_APP_CREATE(m, n)
	C
4 5 6 7	INOUT m  Address where the pointer to the array of pmix_app_t structures shall be stored (handle)  IN n  Number of structures to be allocated (size_t)
8 9 <i>PMIx</i>	Free an app structure Release a pmix_app_t structure  V4.0
10	PMIX_APP_RELEASE (m)
11 12	IN m Pointer to a pmix_app_t structure (handle)
13 14 <i>PMIx</i>	Free an app array Release an array of pmix_app_t structures  V1.0
15	PMIX_APP_FREE(m, n)
16 17 18 19	<ul> <li>IN m Pointer to the array of pmix_app_t structures (handle)</li> <li>IN n Number of structures in the array (size_t)</li> </ul>
20 21 22 <i>PMIx</i>	Create the info array of application directives  Create an array of pmix_info_t structures for passing application-level directives, updating the ninfo field of the pmix_app_t structure.  C
23	PMIX_APP_INFO_CREATE(m, n)
24 25 26 27	IN m Pointer to the pmix_app_t structure (handle) IN n Number of directives to be allocated (size_t)

# 11.2.5.2 Spawn Callback Function

### Summary The pmix spawn cbfunc t is used on the PMIx client side by PMIx Spawn nb and on the PMIx server side by pmix server spawn fn t. *PMIx v1.0* typedef void (\*pmix\_spawn\_cbfunc\_t) (pmix\_status\_t status, pmix\_nspace\_t nspace, void \*cbdata); IN status Status associated with the operation (handle)

IN nspace

 Namespace string (pmix\_nspace\_t)

IN cbdata

Callback data passed to original API call (memory reference)

# **Description**

The callback will be executed upon launch of the specified applications in **PMIx\_Spawn\_nb**, or upon failure to launch any of them.

The *status* of the callback will indicate whether or not the spawn succeeded. The *nspace* of the spawned processes will be returned, along with any provided callback data. Note that the returned *nspace* value will not be protected upon return from the callback function, so the receiver must copy it if it needs to be retained.

# 11.3 Connecting and Disconnecting Processes

This section defines functions to connect and disconnect processes in two or more separate PMIx namespaces. The PMIx definition of *connected* solely implies that the host environment should treat the failure of any process in the assemblage as a reportable event, taking action on the assemblage as if it were a single application. For example, if the environment defaults (in the absence of any application directives) to terminating an application upon failure of any process in that application, then the environment should terminate all processes in the connected assemblage upon failure of any member.

The host environment may choose to assign a new namespace to the connected assemblage and/or assign new ranks for its members for its own internal tracking purposes. However, it is not required to communicate such assignments to the participants (e.g., in response to an appropriate call to PMIx\_Query\_info\_nb). The host environment is required to generate a PMIX\_ERR\_PROC\_TERM\_WO\_SYNC event should any process in the assemblage terminate or call PMIx\_Finalize without first disconnecting from the assemblage. If the job including the process is terminated as a result of that action, then the host environment is required to also generate the PMIX\_ERR\_JOB\_TERM\_WO\_SYNC for all jobs that were terminated as a result.

### Advice to PMIx server hosts

The *connect* operation does not require the exchange of job-level information nor the inclusion of information posted by participating processes via <code>PMIx\_Put</code>. Indeed, the callback function utilized in <code>pmix\_server\_connect\_fn\_t</code> cannot pass information back into the PMIx server library. However, host environments are advised that collecting such information at the participating daemons represents an optimization opportunity as participating processes are likely to request such information after the connect operation completes.

# Advice to users

Attempting to *connect* processes solely within the same namespace is essentially a *no-op* operation. While not explicitly prohibited, users are advised that a PMIx implementation or host environment may return an error in such cases.

Neither the PMIx implementation nor host environment are required to provide any tracking support for the assemblage. Thus, the application is responsible for maintaining the membership list of the assemblage.

# 13 11.3.1 PMIx Connect

# 14 Summary

1

2

4

5

6

7

8

9

10

11

12

15

Connect namespaces.

1	Format C
2	pmix_status_t
3	PMIx_Connect(const pmix_proc_t procs[], size_t nprocs,
4	const pmix_info_t info[], size_t ninfo)
	C
5	IN procs
6	Array of proc structures (array of handles)
7	IN nprocs
8	Number of elements in the <i>procs</i> array (integer)
9	IN info
0	Array of info structures (array of handles)
1	IN ninfo
2	Number of elements in the <i>info</i> array (integer)
3	Returns <b>PMIX_SUCCESS</b> or a negative value indicating the error.
	▼
4 5	PMIx libraries are not required to directly support any attributes for this function. However, any provided attributes must be passed to the host SMS daemon for processing.
	▼Optional Attributes
6	The following attributes are optional for PMIx implementations:
7	PMIX_ALL_CLONES_PARTICIPATE "pmix.clone.part" (bool)
8	All <i>clones</i> of the calling process must participate in the collective operation.
9	The following attributes are optional for host environments that support this operation:
20	PMIX_TIMEOUT "pmix.timeout" (int)
21	Time in seconds before the specified operation should time out (zero indicating infinite) and
22	return the PMIX_ERR_TIMEOUT error. Care should be taken to avoid race conditions
23	caused by multiple layers (client, server, and host) simultaneously timing the operation.
	<b>AA</b>

# Description Record the prod

3

4

5

6

7

8

9

10

11

12

13 14

15 16

17

18 19

20

22

23

Record the processes specified by the *procs* array as *connected* as per the PMIx definition. The function will return once all processes identified in *procs* have called either PMIx\_Connect or its non-blocking version, *and* the host environment has completed any supporting operations required to meet the terms of the PMIx definition of *connected* processes.

A process can only engage in one connect operation involving the identical *procs* array at a time. However, a process can be simultaneously engaged in multiple connect operations, each involving a different *procs* array.

As in the case of the **PMIx\_Fence** operation, the *info* array can be used to pass user-level directives regarding timeout constraints and other options available from the host RM.

# Advice to users

All processes engaged in a given **PMIx\_Connect** operation must provide the identical *procs* array as ordering of entries in the array and the method by which those processes are identified (e.g., use of **PMIX\_RANK\_WILDCARD** versus listing the individual processes) *may* impact the host environment's algorithm for uniquely identifying an operation.

# - Advice to PMIx library implementers -

**PMIx\_Connect** and its non-blocking form are both *collective* operations. Accordingly, the PMIx server library is required to aggregate participation by local clients, passing the request to the host environment once all local participants have executed the API.

# Advice to PMIx server hosts —

The host will receive a single call for each collective operation. It is the responsibility of the host to identify the nodes containing participating processes, execute the collective across all participating nodes, and notify the local PMIx server library upon completion of the global collective.

# 11.3.2 PMIx\_Connect\_nb

# Summary

Nonblocking **PMIx\_Connect\_nb** routine.

1	Format C
2 3 4 5	<pre>pmix_status_t PMIx_Connect_nb(const pmix_proc_t procs[], size_t nprocs,</pre>
	C -
6 7	IN procs Array of proc structures (array of handles)
8 9	IN nprocs Number of elements in the <i>procs</i> array (integer)
0	IN info Array of info structures (array of handles)
2	IN ninfo  Number of elements in the <i>info</i> array (integer)
4 5	IN cbfunc  Callback function pmix_op_cbfunc_t (function reference)
6 7	IN cbdata  Data to be passed to the callback function (memory reference)
8 9 20	A successful return indicates that the request is being processed by the host environment and the result will be returned in the provided <i>cbfunc</i> . Note that the library must not invoke the callback function prior to returning from the API. In all other cases, the <i>cbfunc</i> will <i>not</i> be called.
<u>?</u> 1	Returns PMIX_SUCCESS or one of the following error codes when the condition described occurs:
.2 23	• PMIX_OPERATION_SUCCEEDED, indicating that the request was immediately processed and returned <i>success</i> - the <i>cbfunc</i> will <i>not</i> be called
24 25	If none of the above return codes are appropriate, then an implementation must return either a general PMIx error code or an implementation defined error code as described in Section 3.1.1.
	Required Attributes
26 27	PMIx libraries are not required to directly support any attributes for this function. However, any provided attributes must be passed to the host SMS daemon for processing.

### **Optional Attributes** The following attributes are optional for PMIx implementations: 1 2 PMIX ALL CLONES PARTICIPATE "pmix.clone.part" (bool) All *clones* of the calling process must participate in the collective operation. 3 4 The following attributes are optional for host environments that support this operation: PMIX\_TIMEOUT "pmix.timeout" (int) 5 Time in seconds before the specified operation should time out (zero indicating infinite) and 6 7 return the PMIX ERR TIMEOUT error. Care should be taken to avoid race conditions caused by multiple layers (client, server, and host) simultaneously timing the operation. **Description** 9 10 Nonblocking version of **PMIx\_Connect**. The callback function is called once all processes identified in procs have called either **PMIx\_Connect** or its non-blocking version, and the host 11 environment has completed any supporting operations required to meet the terms of the PMIx 12 definition of connected processes. See the advice provided in the description for PMIx\_Connect 13 14 for more information. 11.3.3 PMIx\_Disconnect 15 Summary 16 17 Disconnect a previously connected set of processes. **Format** PMIx v1.0 19 pmix status t PMIx\_Disconnect(const pmix\_proc\_t procs[], size\_t nprocs, 20 const pmix\_info\_t info[], size\_t ninfo); 21 IN 22 procs Array of proc structures (array of handles) 23 IN 24 nprocs Number of elements in the procs array (integer) 25 IN 26 Array of info structures (array of handles) 27 28 IN ninfo 29 Number of elements in the *info* array (integer) Returns PMIX\_SUCCESS or one of the following error codes when the condition described occurs: 30

1 2	• the PMIX_ERR_INVALID_OPERATION error indicating that the specified set of <i>procs</i> was not previously <i>connected</i> via a call to PMIx_Connect or its non-blocking form.
3 4	If none of the above return codes are appropriate, then an implementation must return either a general PMIx error code or an implementation defined error code as described in Section 3.1.1.
	▼ Required Attributes
5 6	PMIx libraries are not required to directly support any attributes for this function. However, any provided attributes must be passed to the host SMS daemon for processing.
	▼ Optional Attributes
7	The following attributes are optional for PMIx implementations:
8 9	PMIX_ALL_CLONES_PARTICIPATE "pmix.clone.part" (bool) All <i>clones</i> of the calling process must participate in the collective operation.
10	The following attributes are optional for host environments that support this operation:
11 12 13 14	PMIX_TIMEOUT "pmix.timeout" (int)  Time in seconds before the specified operation should time out (zero indicating infinite) and return the PMIX_ERR_TIMEOUT error. Care should be taken to avoid race conditions caused by multiple layers (client, server, and host) simultaneously timing the operation.
15 16 17 18	<b>Description</b> Disconnect a previously connected set of processes. The function will return once all processes identified in <i>procs</i> have called either <b>PMIx_Disconnect</b> or its non-blocking version, <i>and</i> the host environment has completed any required supporting operations.
19 20 21	A process can only engage in one disconnect operation involving the identical <i>procs</i> array at a time. However, a process can be simultaneously engaged in multiple disconnect operations, each involving a different <i>procs</i> array.
22 23 24	As in the case of the <b>PMIx_Fence</b> operation, the <i>info</i> array can be used to pass user-level directives regarding the algorithm to be used for any collective operation involved in the operation, timeout constraints, and other options available from the host RM.
	Advice to users —
25 26 27 28	All processes engaged in a given <b>PMIx_Disconnect</b> operation must provide the identical <i>procs</i> array as ordering of entries in the array and the method by which those processes are identified (e.g., use of <b>PMIX_RANK_WILDCARD</b> versus listing the individual processes) <i>may</i> impact the host environment's algorithm for uniquely identifying an operation.

# - Advice to PMIx library implementers -

**PMIx\_Disconnect** and its non-blocking form are both *collective* operations. Accordingly, the PMIx server library is required to aggregate participation by local clients, passing the request to the host environment once all local participants have executed the API.

# Advice to PMIx server hosts

The host will receive a single call for each collective operation. The host will receive a single call for each collective operation. It is the responsibility of the host to identify the nodes containing participating processes, execute the collective across all participating nodes, and notify the local PMIx server library upon completion of the global collective.

# 11.3.4 PMIx Disconnect nb

### Summary

Nonblocking **PMIx\_Disconnect** routine.

# PMIx v1.0 Format

1

2

3

4 5

6

7

9

10

13

14 15

17

18

19

20

21 22

23

24

25 26

27

12 pmix status t

pmix\_op\_cbfunc\_t cbfunc, void \*cbdata);

16 **IN** procs

Array of proc structures (array of handles)

IN nprocs

Number of elements in the *procs* array (integer)

IN info

Array of info structures (array of handles)

IN ninfo

Number of elements in the *info* array (integer)

IN cbfunc

Callback function **pmix\_op\_cbfunc\_t** (function reference)

IN cbdata

Data to be passed to the callback function (memory reference)

2	result will be returned in the provided <i>cbfunc</i> . Note that the library must not invoke the callback function prior to returning from the API. In all other cases, the <i>cbfunc</i> will <i>not</i> be called.
4	Returns PMIX_SUCCESS or one of the following error codes when the condition described occurs:
5 6	• PMIX_OPERATION_SUCCEEDED, indicating that the request was immediately processed and returned <i>success</i> - the <i>cbfunc</i> will <i>not</i> be called
7 8	If none of the above return codes are appropriate, then an implementation must return either a general PMIx error code or an implementation defined error code as described in Section 3.1.1.
	Required Attributes
9 10	PMIx libraries are not required to directly support any attributes for this function. However, any provided attributes must be passed to the host SMS daemon for processing.
	▼ Optional Attributes
11	The following attributes are optional for PMIx implementations:
12 13	PMIX_ALL_CLONES_PARTICIPATE "pmix.clone.part" (bool)  All <i>clones</i> of the calling process must participate in the collective operation.
14	The following attributes are optional for host environments that support this operation:
15 16 17 18	PMIX_TIMEOUT "pmix.timeout" (int)  Time in seconds before the specified operation should time out (zero indicating infinite) and return the PMIX_ERR_TIMEOUT error. Care should be taken to avoid race conditions caused by multiple layers (client, server, and host) simultaneously timing the operation.
19	Description
20	Nonblocking <b>PMIx_Disconnect</b> routine. The callback function is called either:
21 22	<ul> <li>to return the PMIX_ERR_INVALID_OPERATION error indicating that the specified set of procs was not previously connected via a call to PMIx_Connect or its non-blocking form;</li> </ul>
23	• to return a PMIx error constant indicating that the operation failed; or
24 25	• once all processes identified in <i>procs</i> have called either <b>PMIx_Disconnect_nb</b> or its blocking version, <i>and</i> the host environment has completed any required supporting operations.
26	See the advice provided in the description for <b>PMIx_Disconnect</b> for more information.

# 11.4 Process Locality

The relative locality of processes is often used to optimize their interactions with the hardware and other processes. PMIx provides a means by which the host environment can communicate the locality of a given process using the <code>PMIx\_server\_generate\_locality\_string</code> to generate an abstracted representation of that value. This provides a human-readable format and allows the client to parse the locality string with a method of its choice that may differ from the one used by the server that generated it.

There are times, however, when relative locality and other PMIx-provided information doesn't include some element required by the application. In these instances, the application may need access to the full description of the local hardware topology. PMIx does not itself generate such descriptions - there are multiple third-party libraries that fulfill that role. Instead, PMIx offers an abstraction method by which users can obtain a pointer to the description. This transparently enables support for different methods of sharing the topology between the host environment (which may well have already generated it prior to local start of application processes) and the clients - e.g., through passing of a shared memory region.

# 16 11.4.1 PMIx\_Load\_topology

# **Summary**

**Format** 

Load the local hardware topology description

# $^{19}$ PMIx v4.0

### **V**

pmix\_status\_t

PMIx\_Load\_topology(pmix\_topology\_t \*topo);

### INOUT topo

Address of a **pmix\_topology\_t** structure where the topology information is to be loaded (handle)

A successful return indicates that the *topo* was successfully loaded.

Returns **PMIX\_SUCCESS** or a negative value indicating the error.

### Description

Obtain a pointer to the topology description of the local node. If the *source* field of the provided <code>pmix\_topology\_t</code> is set, then the PMIx library must return a description from the specified implementation or else indicate that the implementation is not available by returning the <code>PMIX\_ERR\_NOT\_SUPPORTED</code> error constant.

The returned pointer may point to a shared memory region or an actual instance of the topology description. In either case, the description shall be treated as a "read-only" object - attempts to modify the object are likely to fail and return an error. The PMIx library is responsible for performing any required cleanup when the client library finalizes.

```
Advice to users
```

It is the responsibility of the user to ensure that the topo argument is properly initialized prior to calling this API, and to check the returned source to verify that the returned topology description is compatible with the user's code.

### 11.4.2 PMIx Get relative locality

### Summary

Format

1 2

3

5

12

13

14

15 16

17

18

19

20 21

22

23

24 25

26

27

Get the relative locality of two local processes given their locality strings.

```
<sup>7</sup> PMIx v4.0
8
             pmix_status_t
             PMIx Get_relative_locality(const char *locality1,
9
10
                                            const char *locality2,
                                            pmix_locality_t *locality);
11
```

```
IN
    locality1
```

String returned by the **PMIx\_server\_generate\_locality\_string** API (handle)

IN locality2

String returned by the PMIx server generate locality string API (handle)

### **INOUT** locality

Location where the relative locality bitmask is to be constructed (memory reference)

A successful return indicates that the *locality* was successfully loaded.

Returns **PMIX\_SUCCESS** or a negative value indicating the error.

### **Description**

Parse the locality strings of two processes (as returned by PMIx Get using the

PMIX LOCALITY STRING key) and set the appropriate pmix locality t locality bits in the provided memory location.

# 11.4.2.1 Topology description

The pmix topology t structure contains a (case-insensitive) string identifying the source of the topology (e.g., "hwloc") and a pointer to the corresponding implementation-specific topology description.

```
PMIx v4.0
28
            typedef struct pmix_topology {
29
                 char *source;
30
                 void *topology;
31
             } pmix_topoology_t;
```

### 11.4.2.2 Topology support macros 2 The following macros support the **pmix\_topology\_t** structure. 3 Initialize the topology structure Initialize the pmix\_topology\_t fields to NULL PMIx v4.0 5 PMIX TOPOLOGY CONSTRUCT (m) IN 6 Pointer to the structure to be initialized (pointer to pmix\_topology\_t 7 Destruct the topology structure 8 9 Destruct the pmix\_topology\_t fields PMIx v4.0 10 PMIX TOPOLOGY DESTRUCT (m) 11 IN m Pointer to the structure to be destructed (pointer to pmix\_topology\_t) 12 13 Create a topology array Allocate and initialize a **pmix\_topology\_t** array. 14 PMIx v4.0 15 PMIX TOPOLOGY CREATE (m, n) 16 INOUT m Address where the pointer to the array of **pmix\_topology\_t** structures shall be stored 17 (handle) 18 IN 19 20 Number of structures to be allocated (size t) 21 Release a topology array 22 Release a pmix\_topology\_t array. PMIx v4.0 23 PMIX TOPOLOGY FREE (m, n) 24 INOUT m Address of the array of pmix\_topology\_t structures to be released (handle) 25 26 IN 27 Number of structures in the array (size\_t)

# 1 11.4.2.3 Relative locality of two processes

The **pmix\_locality\_t** datatype is a **uint16\_t** bitmask that defines the relative locality of two processes on a node. The following constants represent specific bits in the mask and can be used to test a locality value using standard bit-test methods.

PMIX\_LOCALITY\_UNKNOWN All bits are set to zero, indicating that the relative locality of the two processes is unknown

PMIX\_LOCALITY\_NONLOCAL The two processes do not share any common locations

PMIX\_LOCALITY\_SHARE\_HWTHREAD The two processes share at least one hardware thread
PMIX\_LOCALITY\_SHARE\_CORE The two processes share at least one core

PMIX LOCALITY SHARE L1CACHE The two processes share at least one core

PMIX\_LOCALITY\_SHARE\_L2CACHE The two processes share at least an L2 cache

PMIX\_LOCALITY\_SHARE\_L3CACHE

PMIX\_LOCALITY\_SHARE\_PACKAGE

The two processes share at least a package

The two processes share at least a package

PMIX\_LOCALITY\_SHARE\_NUMA The two processes share at least one Non-Uniform

Memory Access (NUMA) region

**PMIX\_LOCALITY\_SHARE\_NODE** The two processes are executing on the same node

Implementers and vendors may choose to extend these definitions as needed to describe a particular system.

# 19 11.4.2.4 Locality keys

2

3

4 5

6

7

8

9

10

11

12

13

14

15

16

17 18

20 21

22

23

24

25

26 27

28

29

30

# PMIX\_LOCALITY\_STRING "pmix.locstr" (char\*)

String describing a process's bound location - referenced using the process's rank. The string is prefixed by the implementation that created it (e.g., "hwloc") followed by a colon. The remainder of the string represents the corresponding locality as expressed by the underlying implementation. The entire string must be passed to PMIx\_Get\_relative\_locality for processing. Note that hosts are only required to provide locality strings for local client processes - thus, a call to PMIx\_Get for the locality string of a process that returns PMIX\_ERR\_NOT\_FOUND indicates that the process is not executing on the same node.

# 11.4.3 PMIx\_Parse\_cpuset\_string

### Summary

**Format** 

Parse the PU binding bitmap from its string representation.

```
32 pmix_status_t
33 pMIx_Parse_cpuset_string(const char *cpuset_string,
34 pmix_cpuset_t *cpuset);
```

1 2 3 4		N cpuset_string String returned by the PMIx_server_generate_cpuset_string API (handle)  NOUT cpuset  Address of an object where the bitmap is to be stored (memory reference)
5		A successful return indicates that the <i>cpuset</i> was successfully loaded.
6		Returns PMIX_SUCCESS or a negative value indicating the error.
7 8 9 10		Description Parse the string representation of the binding bitmap (as returned by PMIx_Get using the PMIX_CPUSET key) and set the appropriate PU binding location information in the provided memory location.
11	11.4.4	PMIx_Get_cpuset
12 13		Get the PU binding bitmap of the current process.
14	PMIx v4.0	Format C
15 16		<pre>omix_status_t MIx_Get_cpuset(pmix_cpuset_t *cpuset, pmix_bind_envelope_t ref);</pre>
17 18 19 20 21		NOUT cpuset  Address of an object where the bitmap is to be stored (memory reference)  N ref  The binding envelope to be considered when formulating the bitmap  (pmix_bind_envelope_t)
22		a successful return indicates that the <i>cpuset</i> was successfully loaded.
23		Returns PMIX_SUCCESS or a negative value indicating the error.
24 25 26		<b>Description</b> Description Desc
27 11.4.4.1 Binding envelope		
28 29 30	PMIx v4.0	The <b>pmix_bind_envelope_t</b> data type defines the envelope of threads within a possibly multi-threaded process that are to be considered when getting the cpuset associated with the rocess. Valid values include:
31 32 33		WIX_CPUBIND_PROCESS Use the location of all threads in the possibly multi-threaded process.  Use only the location of the thread calling the API.

# 11.4.5 PMIx\_Compute\_distances

# Summary

Compute distances from specified process location to local devices.

<sup>4</sup> *PMIx v4.0* 

3

5

6 7

8

9 10

12

13

14

15 16

17

18

19 20

21

22

23 24

25

26

27

28

29 30

31

32

33 34

# Format

11 IN topo

Pointer to the topology description of the node where the process is located (**NULL** indicates the local node) (**pmix\_topology\_t**)

IN cpuset

Pointer to the location of the process (pmix\_cpuset\_t)

IN info

Array of **pmix\_info\_t** describing the devices whose distance is to be computed (handle)

IN ninfo

Number of elements in *info* (integer)

### **INOUT** distances

Pointer to an address where the array of pmix\_device\_distance\_t structures containing the distances from the caller to the specified devices is to be returned (handle)

### INOUT ndist

Pointer to an address where the number of elements in the *distances* array is to be returned (handle)

Returns **PMIX\_SUCCESS** or a negative value indicating the error.

# **Description**

Both the minimum and maximum distance fields in the elements of the array shall be filled with the respective distances between the current process location and the types of devices or specific device identified in the *info* directives. In the absence of directives, distances to all supported device types shall be returned.

### Advice to users

A process whose threads are not all bound to the same location may return inconsistent results from calls to this API by different threads if the **PMIX\_CPUBIND\_THREAD** binding envelope was used when generating the *cpuset*.

# 11.4.6 PMIx\_Compute\_distances\_nb

33

### Summarv 3 Compute distances from specified process location to local devices. **Format** PMIx v4.0 5 pmix\_status\_t PMIx Compute\_distances\_nb(pmix\_topology\_t \*topo, 6 7 pmix\_cpuset\_t \*cpuset, pmix\_info\_t info[], size\_t ninfo[], 8 pmix\_device\_dist\_cbfunc\_t cbfunc, 9 10 void \*cbdata); IN 11 topo 12 Pointer to the topology description of the node where the process is located (NULL indicates the local node) (pmix topology t) 13 IN cpuset 14 Pointer to the location of the process (pmix\_cpuset\_t) 15 16 IN 17 Array of **pmix\_info\_t** describing the devices whose distance is to be computed (handle) ninfo IN 18 Number of elements in *info* (integer) 19 20 IN Callback function **pmix\_info\_cbfunc\_t** (function reference) 21 22 IN cbdata Data to be passed to the callback function (memory reference) 23 24 A successful return indicates that the request is being processed by the host environment and the result will be returned in the provided cbfunc. Note that the library must not invoke the callback 25 function prior to returning from the API. In all other cases, the cbfunc will not be called. 26 27 Returns PMIX\_SUCCESS or one of the following error codes when the condition described occurs: • PMIX\_OPERATION\_SUCCEEDED, indicating that the request was immediately processed 28 29 successfully - the *cbfunc* will *not* be called. 30 If none of the above return codes are appropriate, then an implementation must return either a general PMIx error code or an implementation defined error code as described in Section 3.1.1. 31 Description 32

Non-blocking form of the PMIx Compute distances API.

191

# 11.4.7 Device Distance Callback Function

```
Summarv
 3
               The pmix_device_dist_cbfunc_t is used to return an array of device distances.
               typedef void (*pmix_device_dist_cbfunc_t)
4
 5
                    (pmix_status_t status,
6
                     pmix device distance t *dist,
7
                     size_t ndist,
8
                     void *cbdata,
9
                     pmix_release_cbfunc_t release_fn,
                     void *release_cbdata);
10
               IN
11
                    status
                   Status associated with the operation (pmix status t)
12
13
               IN
14
                   Array of pmix device distance t returned by the operation (pointer)
15
               IN
                   Number of elements in the dist array (size t)
16
               IN
                  cbdata
17
18
                   Callback data passed to original API call (memory reference)
               IN
19
                  release fn
20
                   Function to be called when done with the dist data (function pointer)
21
               IN
                  release cbdata
                   Callback data to be passed to release_fn (memory reference)
22
               Description
23
24
               The status indicates if requested data was found or not. The array of
               pmix device distance t will contain the distance information.
25
    11.4.8
              Device type
26
27
               The pmix device type t is a uint 64 t bitmask for identifying the type(s) whose
28
               distances are being requested, or the type of a specific device being referenced (e.g., in a
29
               pmix device distance t object).
  PMIx v1.0
```

```
1
               typedef uint16 t pmix device type t;
               The following constants can be used to set a variable of the type pmix device_type_t.
 2
               PMIX DEVTYPE UNKNOWN
                                              The device is of an unknown type - will not be included in
 3
 4
                    returned device distances.
 5
               PMIX DEVTYPE BLOCK
                                           Operating system block device, or non-volatile memory device
                    (e.g., "sda" or "dax2.0" on Linux).
 6
                                        Operating system Graphics Processing Unit (GPU) device (e.g.,
 7
               PMIX_DEVTYPE_GPU
                    "card0" for a Linux Direct Rendering Manager (DRM) device).
 8
 9
               PMIX DEVTYPE NETWORK
                                              Operating system network device (e.g., the "eth0" interface on
                    Linux).
10
               PMIX DEVTYPE OPENFABRICS
                                                   Operating system OpenFabrics device (e.g., an "mlx4_0"
11
                    InfiniBand Host Channel Adapter (HCA), or "hfi1_0" Omni-Path interface on Linux).
12
                                        Operating system Direct Memory Access (DMA) engine device (e.g.,
               PMIX DEVTYPE DMA
13
14
                    the "dma0chan0" DMA channel on Linux).
                                            Operating system co-processor device (e.g., "mic0" for a Xeon Phi
15
               PMIX DEVTYPE COPROC
                    on Linux, "opencl0d0" for a OpenCL device, or "cuda0" for a Compute Unified Device
16
                    Architecture (CUDA) device).
17
               Device Distance Structure
    11.4.9
19
               The pmix device distance t structure contains the minimum and maximum relative
               distance from the caller to a given device.
20
   PMIx v4.0
21
               typedef struct pmix_device_distance {
22
                     char *uuid;
23
                     char *osname;
                    pmix_device_type_t type;
24
25
                    uint16 t mindist;
                     uint16 t maxdist;
26
27
               } pmix device distance t;
               The uuid is a string identifier guaranteed to be unique within the cluster and is typically assembled
28
29
               from discovered device attributes (e.g., the Internet Protocol (IP) address of the device). The
               osname is the local operating system name of the device and is only unique to that node.
30
```

The two distance fields provide the minimum and maximum relative distance to the device from the specified location of the process, expressed as a 16-bit integer value where a smaller number

indicates that this device is closer to the process than a device with a larger distance value. Note

31

32

33

that relative distance values are not necessarily correlated to a physical property - e.g., a device at 1 2 twice the distance from another device does not necessarily have twice the latency for communication with it. 3 Relative distances only apply to similar devices and cannot be used to compare devices of different 1 types. Both minimum and maximum distances are provided to support cases where the process may 5 6 be bound to more than one location, and the locations are at different distances from the device. 7 A relative distance value of **UINT16 MAX** indicates that the distance from the process to the 8 device could not be provided. This may be due to lack of available information (e.g., the PMIx 9 library not having access to device locations) or other factors. 11.4.10 **Device distance support macros** The following macros are provided to support the **pmix\_device\_distance\_t** structure. 11 12 Initialize the device distance structure 13 Initialize the pmix device distance t fields. PMIx v4.0PMIX DEVICE DIST CONSTRUCT (m) 14 15 IN Pointer to the structure to be initialized (pointer to pmix device distance t) 16 17 Destruct the device distance structure Destruct the pmix device distance t fields. 18 PMIx v4.0PMIX DEVICE DIST DESTRUCT (m) 19 IN 20 21 Pointer to the structure to be destructed (pointer to pmix device distance t) 22 Create an device distance array Allocate and initialize a pmix device distance t array. 23 PMIx v4.0 24 PMIX DEVICE DIST CREATE (m, n) INOUT m 25 Address where the pointer to the array of **pmix\_device\_distance\_t** structures shall be 26 stored (handle) 27 IN 28 Number of structures to be allocated (size t) 29

# Release an device distance array Release an array of pmix\_device\_distance\_t structures. PMIX\_DEVICE\_DIST\_FREE (m, n) IN m Pointer to the array of pmix\_device\_distance\_t structures (handle) IN n Number of structures in the array (size\_t)

# 11.4.11 Device distance attributes

9

10

11

12

13

14

15

16

17

18

19

20

The following attributes can be used to retrieve device distances from the PMIx data store. Note that distances stored by the host environment are based on the process location at the time of start of execution and may not reflect changes to location imposed by the process itself.

PMIX\_DEVICE\_DISTANCES "pmix.dev.dist" (pmix\_data\_array\_t)

Return an array of **pmix\_device\_distance\_t** containing the minimum and maximum distances of the given process location to all devices of the specified type on the local node.

PMIX\_DEVICE\_TYPE "pmix.dev.type" (pmix\_device\_type\_t)

Bitmask specifying the type(s) of device(s) whose information is being requested. Only used as a directive/qualifier.

PMIX\_DEVICE\_ID "pmix.dev.id" (string)

System-wide Universally Unique IDentifier (UUID) or node-local Operating System (OS) name of a particular device.

# **CHAPTER 12**

# **Job Management and Reporting**

1		The job management APIs provide an application with the ability to orchestrate its operation in		
2		partnership with the SMS. Members of this category include the		
3		PMIx_Allocation_request, PMIx_Job_control, and PMIx_Process_monitor		
4		APIs.		
5	12.1	Allocation Requests		
6 7		This section defines functionality to request new allocations from the RM, and request modifications to existing allocations. These are primarily used in the following scenarios:		
8		• Evolving applications that dynamically request and return resources as they execute.		
9 10		<ul> <li>Malleable environments where the scheduler redirects resources away from executing applications for higher priority jobs or load balancing.</li> </ul>		
11		• Resilient applications that need to request replacement resources in the face of failures.		
12 13		• <i>Rigid</i> jobs where the user has requested a static allocation of resources for a fixed period of time, but realizes that they underestimated their required time while executing.		
14		PMIx attempts to address this range of use-cases with a flexible API.		
15	12.1.1	PMIx_Allocation_request		
16		Summary		
17		Request an allocation operation from the host resource manager.		
18	PMIx v3.0	Format C		
19		pmix_status_t		
20		PMIx_Allocation_request(pmix_alloc_directive_t directive,		
21		<pre>pmix_info_t info[], size_t ninfo,</pre>		
22		<pre>pmix_info_t *results[], size_t *nresults);</pre>		

1	<pre>IN directive</pre>
2	Allocation directive (pmix_alloc_directive_t)
3	IN info
4	Array of pmix_info_t structures (array of handles)
5	IN ninfo
6	Number of elements in the <i>info</i> array (integer)
7	INOUT results
8	Address where a pointer to an array of <b>pmix_info_t</b> containing the results of the request
9	can be returned (memory reference)
10	INOUT nresults
11	Address where the number of elements in <i>results</i> can be returned (handle)
12	Returns <b>PMIX_SUCCESS</b> or a negative value indicating the error.
	▼ Required Attributes
13 14 15 16	PMIx libraries are not required to directly support any attributes for this function. However, any provided attributes must be passed to the host SMS daemon for processing, and the PMIx library is <i>required</i> to add the PMIX_USERID and the PMIX_GRPID attributes of the client process making the request.
17 18	Host environments that implement support for this operation are required to support the following attributes:
19 20 21	<pre>PMIX_ALLOC_REQ_ID "pmix.alloc.reqid" (char*) User-provided string identifier for this allocation request which can later be used to query status of the request.</pre>
22 23	<pre>PMIX_ALLOC_NUM_NODES "pmix.alloc.nnodes" (uint64_t) The number of nodes being requested in an allocation request.</pre>
24 25	<pre>PMIX_ALLOC_NUM_CPUS "pmix.alloc.ncpus" (uint64_t) Number of PUs being requested in an allocation request.</pre>
26 27	PMIX_ALLOC_TIME "pmix.alloc.time" (uint32_t)  Total session time (in seconds) being requested in an allocation request.

# Optional Attributes -----

1	The following attributes are optional for host environments that support this operation:
2	PMIX_ALLOC_NODE_LIST "pmix.alloc.nlist" (char*)  Regular expression of the specific nodes being requested in an allocation request.
4 5 6	<pre>PMIX_ALLOC_NUM_CPU_LIST "pmix.alloc.ncpulist" (char*) Regular expression of the number of PUs for each node being requested in an allocation request.</pre>
7 8	PMIX_ALLOC_CPU_LIST "pmix.alloc.cpulist" (char*)  Regular expression of the specific PUs being requested in an allocation request.
9 10 11	<pre>PMIX_ALLOC_MEM_SIZE "pmix.alloc.msize" (float)     Number of Megabytes[base2] of memory (per process) being requested in an allocation request.</pre>
12	<pre>PMIX_ALLOC_FABRIC "pmix.alloc.net" (array)</pre>
13	Array of pmix_info_t describing requested fabric resources. This must include at least:
14	PMIX_ALLOC_FABRIC_ID, PMIX_ALLOC_FABRIC_TYPE, and
15	<b>PMIX_ALLOC_FABRIC_ENDPTS</b> , plus whatever other descriptors are desired.
16 17	<pre>PMIX_ALLOC_FABRIC_ID "pmix.alloc.netid" (char*)</pre> The key to be used when accessing this requested fabric allocation. The fabric allocation
18	will be returned/stored as a pmix_data_array_t of pmix_info_t whose first
19	element is composed of this key and the allocated resource description. The type of the
20	included value depends upon the fabric support. For example, a Transmission Control
21	Protocol (TCP) allocation might consist of a comma-delimited string of socket ranges such
22	as "32000-32100, 33005, 38123-38146". Additional array entries will consist of
23	any provided resource request directives, along with their assigned values. Examples
24 25	include: <b>PMIX_ALLOC_FABRIC_TYPE</b> - the type of resources provided; <b>PMIX_ALLOC_FABRIC_PLANE</b> - if applicable, what plane the resources were assigned
26	from; PMIX_ALLOC_FABRIC_QOS - the assigned QoS; PMIX_ALLOC_BANDWIDTH -
27	the allocated bandwidth; PMIX_ALLOC_FABRIC_SEC_KEY - a security key for the
28	requested fabric allocation. NOTE: the array contents may differ from those requested,
29	especially if PMIX_INFO_REQD was not set in the request.
30	PMIX_ALLOC_BANDWIDTH "pmix.alloc.bw" (float)
31	Fabric bandwidth (in Megabits[base2]/sec) for the job being requested in an allocation
32	request.
33	<pre>PMIX_ALLOC_FABRIC_QOS "pmix.alloc.netqos" (char*)</pre>
34	Fabric quality of service level for the job being requested in an allocation request.
35	<pre>PMIX_ALLOC_FABRIC_TYPE "pmix.alloc.nettype" (char*)</pre>
36	Type of desired transport (e.g., "tcp", "udp") being requested in an allocation request.
37	PMIX ALLOC FABRIC PLANE "pmix.alloc.netplane" (char*)
U i	THIN RUDOU FRUNTO FURNE PHILA.GIIOU.HEUPIGHE (CHGI*)

1	ID string for the <i>fabric plane</i> to be used for the requested allocation.
2 3	<pre>PMIX_ALLOC_FABRIC_ENDPTS "pmix.alloc.endpts" (size_t) Number of endpoints to allocate per process in the job.</pre>
4 5	PMIX_ALLOC_FABRIC_ENDPTS_NODE "pmix.alloc.endpts.nd" (size_t)  Number of endpoints to allocate per <i>node</i> for the job.
6 7	PMIX_ALLOC_FABRIC_SEC_KEY "pmix.alloc.nsec" (pmix_byte_object_t)  Request that the allocation include a fabric security key for the spawned job.

#### Description

 Request an allocation operation from the host resource manager. Several broad categories are envisioned, including the ability to:

- Request allocation of additional resources, including memory, bandwidth, and compute. This should be accomplished in a non-blocking manner so that the application can continue to progress while waiting for resources to become available. Note that the new allocation will be disjoint from (i.e., not affiliated with) the allocation of the requestor thus the termination of one allocation will not impact the other.
- Extend the reservation on currently allocated resources, subject to scheduling availability and priorities. This includes extending the time limit on current resources, and/or requesting additional resources be allocated to the requesting job. Any additional allocated resources will be considered as part of the current allocation, and thus will be released at the same time.
- Return no-longer-required resources to the scheduler. This includes the "loan" of resources back to the scheduler with a promise to return them upon subsequent request.

If successful, the returned results for a request for additional resources must include the host resource manager's identifier (PMIX\_ALLOC\_ID) that the requester can use to specify the resources in, for example, a call to PMIx\_Spawn.

# 12.1.2 PMIx\_Allocation\_request\_nb

#### Summary

Request an allocation operation from the host resource manager.

1	Format C
2 3 4 5	<pre>pmix_status_t PMIx_Allocation_request_nb(pmix_alloc_directive_t directive,</pre>
6 7 8 9 10 11 12 13	IN directive Allocation directive (pmix_alloc_directive_t) IN info Array of pmix_info_t structures (array of handles) IN ninfo Number of elements in the info array (integer) IN cbfunc Callback function pmix_info_cbfunc_t (function reference) IN cbdata
15 16 17 18	Data to be passed to the callback function (memory reference)  Returns one of the following:  A successful return indicates that the request is being processed by the host environment and the result will be returned in the provided <i>cbfunc</i> . Note that the library must not invoke the callback
19 20 21 22	function prior to returning from the API. In all other cases, the <i>cbfunc</i> will <i>not</i> be called.  Returns PMIX_SUCCESS or one of the following error codes when the condition described occurs:  • PMIX_OPERATION_SUCCEEDED, indicating that the request was immediately processed and returned <i>success</i> - the <i>cbfunc</i> will <i>not</i> be called
23 24	If none of the above return codes are appropriate, then an implementation must return either a general PMIx error code or an implementation defined error code as described in Section 3.1.1.  Required Attributes
25 26 27 28	PMIx libraries are not required to directly support any attributes for this function. However, any provided attributes must be passed to the host SMS daemon for processing, and the PMIx library is required to add the PMIX_USERID and the PMIX_GRPID attributes of the client process making the request.
29 30	Host environments that implement support for this operation are required to support the following attributes:
31 32 33	<pre>PMIX_ALLOC_REQ_ID "pmix.alloc.reqid" (char*)  User-provided string identifier for this allocation request which can later be used to query status of the request.</pre>
34	<pre>PMIX_ALLOC_NUM_NODES "pmix.alloc.nnodes" (uint64_t)</pre>

I	The number of nodes being requested in an allocation request.
2	<pre>PMIX_ALLOC_NUM_CPUS "pmix.alloc.ncpus" (uint64_t) Number of PUs being requested in an allocation request.</pre>
4 5	PMIX_ALLOC_TIME "pmix.alloc.time" (uint32_t)  Total session time (in seconds) being requested in an allocation request.
	▼ Optional Attributes
6	The following attributes are optional for host environments that support this operation:
7 8	<pre>PMIX_ALLOC_NODE_LIST "pmix.alloc.nlist" (char*) Regular expression of the specific nodes being requested in an allocation request.</pre>
9 10 11	<pre>PMIX_ALLOC_NUM_CPU_LIST "pmix.alloc.ncpulist" (char*)     Regular expression of the number of PUs for each node being requested in an allocation request.</pre>
12 13	<pre>PMIX_ALLOC_CPU_LIST "pmix.alloc.cpulist" (char*) Regular expression of the specific PUs being requested in an allocation request.</pre>
14 15 16	<pre>PMIX_ALLOC_MEM_SIZE "pmix.alloc.msize" (float)     Number of Megabytes[base2] of memory (per process) being requested in an allocation request.</pre>
17 18 19 20	PMIX_ALLOC_FABRIC "pmix.alloc.net" (array)  Array of pmix_info_t describing requested fabric resources. This must include at least:  PMIX_ALLOC_FABRIC_ID, PMIX_ALLOC_FABRIC_TYPE, and  PMIX_ALLOC_FABRIC_ENDPTS, plus whatever other descriptors are desired.
21 22 23 24 25 26 27 28 29 30 31 32 33 34	PMIX_ALLOC_FABRIC_ID "pmix.alloc.netid" (char*)  The key to be used when accessing this requested fabric allocation. The fabric allocation will be returned/stored as a pmix_data_array_t of pmix_info_t whose first element is composed of this key and the allocated resource description. The type of the included value depends upon the fabric support. For example, a TCP allocation might consist of a comma-delimited string of socket ranges such as "32000-32100, 33005, 38123-38146". Additional array entries will consist of any provided resource request directives, along with their assigned values. Examples include:  PMIX_ALLOC_FABRIC_TYPE - the type of resources provided;  PMIX_ALLOC_FABRIC_PLANE - if applicable, what plane the resources were assigned from; PMIX_ALLOC_FABRIC_QOS - the assigned QoS; PMIX_ALLOC_BANDWIDTH - the allocated bandwidth; PMIX_ALLOC_FABRIC_SEC_KEY - a security key for the requested fabric allocation. NOTE: the array contents may differ from those requested, especially if PMIX_INFO_REQD was not set in the request.
35	PMIX_ALLOC_BANDWIDTH "pmix.alloc.bw" (float)

```
Fabric bandwidth (in Megabits[base2]/sec) for the job being requested in an allocation
 1
 2
                     request.
 3
               PMIX ALLOC FABRIC QOS "pmix.alloc.netgos" (char*)
                     Fabric quality of service level for the job being requested in an allocation request.
 4
               PMIX ALLOC FABRIC TYPE "pmix.alloc.nettype" (char*)
 5
                     Type of desired transport (e.g., "tcp", "udp") being requested in an allocation request.
 6
 7
               PMIX ALLOC FABRIC PLANE "pmix.alloc.netplane" (char*)
                     ID string for the fabric plane to be used for the requested allocation.
8
9
               PMIX_ALLOC_FABRIC_ENDPTS "pmix.alloc.endpts" (size_t)
10
                     Number of endpoints to allocate per process in the job.
               PMIX_ALLOC_FABRIC_ENDPTS_NODE "pmix.alloc.endpts.nd" (size_t)
11
                     Number of endpoints to allocate per node for the job.
12
13
               PMIX_ALLOC_FABRIC_SEC_KEY "pmix.alloc.nsec" (pmix_byte_object_t)
                     Request that the allocation include a fabric security key for the spawned job.
14
               Description
15
               Non-blocking form of the PMIx_Allocation_request API.
16
    12.1.3
               Job Allocation attributes
17
               Attributes used to describe the job allocation - these are values passed to and/or returned by the
18
               PMIx Allocation request nb and PMIx Allocation request APIs and are not
19
20
               accessed using the PMIx Get API.
21
               PMIX ALLOC REQ ID "pmix.alloc.regid" (char*)
22
                     User-provided string identifier for this allocation request which can later be used to query
23
                     status of the request.
               PMIX ALLOC ID "pmix.alloc.id" (char*)
24
25
                     A string identifier (provided by the host environment) for the resulting allocation which can
                     later be used to reference the allocated resources in, for example, a call to PMIx Spawn.
26
27
               PMIX_ALLOC_QUEUE "pmix.alloc.queue" (char*)
                     Name of the WLM queue to which the allocation request is to be directed, or the queue being
28
29
                     referenced in a query.
               PMIX ALLOC NUM NODES "pmix.alloc.nnodes" (uint64 t)
30
                     The number of nodes being requested in an allocation request.
31
32
               PMIX ALLOC NODE LIST "pmix.alloc.nlist" (char*)
                     Regular expression of the specific nodes being requested in an allocation request.
33
34
               PMIX ALLOC NUM CPUS "pmix.alloc.ncpus" (uint64 t)
                     Number of PUs being requested in an allocation request.
35
```

1	<pre>PMIX_ALLOC_NUM_CPU_LIST "pmix.alloc.ncpulist" (char*)</pre>
2	Regular expression of the number of PUs for each node being requested in an allocation
3	request.
4	<pre>PMIX_ALLOC_CPU_LIST "pmix.alloc.cpulist" (char*)</pre>
5	Regular expression of the specific PUs being requested in an allocation request.
6	PMIX_ALLOC_MEM_SIZE "pmix.alloc.msize" (float)
7	Number of Megabytes[base2] of memory (per process) being requested in an allocation
8	request.
9	PMIX_ALLOC_FABRIC "pmix.alloc.net" (array)
0	Array of pmix_info_t describing requested fabric resources. This must include at least
1	PMIX_ALLOC_FABRIC_ID, PMIX_ALLOC_FABRIC_TYPE, and
2	PMIX_ALLOC_FABRIC_ENDPTS, plus whatever other descriptors are desired.
3	PMIX_ALLOC_FABRIC_ID "pmix.alloc.netid" (char*)
4	The key to be used when accessing this requested fabric allocation. The fabric allocation
5	will be returned/stored as a pmix_data_array_t of pmix_info_t whose first
6	element is composed of this key and the allocated resource description. The type of the
7	included value depends upon the fabric support. For example, a TCP allocation might
8	consist of a comma-delimited string of socket ranges such as "32000-32100,
9	33005, 38123-38146". Additional array entries will consist of any provided resource
0	request directives, along with their assigned values. Examples include:
1	<pre>PMIX_ALLOC_FABRIC_TYPE - the type of resources provided;</pre>
2	PMIX_ALLOC_FABRIC_PLANE - if applicable, what plane the resources were assigned
3	from; PMIX_ALLOC_FABRIC_QOS - the assigned QoS; PMIX_ALLOC_BANDWIDTH -
4	the allocated bandwidth; PMIX_ALLOC_FABRIC_SEC_KEY - a security key for the
5	requested fabric allocation. NOTE: the array contents may differ from those requested,
6	especially if PMIX_INFO_REQD was not set in the request.
7	PMIX_ALLOC_BANDWIDTH "pmix.alloc.bw" (float)
8	Fabric bandwidth (in Megabits[base2]/sec) for the job being requested in an allocation
9	request.
0	<pre>PMIX_ALLOC_FABRIC_QOS "pmix.alloc.netqos" (char*)</pre>
1	Fabric quality of service level for the job being requested in an allocation request.
2	<pre>PMIX_ALLOC_TIME "pmix.alloc.time" (uint32_t)</pre>
3	Total session time (in seconds) being requested in an allocation request.
4	<pre>PMIX_ALLOC_FABRIC_TYPE "pmix.alloc.nettype" (char*)</pre>
5	Type of desired transport (e.g., "tcp", "udp") being requested in an allocation request.
6	<pre>PMIX_ALLOC_FABRIC_PLANE "pmix.alloc.netplane" (char*)</pre>
7	ID string for the <i>fabric plane</i> to be used for the requested allocation.
8	PMIX_ALLOC_FABRIC_ENDPTS "pmix.alloc.endpts" (size_t)
9	Number of endpoints to allocate per <i>process</i> in the job.
0	<pre>PMIX_ALLOC_FABRIC_ENDPTS_NODE "pmix.alloc.endpts.nd" (size_t)</pre>
1	Number of endpoints to allocate per <i>node</i> for the job.
2	PMIX_ALLOC_FABRIC_SEC_KEY "pmix.alloc.nsec" (pmix_byte_object_t)
3	Request that the allocation include a fabric security key for the spawned job.

#### 1 12.1.4 Job Allocation Directives

The <code>pmix\_alloc\_directive\_t</code> structure is a <code>uint8\_t</code> type that defines the behavior of allocation requests. The following constants can be used to set a variable of the type <code>pmix\_alloc\_directive\_t</code>. All definitions were introduced in version 2 of the standard unless otherwise marked.

**PMIX\_ALLOC\_NEW** A new allocation is being requested. The resulting allocation will be disjoint (i.e., not connected in a job sense) from the requesting allocation.

**PMIX\_ALLOC\_EXTEND** Extend the existing allocation, either in time or as additional resources.

**PMIX\_ALLOC\_RELEASE** Release part of the existing allocation. Attributes in the accompanying **pmix\_info\_t** array may be used to specify permanent release of the identified resources, or "lending" of those resources for some period of time.

**PMIX\_ALLOC\_REAQUIRE** Reacquire resources that were previously "lent" back to the scheduler.

**PMIX\_ALLOC\_EXTERNAL** A value boundary above which implementers are free to define their own directive values.

# 12.2 Job Control

This section defines APIs that enable the application and host environment to coordinate the response to failures and other events. This can include requesting termination of the entire job or a subset of processes within a job, but can also be used in combination with other PMIx capabilities (e.g., allocation support and event notification) for more nuanced responses. For example, an application notified of an incipient over-temperature condition on a node could use the PMIx\_Allocation\_request\_nb interface to request replacement nodes while simultaneously using the PMIx\_Job\_control\_nb interface to direct that a checkpoint event be delivered to all processes in the application. If replacement resources are not available, the application might use the PMIx\_Job\_control\_nb interface to request that the job continue at a lower power setting, perhaps sufficient to avoid the over-temperature failure.

The job control APIs can also be used by an application to register itself as available for preemption when operating in an environment such as a cloud or where incentives, financial or otherwise, are provided to jobs willing to be preempted. Registration can include attributes indicating how many resources are being offered for preemption (e.g., all or only some portion), whether the application will require time to prepare for preemption, etc. Jobs that request a warning will receive an event notifying them of an impending preemption (possibly including information as to the resources that will be taken away, how much time the application will be given prior to being preempted, whether the preemption will be a suspension or full termination, etc.) so they have an opportunity to save their work. Once the application is ready, it calls the provided event completion callback function to indicate that the SMS is free to suspend or terminate it, and can include directives regarding any desired restart.

#### Summary 3 Request a job control action. Format PMIx v3.0 5 pmix\_status\_t 6 PMIx\_Job\_control(const pmix\_proc\_t targets[], size\_t ntargets, 7 const pmix\_info\_t directives[], size\_t ndirs, pmix\_info\_t \*results[], size\_t \*nresults); 8 IN 9 targets Array of proc structures (array of handles) 10 11 IN ntargets 12 Number of elements in the *targets* array (integer) IN directives 13 14 Array of info structures (array of handles) 15 IN ndirs 16 Number of elements in the *directives* array (integer) 17 **INOUT** results Address where a pointer to an array of pmix info t containing the results of the request 18 can be returned (memory reference) 19 **INOUT** nresults 20 Address where the number of elements in results can be returned (handle) 21 Returns **PMIX SUCCESS** or a negative value indicating the error. 22 Required Attributes PMIx libraries are not required to directly support any attributes for this function. However, any 23 provided attributes must be passed to the host SMS daemon for processing, and the PMIx library is 24 required to add the PMIX USERID and the PMIX GRPID attributes of the client process making 25 26 the request. 27 Host environments that implement support for this operation are required to support the following 28 attributes: PMIX JOB CTRL ID "pmix.jctrl.id" (char\*) 29 30 Provide a string identifier for this request. The user can provide an identifier for the requested operation, thus allowing them to later request status of the operation or to 31 terminate it. The host, therefore, shall track it with the request for future reference. 32 PMIX JOB CTRL PAUSE "pmix.jctrl.pause" (bool) 33 Pause the specified processes. 34 35 PMIX JOB CTRL RESUME "pmix.jctrl.resume" (bool)

12.2.1

PMIx Job control

1	Resume ("un-pause") the specified processes.
2	<pre>PMIX_JOB_CTRL_KILL "pmix.jctrl.kill" (bool) Forcibly terminate the specified processes and cleanup.</pre>
4 5	PMIX_JOB_CTRL_SIGNAL "pmix.jctrl.sig" (int) Send given signal to specified processes.
6 7	<pre>PMIX_JOB_CTRL_TERMINATE "pmix.jctrl.term" (bool)     Politely terminate the specified processes.</pre>
8 9	<pre>PMIX_REGISTER_CLEANUP "pmix.reg.cleanup" (char*) Comma-delimited list of files to be removed upon process termination.</pre>
10 11	<pre>PMIX_REGISTER_CLEANUP_DIR "pmix.reg.cleanupdir" (char*) Comma-delimited list of directories to be removed upon process termination.</pre>
12 13	PMIX_CLEANUP_RECURSIVE "pmix.clnup.recurse" (bool)  Recursively cleanup all subdirectories under the specified one(s).
14 15	PMIX_CLEANUP_EMPTY "pmix.clnup.empty" (bool) Only remove empty subdirectories.
16 17	<pre>PMIX_CLEANUP_IGNORE "pmix.clnup.ignore" (char*) Comma-delimited list of filenames that are not to be removed.</pre>
18 19 20	PMIX_CLEANUP_LEAVE_TOPDIR "pmix.clnup.lvtop" (bool)  When recursively cleaning subdirectories, do not remove the top-level directory (the one given in the cleanup request).
	▼ Optional Attributes
21	The following attributes are optional for host environments that support this operation:
22 23 24 25	<pre>PMIX_JOB_CTRL_CANCEL "pmix.jctrl.cancel" (char*)     Cancel the specified request - the provided request ID must match the     PMIX_JOB_CTRL_ID provided to a previous call to PMIx_Job_control. An ID of     NULL implies cancel all requests from this requestor.</pre>
26 27	<pre>PMIX_JOB_CTRL_RESTART "pmix.jctrl.restart" (char*) Restart the specified processes using the given checkpoint ID.</pre>
28 29	<pre>PMIX_JOB_CTRL_CHECKPOINT "pmix.jctrl.ckpt" (char*)</pre>
30 31	<pre>PMIX_JOB_CTRL_CHECKPOINT_EVENT "pmix.jctrl.ckptev" (bool) Use event notification to trigger a process checkpoint.</pre>
32 33	<pre>PMIX_JOB_CTRL_CHECKPOINT_SIGNAL "pmix.jctrl.ckptsig" (int) Use the given signal to trigger a process checkpoint.</pre>

```
PMIX_JOB_CTRL_CHECKPOINT_TIMEOUT "pmix.jctrl.ckptsig" (int)
 1
 2
                    Time in seconds to wait for a checkpoint to complete.
 3
               PMIX JOB CTRL CHECKPOINT METHOD
               "pmix.jctrl.ckmethod" (pmix_data_array_t)
 4
 5
                    Array of pmix_info_t declaring each method and value supported by this application.
6
               PMIX_JOB_CTRL_PROVISION "pmix.jctrl.pvn" (char*)
                    Regular expression identifying nodes that are to be provisioned.
 7
8
               PMIX_JOB_CTRL_PROVISION_IMAGE "pmix.jctrl.pvnimg" (char*)
9
                    Name of the image that is to be provisioned.
               PMIX JOB CTRL PREEMPTIBLE "pmix.jctrl.preempt" (bool)
10
                    Indicate that the job can be pre-empted.
11
               Description
12
13
               Request a job control action. The targets array identifies the processes to which the requested job
               control action is to be applied. All clones of an identified process are to have the requested action
14
15
               applied to them. A NULL value can be used to indicate all processes in the caller's namespace. The
               use of PMIX_RANK_WILDCARD can also be used to indicate that all processes in the given
16
17
               namespace are to be included.
18
               The directives are provided as pmix_info_t structures in the directives array. The returned
               status indicates whether or not the request was granted, and information as to the reason for any
19
20
               denial of the request shall be returned in the results array.
    12.2.2
               PMIx Job control nb
22
               Summary
23
               Request a job control action.
               Format
   PMIx v2 0
25
               pmix status t
               PMIx Job_control_nb(const pmix_proc_t targets[], size_t ntargets,
26
27
                                         const pmix_info_t directives[], size_t ndirs,
                                        pmix info cbfunc t cbfunc, void *cbdata);
28
```

1	IN targets
2	Array of proc structures (array of handles)
3	IN ntargets
4	Number of elements in the <i>targets</i> array (integer)
5	IN directives
6 7	Array of info structures (array of handles)  IN ndirs
8	Number of elements in the <i>directives</i> array (integer)
9	IN abfunc
10	Callback function pmix_info_cbfunc_t (function reference)
11	IN cbdata
12	Data to be passed to the callback function (memory reference)
13	A successful return indicates that the request is being processed by the host environment and the
14	result will be returned in the provided <i>cbfunc</i> . Note that the library must not invoke the callback
15	function prior to returning from the API. In all other cases, the cbfunc will not be called.
16	Returns PMIX_SUCCESS or one of the following error codes when the condition described occurs
17 18	• <b>PMIX_OPERATION_SUCCEEDED</b> , indicating that the request was immediately processed and returned <i>success</i> - the <i>cbfunc</i> will <i>not</i> be called
19 20	If none of the above return codes are appropriate, then an implementation must return either a general PMIx error code or an implementation defined error code as described in Section 3.1.1.
	Required Attributes
21	PMIx libraries are not required to directly support any attributes for this function. However, any
22	provided attributes must be passed to the host SMS daemon for processing, and the PMIx library is
23	required to add the PMIX_USERID and the PMIX_GRPID attributes of the client process making
24	the request.
25	Host environments that implement support for this operation are required to support the following
26	attributes:
27	<pre>PMIX_JOB_CTRL_ID "pmix.jctrl.id" (char*)</pre>
28	Provide a string identifier for this request. The user can provide an identifier for the
29	requested operation, thus allowing them to later request status of the operation or to
30	terminate it. The host, therefore, shall track it with the request for future reference.
31	PMIX_JOB_CTRL_PAUSE "pmix.jctrl.pause" (bool)
32	Pause the specified processes.
33	PMIX_JOB_CTRL_RESUME "pmix.jctrl.resume" (bool)
34	Resume ("un-pause") the specified processes.
35	<pre>PMIX_JOB_CTRL_KILL "pmix.jctrl.kill" (bool)</pre>

1	Forcibly terminate the specified processes and cleanup.
2	PMIX_JOB_CTRL_SIGNAL "pmix.jctrl.sig" (int) Send given signal to specified processes.
4 5	PMIX_JOB_CTRL_TERMINATE "pmix.jctrl.term" (bool) Politely terminate the specified processes.
6 7	PMIX_REGISTER_CLEANUP "pmix.reg.cleanup" (char*)  Comma-delimited list of files to be removed upon process termination.
8 9	<pre>PMIX_REGISTER_CLEANUP_DIR "pmix.reg.cleanupdir" (char*) Comma-delimited list of directories to be removed upon process termination.</pre>
10 11	PMIX_CLEANUP_RECURSIVE "pmix.clnup.recurse" (bool)  Recursively cleanup all subdirectories under the specified one(s).
12 13	PMIX_CLEANUP_EMPTY "pmix.clnup.empty" (bool) Only remove empty subdirectories.
14 15	PMIX_CLEANUP_IGNORE "pmix.clnup.ignore" (char*)  Comma-delimited list of filenames that are not to be removed.
16 17 18	<pre>PMIX_CLEANUP_LEAVE_TOPDIR "pmix.clnup.lvtop" (bool)     When recursively cleaning subdirectories, do not remove the top-level directory (the one given in the cleanup request).</pre>
	▼ Optional Attributes
19	The following attributes are optional for host environments that support this operation:
20 21 22 23	<pre>PMIX_JOB_CTRL_CANCEL "pmix.jctrl.cancel" (char*)     Cancel the specified request - the provided request ID must match the     PMIX_JOB_CTRL_ID provided to a previous call to PMIx_Job_control. An ID of     NULL implies cancel all requests from this requestor.</pre>
24 25	<pre>PMIX_JOB_CTRL_RESTART "pmix.jctrl.restart" (char*) Restart the specified processes using the given checkpoint ID.</pre>
26 27	<pre>PMIX_JOB_CTRL_CHECKPOINT "pmix.jctrl.ckpt" (char*) Checkpoint the specified processes and assign the given ID to it.</pre>
28 29	<pre>PMIX_JOB_CTRL_CHECKPOINT_EVENT "pmix.jctrl.ckptev" (bool) Use event notification to trigger a process checkpoint.</pre>
30 31	PMIX_JOB_CTRL_CHECKPOINT_SIGNAL "pmix.jctrl.ckptsig" (int) Use the given signal to trigger a process checkpoint.
32 33	<pre>PMIX_JOB_CTRL_CHECKPOINT_TIMEOUT "pmix.jctrl.ckptsig" (int) Time in seconds to wait for a checkpoint to complete.</pre>

```
1
               PMIX_JOB_CTRL_CHECKPOINT_METHOD
 2
               "pmix.jctrl.ckmethod" (pmix data array t)
 3
                     Array of pmix_info_t declaring each method and value supported by this application.
               PMIX JOB CTRL_PROVISION "pmix.jctrl.pvn" (char*)
 4
 5
                     Regular expression identifying nodes that are to be provisioned.
               PMIX JOB CTRL PROVISION IMAGE "pmix.jctrl.pvnimg" (char*)
 6
                     Name of the image that is to be provisioned.
 7
 8
               PMIX_JOB_CTRL_PREEMPTIBLE "pmix.jctrl.preempt" (bool)
 9
                     Indicate that the job can be pre-empted.
10
               Description
11
               Non-blocking form of the PMIx Job control API. The targets array identifies the processes to
12
               which the requested job control action is to be applied. All clones of an identified process are to
               have the requested action applied to them. A NULL value can be used to indicate all processes in
13
               the caller's namespace. The use of PMIX RANK WILDCARD can also be used to indicate that all
14
15
               processes in the given namespace are to be included.
16
               The directives are provided as pmix info t structures in the directives array. The callback
17
               function provides a status to indicate whether or not the request was granted, and to provide some
18
               information as to the reason for any denial in the pmix info cbfunc t array of
               pmix info t structures.
19
    12.2.3
               Job control constants
20
               The following constants are specifically defined for return by the job control APIs:
21
22
               PMIX ERR CONFLICTING CLEANUP DIRECTIVES
                                                                       Conflicting directives given for
23
                    job/process cleanup.
    12.2.4
               Job control events
25
               The following job control events may be available for registration, depending upon implementation
26
               and host environment support:
27
               PMIX JCTRL CHECKPOINT
                                               Monitored by PMIx client to trigger a checkpoint operation.
28
               PMIX JCTRL CHECKPOINT COMPLETE
                                                           Sent by a PMIx client and monitored by a PMIx
                    server to notify that requested checkpoint operation has completed.
29
               PMIX_JCTRL_PREEMPT_ALERT
                                                   Monitored by a PMIx client to detect that an RM intends to
30
31
                    preempt the job.
32
               PMIX ERR PROC RESTART
                                               Error in process restart.
33
               PMIX ERR PROC CHECKPOINT
                                                   Error in process checkpoint.
```

34

Error in process migration.

PMIX ERR PROC MIGRATE

# 1 12.2.5 Job control attributes

2 3	Attributes used to request control operations on an executing application - these are values passed to the job control APIs and are not accessed using the <b>PMIx_Get</b> API.
4	PMIX_JOB_CTRL_ID "pmix.jctrl.id" (char*)
5	Provide a string identifier for this request. The user can provide an identifier for the
6	requested operation, thus allowing them to later request status of the operation or to
7	terminate it. The host, therefore, shall track it with the request for future reference.
8	PMIX_JOB_CTRL_PAUSE "pmix.jctrl.pause" (bool)
9	Pause the specified processes.
0	PMIX_JOB_CTRL_RESUME "pmix.jctrl.resume" (bool)
1	Resume ("un-pause") the specified processes.
2	PMIX_JOB_CTRL_CANCEL "pmix.jctrl.cancel" (char*)
3	Cancel the specified request - the provided request ID must match the
4	<b>PMIX_JOB_CTRL_ID</b> provided to a previous call to <b>PMIx_Job_control</b> . An ID of
5	<b>NULL</b> implies cancel all requests from this requestor.
6	PMIX_JOB_CTRL_KILL "pmix.jctrl.kill" (bool)
7	Forcibly terminate the specified processes and cleanup.
8	<pre>PMIX_JOB_CTRL_RESTART "pmix.jctrl.restart" (char*)</pre>
9	Restart the specified processes using the given checkpoint ID.
20	<pre>PMIX_JOB_CTRL_CHECKPOINT "pmix.jctrl.ckpt" (char*)</pre>
21	Checkpoint the specified processes and assign the given ID to it.
2	PMIX_JOB_CTRL_CHECKPOINT_EVENT "pmix.jctrl.ckptev" (bool)
23	Use event notification to trigger a process checkpoint.
24	PMIX_JOB_CTRL_CHECKPOINT_SIGNAL "pmix.jctrl.ckptsig" (int)
25	Use the given signal to trigger a process checkpoint.
26	PMIX_JOB_CTRL_CHECKPOINT_TIMEOUT "pmix.jctrl.ckptsig" (int)
27	Time in seconds to wait for a checkpoint to complete.
28	PMIX_JOB_CTRL_CHECKPOINT_METHOD
9	"pmix.jctrl.ckmethod" (pmix_data_array_t)
80	Array of pmix_info_t declaring each method and value supported by this application.
31	PMIX_JOB_CTRL_SIGNAL "pmix.jctrl.sig" (int)
2	Send given signal to specified processes.
3	PMIX_JOB_CTRL_PROVISION "pmix.jctrl.pvn" (char*)
34	Regular expression identifying nodes that are to be provisioned.
15	PMIX_JOB_CTRL_PROVISION_IMAGE "pmix.jctrl.pvnimg" (char*)
86	Name of the image that is to be provisioned.
37	PMIX_JOB_CTRL_PREEMPTIBLE "pmix.jctrl.preempt" (bool)
8	Indicate that the job can be pre-empted.
19	PMIX_JOB_CTRL_TERMINATE "pmix.jctrl.term" (bool)
0	Politely terminate the specified processes.
1	PMIX_REGISTER_CLEANUP "pmix.reg.cleanup" (char*)
2	Comma-delimited list of files to be removed upon process termination.

```
PMIX_REGISTER_CLEANUP_DIR "pmix.reg.cleanupdir" (char*)
1
2
                    Comma-delimited list of directories to be removed upon process termination.
3
              PMIX CLEANUP RECURSIVE "pmix.clnup.recurse" (bool)
4
                    Recursively cleanup all subdirectories under the specified one(s).
              PMIX_CLEANUP_EMPTY "pmix.clnup.empty" (bool)
5
6
                    Only remove empty subdirectories.
7
              PMIX_CLEANUP_IGNORE "pmix.clnup.ignore" (char*)
                    Comma-delimited list of filenames that are not to be removed.
8
9
              PMIX CLEANUP_LEAVE_TOPDIR "pmix.clnup.lvtop" (bool)
10
                    When recursively cleaning subdirectories, do not remove the top-level directory (the one
11
                    given in the cleanup request).
```

# 2 12.3 Process and Job Monitoring

In addition to external faults, a common problem encountered in HPC applications is a failure to make progress due to some internal conflict in the computation. These situations can result in a significant waste of resources as the SMS is unaware of the problem, and thus cannot terminate the job. Various watchdog methods have been developed for detecting this situation, including requiring a periodic "heartbeat" from the application and monitoring a specified file for changes in size and/or modification time.

The following APIs allow applications to request monitoring, directing what is to be monitored, the frequency of the associated check, whether or not the application is to be notified (via the event notification subsystem) of stall detection, and other characteristics of the operation.

### 12.3.1 PMIx\_Process\_monitor

```
    Summary
    Request that application processes be monitored.
```

```
25 PMIx v3.0

Pmix_status_t
PMIx_Process_monitor(const pmix_info_t *monitor,
pmix_status_t error,
const pmix_info_t directives[], size_t ndirs,
pmix_info_t *results[], size_t *nresults);

C

IN monitor
```

```
32 info (handle)
33 IN error
34 status (integer)
```

13

14

15 16

17 18

19

20

1 2 3	IN directives  Array of info structures (array of handles)  IN ndirs
4	Number of elements in the <i>directives</i> array (integer)
5	INOUT results
6	Address where a pointer to an array of <b>pmix_info_t</b> containing the results of the request
7	can be returned (memory reference)
8 9	INOUT nresults  Address where the number of elements in <i>results</i> can be returned (handle)
10	A successful return indicates that the results have been placed in the <i>results</i> array.
11	Returns <b>PMIX_SUCCESS</b> or a negative value indicating the error.
	▼ Optional Attributes
12	The following attributes may be implemented by a PMIx library or by the host environment. If
13	supported by the PMIx server library, then the library must not pass the supported attributes to the
14	host environment. All attributes not directly supported by the server library must be passed to the host environment if it supports this operation, and the library is <i>required</i> to add the
15 16	PMIX_USERID and the PMIX_GRPID attributes of the requesting process:
17 18	<pre>PMIX_MONITOR_ID "pmix.monitor.id" (char*) Provide a string identifier for this request.</pre>
19 20	<pre>PMIX_MONITOR_CANCEL "pmix.monitor.cancel" (char*) Identifier to be canceled (NULL means cancel all monitoring for this process).</pre>
21	PMIX_MONITOR_APP_CONTROL "pmix.monitor.appctrl" (bool)
22	The application desires to control the response to a monitoring event - i.e., the application is
23	requesting that the host environment not take immediate action in response to the event (e.g.,
24	terminating the job).
25	<pre>PMIX_MONITOR_HEARTBEAT "pmix.monitor.mbeat" (void)</pre>
26	Register to have the PMIx server monitor the requestor for heartbeats.
27	<pre>PMIX_MONITOR_HEARTBEAT_TIME "pmix.monitor.btime" (uint32_t)</pre>
28	Time in seconds before declaring heartbeat missed.
29	<pre>PMIX_MONITOR_HEARTBEAT_DROPS "pmix.monitor.bdrop" (uint32_t)</pre>
30	Number of heartbeats that can be missed before generating the event.
31	<pre>PMIX_MONITOR_FILE "pmix.monitor.fmon" (char*)</pre>
32	Register to monitor file for signs of life.
33	<pre>PMIX_MONITOR_FILE_SIZE "pmix.monitor.fsize" (bool)</pre>
34	Monitor size of given file is growing to determine if the application is running.
35	<pre>PMIX_MONITOR_FILE_ACCESS "pmix.monitor.faccess" (char*)</pre>
36	Monitor time since last access of given file to determine if the application is running.

PMIX\_MONITOR\_FILE\_MODIFY "pmix.monitor.fmod" (char\*) 1 2 Monitor time since last modified of given file to determine if the application is running. 3 PMIX\_MONITOR\_FILE\_CHECK\_TIME "pmix.monitor.ftime" (uint32\_t) Time in seconds between checking the file. 4 PMIX\_MONITOR\_FILE\_DROPS "pmix.monitor.fdrop" (uint32 t) 5 Number of file checks that can be missed before generating the event. 6 7 PMIX\_SEND\_HEARTBEAT "pmix.monitor.beat" (void) 8 Send heartbeat to local PMIx server.

#### Description

9

10

11 12

13

14

15

16 17

18

19

20 21

22

23

25 26 Request that application processes be monitored via several possible methods. For example, that the server monitor this process for periodic heartbeats as an indication that the process has not become "wedged". When a monitor detects the specified alarm condition, it will generate an event notification using the provided error code and passing along any available relevant information. It is up to the caller to register a corresponding event handler.

The *monitor* argument is an attribute indicating the type of monitor being requested. For example, **PMIX\_MONITOR\_FILE** to indicate that the requestor is asking that a file be monitored.

The *error* argument is the status code to be used when generating an event notification alerting that the monitor has been triggered. The range of the notification defaults to **PMIX RANGE NAMESPACE**. This can be changed by providing a **PMIX RANGE** directive.

The *directives* argument characterizes the monitoring request (e.g., monitor file size) and frequency of checking to be done

The returned *status* indicates whether or not the request was granted, and information as to the reason for any denial of the request shall be returned in the *results* array.

## 12.3.2 PMIx\_Process\_monitor\_nb

#### Summary

Request that application processes be monitored.

1	Format C
2	pmix_status_t
3	PMIx Process monitor nb(const pmix info t *monitor,
4	pmix_status_t error,
5	const pmix_info_t directives[],
6	size_t ndirs,
7	<pre>pmix_info_cbfunc_t cbfunc, void *cbdata);</pre>
•	C C
8	IN monitor
9	info (handle)
10	IN error
11	status (integer)
12	IN directives
13	Array of info structures (array of handles)
14	IN ndirs
15	Number of elements in the <i>directives</i> array (integer)
16	IN cbfunc
17	Callback function pmix_info_cbfunc_t (function reference)
18	IN cbdata
19	Data to be passed to the callback function (memory reference)
20	Returns one of the following:
21	A successful return indicates that the request is being processed by the host environment and the
22	result will be returned in the provided <i>cbfunc</i> . Note that the library must not invoke the callback
23	function prior to returning from the API. In all other cases, the <i>cbfunc</i> will <i>not</i> be called.
24	Returns PMIX_SUCCESS or one of the following error codes when the condition described occurs:
25	• PMIX_OPERATION_SUCCEEDED, indicating that the request was immediately processed and
26	returned <i>success</i> - the <i>cbfunc</i> will <i>not</i> be called
27	If none of the above return codes are appropriate, then an implementation must return either a
28	general PMIx error code or an implementation defined error code as described in Section 3.1.1.
	Optional Attributes
	Optional Attributes
29	The following attributes may be implemented by a PMIx library or by the host environment. If
30	supported by the PMIx server library, then the library must not pass the supported attributes to the
31	host environment. All attributes not directly supported by the server library must be passed to the
32	host environment if it supports this operation, and the library is required to add the
33	PMIX_USERID and the PMIX_GRPID attributes of the requesting process:
34	<pre>PMIX_MONITOR_ID "pmix.monitor.id" (char*)</pre>
35	Provide a string identifier for this request.

1 2		<pre>PMIX_MONITOR_CANCEL "pmix.monitor.cancel" (char*)     Identifier to be canceled (NULL means cancel all monitoring for this process).</pre>
3 4 5 6		PMIX_MONITOR_APP_CONTROL "pmix.monitor.appctrl" (bool)  The application desires to control the response to a monitoring event - i.e., the application is requesting that the host environment not take immediate action in response to the event (e.g., terminating the job).
7 8		PMIX_MONITOR_HEARTBEAT "pmix.monitor.mbeat" (void) Register to have the PMIx server monitor the requestor for heartbeats.
9 10		PMIX_MONITOR_HEARTBEAT_TIME "pmix.monitor.btime" (uint32_t) Time in seconds before declaring heartbeat missed.
11 12		<pre>PMIX_MONITOR_HEARTBEAT_DROPS "pmix.monitor.bdrop" (uint32_t) Number of heartbeats that can be missed before generating the event.</pre>
13 14		<pre>PMIX_MONITOR_FILE "pmix.monitor.fmon" (char*) Register to monitor file for signs of life.</pre>
15 16		<pre>PMIX_MONITOR_FILE_SIZE "pmix.monitor.fsize" (bool)     Monitor size of given file is growing to determine if the application is running.</pre>
17 18		<pre>PMIX_MONITOR_FILE_ACCESS "pmix.monitor.faccess" (char*)</pre>
19 20		<pre>PMIX_MONITOR_FILE_MODIFY "pmix.monitor.fmod" (char*)     Monitor time since last modified of given file to determine if the application is running.</pre>
21 22		<pre>PMIX_MONITOR_FILE_CHECK_TIME "pmix.monitor.ftime" (uint32_t) Time in seconds between checking the file.</pre>
23 24		<pre>PMIX_MONITOR_FILE_DROPS "pmix.monitor.fdrop" (uint32_t) Number of file checks that can be missed before generating the event.</pre>
25 26		PMIX_SEND_HEARTBEAT "pmix.monitor.beat" (void) Send heartbeat to local PMIx server.
27 28 29 30	12.3.3	Description  Non-blocking form of the PMIx_Process_monitor API. The <i>cbfunc</i> function provides a <i>status</i> to indicate whether or not the request was granted, and to provide some information as to the reason for any denial in the pmix_info_cbfunc_t array of pmix_info_t structures.  PMIx Heartbeat
32	12.0.0	Summary
33		Send a heartbeat to the PMIx server library

1		Format C
2		PMIx_Heartbeat();
3 4 5		<b>Description</b> A simplified macro wrapping <b>PMIx_Process_monitor_nb</b> that sends a heartbeat to the PMIx server library.
6	12.3.4	Monitoring events
7 8		The following monitoring events may be available for registration, depending upon implementation and host environment support:
9 10 11 12		<ul> <li>PMIX_MONITOR_HEARTBEAT_ALERT Heartbeat failed to arrive within specified window. The process that triggered this alert will be identified in the event.</li> <li>PMIX_MONITOR_FILE_ALERT File failed its monitoring detection criteria. The file that triggered this alert will be identified in the event.</li> </ul>
13	12.3.5	Monitoring attributes
14 15		Attributes used to control monitoring of an executing application- these are values passed to the <b>PMIx_Process_monitor_nb</b> API and are not accessed using the <b>PMIx_Get</b> API.
16		PMIX_MONITOR_ID "pmix.monitor.id" (char*) Provide a string identifier for this request.
18 19 20		PMIX_MONITOR_CANCEL "pmix.monitor.cancel" (char*)  Identifier to be canceled (NULL means cancel all monitoring for this process).  PMIX_MONITOR_APP_CONTROL "pmix.monitor.appctrl" (bool)
21 22		The application desires to control the response to a monitoring event - i.e., the application is requesting that the host environment not take immediate action in response to the event (e.g.,
23 24 25		terminating the job).  PMIX_MONITOR_HEARTBEAT "pmix.monitor.mbeat" (void)  Register to have the PMIx server monitor the requestor for heartbeats.
26 27		PMIX_SEND_HEARTBEAT "pmix.monitor.beat" (void)  Send heartbeat to local PMIx server.
28 29		PMIX_MONITOR_HEARTBEAT_TIME "pmix.monitor.btime" (uint32_t) Time in seconds before declaring heartbeat missed.
30		PMIX_MONITOR_HEARTBEAT_DROPS "pmix.monitor.bdrop" (uint32_t)  Number of heartbeats that can be missed before generating the event.
32 33 34		<pre>PMIX_MONITOR_FILE "pmix.monitor.fmon" (char*)     Register to monitor file for signs of life. PMIX_MONITOR_FILE_SIZE "pmix.monitor.fsize" (bool)</pre>
35		Monitor size of given file is growing to determine if the application is running.

```
PMIX_MONITOR_FILE_ACCESS "pmix.monitor.faccess" (char*)
 1
 2
                     Monitor time since last access of given file to determine if the application is running.
               PMIX_MONITOR_FILE_MODIFY "pmix.monitor.fmod" (char*)
 3
 4
                     Monitor time since last modified of given file to determine if the application is running.
 5
               PMIX_MONITOR_FILE_CHECK_TIME "pmix.monitor.ftime" (uint32_t)
 6
                     Time in seconds between checking the file.
 7
               PMIX MONITOR FILE DROPS "pmix.monitor.fdrop" (uint32 t)
 8
                     Number of file checks that can be missed before generating the event.
    12.4 Logging
10
               The logging interface supports posting information by applications and SMS elements to persistent
               storage. This function is not intended for output of computational results, but rather for reporting
11
               status and saving state information such as inserting computation progress reports into the
12
13
               application's SMS job log or error reports to the local syslog.
    12.4.1
                PMIx Log
15
               Summary
16
               Log data to a data service.
<sup>17</sup> PMIx v3.0
               Format
18
               pmix_status_t
               PMIx Log(const pmix info t data[], size t ndata,
19
20
                           const pmix info t directives[], size t ndirs);
               IN
21
                     data
                    Array of info structures (array of handles)
22
               IN
23
24
                    Number of elements in the data array (size t)
25
               IN
                     directives
                    Array of info structures (array of handles)
26
               IN
                    ndirs
27
28
                    Number of elements in the directives array (size_t)
               Returns PMIX_SUCCESS or one of the following error codes when the condition described occurs:
29
                PMIX ERR BAD PARAM The logging request contains at least one incorrect entry.
30
31
               If none of the above return codes are appropriate, then an implementation must return either a
```

general PMIx error code or an implementation defined error code as described in Section 3.1.1.

	Required Attributes
1 2 3	If the PMIx library does not itself perform this operation, then it is required to pass any attributes provided by the client to the host environment for processing. In addition, it must include the following attributes in the passed <i>info</i> array:
4 5	PMIX_USERID "pmix.euid" (uint32_t)  Effective user ID of the connecting process.
6 7	PMIX_GRPID "pmix.egid" (uint32_t)  Effective group ID of the connecting process.
8 9	Host environments or PMIx libraries that implement support for this operation are required to support the following attributes:
10 11	<pre>PMIX_LOG_STDERR "pmix.log.stderr" (char*) Log string to stderr.</pre>
12 13	<pre>PMIX_LOG_STDOUT "pmix.log.stdout" (char*) Log string to stdout.</pre>
14 15 16	<pre>PMIX_LOG_SYSLOG "pmix.log.syslog" (char*) Log data to syslog. Defaults to ERROR priority. Will log to global syslog if available, otherwise to local syslog.</pre>
17 18	<pre>PMIX_LOG_LOCAL_SYSLOG "pmix.log.lsys" (char*) Log data to local syslog. Defaults to ERROR priority.</pre>
19 20	<pre>PMIX_LOG_GLOBAL_SYSLOG "pmix.log.gsys" (char*) Forward data to system "gateway" and log msg to that syslog Defaults to ERROR priority.</pre>
21 22	<pre>PMIX_LOG_SYSLOG_PRI "pmix.log.syspri" (int)     Syslog priority level.</pre>
23 24 25	PMIX_LOG_ONCE "pmix.log.once" (bool)  Only log this once with whichever channel can first support it, taking the channels in priority order.
	→Optional Attributes
26 27	The following attributes are optional for host environments or PMIx libraries that support this operation:
28 29	<pre>PMIX_LOG_SOURCE "pmix.log.source" (pmix_proc_t*) ID of source of the log request.</pre>
30 31	<pre>PMIX_LOG_TIMESTAMP "pmix.log.tstmp" (time_t)     Timestamp for log report.</pre>
32	PMIX_LOG_GENERATE_TIMESTAMP "pmix.log.gtstmp" (bool)

```
Generate timestamp for log.
 1
               PMIX LOG TAG OUTPUT "pmix.log.tag" (bool)
 2
                    Label the output stream with the channel name (e.g., "stdout").
 3
               PMIX LOG TIMESTAMP OUTPUT "pmix.log.tsout" (bool)
 4
5
                    Print timestamp in output string.
6
               PMIX LOG XML OUTPUT "pmix.log.xml" (bool)
                    Print the output stream in eXtensible Markup Language (XML) format.
 7
               PMIX_LOG_EMAIL "pmix.log.email" (pmix_data_array_t)
8
                    Log via email based on pmix info t containing directives.
9
               PMIX_LOG_EMAIL_ADDR "pmix.log.emaddr" (char*)
10
                    Comma-delimited list of email addresses that are to receive the message.
11
12
               PMIX_LOG_EMAIL_SENDER_ADDR "pmix.log.emfaddr" (char*)
13
                    Return email address of sender.
               PMIX_LOG_EMAIL_SERVER "pmix.log.esrvr" (char*)
14
                    Hostname (or IP address) of SMTP server.
15
16
               PMIX LOG EMAIL SRVR PORT "pmix.log.esrvrprt" (int32 t)
17
                    Port the email server is listening to.
               PMIX LOG EMAIL SUBJECT "pmix.log.emsub" (char*)
18
                    Subject line for email.
19
20
               PMIX LOG EMAIL MSG "pmix.log.emmsg" (char*)
                    Message to be included in email.
21
               PMIX_LOG_JOB_RECORD "pmix.log.jrec" (bool)
22
23
                    Log the provided information to the host environment's job record.
24
               PMIX LOG GLOBAL DATASTORE "pmix.log.gstore" (bool)
                    Store the log data in a global data store (e.g., database).
25
               Description
26
27
               Log data subject to the services offered by the host environment. The data to be logged is provided
28
               in the data array. The (optional) directives can be used to direct the choice of logging channel.
                                                Advice to users
29
               It is strongly recommended that the PMIx_Log API not be used by applications for streaming data
               as it is not a "performant" transport and can perturb the application since it involves the local PMIx
30
               server and host SMS daemon. Note that a return of PMIX_SUCCESS only denotes that the data
31
```

was successfully handed to the appropriate system call (for local channels) or the host environment

32

33

and does not indicate receipt at the final destination.

1 12.4.2	PMIx_Log_nb
2 3	Summary Log data to a data service.
4 <i>PMIx v2.0</i>	Format C
5 6 7 8	<pre>pmix_status_t PMIx_Log_nb(const pmix_info_t data[], size_t ndata,</pre>
9 10 11 12 13 14 15 16 17	IN data Array of info structures (array of handles)  IN ndata Number of elements in the data array (size_t)  IN directives Array of info structures (array of handles)  IN ndirs Number of elements in the directives array (size_t)  IN cbfunc Callback function pmix_op_cbfunc_t (function reference)  IN cbdata
20 21	Data to be passed to the callback function (memory reference)  Return codes are one of the following:
22 23 24	A successful return indicates that the request is being processed by the host environment and the result will be returned in the provided <i>cbfunc</i> . Note that the library must not invoke the callback function prior to returning from the API. In all other cases, the <i>cbfunc</i> will <i>not</i> be called.
25	Returns PMIX_SUCCESS or one of the following error codes when the condition described occurs:
26 27 28 29	<pre>PMIX_OPERATION_SUCCEEDED, indicating that the request was immediately processed and   returned success - the cbfunc will not be called PMIX_ERR_BAD_PARAM The logging request contains at least one incorrect entry that prevents   it from being processed. The callback function will not be called.</pre>
30 31	If none of the above return codes are appropriate, then an implementation must return either a general PMIx error code or an implementation defined error code as described in Section 3.1.1.

#### Required Attributes If the PMIx library does not itself perform this operation, then it is required to pass any attributes 1 provided by the client to the host environment for processing. In addition, it must include the 2 following attributes in the passed *info* array: 3 PMIX USERID "pmix.euid" (uint32 t) 4 Effective user ID of the connecting process. 5 PMIX GRPID "pmix.egid" (uint32 t) 6 Effective group ID of the connecting process. 7 Host environments or PMIx libraries that implement support for this operation are required to 8 support the following attributes: 9 PMIX LOG STDERR "pmix.log.stderr" (char\*) 10 Log string to **stderr**. 11 PMIX LOG STDOUT "pmix.log.stdout" (char\*) 12 13 Log string to **stdout**. PMIX LOG SYSLOG "pmix.log.syslog" (char\*) 14 Log data to syslog. Defaults to **ERROR** priority. Will log to global syslog if available, 15 otherwise to local syslog. 16 PMIX LOG LOCAL SYSLOG "pmix.log.lsys" (char\*) 17 Log data to local syslog. Defaults to **ERROR** priority. 18 PMIX\_LOG\_GLOBAL\_SYSLOG "pmix.log.gsys" (char\*) 19 Forward data to system "gateway" and log msg to that syslog Defaults to **ERROR** priority. 20 PMIX\_LOG\_SYSLOG\_PRI "pmix.log.syspri" (int) 21 Syslog priority level. 22 PMIX\_LOG\_ONCE "pmix.log.once" (bool) 23 Only log this once with whichever channel can first support it, taking the channels in priority 24 25 \_\_\_\_\_\_ Optional Attributes 26 The following attributes are optional for host environments or PMIx libraries that support this operation: 27 PMIX\_LOG\_SOURCE "pmix.log.source" (pmix\_proc\_t\*) 28 29 ID of source of the log request. 30 PMIX LOG TIMESTAMP "pmix.log.tstmp" (time t) 31 Timestamp for log report. PMIX\_LOG\_GENERATE\_TIMESTAMP "pmix.log.gtstmp" (bool) 32

```
Generate timestamp for log.
 1
              PMIX LOG TAG OUTPUT "pmix.log.tag" (bool)
 2
                    Label the output stream with the channel name (e.g., "stdout").
 3
              PMIX LOG TIMESTAMP OUTPUT "pmix.log.tsout" (bool)
 4
 5
                    Print timestamp in output string.
6
              PMIX LOG XML OUTPUT "pmix.log.xml" (bool)
 7
                    Print the output stream in XML format.
              PMIX_LOG_EMAIL "pmix.log.email" (pmix_data_array_t)
8
                    Log via email based on pmix info t containing directives.
9
              PMIX_LOG_EMAIL_ADDR "pmix.log.emaddr" (char*)
10
                    Comma-delimited list of email addresses that are to receive the message.
11
12
              PMIX_LOG_EMAIL_SENDER_ADDR "pmix.log.emfaddr" (char*)
13
                    Return email address of sender.
              PMIX_LOG_EMAIL_SERVER "pmix.log.esrvr" (char*)
14
                    Hostname (or IP address) of SMTP server.
15
16
              PMIX LOG EMAIL SRVR PORT "pmix.log.esrvrprt" (int32 t)
                    Port the email server is listening to.
17
              PMIX_LOG_EMAIL_SUBJECT "pmix.log.emsub" (char*)
18
                    Subject line for email.
19
20
              PMIX LOG EMAIL MSG "pmix.log.emmsg" (char*)
                    Message to be included in email.
21
              PMIX_LOG_JOB_RECORD "pmix.log.jrec" (bool)
22
                    Log the provided information to the host environment's job record.
23
24
              PMIX LOG GLOBAL DATASTORE "pmix.log.gstore" (bool)
                    Store the log data in a global data store (e.g., database).
25
```

### Description

26

27

28 29

30

Log data subject to the services offered by the host environment. The data to be logged is provided in the *data* array. The (optional) *directives* can be used to direct the choice of logging channel. The callback function will be executed when the log operation has been completed. The *data* and *directives* arrays must be maintained until the callback is provided.

#### Advice to users

It is strongly recommended that the PMIx\_Log\_nb API not be used by applications for streaming data as it is not a "performant" transport and can perturb the application since it involves the local PMIx server and host SMS daemon. Note that a return of PMIX\_SUCCESS only denotes that the data was successfully handed to the appropriate system call (for local channels) or the host environment and does not indicate receipt at the final destination.

# 12.4.3 Log attributes

1

2

4

5

7

8

Attributes used to describe **PMIx\_Log** behavior - these are values passed to the **PMIx\_Log** API and therefore are not accessed using the **PMIx\_Get** API.

```
9
              PMIX_LOG_SOURCE "pmix.log.source" (pmix_proc_t*)
10
                    ID of source of the log request.
              PMIX_LOG_STDERR "pmix.log.stderr" (char*)
11
12
                    Log string to stderr.
13
              PMIX LOG STDOUT "pmix.log.stdout" (char*)
14
                    Log string to stdout.
15
              PMIX LOG SYSLOG "pmix.log.syslog" (char*)
                    Log data to syslog. Defaults to ERROR priority. Will log to global syslog if available,
16
17
                    otherwise to local syslog.
              PMIX LOG LOCAL SYSLOG "pmix.log.lsys" (char*)
18
                    Log data to local syslog. Defaults to ERROR priority.
19
              PMIX LOG GLOBAL SYSLOG "pmix.log.gsys" (char*)
20
                    Forward data to system "gateway" and log msg to that syslog Defaults to ERROR priority.
21
22
              PMIX LOG SYSLOG PRI "pmix.log.syspri" (int)
23
                    Syslog priority level.
              PMIX_LOG_TIMESTAMP "pmix.log.tstmp" (time_t)
24
                    Timestamp for log report.
25
              PMIX LOG GENERATE TIMESTAMP "pmix.log.gtstmp" (bool)
26
27
                    Generate timestamp for log.
              PMIX LOG TAG_OUTPUT "pmix.log.tag" (bool)
28
29
                    Label the output stream with the channel name (e.g., "stdout").
30
              PMIX_LOG_TIMESTAMP_OUTPUT "pmix.log.tsout" (bool)
31
                    Print timestamp in output string.
              PMIX_LOG_XML_OUTPUT "pmix.log.xml" (bool)
32
                    Print the output stream in XML format.
33
34
              PMIX LOG ONCE "pmix.log.once" (bool)
35
                    Only log this once with whichever channel can first support it, taking the channels in priority
```

36

37

order.

PMIX\_LOG\_MSG "pmix.log.msg" (pmix\_byte\_object\_t)

Message blob to be sent somewhere.
PMIX_LOG_EMAIL "pmix.log.email" (pmix_data_array_t)
Log via email based on <b>pmix_info_t</b> containing directives.
PMIX_LOG_EMAIL_ADDR "pmix.log.emaddr" (char*)
Comma-delimited list of email addresses that are to receive the message.
PMIX_LOG_EMAIL_SENDER_ADDR "pmix.log.emfaddr" (char*)
Return email address of sender.
PMIX_LOG_EMAIL_SUBJECT "pmix.log.emsub" (char*)
Subject line for email.
PMIX_LOG_EMAIL_MSG "pmix.log.emmsg" (char*)
Message to be included in email.
PMIX_LOG_EMAIL_SERVER "pmix.log.esrvr" (char*)
Hostname (or IP address) of SMTP server.
PMIX_LOG_EMAIL_SRVR_PORT "pmix.log.esrvrprt" (int32_t)
Port the email server is listening to.
PMIX_LOG_GLOBAL_DATASTORE "pmix.log.gstore" (bool)
Store the log data in a global data store (e.g., database).
PMIX_LOG_JOB_RECORD "pmix.log.jrec" (bool)
Log the provided information to the host environment's job record.

#### **CHAPTER 13**

# **Process Sets and Groups**

PMIx supports two slightly related, but functionally different concepts known as *process sets* and *process groups*. This chapter defines these two concepts and describes how they are utilized, along with their corresponding APIs.

### 4 13.1 Process Sets

A PMIx *Process Set* is a user-provided or host environment assigned label associated with a given set of application processes. Processes can belong to multiple process *sets* at a time. Users may define a PMIx process set at time of application execution. For example, if using the command line parallel launcher "prun", one could specify process sets as follows:

\$ prun -n 4 --pset ocean myoceanapp : -n 3 --pset ice myiceapp

In this example, the processes in the first application will be labeled with a PMIX\_PSET\_NAMES attribute with a value of *ocean* while those in the second application will be labeled with an *ice* value. During the execution, application processes could lookup the process set attribute for any process using PMIx\_Get. Alternatively, other executing applications could utilize the PMIx\_Query\_info APIs to obtain the number of declared process sets in the system, a list of their names, and other information about them. In other words, the *process set* identifier provides a label by which an application can derive information about a process and its application - it does *not*, however, confer any operational function.

Host environments can create or delete process sets at any time through the PMIx\_server\_define\_process\_set and PMIx\_server\_delete\_process\_set APIs. PMIx servers shall notify all local clients of process set operations via the PMIX\_PROCESS\_SET\_DEFINE or PMIX\_PROCESS\_SET\_DELETE events.

Process sets differ from process groups in several key ways:

- Process *sets* have no implied relationship between their members i.e., a process in a process set has no concept of a "pset rank" as it would in a process *group*.
- Process set identifiers are set by the host environment or by the user at time of application submission for execution - there are no PMIx APIs provided by which an application can define a process set or change a process set membership. In contrast, PMIx process groups can only be defined dynamically by the application.

- Process *sets* are immutable members cannot be added or removed once the set has been defined. In contrast, PMIx process *groups* can dynamically change their membership using the appropriate APIs.
- Process *groups* can be used in calls to PMIx operations. Members of process *groups* that are involved in an operation are translated by their PMIx server into their *native* identifier prior to the operation being passed to the host environment. For example, an application can define a process group to consist of ranks 0 and 1 from the host-assigned namespace of 210456, identified by the group id of *foo*. If the application subsequently calls the PMIx\_Fence API with a process identifier of {foo, PMIX\_RANK\_WILDCARD}, the PMIx server will replace that identifier with an array consisting of {210456, 0} and {210456, 1} the host-assigned identifiers of the participating processes prior to processing the request.
- Process groups can request that the host environment assign a unique size\_t Process Group
  Context IDentifier (PGCID) to the group at time of group construction. An Message Passing
  Interface (MPI) library may, for example, use the PGCID as the MPI communicator identifier for
  the group.

The two concepts do, however, overlap in that they both involve collections of processes. Users desiring to create a process group based on a process set could, for example, obtain the membership array of the process set and use that as input to <code>PMIx\_Group\_construct</code>, perhaps including the process set name as the group identifier for clarity. Note that no linkage between the set and group of the same name is implied nor maintained - e.g., changes in process group membership can not be reflected in the process set using the same identifier.

#### Advice to PMIx server hosts -

The host environment is responsible for ensuring:

- consistent knowledge of process set membership across all involved PMIx servers; and
- that process set names do not conflict with system-assigned namespaces within the scope of the set.

## 13.1.1 Process Set Constants

PMIx v4.0

 The PMIx server is required to send a notification to all local clients upon creation or deletion of process sets. Client processes wishing to receive such notifications must register for the corresponding event:

PMIX\_PROCESS\_SET\_DEFINE The host environment has defined a new process set - the event will include the process set name (PMIX\_PSET\_NAME) and the membership (PMIX\_PSET\_MEMBERS).

**PMIX\_PROCESS\_SET\_DELETE** The host environment has deleted a process set - the event will include the process set name (**PMIX\_PSET\_NAME**).

#### 13.1.2 Process Set Attributes

2 Several attributes are provided for querying the system regarding process sets using the 3 PMIx\_Query\_info APIs. 4 PMIX\_QUERY\_NUM\_PSETS "pmix.qry.psetnum" (size\_t) Return the number of process sets defined in the specified range (defaults to 5 6 PMIX\_RANGE\_SESSION). 7 PMIX\_QUERY\_PSET\_NAMES "pmix.qry.psets" (pmix\_data\_array\_t\*) 8 Return a pmix\_data\_array\_t containing an array of strings of the process set names 9 defined in the specified range (defaults to PMIX RANGE SESSION). PMIX QUERY PSET MEMBERSHIP "pmix.qry.pmems" (pmix\_data\_array\_t\*) 10 Return an array of pmix proc t containing the members of the specified process set. 11 12 The PMIX PROCESS SET DEFINE event shall include the name of the newly defined process 13 set and its members: PMIX\_PSET\_NAME "pmix.pset.nm" (char\*) The name of the newly defined process set. 14 15 PMIX\_PSET\_MEMBERS "pmix.pset.mems" (pmix\_data\_array\_t\*) 16 An array of **pmix\_proc\_t** containing the members of the newly defined process set. 17 In addition, a process can request (via PMIx\_Get) the process sets to which a given process (including itself) belongs: 18 19 PMIX\_PSET\_NAMES "pmix.pset.nms" (pmix\_data\_array\_t\*) Returns an array of char\* string names of the process sets in which the given process is a 20 21 member.

# 13.2 Process Groups

PMIx *Groups* are defined as a collection of processes desiring a common, unique identifier for operational purposes such as passing events or participating in PMIx fence operations. As with processes that assemble via PMIx\_Connect, each member of the group is provided with both the job-level information of any other namespace represented in the group, and the contact information for all group members.

However, members of PMIx Groups are *loosely coupled* as opposed to *tightly connected* when constructed via **PMIx\_Connect**. Thus, *groups* differ from **PMIx\_Connect** assemblages in several key areas, as detailed in the following sections.

## 31 13.2.1 Relation to the host environment

Calls to PMIx Group APIs are first processed within the local PMIx server. When constructed, the server creates a tracker that associates the specified processes with the user-provided group identifier, and assigns a new *group rank* based on their relative position in the array of processes provided in the call to PMIx\_Group\_construct. Members of the group can subsequently

23

24

25 26

27

28

29

30

32

33

utilize the group identifier in PMIx function calls to address the group's members, using either PMIX\_RANK\_WILDCARD to refer to all of them or the group-level rank of specific members. The PMIx server will translate the specified processes into their RM-assigned identifiers prior to passing the request up to its host. Thus, the host environment has no visibility into the group's existence or membership.

In contrast, calls to PMIx\_Connect are relayed to the host environment. This means that the host RM should treat the failure of any process in the specified assemblage as a reportable event and take appropriate action. However, the environment is not required to define a new identifier for the connected assemblage or any of its member processes, nor does it define a new rank for each process within that assemblage. In addition, the PMIx server does not provide any tracking support for the assemblage. Thus, the caller is responsible for addressing members of the connected assemblage using their RM-provided identifiers.

#### Advice to users

User-provided group identifiers must be distinct from both other group identifiers within the system and namespaces provided by the RM so as to avoid collisions between group identifiers and RM-assigned namespaces. This can usually be accomplished through the use of an application-specific prefix - e.g., "myapp-foo"

# 13.2.2 Construction procedure

 **PMIx\_Connect** calls require that every process call the API before completing – i.e., it is modeled upon the bulk synchronous traditional MPI connect/accept methodology. Thus, a given application thread can only be involved in one connect/accept operation at a time, and is blocked in that operation until all specified processes participate. In addition, there is no provision for replacing processes in the assemblage due to failure to participate, nor a mechanism by which a process might decline participation.

In contrast, PMIx Groups are designed to be more flexible in their construction procedure by relaxing these constraints. While a standard blocking form of constructing groups is provided, the event notification system is utilized to provide a designated *group leader* with the ability to replace participants that fail to participate within a given timeout period. This provides a mechanism by which the application can, if desired, replace members on-the-fly or allow the group to proceed with partial membership. In such cases, the final group membership is returned to all participants upon completion of the operation.

Additionally, PMIx supports dynamic definition of group membership based on an invite/join model. A process can asynchronously initiate construction of a group of any processes via the PMIx\_Group\_invite function call. Invitations are delivered via a PMIx event (using the PMIX\_GROUP\_INVITED event) to the invited processes which can then either accept or decline the invitation using the PMIx\_Group\_join API. The initiating process tracks responses by registering for the events generated by the call to PMIx\_Group\_join, timeouts, or process

terminations, optionally replacing processes that decline the invitation, fail to respond in time, or terminate without responding. Upon completion of the operation, the final list of participants is communicated to each member of the new group.

# 13.2.3 Destruct procedure

Members of a PMIx Group may depart the group at any time via the PMIx\_Group\_leave API. Other members are notified of the departure via the PMIX\_GROUP\_LEFT event to distinguish such events from those reporting process termination. This leaves the remaining members free to continue group operations. The PMIx\_Group\_destruct operation offers a collective method akin to PMIx\_Disconnect for deconstructing the entire group.

In contrast, processes that assemble via **PMIx\_Connect** must all depart the assemblage together – i.e., no member can depart the assemblage while leaving the remaining members in it. Even the non-blocking form of **PMIx\_Disconnect** retains this requirement in that members remain a part of the assemblage until all members have called **PMIx\_Disconnect\_nb** 

Note that applications supporting dynamic group behaviors such as asynchronous departure take responsibility for ensuring global consistency in the group definition prior to executing group collective operations - i.e., it is the application's responsibility to either ensure that knowledge of the current group membership is globally consistent across the participants, or to register for appropriate events to deal with the lack of consistency during the operation.

#### Advice to users

The reliance on PMIx events in the PMIx Group concept dictates that processes utilizing these APIs must register for the corresponding events. Failure to do so will likely lead to operational failures. Users are recommended to utilize the PMIX\_TIMEOUT directive (or retain an internal timer) on calls to PMIx Group APIs (especially the blocking form of those functions) as processes that have not registered for required events will never respond.

# 24 13.2.4 Process Group Events

25 PMIx v4.0 Asynchronous process group care.

Asynchronous process group operations rely heavily on PMIx events. The following events have been defined for that purpose.

**PMIX\_GROUP\_INVITED** The process has been invited to join a PMIx Group - the identifier of the group and the ID's of other invited (or already joined) members will be included in the notification.

**PMIX\_GROUP\_LEFT** A process has asynchronously left a PMIx Group - the process identifier of the departing process will in included in the notification.

**PMIX\_GROUP\_MEMBER\_FAILED** A member of a PMIx Group has abnormally terminated (i.e., without formally leaving the group prior to termination) - the process identifier of the failed process will be included in the notification.

- PMIX\_GROUP\_INVITE\_ACCEPTED A process has accepted an invitation to join a PMIx 1 2 Group - the identifier of the group being joined will be included in the notification. 3 PMIX GROUP INVITE DECLINED A process has declined an invitation to join a PMIx Group - the identifier of the declined group will be included in the notification. 4 5 PMIX\_GROUP\_INVITE\_FAILED An invited process failed or terminated prior to responding 6 to the invitation - the identifier of the failed process will be included in the notification. 7 PMIX GROUP MEMBERSHIP UPDATE The membership of a PMIx group has changed - the identifiers of the revised membership will be included in the notification. 8 9 PMIX GROUP CONSTRUCT ABORT Any participant in a PMIx group construct operation that returns PMIX\_GROUP\_CONSTRUCT\_ABORT from the leader failed event handler will 10 cause all participants to receive an event notifying them of that status. Similarly, the leader 11 12 may elect to abort the procedure by either returning this error code from the handler assigned to the PMIX GROUP INVITE ACCEPTED or PMIX GROUP INVITE DECLINED 13 codes, or by generating an event for the abort code. Abort events will be sent to all invited or 14 existing members of the group. 15 16 PMIX GROUP CONSTRUCT COMPLETE The group construct operation has completed - the final membership will be included in the notification. 17 PMIX GROUP LEADER FAILED The current leader of a group including this process has 18 abnormally terminated - the group identifier will be included in the notification. 19 20 PMIX GROUP LEADER SELECTED A new *leader* of a group including this process has been 21 selected - the identifier of the new leader will be included in the notification. PMIX\_GROUP\_CONTEXT\_ID\_ASSIGNED A new PGCID has been assigned by the host 22 environment to a group that includes this process - the group identifier will be included in the 23 24 notification. **Process Group Attributes** 13.2.5 25 PMIx v4.0 Attributes for querying the system regarding process groups include: PMIX\_QUERY\_NUM\_GROUPS "pmix.qry.pqrpnum" (size\_t) 27 Return the number of process groups defined in the specified range (defaults to session). 28 OPTIONAL QUALIFERS: PMIX RANGE. 29 30 PMIX\_QUERY\_GROUP\_NAMES "pmix.qry.pgrp" (pmix\_data\_array\_t\*) Return a pmix data array t containing an array of string names of the process groups 31 defined in the specified range (defaults to session). OPTIONAL QUALIFERS: 32 33 PMIX\_RANGE. PMIX QUERY GROUP MEMBERSHIP 34 35 "pmix.qry.pgrpmems" (pmix\_data\_array\_t\*) Return a pmix\_data\_array\_t of pmix\_proc\_t containing the members of the 36
  - The following attributes are used as directives in PMIx Group operations:

specified process group. REQUIRED QUALIFIERS: PMIX\_GROUP\_ID.

37

```
1
 2
 3
 4
 5
 6
 7
 8
 9
10
11
12
13
14
15
16
17
18
19
20
21
22
23
24
25
26
27
28
```

User-provided group identifier - as the group identifier may be used in PMIx operations, the user is required to ensure that the provided ID is unique within the scope of the host environment (e.g., by including some user-specific or application-specific prefix or suffix to the string).

PMIX\_GROUP\_LEADER "pmix.grp.ldr" (bool)

This process is the leader of the group.

PMIX\_GROUP\_OPTIONAL "pmix.grp.opt" (bool)

Participation is optional - do not return an error if any of the specified processes terminate without having joined. The default is **false**.

PMIX\_GROUP\_NOTIFY\_TERMINATION "pmix.grp.notterm" (bool)

Notify remaining members when another member terminates without first leaving the group.

PMIX\_GROUP\_FT\_COLLECTIVE "pmix.grp.ftcoll" (bool)

Adjust internal tracking on-the-fly for terminated processes during a PMIx group collective operation.

PMIX\_GROUP\_MEMBERSHIP "pmix.grp.mbrs" (pmix\_data\_array\_t\*)

Array **pmix proc t** identifiers identifying the members of the specified group.

PMIX\_GROUP\_ASSIGN\_CONTEXT\_ID "pmix.grp.actxid" (bool)

Requests that the RM assign a new context identifier to the newly created group. The identifier is an unsigned, <code>size\_t</code> value that the RM guarantees to be unique across the range specified in the request. Thus, the value serves as a means of identifying the group within that range. If no range is specified, then the request defaults to <code>PMIX\_RANGE\_SESSION</code>.

PMIX\_GROUP\_LOCAL\_ONLY "pmix.grp.lcl" (bool)

Group operation only involves local processes. PMIx implementations are *required* to automatically scan an array of group members for local vs remote processes - if only local processes are detected, the implementation need not execute a global collective for the operation unless a context ID has been requested from the host environment. This can result in significant time savings. This attribute can be used to optimize the operation by indicating whether or not only local processes are represented, thus allowing the implementation to bypass the scan.

The following attributes are used to return information at the conclusion of a PMIx Group operation and/or in event notifications:

```
PMIX_GROUP_CONTEXT_ID "pmix.grp.ctxid" (size_t)
```

Context identifier assigned to the group by the host RM.

```
PMIX_GROUP_ENDPT_DATA "pmix.grp.endpt" (pmix_byte_object_t)
```

Data collected during group construction to ensure communication between group members is supported upon completion of the operation.

In addition, a process can request (via **PMIx\_Get**) the process groups to which a given process (including itself) belongs:

```
PMIX_GROUP_NAMES "pmix.pgrp.nm" (pmix_data_array_t*)
```

Returns an array of **char\*** string names of the process groups in which the given process is 1 2 a member. 13.2.6 PMIx\_Group\_construct Summary 4 5 Construct a PMIx process group. Format PMIx v4.0 7 pmix\_status\_t 8 PMIx Group construct(const char grp[], 9 const pmix\_proc\_t procs[], size\_t nprocs, 10 const pmix\_info\_t directives[], 11 size t ndirs, 12 pmix\_info\_t \*\*results, 13 size\_t \*nresults); 14 IN grp 15 NULL-terminated character array of maximum size PMIX\_MAX\_NSLEN containing the group identifier (string) 16 IN 17 procs Array of pmix proc t structures containing the PMIx identifiers of the member processes 18 19 (array of handles) 20 IN nprocs Number of elements in the *procs* array (size\_t) 21 22 IN directives 23 Array of **pmix\_info\_t** structures (array of handles) 24 IN ndirs Number of elements in the *directives* array (size\_t) 25 **INOUT** results 26 Pointer to a location where the array of **pmix** info t describing the results of the 27 28 operation is to be returned (pointer to handle) INOUT nresults 29

(memory reference)

30

31

32

Returns **PMIX\_SUCCESS** or a negative value indicating the error.

Pointer to a size t location where the number of elements in results is to be returned

	→ Required Attributes
1 2	The following attributes are <i>required</i> to be supported by all PMIx libraries that support this operation:
3 4	PMIX_GROUP_LEADER "pmix.grp.ldr" (bool)  This process is the leader of the group.
5 6 7	<pre>PMIX_GROUP_OPTIONAL "pmix.grp.opt" (bool) Participation is optional - do not return an error if any of the specified processes terminate without having joined. The default is false.</pre>
8 9 10 11 12 13 14	PMIX_GROUP_LOCAL_ONLY "pmix.grp.lcl" (bool)  Group operation only involves local processes. PMIx implementations are required to automatically scan an array of group members for local vs remote processes - if only local processes are detected, the implementation need not execute a global collective for the operation unless a context ID has been requested from the host environment. This can result in significant time savings. This attribute can be used to optimize the operation by indicating whether or not only local processes are represented, thus allowing the implementation to bypass the scan.
16 17 18	<pre>PMIX_GROUP_FT_COLLECTIVE "pmix.grp.ftcoll" (bool)    Adjust internal tracking on-the-fly for terminated processes during a PMIx group collective operation.</pre>
19	Host environments that support this operation are required to support the following attributes:
20 21 22 23 24	PMIX_GROUP_ASSIGN_CONTEXT_ID "pmix.grp.actxid" (bool)  Requests that the RM assign a new context identifier to the newly created group. The identifier is an unsigned, size_t value that the RM guarantees to be unique across the range specified in the request. Thus, the value serves as a means of identifying the group within that range. If no range is specified, then the request defaults to PMIX_RANGE_SESSION.
25 26 27	<pre>PMIX_GROUP_NOTIFY_TERMINATION "pmix.grp.notterm" (bool)    Notify remaining members when another member terminates without first leaving the group.</pre>
	→Optional Attributes
28	The following attributes are optional for host environments that support this operation:
29 30 31 32	PMIX_TIMEOUT "pmix.timeout" (int)  Time in seconds before the specified operation should time out (zero indicating infinite) and return the PMIX_ERR_TIMEOUT error. Care should be taken to avoid race conditions caused by multiple layers (client, server, and host) simultaneously timing the operation.

### **Description**

Construct a new group composed of the specified processes and identified with the provided group identifier. The group identifier is a user-defined, **NULL**-terminated character array of length less than or equal to **PMIX\_MAX\_NSLEN**. Only characters accepted by standard string comparison functions (e.g., *strncmp*) are supported. Processes may engage in multiple simultaneous group construct operations so long as each is provided with a unique group ID. The *directives* array can be used to pass user-level directives regarding timeout constraints and other options available from the PMIx server.

If the PMIX\_GROUP\_NOTIFY\_TERMINATION attribute is provided and has a value of true, then either the construct leader (if PMIX\_GROUP\_LEADER is provided) or all participants who register for the PMIX\_GROUP\_MEMBER\_FAILED event will receive events whenever a process fails or terminates prior to calling PMIx\_Group\_construct – i.e. if a group leader is declared, only that process will receive the event. In the absence of a declared leader, all specified group members will receive the event.

The event will contain the identifier of the process that failed to join plus any other information that the host RM provided. This provides an opportunity for the leader or the collective members to react to the event – e.g., to decide to proceed with a smaller group or to abort the operation. The decision is communicated to the PMIx library in the results array at the end of the event handler. This allows PMIx to properly adjust accounting for procedure completion. When construct is complete, the participating PMIx servers will be alerted to any change in participants and each group member will receive an updated group membership (marked with the PMIX GROUP MEMBERSHIP attribute) as part of the *results* array returned by this API.

Failure of the declared leader at any time will cause a PMIX\_GROUP\_LEADER\_FAILED event to be delivered to all participants so they can optionally declare a new leader. A new leader is identified by providing the PMIX\_GROUP\_LEADER attribute in the results array in the return of the event handler. Only one process is allowed to return that attribute, thereby declaring itself as the new leader. Results of the leader selection will be communicated to all participants via a PMIX\_GROUP\_LEADER\_SELECTED event identifying the new leader. If no leader was selected, then the pmix\_info\_t provided to that event handler will include that information so the participants can take appropriate action.

Any participant that returns PMIX\_GROUP\_CONSTRUCT\_ABORT from either the PMIX\_GROUP\_MEMBER\_FAILED or the PMIX\_GROUP\_LEADER\_FAILED event handler will cause the construct process to abort, returning from the call with a PMIX\_GROUP\_CONSTRUCT\_ABORT status.

If the PMIX\_GROUP\_NOTIFY\_TERMINATION attribute is not provided or has a value of false, then the PMIx\_Group\_construct operation will simply return an error whenever a proposed group member fails or terminates prior to calling PMIx\_Group\_construct.

Providing the PMIX\_GROUP\_OPTIONAL attribute with a value of true directs the PMIx library to consider participation by any specified group member as non-required - thus, the operation will return PMIX\_SUCCESS if all members participate, or PMIX\_ERR\_PARTIAL\_SUCCESS if some

members fail to participate. The *results* array will contain the final group membership in the latter case. Note that this use-case can cause the operation to hang if the **PMIX\_TIMEOUT** attribute is not specified and one or more group members fail to call **PMIx\_Group\_construct** while continuing to execute. Also, note that no leader or member failed events will be generated during the operation.

Processes in a group under construction are not allowed to leave the group until group construction is complete. Upon completion of the construct procedure, each group member will have access to the job-level information of all namespaces represented in the group plus any information posted via **PMIx\_Put** (subject to the usual scoping directives) for every group member.

### Advice to PMIx library implementers

At the conclusion of the construct operation, the PMIx library is *required* to ensure that job-related information from each participating namespace plus any information posted by group members via **PMIx\_Put** (subject to scoping directives) is available to each member via calls to **PMIx\_Get**.

#### Advice to PMIx server hosts

The collective nature of this API generally results in use of a fence-like operation by the backend host environment. Host environments that utilize the array of process participants as a *signature* for such operations may experience potential conflicts should both a **PMIx\_Group\_construct** and a **PMIx\_Fence** operation involving the same participants be simultaneously executed. As PMIx allows for such use-cases, it is therefore the responsibility of the host environment to resolve any potential conflicts.

### 13.2.7 PMIx\_Group\_construct\_nb

#### Summary

Non-blocking form of **PMIx\_Group\_construct**.

1

2

3

5

6 7

8

9

10

11

12

13

14

15

16

17

18 19

20

21

22

23 24

25

26 27

28 29

30

31 32

33

34 35

36

A successful return indicates that the request is being processed by the host environment and the result will be returned in the provided *cbfunc*. Note that the library must not invoke the callback function prior to returning from the API. In all other cases, the *cbfunc* will *not* be called.

Returns PMIX\_SUCCESS or one of the following error codes when the condition described occurs:

**PMIX\_OPERATION\_SUCCEEDED**, indicating that the request was immediately processed successfully - the *cbfunc* will *not* be called.

If none of the above return codes are appropriate, then an implementation must return either a general PMIx error code or an implementation defined error code as described in Section 3.1.1.

If executed, the status returned in the provided callback function will be one of the following constants:

- PMIX\_SUCCESS The operation succeeded and all specified members participated.
- PMIX\_ERR\_PARTIAL\_SUCCESS The operation succeeded but not all specified members participated - the final group membership is included in the callback function.

1 2	<ul> <li>PMIX_ERR_NOT_SUPPORTED While the PMIx server supports this operation, the host RM does not.</li> </ul>
3	• a non-zero PMIx error constant indicating a reason for the request's failure.
	Required Attributes
4 5	PMIx libraries that choose not to support this operation <i>must</i> return  PMIX_ERR_NOT_SUPPORTED when the function is called.
6 7	The following attributes are <i>required</i> to be supported by all PMIx libraries that support this operation:
8 9	PMIX_GROUP_LEADER "pmix.grp.ldr" (bool)  This process is the leader of the group.
0 1 2	<pre>PMIX_GROUP_OPTIONAL "pmix.grp.opt" (bool)     Participation is optional - do not return an error if any of the specified processes terminate without having joined. The default is false.</pre>
3 4 5 6 7 8 9	PMIX_GROUP_LOCAL_ONLY "pmix.grp.lcl" (bool)  Group operation only involves local processes. PMIx implementations are <i>required</i> to automatically scan an array of group members for local vs remote processes - if only local processes are detected, the implementation need not execute a global collective for the operation unless a context ID has been requested from the host environment. This can result in significant time savings. This attribute can be used to optimize the operation by indicating whether or not only local processes are represented, thus allowing the implementation to bypass the scan.
21 22 23	<pre>PMIX_GROUP_FT_COLLECTIVE "pmix.grp.ftcoll" (bool)    Adjust internal tracking on-the-fly for terminated processes during a PMIx group collective operation.</pre>
24	Host environments that support this operation are required to provide the following attributes:
25 26 27 28	PMIX_GROUP_ASSIGN_CONTEXT_ID "pmix.grp.actxid" (bool)  Requests that the RM assign a new context identifier to the newly created group. The identifier is an unsigned, size_t value that the RM guarantees to be unique across the range specified in the request. Thus, the value serves as a means of identifying the group within that range. If no range is specified, then the request defaults to PMIX_RANGE_SESSION.
30 31	<pre>PMIX_GROUP_NOTIFY_TERMINATION "pmix.grp.notterm" (bool) Notify remaining members when another member terminates without first leaving the group.</pre>

	▼ Optional Attributes		
1	The following attributes are optional for host environments that support this operation:		
2 3 4 5	PMIX_TIMEOUT "pmix.timeout" (int)  Time in seconds before the specified operation should time out (zero indicating infinite) and return the PMIX_ERR_TIMEOUT error. Care should be taken to avoid race conditions caused by multiple layers (client, server, and host) simultaneously timing the operation.		
6 7 8 9	Description  Non-blocking version of the PMIx_Group_construct operation. The callback function will be called once all group members have called either PMIx_Group_construct or PMIx_Group_construct_nb.		
o <b>13.2.8</b>	PMIx_Group_destruct		
1 2	Summary Destruct a PMIx process group.		
3 <i>PMIx v4.0</i>	Format		
4	pmix_status_t		
5	PMIx_Group_destruct(const char grp[],		
6	<pre>const pmix_info_t directives[],</pre>		
7	<pre>size_t ndirs);</pre>		
	C		
0	IN		
8	IN grp NULL-terminated character array of maximum size PMIX_MAX_NSLEN containing the		
9 0	identifier of the group to be destructed (string)		
1	IN directives		
2	Array of pmix_info_t structures (array of handles)		
3	IN ndirs		
4	Number of elements in the <i>directives</i> array (size_t)		
5	Returns <b>PMIX_SUCCESS</b> or a negative value indicating the error.		
	Required Attributes		
6	For implementations and host environments that support the operation, there are no identified		
7	required attributes for this API.		

### **Optional Attributes**

The following attributes are optional for host environments that support this operation:

#### PMIX\_TIMEOUT "pmix.timeout" (int)

Time in seconds before the specified operation should time out (zero indicating infinite) and return the **PMIX\_ERR\_TIMEOUT** error. Care should be taken to avoid race conditions caused by multiple layers (client, server, and host) simultaneously timing the operation.

### Description

Destruct a group identified by the provided group identifier. Processes may engage in multiple simultaneous group destruct operations so long as each involves a unique group ID. The *directives* array can be used to pass user-level directives regarding timeout constraints and other options available from the PMIx server.

The destruct API will return an error if any group process fails or terminates prior to calling PMIx\_Group\_destruct or its non-blocking version unless the PMIX\_GROUP\_NOTIFY\_TERMINATION attribute was provided (with a value of false) at time of group construction. If notification was requested, then the PMIX\_GROUP\_MEMBER\_FAILED event will be delivered for each process that fails to call destruct and the destruct tracker updated to account for the lack of participation. The PMIx\_Group\_destruct operation will subsequently return PMIX\_SUCCESS when the remaining processes have all called destruct – i.e., the event will serve in place of return of an error.

### Advice to PMIx server hosts -

The collective nature of this API generally results in use of a fence-like operation by the backend host environment. Host environments that utilize the array of process participants as a *signature* for such operations may experience potential conflicts should both a **PMIx\_Group\_destruct** and a **PMIx\_Fence** operation involving the same participants be simultaneously executed. As PMIx allows for such use-cases, it is therefore the responsibility of the host environment to resolve any potential conflicts.

### 13.2.9 PMIx\_Group\_destruct\_nb

### Summary

Non-blocking form of PMIx\_Group\_destruct.

1	Format C		
2	pmix_status_t		
3	PMIx_Group_destruct_nb(const char grp[],		
4	const pmix_info_t directives[],		
5	size t ndirs,		
6	<pre>pmix_op_cbfunc_t cbfunc, void *cbdata);</pre>		
Ü	pzop_oszuno_s oszuno, vozu **osuuoz,/		
7	IN grp		
8	<b>NULL</b> -terminated character array of maximum size <b>PMIX_MAX_NSLEN</b> containing the		
9	identifier of the group to be destructed (string)		
0	IN directives		
1	Array of pmix_info_t structures (array of handles)		
2	IN ndirs		
3	Number of elements in the <i>directives</i> array (size_t)		
4	IN cbfunc		
5	Callback function <b>pmix_op_cbfunc_t</b> (function reference)		
6	IN cbdata		
7	Data to be passed to the callback function (memory reference)		
8	A successful return indicates that the request is being processed by the host environment and the		
9	result will be returned in the provided <i>cbfunc</i> . Note that the library must not invoke the callback		
20	function prior to returning from the API. In all other cases, the <i>cbfunc</i> will <i>not</i> be called.		
21	Returns PMIX_SUCCESS or one of the following error codes when the condition described occurs:		
22	PMIX_OPERATION_SUCCEEDED, indicating that the request was immediately processed		
23	successfully - the <i>cbfunc</i> will <i>not</i> be called.		
24	If none of the above return codes are appropriate, then an implementation must return either a		
25	general PMIx error code or an implementation defined error code as described in Section 3.1.1.		
.0			
26	If executed, the status returned in the provided callback function will be one of the following		
27	constants:		
28	• PMIX_SUCCESS The operation was successfully completed.		
29	• PMIX_ERR_NOT_SUPPORTED While the PMIx server supports this operation, the host RM		
80	does not.		
81	• a non-zero PMIx error constant indicating a reason for the request's failure.		
	Required Attributes		
22	DMIv libraries that chaose not to support this energian wast return		
32 33	PMIx libraries that choose not to support this operation <i>must</i> return  PMIX_ERR_NOT_SUPPORTED when the function is called. For implementations and host		
J	EMIA_ERR_NOT_SOFFORTED when the function is called. For implementations and nost		

environments that support the operation, there are no identified required attributes for this API.

```
Optional Attributes
               The following attributes are optional for host environments that support this operation:
 1
 2
               PMIX_TIMEOUT "pmix.timeout" (int)
 3
                     Time in seconds before the specified operation should time out (zero indicating infinite) and
 4
                     return the PMIX ERR TIMEOUT error. Care should be taken to avoid race conditions
                     caused by multiple layers (client, server, and host) simultaneously timing the operation.
 5
               Description
6
 7
               Non-blocking version of the PMIx Group destruct operation. The callback function will be
8
               called once all members of the group have executed either PMIx Group destruct or
9
               PMIx Group destruct nb.
    13.2.10
                 PMIx Group invite
               Summary
11
               Asynchronously construct a PMIx process group.
12
13 PMIx v4.0
               Format
14
               pmix_status_t
               PMIx_Group_invite(const char grp[],
15
16
                                      const pmix_proc_t procs[], size_t nprocs,
17
                                      const pmix_info_t directives[], size_t ndirs,
18
                                      pmix info t **results, size t *nresult);
               IN
19
                    grp
20
                   NULL-terminated character array of maximum size PMIX_MAX_NSLEN containing the group
                   identifier (string)
21
22
               IN
                    procs
23
                    Array of pmix proc_t structures containing the PMIx identifiers of the processes to be
                   invited (array of handles)
24
               IN
                    nprocs
25
                   Number of elements in the procs array (size_t)
26
27
               IN
                    directives
                   Array of pmix info t structures (array of handles)
28
               IN
29
                   ndirs
30
                   Number of elements in the directives array (size t)
```

1 2 3 4 5	<pre>INOUT results     Pointer to a location where the array of pmix_info_t describing the results of the operation is to be returned (pointer to handle) INOUT nresults     Pointer to a size_t location where the number of elements in results is to be returned (memory reference)</pre>
7	Returns <b>PMIX_SUCCESS</b> or a negative value indicating the error.
	Required Attributes
8 9	The following attributes are <i>required</i> to be supported by all PMIx libraries that support this operation:
10 11 12	PMIX_GROUP_OPTIONAL "pmix.grp.opt" (bool)  Participation is optional - do not return an error if any of the specified processes terminate without having joined. The default is false.
13 14 15	<pre>PMIX_GROUP_FT_COLLECTIVE "pmix.grp.ftcoll" (bool)    Adjust internal tracking on-the-fly for terminated processes during a PMIx group collective operation.</pre>
16	Host environments that support this operation are required to provide the following attributes:
17 18 19 20 21	PMIX_GROUP_ASSIGN_CONTEXT_ID "pmix.grp.actxid" (bool)  Requests that the RM assign a new context identifier to the newly created group. The identifier is an unsigned, size_t value that the RM guarantees to be unique across the range specified in the request. Thus, the value serves as a means of identifying the group within that range. If no range is specified, then the request defaults to PMIX_RANGE_SESSION.
22 23 24	PMIX_GROUP_NOTIFY_TERMINATION "pmix.grp.notterm" (bool)  Notify remaining members when another member terminates without first leaving the group.  Optional Attributes
05	
25 26 27 28 29	The following attributes are optional for host environments that support this operation:  PMIX_TIMEOUT "pmix.timeout" (int)  Time in seconds before the specified operation should time out (zero indicating infinite) and return the PMIX_ERR_TIMEOUT error. Care should be taken to avoid race conditions caused by multiple layers (client, server, and host) simultaneously timing the operation.

### **Description**

Explicitly invite the specified processes to join a group. The process making the <code>PMIx\_Group\_invite</code> call is automatically declared to be the <code>group leader</code>. Each invited process will be notified of the invitation via the <code>PMIX\_GROUP\_INVITED</code> event - the processes being invited must therefore register for the <code>PMIX\_GROUP\_INVITED</code> event in order to be notified of the invitation. Note that the PMIx event notification system caches events - thus, no ordering of invite versus event registration is required.

The invitation event will include the identity of the inviting process plus the name of the group. When ready to respond, each invited process provides a response using either the blocking or non-blocking form of PMIx\_Group\_join. This will notify the inviting process that the invitation was either accepted (via the PMIX\_GROUP\_INVITE\_ACCEPTED event) or declined (via the PMIX\_GROUP\_INVITE\_DECLINED event). The PMIX\_GROUP\_INVITE\_ACCEPTED event is captured by the PMIx client library of the inviting process – i.e., the application itself does not need to register for this event. The library will track the number of accepting processes and alert the inviting process (by returning from the blocking form of PMIx\_Group\_invite or calling the callback function of the non-blocking form) when group construction completes.

The inviting process should, however, register for the PMIX\_GROUP\_INVITE\_DECLINED if the application allows invited processes to decline the invitation. This provides an opportunity for the application to either invite a replacement, declare "abort", or choose to remove the declining process from the final group. The inviting process should also register to receive PMIX\_GROUP\_INVITE\_FAILED events whenever a process fails or terminates prior to responding to the invitation. Actions taken by the inviting process in response to these events must be communicated at the end of the event handler by returning the corresponding result so that the PMIx library can adjust accordingly.

Upon completion of the operation, all members of the new group will receive access to the job-level information of each other's namespaces plus any information posted via **PMIx\_Put** by the other members.

The inviting process is automatically considered the leader of the asynchronous group construction procedure and will receive all failure or termination events for invited members prior to completion. The inviting process is required to provide a PMIX\_GROUP\_CONSTRUCT\_COMPLETE event once the group has been fully assembled – this event is used by the PMIx library as a trigger to release participants from their call to PMIx\_Group\_join and provides information (e.g., the final group membership) to be returned in the *results* array.

Failure of the inviting process at any time will cause a PMIX\_GROUP\_LEADER\_FAILED event to be delivered to all participants so they can optionally declare a new leader. A new leader is identified by providing the PMIX\_GROUP\_LEADER attribute in the results array in the return of the event handler. Only one process is allowed to return that attribute, declaring itself as the new leader. Results of the leader selection will be communicated to all participants via a PMIX\_GROUP\_LEADER\_SELECTED event identifying the new leader. If no leader was selected, then the status code provided in the event handler will provide an error value so the participants can take appropriate action.

#### Advice to users

Applications are not allowed to use the group in any operations until group construction is complete. This is required in order to ensure consistent knowledge of group membership across all participants.

### 13.2.11 PMIx\_Group\_invite\_nb

#### Summary

Non-blocking form of PMIx\_Group\_invite.

```
PMIx v4.0 Format
```

1

2

5

8

10

11 12

13

14

15 16

17

18

19

20

21

22

23 24

25

26

27

28 29

30

31 32 const pmix\_info\_t directives[], size\_t ndirs,
pmix info cbfunc t cbfunc, void \*cbdata);

pmix\_info\_cbfunc\_t cbfunc, void \*cbdata);

IN grp

**NULL**-terminated character array of maximum size **PMIX\_MAX\_NSLEN** containing the group identifier (string)

IN procs

Array of **pmix\_proc\_t** structures containing the PMIx identifiers of the processes to be invited (array of handles)

IN nprocs

Number of elements in the *procs* array (size\_t)

IN directives

Array of pmix\_info\_t structures (array of handles)

IN ndirs

Number of elements in the *directives* array (size\_t)

IN cbfunc

Callback function **pmix\_info\_cbfunc\_t** (function reference)

IN cbdata

Data to be passed to the callback function (memory reference)

A successful return indicates that the request is being processed by the host environment and the result will be returned in the provided *cbfunc*. Note that the library must not invoke the callback function prior to returning from the API. In all other cases, the *cbfunc* will *not* be called.

Returns PMIX\_SUCCESS or one of the following error codes when the condition described occurs:

1 2	<b>PMIX_OPERATION_SUCCEEDED</b> , indicating that the request was immediately processed successfully - the <i>cbfunc</i> will <i>not</i> be called.
3 4	If none of the above return codes are appropriate, then an implementation must return either a general PMIx error code or an implementation defined error code as described in Section 3.1.1.
5 6	If executed, the status returned in the provided callback function will be one of the following constants:
7	PMIX_SUCCESS The operation succeeded and all specified members participated.
8 9	<ul> <li>PMIX_ERR_PARTIAL_SUCCESS The operation succeeded but not all specified members participated - the final group membership is included in the callback function.</li> </ul>
10 11	• PMIX_ERR_NOT_SUPPORTED While the PMIx server supports this operation, the host RM does not.
12	• a non-zero PMIx error constant indicating a reason for the request's failure.
	Required Attributes
13 14	The following attributes are <i>required</i> to be supported by all PMIx libraries that support this operation:
15 16 17	<pre>PMIX_GROUP_OPTIONAL "pmix.grp.opt" (bool)     Participation is optional - do not return an error if any of the specified processes terminate without having joined. The default is false.</pre>
18 19 20	<pre>PMIX_GROUP_FT_COLLECTIVE "pmix.grp.ftcoll" (bool)    Adjust internal tracking on-the-fly for terminated processes during a PMIx group collective operation.</pre>
21	Host environments that support this operation are required to provide the following attributes:
22 23 24 25 26	PMIX_GROUP_ASSIGN_CONTEXT_ID "pmix.grp.actxid" (bool)  Requests that the RM assign a new context identifier to the newly created group. The identifier is an unsigned, size_t value that the RM guarantees to be unique across the rang specified in the request. Thus, the value serves as a means of identifying the group within that range. If no range is specified, then the request defaults to PMIX_RANGE_SESSION.
27 28 29	PMIX_GROUP_NOTIFY_TERMINATION "pmix.grp.notterm" (bool)  Notify remaining members when another member terminates without first leaving the group

```
Optional Attributes
               The following attributes are optional for host environments that support this operation:
 1
 2
               PMIX TIMEOUT "pmix.timeout" (int)
 3
                     Time in seconds before the specified operation should time out (zero indicating infinite) and
                     return the PMIX ERR TIMEOUT error. Care should be taken to avoid race conditions
                     caused by multiple layers (client, server, and host) simultaneously timing the operation.
 5
               Description
6
 7
               Non-blocking version of the PMIx Group invite operation. The callback function will be
               called once all invited members of the group (or their substitutes) have executed either
8
               PMIx_Group_join or PMIx_Group_join_nb.
9
    13.2.12
                 PMIx Group join
               Summary
11
12
               Accept an invitation to join a PMIx process group.
               Format
   PMIx v4.0
               pmix status t
14
               PMIx_Group_join(const char grp[],
15
                                    const pmix proc t *leader,
16
                                    pmix group opt t opt,
17
18
                                    const pmix info t directives[], size t ndirs,
                                    pmix_info_t **results, size_t *nresult);
19
20
               IN
                    grp
                    NULL-terminated character array of maximum size PMIX MAX NSLEN containing the group
21
22
                    identifier (string)
               IN
                    leader
23
                    Process that generated the invitation (handle)
24
               IN
25
                    Accept or decline flag (pmix_group_opt_t)
26
                    directives
27
                    Array of pmix_info_t structures (array of handles)
28
29
               IN
                    ndirs
30
                    Number of elements in the directives array (size_t)
31
               INOUT results
32
                    Pointer to a location where the array of pmix_info_t describing the results of the
                    operation is to be returned (pointer to handle)
33
```

**INOUT** nresults 1 2 Pointer to a size t location where the number of elements in results is to be returned (memory reference) 3 4 Returns **PMIX SUCCESS** or a negative value indicating the error. Required Attributes \_\_\_\_\_ 5 There are no identified required attributes for implementers. Optional Attributes 6 The following attributes are optional for host environments that support this operation: 7 PMIX\_TIMEOUT "pmix.timeout" (int) 8 Time in seconds before the specified operation should time out (zero indicating infinite) and return the **PMIX\_ERR\_TIMEOUT** error. Care should be taken to avoid race conditions 9 caused by multiple layers (client, server, and host) simultaneously timing the operation. 10 **Description** 11 Respond to an invitation to join a group that is being asynchronously constructed. The process must 12 have registered for the PMIX GROUP INVITED event in order to be notified of the invitation. 13 14 When called, the event information will include the pmix proc t identifier of the process that 15 generated the invitation along with the identifier of the group being constructed. When ready to respond, the process provides a response using either form of **PMIx Group** join. 16 Advice to users -Since the process is alerted to the invitation in a PMIx event handler, the process must not use the 17 blocking form of this call unless it first "thread shifts" out of the handler and into its own thread 18 19 context. Likewise, while it is safe to call the non-blocking form of the API from the event handler, 20 the process *must not* block in the handler while waiting for the callback function to be called.

Calling this function causes the inviting process (aka the *group leader*) to be notified that the process has either accepted or declined the request. The blocking form of the API will return once the group has been completely constructed or the group's construction has failed (as described below) – likewise, the callback function of the non-blocking form will be executed upon the same conditions.

Failure of the leader during the call to PMIx\_Group\_join will cause a

PMIX\_GROUP\_LEADER\_FAILED event to be delivered to all invited participants so they can
optionally declare a new leader. A new leader is identified by providing the

PMIX\_GROUP\_LEADER attribute in the results array in the return of the event handler. Only one
process is allowed to return that attribute, declaring itself as the new leader. Results of the leader
selection will be communicated to all participants via a PMIX\_GROUP\_LEADER\_SELECTED
event identifying the new leader. If no leader was selected, then the status code provided in the
event handler will provide an error value so the participants can take appropriate action.

Any participant that returns PMIX\_GROUP\_CONSTRUCT\_ABORT from the leader failed event handler will cause all participants to receive an event notifying them of that status. Similarly, the leader may elect to abort the procedure by either returning PMIX\_GROUP\_CONSTRUCT\_ABORT from the handler assigned to the PMIX\_GROUP\_INVITE\_ACCEPTED or PMIX\_GROUP\_INVITE\_DECLINED codes, or by generating an event for the abort code. Abort events will be sent to all invited participants.

### 13.2.13 PMIx\_Group\_join\_nb

identifier (string)

Process that generated the invitation (handle)

leader

IN

Summary

```
Non-blocking form of PMIx_Group_join
22
             Format
   PMIx v4.0
24
             pmix status t
             PMIx_Group_join_nb(const char grp[],
25
                                   const pmix_proc_t *leader,
26
27
                                   pmix_group_opt_t opt,
28
                                   const pmix_info_t directives[], size_t ndirs,
29
                                   pmix_info_cbfunc_t cbfunc, void *cbdata);
             IN
30
                 NULL-terminated character array of maximum size PMIX_MAX_NSLEN containing the group
31
```

1	IN opt
2	Accept or decline flag (pmix_group_opt_t)
3	<pre>IN directives</pre>
4	Array of pmix_info_t structures (array of handles)
5	IN ndirs
6	Number of elements in the <i>directives</i> array (size_t)
7	IN cbfunc
8	Callback function pmix_info_cbfunc_t (function reference)
9 10	IN cbdata  Data to be passed to the callback function (memory reference)
1  2  3	A successful return indicates that the request is being processed by the host environment and the result will be returned in the provided <i>cbfunc</i> . Note that the library must not invoke the callback function prior to returning from the API. In all other cases, the <i>cbfunc</i> will <i>not</i> be called.
14	Returns PMIX_SUCCESS or one of the following error codes when the condition described occurs:
15 16	<b>PMIX_OPERATION_SUCCEEDED</b> , indicating that the request was immediately processed successfully - the <i>cbfunc</i> will <i>not</i> be called.
17 18	If none of the above return codes are appropriate, then an implementation must return either a general PMIx error code or an implementation defined error code as described in Section 3.1.1.
19 20	If executed, the status returned in the provided callback function will be one of the following constants:
21 22	<ul> <li>PMIX_SUCCESS The operation succeeded and group membership is in the callback function parameters.</li> </ul>
23 24	• PMIX_ERR_NOT_SUPPORTED While the PMIx server supports this operation, the host RM does not.
25	• a non-zero PMIx error constant indicating a reason for the request's failure.
	Required Attributes
26	There are no identified required attributes for implementers.
	→Optional Attributes
27	The following attributes are optional for host environments that support this operation:
28	PMIX_TIMEOUT "pmix.timeout" (int)
29	Time in seconds before the specified operation should time out (zero indicating infinite) and
30	return the PMIX_ERR_TIMEOUT error. Care should be taken to avoid race conditions
31	caused by multiple layers (client, server, and host) simultaneously timing the operation.
	A

```
Description
 1
 2
               Non-blocking version of the PMIx Group join operation. The callback function will be called
               once all invited members of the group (or their substitutes) have executed either
 3
 4
               PMIx Group join or PMIx Group join nb.
                 Group accept/decline directives
    13.2.13.1
   PMIx v4.0
               The pmix_group_opt_t type is a uint8_t value used with the PMIx_Group_join API to
               indicate accept or decline of the invitation - these are provided for readability of user code:
 7
8
               PMIX GROUP DECLINE
                                          Decline the invitation.
9
               PMIX GROUP ACCEPT
                                         Accept the invitation.
    13.2.14
                 PMIx Group leave
11
               Summary
               Leave a PMIx process group.
12
               Format
   PMIx v4.0
14
               pmix_status t
               PMIx_Group_leave(const char grp[],
15
                                     const pmix_info_t directives[],
16
17
                                     size t ndirs);
               IN
18
19
                   NULL-terminated character array of maximum size PMIX_MAX_NSLEN containing the group
20
                   identifier (string)
               IN
                   directives
21
                   Array of pmix_info_t structures (array of handles)
22
                  ndirs
23
               IN
                   Number of elements in the directives array (size_t)
24
               Returns PMIX_SUCCESS or a negative value indicating the error.
25
                                              Required Attributes
26
               There are no identified required attributes for implementers.
```

#### Description

*PMIx v4.0* 

Calls to **PMIx\_Group\_leave** (or its non-blocking form) will cause a **PMIX\_GROUP\_LEFT** event to be generated notifying all members of the group of the caller's departure. The function will return (or the non-blocking function will execute the specified callback function) once the event has been locally generated and is not indicative of remote receipt.

#### Advice to users

The **PMIx\_Group\_leave** API is intended solely for asynchronous departures of individual processes from a group as it is not a scalable operation – i.e., when a process determines it should no longer be a part of a defined group, but the remainder of the group retains a valid reason to continue in existence. Developers are advised to use **PMIx\_Group\_destruct** (or its non-blocking form) for all other scenarios as it represents a more scalable operation.

### 13.2.15 PMIx\_Group\_leave\_nb

#### Summary

Non-blocking form of PMIx\_Group\_leave.

#### Format

#### IN grp

**NULL**-terminated character array of maximum size **PMIX\_MAX\_NSLEN** containing the group identifier (string)

IN directives

Array of pmix info t structures (array of handles)

IN ndirs

Number of elements in the *directives* array (size\_t)

IN cbfunc

Callback function **pmix\_op\_cbfunc\_t** (function reference)

IN cbdata

Data to be passed to the callback function (memory reference)

A successful return indicates that the request is being processed by the host environment and the result will be returned in the provided cbfunc. Note that the library must not invoke the callback function prior to returning from the API. In all other cases, the cbfunc will not be called. Returns PMIX SUCCESS or one of the following error codes when the condition described occurs: PMIX\_OPERATION\_SUCCEEDED, indicating that the request was immediately processed successfully - the *cbfunc* will *not* be called. If none of the above return codes are appropriate, then an implementation must return either a general PMIx error code or an implementation defined error code as described in Section 3.1.1. If executed, the status returned in the provided callback function will be one of the following constants: • PMIX\_SUCCESS The operation succeeded - i.e., the PMIX\_GROUP\_LEFT event was generated. • PMIX\_ERR\_NOT\_SUPPORTED While the PMIx library supports this operation, the host RM does not. • a non-zero PMIx error constant indicating a reason for the request's failure. Required Attributes There are no identified required attributes for implementers. **Description** Non-blocking version of the PMIx\_Group\_leave operation. The callback function will be called once the event has been locally generated and is not indicative of remote receipt.

1

3

4

5

6 7

8

9 10

11

12

13 14

15

16

17

#### **CHAPTER 14**

# **Fabric Support Definitions**

As the drive for performance continues, interest has grown in scheduling algorithms that take into account network locality of the allocated resources and in optimizing collective communication patterns by structuring them to follow fabric topology. In addition, concerns over the time required to initiate execution of parallel applications and enable communication across them have grown as the size of those applications extends into the hundreds of thousands of individual processes spanning tens of thousands of nodes.

PMIx supports the communication part of these efforts by defining data types and attributes by which fabric endpoints and coordinates for processes and devices can be obtained from the host environment. When used in conjunction with other PMIx methods described in Chapter 16, this results in the ability of a process to obtain the fabric endpoint and coordinate of all other processes without incurring additional overhead associated with a global exchange of that information. This includes:

- Defining several interfaces specifically intended to support WLMs by providing access to information of potential use to scheduling algorithms e.g., information on communication costs between different points on the fabric.
- Supporting hierarchical collective operations by providing the fabric coordinates for all devices
  on participating nodes as well as a list of the peers sharing each fabric switch. This enables one,
  for example, to aggregate the contribution from all processes on a node, then again across all
  nodes on a common switch, and finally across all switches based on detailed knowledge of the
  fabric location of each participant.
- Enabling the "*instant on*" paradigm to mitigate the scalable launch problem by providing each process with a rich set of information about the environment and the application, including everything required for communication between peers within the application, at time of process start of execution.

Meeting these needs in the case where only a single fabric device exists on each node is relatively straightforward - PMIx and the host environment provide a single endpoint for each process plus a coordinate for the device on each node, and there is no uncertainty regarding the endpoint each process will use. Extending this to the multiple device per node case is more difficult as the choice of endpoint by any given process cannot be known in advance, and questions arise regarding reachability between devices on different nodes. Resolving these ambiguities without requiring a global operation requires that PMIx provide both (a) an endpoint for each application process on each of its local devices; and (b) the fabric coordinates of all remote and local devices on participating nodes. It also requires that each process open all of its assigned endpoints as the endpoint selected for contact by a remote peer cannot be known in advance.

 While these steps ensure the ability of a process to connect to a remote peer, it leaves unanswered the question of selecting the *preferred* device for that communication. If multiple devices are present on a node, then the application can benefit from having each process utilize its "closest" fabric device (i.e., the device that minimizes the communication distance between the process' location and that device) for messaging operations. In some cases, messaging libraries prefer to also retain the ability to use non-nearest devices, prioritizing the devices based on distance to support multi-device operations (e.g., for large message transmission in parallel).

PMIx supports this requirement by providing the array of process-to-device distance information for each process and local fabric device at start of execution. Both minimum and maximum distances are provided since a single process can occupy multiple processor locations. In addition, since processes can relocate themselves by changing their processor bindings, PMIx provides an API that allows the process to dynamically request an update to its distance array.

However, while these measures assist a process in selecting its own best endpoint, they do not resolve the uncertainty over the choice of preferred device by a remote peer. There are two methods by which this ambiguity can be resolved:

- a) A process can select a remote endpoint to use based on its own preferred device and reachability of the peer's remote devices. Once the initial connection has been made, the two processes can exchange information and mutually determine their desired communication path going forward.
- b) The application can use knowledge of both the local and remote distance arrays to compute the best communication path and establish that connection. In some instances (e.g., a homogeneous system), a PMIx server may provide distance information for both local and remote devices. Alternatively, when this isn't available, an application can opt to collect the information using the PMIX\_COLLECT\_GENERATED\_JOB\_INFO with the PMIX\_Fence API, or can obtain it on a one peer-at-a-time basis using the PMIX\_Get API on systems where the host environment supports the *Direct Modex* operation.

Information on fabric coordinates, endpoints, and device distances are provided as *reserved keys* as detailed in Chapter 6 - i.e., they are to be available at client start of execution and are subject to the retrieval rules of Section 6.2. Examples for retrieving fabric-related information include retrieval of:

- An array of information on fabric devices for a node by passing PMIX\_FABRIC\_DEVICES as
  the key to PMIX\_Get along with the PMIX\_HOSTNAME of the node as a directive
- An array of information on a specific fabric device by passing PMIX\_FABRIC\_DEVICE as the
  key to PMIx\_Get along with the PMIX\_DEVICE\_ID of the device as a directive
- An array of information on a specific fabric device by passing PMIX\_FABRIC\_DEVICE as the
  key to PMIx\_Get along with both PMIX\_FABRIC\_DEVICE\_NAME of the device and the
  PMIX\_HOSTNAME of the node as directives

When requesting data on a device, returned data must include at least the following attributes:

• PMIX HOSTNAME "pmix.hname" (char\*)

2	<b>PMIX_NODEID</b> may be returned in its place, or in addition to the hostname.
3 4	PMIX_DEVICE_ID "pmix.dev.id" (string)     System-wide UUID or node-local OS name of a particular device.
5 6 7	• PMIX_FABRIC_DEVICE_NAME "pmix.fabdev.nm" (string)  The operating system name associated with the device. This may be a logical fabric interface name (e.g. "eth0" or "eno1") or an absolute filename.
8 9	• PMIX_FABRIC_DEVICE_VENDOR "pmix.fabdev.vndr" (string) Indicates the name of the vendor that distributes the device.
10 11	• PMIX_FABRIC_DEVICE_BUS_TYPE "pmix.fabdev.btyp" (string)  The type of bus to which the device is attached (e.g., "PCI", "GEN-Z").
12 13 14 15 16 17 18 19 20	• PMIX_FABRIC_DEVICE_PCI_DEVID "pmix.fabdev.pcidevid" (string)  A node-level unique identifier for a Peripheral Component Interconnect (PCI) device.  Provided only if the device is located on a PCI bus. The identifier is constructed as a four-part tuple delimited by colons comprised of the PCI 16-bit domain, 8-bit bus, 8-bit device, and 8-bit function IDs, each expressed in zero-extended hexadecimal form. Thus, an example identifier might be "abc1:0f:23:01". The combination of node identifier (PMIX_HOSTNAME or PMIX_NODEID) and PMIX_FABRIC_DEVICE_PCI_DEVID shall be unique within the overall system. This item should be included if the device bus type is PCI - the equivalent should be provided for any other bus type.
21	The returned array may optionally contain one or more of the following in addition to the above list:
22 23	• PMIX_FABRIC_DEVICE_INDEX "pmix.fabdev.idx" (uint32_t)  Index of the device within an associated communication cost matrix.
24 25	• PMIX_FABRIC_DEVICE_VENDORID "pmix.fabdev.vendid" (string)  This is a vendor-provided identifier for the device or product.
26 27	• PMIX_FABRIC_DEVICE_DRIVER "pmix.fabdev.driver" (string)  The name of the driver associated with the device.
28 29	• PMIX_FABRIC_DEVICE_FIRMWARE "pmix.fabdev.fmwr" (string) The device's firmware version.
30 31 32	• PMIX_FABRIC_DEVICE_ADDRESS "pmix.fabdev.addr" (string)  The primary link-level address associated with the device, such as a Media Access Control (MAC) address. If multiple addresses are available, only one will be reported.
33 34 35	• PMIX_FABRIC_DEVICE_COORDINATES "pmix.fab.coord" (pmix_geometry_t)  The pmix_geometry_t fabric coordinates for the device, including values for all supported coordinate views.

Name of the host, as returned by the **gethostname** utility or its equivalent. The

• PMIX\_FABRIC\_DEVICE\_MTU "pmix.fabdev.mtu" (size\_t) 1 2 The maximum transfer unit of link level frames or packets, in bytes. 3 • PMIX\_FABRIC\_DEVICE\_SPEED "pmix.fabdev.speed" (size\_t) The active link data rate, given in bits per second. 4 5 • PMIX\_FABRIC\_DEVICE\_STATE "pmix.fabdev.state" (pmix\_link\_state\_t) 6 The last available physical port state for the specified device. Possible values are 7 PMIX\_LINK\_STATE\_UNKNOWN, PMIX\_LINK\_DOWN, and PMIX\_LINK\_UP, to 8 indicate if the port state is unknown or not applicable (unknown), inactive (down), or 9 active (up). 10 PMIX FABRIC DEVICE TYPE "pmix.fabdev.type" (string) 11 Specifies the type of fabric interface currently active on the device, such as Ethernet or InfiniBand. 12 13 The remainder of this chapter details the events, data types, attributes, and APIs associated with 14 fabric-related operations. 14.1 Fabric Support Events 16 The following events are defined for use in fabric-related operations. 17 PMIX FABRIC UPDATE PENDING The PMIx server library has been alerted to a change in the fabric that requires updating of one or more registered **pmix fabric t** objects. 18 19 PMIX FABRIC UPDATED The PMIx server library has completed updating the entries of all 20 affected pmix fabric t objects registered with the library. Access to the entries of those 21 objects may now resume. 22 PMIX FABRIC UPDATE ENDPOINTS Endpoint assignments have been updated, usually in 23 response to migration or restart of a process. Clients should use **PMIx\_Get** to update any 24 internally cached connections. 14.2 **Fabric Support Datatypes** 

## 27 14.2.1 Fabric Endpoint Structure

26

The pmix\_endpoint\_t structure contains an assigned endpoint for a given fabric device.

PMIx v4.0

Several datatype definitions have been created to support fabric-related operations and information.

```
1
               typedef struct pmix endpoint {
 2
                    char *uuid:
 3
                    char *osname;
                    pmix_byte_object_t endpt;
 4
               } pmix_endpoint_t;
 5
               The uuid field contains the UUID of the fabric device, the osname is the local operating system's
6
 7
               name for the device, and the endpt field contains a fabric vendor-specific object identifying the
8
               communication endpoint assigned to the process.
    14.2.2
               Fabric endpoint support macros
10
               The following macros are provided to support the pmix endpoint t structure.
11
               Initialize the endpoint structure
               Initialize the pmix_endpoint_t fields.
12
  PMIx v4.0
13
               PMIX ENDPOINT CONSTRUCT (m)
               IN
14
                    Pointer to the structure to be initialized (pointer to pmix endpoint t)
15
16
               Destruct the endpoint structure
17
               Destruct the pmix endpoint t fields.
  PMIx v4.0
18
               PMIX_ENDPOINT_DESTRUCT (m)
               IN
19
20
                    Pointer to the structure to be destructed (pointer to pmix_endpoint_t)
21
               Create an endpoint array
22
               Allocate and initialize a pmix endpoint t array.
  PMIx v4.0
23
               PMIX_ENDPOINT_CREATE(m, n)
               INOUT m
24
                    Address where the pointer to the array of pmix_endpoint_t structures shall be stored
25
                    (handle)
26
               IN
27
                    n
28
                    Number of structures to be allocated (size t)
```

```
Release an endpoint array
 1
                Release an array of pmix_endpoint_t structures.
 2
   PMIx v4.0
                PMIX ENDPOINT_FREE (m, n)
 3
                IN
 5
                     Pointer to the array of pmix_endpoint_t structures (handle)
 6
                IN
 7
                     Number of structures in the array (size_t)
                Fabric Coordinate Structure
    14.2.3
 9
                The pmix_coord_t structure describes the fabric coordinates of a specified device in a given
                view.
10
11
                typedef struct pmix_coord {
12
                     pmix_coord_view_t view;
13
                     uint32 t *coord;
14
                     size t dims;
                } pmix coord t;
15
                All coordinate values shall be expressed as unsigned integers due to their units being defined in
16
17
                fabric devices and not physical distances. The coordinate is therefore an indicator of connectivity
18
                and not relative communication distance.

    Advice to PMIx library implementers -

                Note that the pmix_coord_t structure does not imply nor mandate any requirement on how the
19
                coordinate data is to be stored within the PMIx library. Implementers are free to store the
20
                coordinate in whatever format they choose.
21
22
                A fabric coordinate is associated with a given fabric device and must be unique within a given view.
23
                Fabric devices are associated with the operating system which hosts them - thus, fabric coordinates
24
                are logically grouped within the node realm (as described in Section 6.1) and can be retrieved per
25
                the rules detailed in Section 6.1.5.
```

### 14.2.4 Fabric coordinate support macros

27

The following macros are provided to support the **pmix coord t** structure.

1	Initialize the coord structure
2	Initialize the pmix_coord_t fields.
3	PMIX_COORD_CONSTRUCT (m)
4 5	IN m Pointer to the structure to be initialized (pointer to pmix_coord_t)
6 7 <i>PMIx v4.0</i>	Destruct the coord structure Destruct the pmix_coord_t fields.
8	PMIX_COORD_DESTRUCT (m)
9 10	IN m Pointer to the structure to be destructed (pointer to pmix_coord_t)
11 12 <i>PMIx v4.0</i> 13	Create a coord array Allocate and initialize a pmix_coord_t array.  PMIX_COORD_CREATE (m, n)
14 15 16 17	INOUT m  Address where the pointer to the array of pmix_coord_t structures shall be stored (handle)  IN n  Number of structures to be allocated (size_t)
18 19 <i>PMIx v4.0</i>	Release a coord array Release an array of pmix_coord_t structures.
20	PMIX_COORD_FREE (m, n)  C  IN m
22 23 24	Pointer to the array of <pre>pmix_coord_t</pre> structures (handle)  IN  Number of structures in the array (size_t)

# 1 14.2.5 Fabric Geometry Structure

2	The pmix_geometry_t structure describes the fabric coordinates of a specified device.		
3 4 5 6 7 8 9	<pre>typedef struct pmix_geometry {     size_t fabric;     char *uuid;     char *osname;     pmix_coord_t *coordinates;     size_t ncoords; } pmix_geometry_t;</pre>		
10 11 12	All coordinate values shall be expressed as unsigned integers due to their units being defined in fabric devices and not physical distances. The coordinate is therefore an indicator of connectivity and not relative communication distance.  Advice to PMIx library implementers		
13 14 15	Note that the <code>pmix_coord_t</code> structure does not imply nor mandate any requirement on how the coordinate data is to be stored within the PMIx library. Implementers are free to store the coordinate in whatever format they choose.		
16 17 18 19	A fabric coordinate is associated with a given fabric device and must be unique within a given view. Fabric devices are associated with the operating system which hosts them - thus, fabric coordinates are logically grouped within the <i>node</i> realm (as described in Section 6.1) and can be retrieved per the rules detailed in Section 6.1.5.		
20 14.2.6	Fabric geometry support macros		
21	The following macros are provided to support the <pre>pmix_geometry_t</pre> structure.		
22 23 <i>PMIx v4.0</i>	Initialize the geometry structure Initialize the pmix_geometry_t fields.		
24	PMIX_GEOMETRY_CONSTRUCT (m)		
25 26	IN m Pointer to the structure to be initialized (pointer to pmix_geometry_t)		

```
Destruct the geometry structure
 1
              Destruct the pmix geometry t fields.
2
 3
              PMIX GEOMETRY DESTRUCT (m)
              IN
 5
                  Pointer to the structure to be destructed (pointer to pmix_geometry_t)
              Create a geometry array
 6
              Allocate and initialize a pmix_geometry_t array.
  PMIx v4.0
              PMIX GEOMETRY CREATE (m, n)
8
              INOUT m
9
10
                  Address where the pointer to the array of pmix_geometry_t structures shall be stored
11
              IN
12
                   n
13
                  Number of structures to be allocated (size_t)
              Release a geometry array
14
              Release an array of pmix_geometry_t structures.
15
  PMIx v4.0
16
              PMIX GEOMETRY FREE (m, n)
              IN
17
                  Pointer to the array of pmix_geometry_t structures (handle)
18
              IN
19
20
                  Number of structures in the array (size t)
              Fabric Coordinate Views
    14.2.7
  PMIx v4.0
22
              typedef uint8 t pmix coord view t;
              #define PMIX COORD VIEW UNDEF
23
                                                           0x00
24
              #define PMIX COORD LOGICAL VIEW
                                                           0x01
              #define PMIX_COORD_PHYSICAL_VIEW
25
                                                           0x02
```

1	Fabric coordinates can be reported based on different views according to user preference at the time
2	of request. The following views have been defined:
3	PMIX_COORD_VIEW_UNDEF The coordinate view has not been defined.
4	PMIX_COORD_LOGICAL_VIEW The coordinates are provided in a <i>logical</i> view, typically
5	given in Cartesian (x,y,z) dimensions, that describes the data flow in the fabric as defined by
6	the arrangement of the hierarchical addressing scheme, fabric segmentation, routing domains,
7	and other similar factors employed by that fabric.
8	PMIX_COORD_PHYSICAL_VIEW The coordinates are provided in a physical view based on
9	the actual wiring diagram of the fabric - i.e., values along each axis reflect the relative
10	position of that interface on the specific fabric cabling.

If the requester does not specify a view, coordinates shall default to the *logical* view.

### 14.2.8 Fabric Link State

11

14

18

19

20

24

25

26 27

28

The pmix\_link\_state\_t is a uint32\_t type for fabric link states.

C

The pmix\_link\_state\_t is a uint32\_t type for fabric link states.

typedef uint8\_t pmix\_link\_state\_t;

The following constants can be used to set a variable of the type **pmix\_link\_state\_t**. All definitions were introduced in version 4 of the standard unless otherwise marked. Valid link state values start at zero.

**PMIX\_LINK\_STATE\_UNKNOWN** The port state is unknown or not applicable.

**PMIX\_LINK\_DOWN** The port is inactive.

**PMIX\_LINK\_UP** The port is active.

### 14.2.9 Fabric Operation Constants

The pmix\_fabric\_operation\_t data type is an enumerated type for specifying fabric operations used in the PMIx server module's pmix\_server\_fabric\_fn\_t API.

PMIX\_FABRIC\_REQUEST\_INFO Request information on a specific fabric - if the fabric isn't specified as per PMIx\_Fabric\_register, then return information on the default fabric of the overall system. Information to be returned is described in pmix\_fabric\_t.

**PMIX\_FABRIC\_UPDATE\_INFO** Update information on a specific fabric - the index of the fabric (**PMIX\_FABRIC\_INDEX**) to be updated must be provided.

### 14.2.10 Fabric registration structure

The **pmix\_fabric\_t** structure is used by a WLM to interact with fabric-related PMIx interfaces, and to provide information about the fabric for use in scheduling algorithms or other purposes.

```
typedef struct pmix_fabric_s {
   char *name;
   size_t index;
   pmix_info_t *info;
   size_t ninfo;
   void *module;
} pmix_fabric_t;;
```

Note that in this structure:

- *name* is an optional user-supplied string name identifying the fabric being referenced by this struct. If provided, the field must be a **NULL**-terminated string composed of standard alphanumeric values supported by common utilities such as *strcmp*.;
- *index* is a PMIx-provided number identifying this object;
- *info* is an array of **pmix\_info\_t** containing information (provided by the PMIx library) about the fabric;
- *ninfo* is the number of elements in the *info* array;
- module points to an opaque object reserved for use by the PMIx server library.

Note that only the *name* field is provided by the user - all other fields are provided by the PMIx library and must not be modified by the user. The *info* array contains a varying amount of information depending upon both the PMIx implementation and information available from the fabric vendor. At a minimum, it must contain (ordering is arbitrary):

### ----- Required Attributes

```
PMIX_FABRIC_VENDOR "pmix.fab.vndr" (string)
```

Name of the vendor (e.g., Amazon, Mellanox, HPE, Intel) for the specified fabric.

```
PMIX FABRIC IDENTIFIER "pmix.fab.id" (string)
```

An identifier for the specified fabric (e.g., MgmtEthernet, Slingshot-11, OmniPath-1).

```
PMIX FABRIC NUM DEVICES "pmix.fab.nverts" (size t)
```

Total number of fabric devices in the overall system - corresponds to the number of rows or columns in the cost matrix.

and may optionally contain one or more of the following:

### Optional Attributes -----

	·
1	<pre>PMIX_FABRIC_COST_MATRIX "pmix.fab.cm" (pointer)</pre>
2	Pointer to a two-dimensional square array of point-to-point relative communication costs
3	expressed as uint16_t values.
4	PMIX_FABRIC_GROUPS "pmix.fab.grps" (string)
5	A string delineating the group membership of nodes in the overall system, where each fabric
6	group consists of the group number followed by a colon and a comma-delimited list of nodes
7	in that group, with the groups delimited by semi-colons (e.g.,
8	0:node000,node002,node004,node006;1:node001,node003,
9	node005, node007)
10	<pre>PMIX_FABRIC_DIMS "pmix.fab.dims" (uint32_t)</pre>
11	Number of dimensions in the specified fabric plane/view. If no plane is specified in a
12	request, then the dimensions of all planes in the overall system will be returned as a
13	<pre>pmix_data_array_t containing an array of uint32_t values. Default is to provide</pre>
14	dimensions in <i>logical</i> view.
15	PMIX_FABRIC_PLANE "pmix.fab.plane" (string)
16	ID string of a fabric plane (e.g., CIDR for Ethernet). When used as a modifier in a request
17	for information, specifies the plane whose information is to be returned. When used directly
18	as a key in a request, returns a pmix_data_array_t of string identifiers for all fabric
19	planes in the overall system.
20	<pre>PMIX_FABRIC_SHAPE "pmix.fab.shape" (pmix_data_array_t*)</pre>
21	The size of each dimension in the specified fabric plane/view, returned in a
22	<pre>pmix_data_array_t containing an array of uint32_t values. The size is defined as</pre>
23	the number of elements present in that dimension - e.g., the number of devices in one
24	dimension of a physical view of a fabric plane. If no plane is specified, then the shape of
25	each plane in the overall system will be returned in a pmix_data_array_t array where
26	each element is itself a two-element array containing the PMIX_FABRIC_PLANE followed
27	by that plane's fabric shape. Default is to provide the shape in <i>logical</i> view.
28	<pre>PMIX_FABRIC_SHAPE_STRING "pmix.fab.shapestr" (string)</pre>
29	Network shape expressed as a string (e.g., "10x12x2"). If no plane is specified, then the
30	shape of each plane in the overall system will be returned in a pmix_data_array_t array
31	where each element is itself a two-element array containing the PMIX_FABRIC_PLANE
32	followed by that plane's fabric shape string. Default is to provide the shape in <i>logical</i> view.
33	While unusual due to scaling issues, implementations may include an array of
34	PMIX_FABRIC_DEVICE elements describing the device information for each device in the
35	overall system. Each element shall contain a pmix_data_array_t of pmix_info_t values
36	describing the device. Each array may contain one or more of the following (ordering is arbitrary):

PMIX\_FABRIC\_DEVICE\_NAME "pmix.fabdev.nm" (string)

1 2	The operating system name associated with the device. This may be a logical fabric interface name (e.g. "eth0" or "eno1") or an absolute filename.
3 4	<pre>PMIX_FABRIC_DEVICE_VENDOR "pmix.fabdev.vndr" (string) Indicates the name of the vendor that distributes the device.</pre>
5 6	PMIX_DEVICE_ID "pmix.dev.id" (string)  System-wide UUID or node-local OS name of a particular device.
7 8	PMIX_HOSTNAME "pmix.hname" (char*)  Name of the host, as returned by the gethostname utility or its equivalent.
9	<pre>PMIX_FABRIC_DEVICE_DRIVER "pmix.fabdev.driver" (string) The name of the driver associated with the device.</pre>
1 2	<pre>PMIX_FABRIC_DEVICE_FIRMWARE "pmix.fabdev.fmwr" (string) The device's firmware version.</pre>
3 4 5	<pre>PMIX_FABRIC_DEVICE_ADDRESS "pmix.fabdev.addr" (string) The primary link-level address associated with the device, such as a MAC address. If multiple addresses are available, only one will be reported.</pre>
6 7	PMIX_FABRIC_DEVICE_MTU "pmix.fabdev.mtu" (size_t) The maximum transfer unit of link level frames or packets, in bytes.
8 9	<pre>PMIX_FABRIC_DEVICE_SPEED "pmix.fabdev.speed" (size_t) The active link data rate, given in bits per second.</pre>
20 21 22 23	PMIX_FABRIC_DEVICE_STATE "pmix.fabdev.state" (pmix_link_state_t)  The last available physical port state for the specified device. Possible values are  PMIX_LINK_STATE_UNKNOWN, PMIX_LINK_DOWN, and PMIX_LINK_UP, to indicate if the port state is unknown or not applicable (unknown), inactive (down), or active (up).
24 25 26	PMIX_FABRIC_DEVICE_TYPE "pmix.fabdev.type" (string)  Specifies the type of fabric interface currently active on the device, such as Ethernet or InfiniBand.
27 28	<pre>PMIX_FABRIC_DEVICE_BUS_TYPE "pmix.fabdev.btyp" (string) The type of bus to which the device is attached (e.g., "PCI", "GEN-Z").</pre>
29 30 31 32 33 34 45	PMIX_FABRIC_DEVICE_PCI_DEVID "pmix.fabdev.pcidevid" (string) A node-level unique identifier for a PCI device. Provided only if the device is located on a PCI bus. The identifier is constructed as a four-part tuple delimited by colons comprised of the PCI 16-bit domain, 8-bit bus, 8-bit device, and 8-bit function IDs, each expressed in zero-extended hexadecimal form. Thus, an example identifier might be "abc1:0f:23:01". The combination of node identifier (PMIX_HOSTNAME or PMIX_NODEID) and PMIX_FABRIC_DEVICE_PCI_DEVID shall be unique within the overall system.
	<b>A</b>

#### 14.2.10.1 Initialize the fabric structure

2 <i>PMIx v4.0</i>	Init	ialize the pmix_fabric_t fields.	_ c	<b>V</b>
3	PM:	IX_FABRIC_CONSTRUCT(m)		
4	IN	m	0	
5		Pointer to the structure to be initialize	ed (pointer to pmix fabric t)	

## 14.3 Fabric Support Attributes

 The following attribute is used by the PMIx server library supporting the system's WLM to indicate that it wants access to the fabric support functions:

```
PMIX_SERVER_SCHEDULER "pmix.srv.sched" (bool)
```

Server is supporting system scheduler and desires access to appropriate WLM-supporting features. Indicates that the library is to be initialized for scheduler support.

The following attributes may be returned in response to fabric-specific APIs or queries (e.g., PMIx\_Get or PMIx\_Query\_info). These attributes are not related to a specific *data realm* (as described in Section 6.1) - the PMIx\_Get function shall therefore ignore the value in its *proc* process identifier argument when retrieving these values.

```
PMIX_FABRIC_COST_MATRIX "pmix.fab.cm" (pointer)
```

Pointer to a two-dimensional square array of point-to-point relative communication costs expressed as uint16\_t values.

```
PMIX_FABRIC_GROUPS "pmix.fab.grps" (string)
```

A string delineating the group membership of nodes in the overall system, where each fabric group consists of the group number followed by a colon and a comma-delimited list of nodes in that group, with the groups delimited by semi-colons (e.g.,

0:node000, node002, node004, node006; 1:node001, node003, node005, node007)

```
PMIX_FABRIC_PLANE "pmix.fab.plane" (string)
```

ID string of a fabric plane (e.g., CIDR for Ethernet). When used as a modifier in a request for information, specifies the plane whose information is to be returned. When used directly as a key in a request, returns a **pmix\_data\_array\_t** of string identifiers for all fabric planes in the overall system.

```
PMIX_FABRIC_SWITCH "pmix.fab.switch" (string)
```

ID string of a fabric switch. When used as a modifier in a request for information, specifies the switch whose information is to be returned. When used directly as a key in a request, returns a **pmix\_data\_array\_t** of string identifiers for all fabric switches in the overall system.

1

2

3 4

5

6 7

8

9

34

37

39

40

21 22

28 29

30 31 32

33

35

36

38

The following attributes may be returned in response to queries (e.g., PMIx\_Get or PMIx Query info). A qualifier (e.g., PMIX FABRIC INDEX) identifying the fabric whose value is being referenced must be provided for queries on systems supporting more than one fabric when values for the non-default fabric are requested. These attributes are not related to a specific data realm (as described in Section 6.1) - the PMIx Get function shall therefore ignore the value in its *proc* process identifier argument when retrieving these values.

```
PMIX FABRIC VENDOR "pmix.fab.vndr" (string)
```

Name of the vendor (e.g., Amazon, Mellanox, HPE, Intel) for the specified fabric.

PMIX FABRIC IDENTIFIER "pmix.fab.id" (string)

An identifier for the specified fabric (e.g., MgmtEthernet, Slingshot-11, OmniPath-1).

PMIX FABRIC INDEX "pmix.fab.idx" (size t)

The index of the fabric as returned in **pmix\_fabric\_t**.

PMIX FABRIC NUM DEVICES "pmix.fab.nverts" (size t)

Total number of fabric devices in the overall system - corresponds to the number of rows or columns in the cost matrix.

PMIX FABRIC DIMS "pmix.fab.dims" (uint32 t)

Number of dimensions in the specified fabric plane/view. If no plane is specified in a request, then the dimensions of all planes in the overall system will be returned as a pmix data array t containing an array of uint32 t values. Default is to provide dimensions in logical view.

PMIX\_FABRIC\_SHAPE "pmix.fab.shape" (pmix\_data\_array\_t\*)

The size of each dimension in the specified fabric plane/view, returned in a pmix data array t containing an array of uint32 t values. The size is defined as the number of elements present in that dimension - e.g., the number of devices in one dimension of a physical view of a fabric plane. If no plane is specified, then the shape of each plane in the overall system will be returned in a pmix\_data\_array\_t array where each element is itself a two-element array containing the PMIX\_FABRIC\_PLANE followed by that plane's fabric shape. Default is to provide the shape in *logical* view.

PMIX FABRIC SHAPE STRING "pmix.fab.shapestr" (string)

Network shape expressed as a string (e.g., "10x12x2"). If no plane is specified, then the shape of each plane in the overall system will be returned in a pmix\_data\_array\_t array where each element is itself a two-element array containing the PMIX\_FABRIC\_PLANE followed by that plane's fabric shape string. Default is to provide the shape in *logical* view.

The following attributes are related to the *node realm* (as described in Section 6.1.5) and are retrieved according to those rules.

```
PMIX_FABRIC_DEVICES "pmix.fab.devs" (pmix_data_array_t)
```

Array of pmix\_info\_t containing information for all devices on the specified node. Each element of the array will contain a PMIX FABRIC DEVICE entry, which in turn will contain an array of information on a given device.

PMIX\_FABRIC\_COORDINATES "pmix.fab.coords" (pmix\_data\_array\_t)

1	Array of <b>pmix_geometry_t</b> fabric coordinates for devices on the specified node. The
2	array will contain the coordinates of all devices on the node, including values for all
3	supported coordinate views. The information for devices on the local node shall be provided
4	if the node is not specified in the request.
5	PMIX_FABRIC_DEVICE "pmix.fabdev" (pmix_data_array_t)
6	An array of <b>pmix_info_t</b> describing a particular fabric device using one or more of the
7	attributes defined below. The first element in the array shall be the PMIX_DEVICE_ID of
8	the device.
9	<pre>PMIX_FABRIC_DEVICE_INDEX "pmix.fabdev.idx" (uint32_t)</pre>
0	Index of the device within an associated communication cost matrix.
1	<pre>PMIX_FABRIC_DEVICE_NAME "pmix.fabdev.nm" (string)</pre>
2	The operating system name associated with the device. This may be a logical fabric interfac
3	name (e.g. "eth0" or "eno1") or an absolute filename.
4	<pre>PMIX_FABRIC_DEVICE_VENDOR "pmix.fabdev.vndr" (string)</pre>
5	Indicates the name of the vendor that distributes the device.
6	<pre>PMIX_FABRIC_DEVICE_BUS_TYPE "pmix.fabdev.btyp" (string)</pre>
7	The type of bus to which the device is attached (e.g., "PCI", "GEN-Z").
8	<pre>PMIX_FABRIC_DEVICE_VENDORID "pmix.fabdev.vendid" (string)</pre>
9	This is a vendor-provided identifier for the device or product.
0	<pre>PMIX_FABRIC_DEVICE_DRIVER "pmix.fabdev.driver" (string)</pre>
1	The name of the driver associated with the device.
2	<pre>PMIX_FABRIC_DEVICE_FIRMWARE "pmix.fabdev.fmwr" (string)</pre>
3	The device's firmware version.
4	<pre>PMIX_FABRIC_DEVICE_ADDRESS "pmix.fabdev.addr" (string)</pre>
5	The primary link-level address associated with the device, such as a MAC address. If
6	multiple addresses are available, only one will be reported.
7	<pre>PMIX_FABRIC_DEVICE_COORDINATES "pmix.fab.coord" (pmix_geometry_t)</pre>
8	The <b>pmix_geometry_t</b> fabric coordinates for the device, including values for all
9	supported coordinate views.
0	<pre>PMIX_FABRIC_DEVICE_MTU "pmix.fabdev.mtu" (size_t)</pre>
1	The maximum transfer unit of link level frames or packets, in bytes.
2	<pre>PMIX_FABRIC_DEVICE_SPEED "pmix.fabdev.speed" (size_t)</pre>
3	The active link data rate, given in bits per second.
4	<pre>PMIX_FABRIC_DEVICE_STATE "pmix.fabdev.state" (pmix_link_state_t)</pre>
5	The last available physical port state for the specified device. Possible values are
6	PMIX_LINK_STATE_UNKNOWN, PMIX_LINK_DOWN, and PMIX_LINK_UP, to indicate
7	if the port state is unknown or not applicable (unknown), inactive (down), or active (up).
8	PMIX_FABRIC_DEVICE_TYPE "pmix.fabdev.type" (string)
9	Specifies the type of fabric interface currently active on the device, such as Ethernet or
0	InfiniBand.
1	<pre>PMIX_FABRIC_DEVICE_PCI_DEVID "pmix.fabdev.pcidevid" (string)</pre>
2	A node-level unique identifier for a PCI device. Provided only if the device is located on a
3	PCI bus. The identifier is constructed as a four-part tuple delimited by colons comprised of

the PCI 16-bit domain, 8-bit bus, 8-bit device, and 8-bit function IDs, each expressed in zero-extended hexadecimal form. Thus, an example identifier might be "abc1:0f:23:01". The combination of node identifier (PMIX\_HOSTNAME or PMIX\_NODEID) and PMIX\_FABRIC\_DEVICE\_PCI\_DEVID shall be unique within the overall system.

The following attributes are related to the *process realm* (as described in Section 6.1.4) and are retrieved according to those rules.

#### PMIX\_FABRIC\_ENDPT "pmix.fab.endpt" (pmix\_data\_array\_t)

Fabric endpoints for a specified process. As multiple endpoints may be assigned to a given process (e.g., in the case where multiple devices are associated with a package to which the process is bound), the returned values will be provided in a pmix\_data\_array\_t of pmix endpoint t elements.

The following attributes are related to the *job realm* (as described in Section 6.1.2) and are retrieved according to those rules. Note that distances to fabric devices are retrieved using the **PMIX DEVICE DISTANCES** key with the appropriate **pmix device type t** qualifier.

#### PMIX\_SWITCH\_PEERS "pmix.speers" (pmix\_data\_array\_t)

Peer ranks that share the same switch as the process specified in the call to PMIx\_Get.

Returns a pmix\_data\_array\_t array of pmix\_info\_t results, each element containing the PMIX\_SWITCH\_PEERS key with a three-element pmix\_data\_array\_t array of pmix\_info\_t containing the PMIX\_DEVICE\_ID of the local fabric device, the PMIX\_FABRIC\_SWITCH identifying the switch to which it is connected, and a comma-delimited string of peer ranks sharing the switch to which that device is connected.

# 14.4 Fabric Support Functions

The following APIs allow the WLM to request specific services from the fabric subsystem via the PMIx library.

#### Advice to PMIx server hosts ·

Due to their high cost in terms of execution, memory consumption, and interactions with other SMS components (e.g., a fabric manager), it is strongly advised that the underlying implementation of these APIs be restricted to a single PMIx server in a system that is supporting the SMS component responsible for the scheduling of allocations (i.e., the system *scheduler*). The PMIX\_SERVER\_SCHEDULER attribute can be used for this purpose to control the execution path. Clients, tools, and other servers utilizing these functions are advised to have their requests forwarded to the server supporting the scheduler using the pmix\_server\_fabric\_fn\_t server module function, as needed.

#### 14.4.1 PMIx Fabric register Summary 3 Register for access to fabric-related information. Format PMIx v4.0 5 pmix\_status\_t 6 PMIx\_Fabric\_register(pmix\_fabric\_t \*fabric, const pmix\_info\_t directives[], 7 size\_t ndirs); 8 INOUT fabric 9 address of a pmix fabric t (backed by storage). User may populate the "name" field at 10 11 will - PMIx does not utilize this field (handle) 12 IN directives an optional array of values indicating desired behaviors and/or fabric to be accessed. If **NULL**, 13 then the highest priority available fabric will be used (array of handles) 14 15 IN ndirs 16 Number of elements in the *directives* array (integer) 17 Returns **PMIX\_SUCCESS** or a negative value indicating the error. Required Attributes The following directives are required to be supported by all PMIx libraries to aid users in 18 identifying the fabric whose data is being sought: 19 PMIX\_FABRIC\_PLANE "pmix.fab.plane" (string) 20 21 ID string of a fabric plane (e.g., CIDR for Ethernet). When used as a modifier in a request for information, specifies the plane whose information is to be returned. When used directly 22 as a key in a request, returns a pmix data array t of string identifiers for all fabric 23 planes in the overall system. 24

PMIX FABRIC IDENTIFIER "pmix.fab.id" (string)

PMIX\_FABRIC\_VENDOR "pmix.fab.vndr" (string)

An identifier for the specified fabric (e.g., MgmtEthernet, Slingshot-11, OmniPath-1).

----

Name of the vendor (e.g., Amazon, Mellanox, HPE, Intel) for the specified fabric.

25

26 27

#### Description

Register for access to fabric-related information, including the communication cost matrix. This call must be made prior to requesting information from a fabric. The caller may request access to a particular fabric using the vendor, type, or identifier, or to a specific *fabric plane* via the **PMIX\_FABRIC\_PLANE** attribute - otherwise, information for the default fabric will be returned. Upon successful completion of the call, information will have been filled into the fields of the provided *fabric* structure.

For performance reasons, the PMIx library does not provide thread protection for accessing the information in the <code>pmix\_fabric\_t</code> structure. Instead, the PMIx implementation shall provide two methods for coordinating updates to the provided fabric information:

- Users may periodically poll for updates using the PMIx\_Fabric\_update API
- Users may register for PMIX\_FABRIC\_UPDATE\_PENDING events indicating that an update to
  the cost matrix is pending. When received, users are required to terminate or pause any actions
  involving access to the cost matrix before returning from the event. Completion of the
  PMIX\_FABRIC\_UPDATE\_PENDING event handler indicates to the PMIx library that the fabric
  object's entries are available for updating. This may include releasing and re-allocating memory
  as the number of vertices may have changed (e.g., due to addition or removal of one or more
  devices). When the update has been completed, the PMIx library will generate a
  PMIX\_FABRIC\_UPDATED event indicating that it is safe to begin using the updated fabric
  object(s).

There is no requirement that the caller exclusively use either one of these options. For example, the user may choose to both register for fabric update events, but poll for an update prior to some critical operation.

#### 4 14.4.2 PMIx Fabric register nb

#### Summary

Register for access to fabric-related information.

```
PMIx v4.0

pmix_status_t

PMIx_Fabric_register_nb(pmix_fabric_t *fabric,

const pmix_info_t directives[],

size_t ndirs,

pmix_op_cbfunc_t cbfunc, void *cbdata);
```

#### **INOUT** fabric

address of a **pmix\_fabric\_t** (backed by storage). User may populate the "name" field at will - PMIx does not utilize this field (handle)

1 2		IN	directives an optional array of values indicating desired behaviors and/or fabric to be accessed. If <b>NULL</b> ,
3			then the highest priority available fabric will be used (array of handles)
4		IN	ndirs
5 6		IN	Number of elements in the <i>directives</i> array (integer)
7 8		IN	Callback function <pre>pmix_op_cbfunc_t</pre> (function reference) cbdata
9			Data to be passed to the callback function (memory reference)
10 11 12		resul	ccessful return indicates that the request is being processed by the host environment and the lt will be returned in the provided <i>cbfunc</i> . Note that the library must not invoke the callback tion prior to returning from the API. In all other cases, the <i>cbfunc</i> will <i>not</i> be called.
13		Retu	rns PMIX_SUCCESS or one of the following error codes when the condition described occurs:
14 15			MIX_OPERATION_SUCCEEDED, indicating that the request was immediately processed and turned <i>success</i> - the <i>cbfunc</i> will not be called
16 17			one of the above return codes are appropriate, then an implementation must return either a real PMIx error code or an implementation defined error code as described in Section 3.1.1.
18 19 20 21		Non- prov	cription  -blocking form of PMIx_Fabric_register. The caller is not allowed to access the ided pmix_fabric_t until the callback function has been executed, at which time the fabric mation will have been loaded into the provided structure.
22	14.4.3	PM	IX_Fabric_update
23 24			nmary ate fabric-related information.
25	PMIx v4.0	For	mat C
26 27		_	<pre>x_status_t x_Fabric_update(pmix_fabric_t *fabric);</pre>
28 29		INO	UT fabric address of a pmix_fabric_t (backed by storage) (handle)
30		Retu	rns <b>PMIX_SUCCESS</b> or a negative value indicating the error.
31 32 33 34		Des Upda fabri acce	ate fabric-related information. This call can be made at any time to request an update of the c information contained in the provided <pre>pmix_fabric_t</pre> object. The caller is not allowed to ss the provided <pre>pmix_fabric_t</pre> until the call has returned. Upon successful return, the
35		infor	mation fields in the <i>fabric</i> structure will have been updated.

# 14.4.4 PMIx\_Fabric\_update\_nb

# SummaryUndate fabric

Update fabric-related information.

# <sup>4</sup> *PMIx v4.0*

5

6

7

8

9 10

11

12

13 14

15

16 17

18

19

20

21

22 23

24 25

26

27 28

#### Format

C

#### INOUT fabric

address of a pmix\_fabric\_t (handle)

IN cbfunc

Callback function **pmix\_op\_cbfunc\_t** (function reference)

IN cbdata

Data to be passed to the callback function (memory reference)

A successful return indicates that the request is being processed by the host environment and the result will be returned in the provided *cbfunc*. Note that the library must not invoke the callback function prior to returning from the API. In all other cases, the *cbfunc* will *not* be called.

Returns PMIX\_SUCCESS or one of the following error codes when the condition described occurs:

• **PMIX\_OPERATION\_SUCCEEDED**, indicating that the request was immediately processed and returned *success* - the *cbfunc* will not be called

If none of the above return codes are appropriate, then an implementation must return either a general PMIx error code or an implementation defined error code as described in Section 3.1.1.

# **Description**

Non-blocking form of **PMIx\_Fabric\_update**. The caller is not allowed to access the provided **pmix\_fabric\_t** until the callback function has been executed, at which time the fields in the provided *fabric* structure will have been updated.

# 14.4.5 PMIx\_Fabric\_deregister

# Summary

Deregister a fabric object.

```
Format
 1
 2
               pmix status t
               PMIx Fabric deregister(pmix_fabric_t *fabric);
 3
               IN
                    fabric
 4
 5
                    address of a pmix fabric t (handle)
 6
               Returns PMIX_SUCCESS or a negative value indicating the error.
               Description
 7
 8
               Deregister a fabric object, providing an opportunity for the PMIx library to cleanup any information
 9
               (e.g., cost matrix) associated with it. Contents of the provided pmix fabric t will be
10
               invalidated upon function return.
    14.4.6
                PMIx_Fabric_deregister_nb
11
12
               Summary
               Deregister a fabric object.
13
               Format
   PMIx v40
15
               pmix status t PMIx Fabric deregister nb(pmix fabric t *fabric,
16
                                                                     pmix_op_cbfunc_t cbfunc,
                                                                      void *cbdata);
17
               IN
                    fabric
18
                    address of a pmix_fabric_t (handle)
19
               IN
20
                     cbfunc
21
                    Callback function pmix_op_cbfunc_t (function reference)
               IN
22
                     cbdata
                    Data to be passed to the callback function (memory reference)
23
24
               A successful return indicates that the request is being processed by the host environment and the
25
               result will be returned in the provided cbfunc. Note that the library must not invoke the callback
26
               function prior to returning from the API. In all other cases, the cbfunc will not be called.
               Returns PMIX SUCCESS or one of the following error codes when the condition described occurs:
27
                • PMIX OPERATION SUCCEEDED, indicating that the request was immediately processed and
28
                  returned success - the cbfunc will not be called
29
               If none of the above return codes are appropriate, then an implementation must return either a
30
               general PMIx error code or an implementation defined error code as described in Section 3.1.1.
31
               Description
32
33
               Non-blocking form of PMIx Fabric deregister. Provided fabric must not be accessed until
34
               after callback function has been executed.
```

#### **CHAPTER 15**

# Security

PMIx utilizes a multi-layered approach toward security that differs for client versus tool processes. By definition, *client* processes must be preregistered with the PMIx server library via the PMIx\_server\_register\_client API before they are spawned. This API requires that the host pass the expected effective UID/GID of the client process.

When the client attempts to connect to the PMIx server, the server shall use available standard OS methods to determine the effective UID/GID of the process requesting the connection. PMIx implementations shall not rely on any values reported by the client process itself. The effective UID/GID reported by the OS is compared to the values provided by the host during registration - if the values fail to match, the PMIx server is required to drop the connection request. This ensures that the PMIx server does not allow connection from a client that doesn't at least meet some minimal security requirement.

Once the requesting client passes the initial test, the PMIx server can, at the choice of the implementor, perform additional security checks. This may involve a variety of methods such as exchange of a system-provided key or credential. At the conclusion of that process, the PMIx server reports the client connection request to the host via the

**pmix\_server\_client\_connected2\_fn\_t** interface, if provided. The host may perform any additional checks and operations before responding with either **PMIX\_SUCCESS** to indicate that the connection is approved, or a PMIx error constant indicating that the connection request is refused. In this latter case, the PMIx server is required to drop the connection.

Tools started by the host environment are classed as a subgroup of client processes and follow the client process procedure. However, tools that are not started by the host environment must be handled differently as registration information is not available prior to the connection request. In these cases, the PMIx server library is required to use available standard OS methods to get the effective UID/GID of the tool and report them upwards as part of invoking the <code>pmix\_server\_tool\_connection\_fn\_t</code> interface, deferring initial security screening to the host. Host environments willing to accept tool connections must therefore both explicitly enable them via the <code>PMIX\_SERVER\_TOOL\_SUPPORT</code> attribute, thereby confirming acceptance of the authentication and authorization burden, and provide the <code>pmix\_server\_tool\_connection\_fn\_t</code> server module function pointer.

# 15.1 Obtaining Credentials

Applications and tools often interact with the host environment in ways that require security beyond just verifying the user's identity - e.g., access to that user's relevant authorizations. This is

particularly important when tools connect directly to a system-level PMIx server that may be 1 2 operating at a privileged level. A variety of system management software packages provide authorization services, but the lack of standardized interfaces makes portability problematic. 3 This section defines two PMIx client-side APIs for this purpose. These are most likely to be used 1 5 by user-space applications/tools, but are not restricted to that realm. 15.1.1 PMIx Get credential Summary Request a credential from the PMIx server library or the host environment. 8 Format PMIx v3.0 10 pmix\_status\_t PMIx\_Get\_credential(const pmix\_info\_t info[], size\_t ninfo, 11 12 pmix\_byte\_object\_t \*credential); IN info 13 Array of pmix\_info\_t structures (array of handles) 14 IN 15 ninfo 16 Number of elements in the *info* array (size t) IN credential 17 Address of a pmix\_byte\_object\_t within which to return credential (handle) 18 19 A successful return indicates that the credential has been returned in the provided 20 pmix\_byte\_object\_t. Returns **PMIX\_SUCCESS** or a negative value indicating the error. 21 Required Attributes 22 There are no required attributes for this API. Note that implementations may choose to internally execute integration for some security environments (e.g., directly contacting a munge server). 23 24 Implementations that support the operation but cannot directly process the client's request must 25 pass any attributes that are provided by the client to the host environment for processing. In 26 addition, the following attributes are required to be included in the *info* array passed from the PMIx library to the host environment: 27 28 PMIX\_USERID "pmix.euid" (uint32\_t) Effective user ID of the connecting process. 29 30 PMIX\_GRPID "pmix.egid" (uint32\_t) Effective group ID of the connecting process. 31

#### **Optional Attributes**

The following attributes are optional for host environments that support this operation:

```
PMIX_TIMEOUT "pmix.timeout" (int)
```

Time in seconds before the specified operation should time out (zero indicating infinite) and return the **PMIX\_ERR\_TIMEOUT** error. Care should be taken to avoid race conditions caused by multiple layers (client, server, and host) simultaneously timing the operation.

#### Description

Request a credential from the PMIx server library or the host environment. The credential is returned as a **pmix\_byte\_object\_t** to support potential binary formats - it is therefore opaque to the caller. No information as to the source of the credential is provided.

#### 15.1.2 PMIx Get credential nb

#### Summary

Request a credential from the PMIx server library or the host environment.

# 13 PMIx v3.0 Format

1

2

3

4

5

6 7

8

9

11

12

14

15 16

17

18

19

20

21 22

23

24

25

26 27

28

29 30

31

32

IN info

Array of pmix\_info\_t structures (array of handles)

IN ninfo

Number of elements in the *info* array (size\_t)

IN cbfunc

Callback function to return credential (pmix\_credential\_cbfunc\_t function reference)

IN cbdata

Data to be passed to the callback function (memory reference)

A successful return indicates that the request is being processed by the host environment and the result will be returned in the provided *cbfunc*. Note that the library must not invoke the callback function prior to returning from the API. In all other cases, the *cbfunc* will *not* be called.

Returns PMIX\_SUCCESS or one of the following error codes when the condition described occurs:

 PMIX\_OPERATION\_SUCCEEDED, indicating that the request was immediately processed successfully - the cbfunc will not be called.

If none of the above return codes are appropriate, then an implementation must return either a 1 2 general PMIx error code or an implementation defined error code as described in Section 3.1.1. Required Attributes There are no required attributes for this API. Note that implementations may choose to internally 3 4 execute integration for some security environments (e.g., directly contacting a *munge* server). 5 Implementations that support the operation but cannot directly process the client's request must pass any attributes that are provided by the client to the host environment for processing. In 6 addition, the following attributes are required to be included in the info array passed from the PMIx 7 8 library to the host environment: PMIX\_USERID "pmix.euid" (uint32\_t) 9 Effective user ID of the connecting process. 10 PMIX\_GRPID "pmix.egid" (uint32\_t) 11 Effective group ID of the connecting process. 12 Optional Attributes The following attributes are optional for host environments that support this operation: 13 PMIX\_TIMEOUT "pmix.timeout" (int) 14 Time in seconds before the specified operation should time out (zero indicating infinite) and 15 return the PMIX\_ERR\_TIMEOUT error. Care should be taken to avoid race conditions 16 17 caused by multiple layers (client, server, and host) simultaneously timing the operation. **Description** 18 19 Request a credential from the PMIx server library or the host environment. This version of the API 20 is generally preferred in scenarios where the host environment may have to contact a remote credential service. Thus, provision is made for the system to return additional information (e.g., the 21 22 identity of the issuing agent) outside of the credential itself and visible to the application. **Credential Attributes** 15.1.3 The following attributes are defined to support credential operations: 24 25 PMIX\_CRED\_TYPE "pmix.sec.ctype" (char\*) 26 When passed in PMIx Get credential, a prioritized, comma-delimited list of desired credential types for use in environments where multiple authentication mechanisms may be 27 28 available. When returned in a callback function, a string identifier of the credential type. PMIX\_CRYPTO\_KEY "pmix.sec.key" (pmix\_byte\_object\_t) 29 30 Blob containing crypto key.

# 15.2 Validating Credentials

Given a credential, PMIx provides two methods by which a caller can request that the system validate it, returning any additional information (e.g., authorizations) conveyed within the credential.

#### 15.2.1 PMIx Validate credential

#### **Summary**

**Format** 

2

3 4

6

7

13

14

15

16 17

18

19

20

21

22

23 24

25 26

27

28 29

30

31 32

33

Request validation of a credential by the PMIx server library or the host environment.

```
8 PMIx v3.0
9
            pmix status t
10
            PMIx Validate credential (const pmix byte object t *cred,
                                       const pmix info t info[], size t ninfo,
11
                                       pmix_info_t **results, size t *nresults);
12
```

```
IN
    cred
```

Pointer to <a href="mailto:pmix\_byte\_object\_t">pmix\_byte\_object\_t</a> containing the credential (handle)

IN

Array of **pmix\_info\_t** structures (array of handles)

IN ninfo

Number of elements in the *info* array (size t)

#### **INOUT** results

Address where a pointer to an array of pmix\_info\_t containing the results of the request can be returned (memory reference)

#### **INOUT** nresults

Address where the number of elements in *results* can be returned (handle)

A successful return indicates that the credential was valid and any information it contained was successfully processed. Details of the result will be returned in the *results* array.

Returns **PMIX SUCCESS** or a negative value indicating the error.

# Required Attributes

There are no required attributes for this API. Note that implementations may choose to internally execute integration for some security environments (e.g., directly contacting a munge server).

Implementations that support the operation but cannot directly process the client's request must pass any attributes that are provided by the client to the host environment for processing. In addition, the following attributes are required to be included in the *info* array passed from the PMIx library to the host environment:

```
PMIX_USERID "pmix.euid" (uint32_t)
```

Effective user ID of the connecting process. 1 PMIX GRPID "pmix.eqid" (uint32 t) 2 Effective group ID of the connecting process. 3 **Optional Attributes** The following attributes are optional for host environments that support this operation: 4 5 PMIX\_TIMEOUT "pmix.timeout" (int) Time in seconds before the specified operation should time out (zero indicating infinite) and 6 return the PMIX ERR TIMEOUT error. Care should be taken to avoid race conditions caused by multiple layers (client, server, and host) simultaneously timing the operation. **Description** 9 Request validation of a credential by the PMIx server library or the host environment. 10 15.2.2 PMIx Validate credential nb **Summary** 12 13 Request validation of a credential by the PMIx server library or the host environment. Provision is made for the system to return additional information regarding possible authorization limitations 14 15 beyond simple authentication.

1	Format C
2	pmix status t
3	PMIx_Validate_credential_nb(const pmix_byte_object_t *cred,
4	const pmix_info_t info[], size_t ninfo,
5	pmix_validation_cbfunc_t cbfunc,
6	void *cbdata);
7	IN cred
8	Pointer to pmix_byte_object_t containing the credential (handle)
9	IN info
10	Array of pmix_info_t structures (array of handles)
11	IN ninfo
12	Number of elements in the <i>info</i> array (size_t)
13 14	IN cbfunc  Callback function to return result (pmix validation cbfunc t function reference)
15	IN cbdata
16	Data to be passed to the callback function (memory reference)
17 18 19	A successful return indicates that the request is being processed by the host environment and the result will be returned in the provided <i>cbfunc</i> . Note that the library must not invoke the callback function prior to returning from the API. In all other cases, the <i>cbfunc</i> will <i>not</i> be called.
20	Returns PMIX_SUCCESS or one of the following error codes when the condition described occurs:
21 22	<b>PMIX_OPERATION_SUCCEEDED</b> , indicating that the request was immediately processed successfully - the <i>cbfunc</i> will <i>not</i> be called.
23 24	If none of the above return codes are appropriate, then an implementation must return either a general PMIx error code or an implementation defined error code as described in Section 3.1.1.
	Required Attributes
25 26	There are no required attributes for this API. Note that implementations may choose to internally execute integration for some security environments (e.g., directly contacting a <i>munge</i> server).
27 28 29 30	Implementations that support the operation but cannot directly process the client's request must pass any attributes that are provided by the client to the host environment for processing. In addition, the following attributes are required to be included in the <i>info</i> array passed from the PMIx library to the host environment:
31 32	PMIX_USERID "pmix.euid" (uint32_t)  Effective user ID of the connecting process.
33 34	<pre>PMIX_GRPID "pmix.egid" (uint32_t) Effective group ID of the connecting process.</pre>

# • Optional Attributes

The following attributes are optional for host environments that support this operation:

PMIX\_TIMEOUT "pmix.timeout" (int)

Time in seconds before the specified operation should time out (zero indicating infinite) and return the **PMIX\_ERR\_TIMEOUT** error. Care should be taken to avoid race conditions caused by multiple layers (client, server, and host) simultaneously timing the operation.

#### **Description**

Request validation of a credential by the PMIx server library or the host environment. This version of the API is generally preferred in scenarios where the host environment may have to contact a remote credential service. Provision is made for the system to return additional information (e.g., possible authorization limitations) beyond simple authentication.

# **CHAPTER 16**

# **Server-Specific Interfaces**

2	First, PMIx provides a set of APIs by which the host can request specific services from its library. This includes:
4 5 6 7 8 9	<ul> <li>collecting inventory to support scheduling algorithms,</li> <li>providing subsystems with an opportunity to precondition their resources for optimized application support,</li> <li>generating regular expressions,</li> <li>registering information to be passed to client processes, and</li> <li>requesting information on behalf of a remote process.</li> </ul>
10 11	Note that the host always has access to all PMIx client APIs - the functions listed below are in addition to those available to a PMIx client.
12 13 14 15	Second, the host can provide a set of callback functions by which the PMIx server library can pass requests upward for servicing by the host. These include notifications of client connection and finalize, as well as requests by clients for information and/or services that the PMIx server library does not itself provide.
16. <b>1</b>	Server Initialization and Finalization
17	Initialization and finalization routines for PMIx servers.
1 <b>6.1.1</b>	PMIx_server_init
19	Summary
20	Initialize the PMIx server.
21 <i>PMIx v1.0</i>	Format C
22	pmix_status_t
23	PMIx_server_init(pmix_server_module_t *module,

pmix\_info\_t info[], size\_t ninfo);

1	INOUT module
2	<pre>pmix_server_module_t structure (handle)</pre>
3	IN info
4	Array of pmix_info_t structures (array of handles)
5	IN ninfo
6	Number of elements in the <i>info</i> array (size_t)
7	Returns <b>PMIX_SUCCESS</b> or a negative value indicating the error.
	Required Attributes
8	The following attributes are required to be supported by all PMIx libraries:
9 10	PMIX_SERVER_NSPACE "pmix.srv.nspace" (char*)  Name of the namespace to use for this PMIx server.
1  2	<pre>PMIX_SERVER_RANK "pmix.srv.rank" (pmix_rank_t) Rank of this PMIx server.</pre>
13	<pre>PMIX_SERVER_TMPDIR "pmix.srvr.tmpdir" (char*)</pre>
14	Top-level temporary directory for all client processes connected to this server, and where the
15	PMIx server will place its tool rendezvous point and contact information.
16	PMIX_SYSTEM_TMPDIR "pmix.sys.tmpdir" (char*)
17	Temporary directory for this system, and where a PMIx server that declares itself to be a
18	system-level server will place a tool rendezvous point and contact information.
19	PMIX_SERVER_TOOL_SUPPORT "pmix.srvr.tool" (bool)
20	The host RM wants to declare itself as willing to accept tool connection requests.
21	PMIX_SERVER_SYSTEM_SUPPORT "pmix.srvr.sys" (bool)
22	The host RM wants to declare itself as being the local system server for PMIx connection
23	requests.
24	PMIX_SERVER_SESSION_SUPPORT "pmix.srvr.sess" (bool)
25	The host RM wants to declare itself as being the local session server for PMIx connection
26	requests.
27	<pre>PMIX_SERVER_GATEWAY "pmix.srv.gway" (bool)</pre>
28	Server is acting as a gateway for PMIx requests that cannot be serviced on backend nodes
29	(e.g., logging to email).
30	PMIX_SERVER_SCHEDULER "pmix.srv.sched" (bool)
31	Server is supporting system scheduler and desires access to appropriate WLM-supporting
32	features. Indicates that the library is to be initialized for scheduler support.

 Ontional	l Attributes

	·
1	The following attributes are optional for implementers of PMIx libraries:
2 3 4	PMIX_USOCK_DISABLE "pmix.usock.disable" (bool)  Disable legacy UNIX socket (usock) support. If the library supports Unix socket connections, this attribute may be supported for disabling it.
5 6 7	PMIX_SOCKET_MODE "pmix.sockmode" (uint32_t)  POSIX mode_t (9 bits valid). If the library supports socket connections, this attribute may be supported for setting the socket mode.
8 9 10	PMIX_SINGLE_LISTENER "pmix.sing.listnr" (bool)  Use only one rendezvous socket, letting priorities and/or environment parameters select the active transport.
11 12 13 14	PMIX_TCP_REPORT_URI "pmix.tcp.repuri" (char*)  If provided, directs that the TCP URI be reported and indicates the desired method of reporting: '-' for stdout, '+' for stderr, or filename. If the library supports TCP socket connections, this attribute may be supported for reporting the URI.
15 16 17 18	PMIX_TCP_IF_INCLUDE "pmix.tcp.ifinclude" (char*)  Comma-delimited list of devices and/or CIDR notation to include when establishing the TCP connection. If the library supports TCP socket connections, this attribute may be supported for specifying the interfaces to be used.
19 20 21 22	PMIX_TCP_IF_EXCLUDE "pmix.tcp.ifexclude" (char*)  Comma-delimited list of devices and/or CIDR notation to exclude when establishing the TCP connection. If the library supports TCP socket connections, this attribute may be supported for specifying the interfaces that are <i>not</i> to be used.
23 24 25	PMIX_TCP_IPV4_PORT "pmix.tcp.ipv4" (int)  The IPv4 port to be used If the library supports IPV4 connections, this attribute may be supported for specifying the port to be used.
26 27 28	PMIX_TCP_IPV6_PORT "pmix.tcp.ipv6" (int)  The IPv6 port to be used. If the library supports IPV6 connections, this attribute may be supported for specifying the port to be used.
29 30 31	PMIX_TCP_DISABLE_IPV4 "pmix.tcp.disipv4" (bool)  Set to true to disable IPv4 family of addresses. If the library supports IPV4 connections, this attribute may be supported for disabling it.
32 33 34	PMIX_TCP_DISABLE_IPV6 "pmix.tcp.disipv6" (bool)  Set to true to disable IPv6 family of addresses. If the library supports IPV6 connections, this attribute may be supported for disabling it.
35	PMIX_SERVER_REMOTE_CONNECTIONS "pmix.srvr.remote" (bool)

1 Allow connections from remote tools. Forces the PMIx server to not exclusively use 2 loopback device. If the library supports connections from remote tools, this attribute may be supported for enabling or disabling it. 3 PMIX EXTERNAL PROGRESS "pmix.evext" (bool) 4 The host shall progress the PMIx library via calls to PMIx Progress 5 PMIX EVENT BASE "pmix.evbase" (void\*) 6 7 Pointer to an event\_base to use in place of the internal progress thread. All PMIx library 8 events are to be assigned to the provided event base. The event base must be compatible with 9 the event library used by the PMIx implementation - e.g., either both the host and PMIx 10 library must use libevent, or both must use libev. Cross-matches are unlikely to work and should be avoided - it is the responsibility of the host to ensure that the PMIx 11 12 implementation supports (and was built with) the appropriate event library. 13 PMIX\_TOPOLOGY2 "pmix.topo2" (pmix\_topology\_t) Provide a pointer to an implementation-specific description of the local node topology. 14 15 PMIX SERVER SHARE TOPOLOGY "pmix.srvr.share" (bool) 16 The PMIx server is to share its copy of the local node topology (whether given to it or 17 self-discovered) with any clients. The PMIx server will perform the necessary actions to scalably expose the description to the local clients. This includes creating any required 18 19 shared memory backing stores and/ or XML representations, plus ensuring that all necessary 20 key-value pairs for clients to access the description are included in the job-level information provided to each client. All required files are to be installed under the effective 21 PMIX\_SERVER\_TMPDIR directory. The PMIx server library is responsible for cleaning up 22 any artifacts (e.g., shared memory backing files or cached key-value pairs) at library finalize. 23 PMIX SERVER ENABLE MONITORING "pmix.srv.monitor" (bool) 24 25 Enable PMIx internal monitoring by the PMIx server. PMIX\_HOMOGENEOUS\_SYSTEM "pmix.homo" (bool) 26 27 The nodes comprising the session are homogeneous - i.e., they each contain the same number of identical packages, fabric interfaces, GPUs, and other devices. 28

# Description

29 30

31 32

33

34

Initialize the PMIx server support library, and provide a pointer to a <code>pmix\_server\_module\_t</code> structure containing the caller's callback functions. The array of <code>pmix\_info\_t</code> structs is used to pass additional info that may be required by the server when initializing. For example, it may include the <code>PMIX\_SERVER\_TOOL\_SUPPORT</code> attribute, thereby indicating that the daemon is willing to accept connection requests from tools.

#### Advice to PMIx server hosts

Providing a value of **NULL** for the *module* argument is permitted, as is passing an empty *module*structure. Doing so indicates that the host environment will not provide support for multi-node operations such as **PMIx\_Fence**, but does intend to support local clients access to information.

# 4 16.1.2 PMIx\_server\_finalize

#### Summary

Finalize the PMIx server library.

# 7 PMIx v1.0 Format

5

8

13

15

16 17

18

19

20 21

22

23

24

25 26

27

28 29

30

31

pmix\_status\_t

PMIx\_server\_finalize(void);

10 Returns **PMIX\_SUCCESS** or a negative value indicating the error.

#### 11 Description

Finalize the PMIx server support library, terminating all connections to attached tools and any local

clients. All memory usage is released.

# 14 16.1.3 Server Initialization Attributes

These attributes are used to direct the configuration and operation of the PMIx server library by passing them into **PMIx\_server\_init**.

```
PMIX_TOPOLOGY2 "pmix.topo2" (pmix_topology_t)
```

Provide a pointer to an implementation-specific description of the local node topology.

```
PMIX_SERVER_SHARE_TOPOLOGY "pmix.srvr.share" (bool)
```

The PMIx server is to share its copy of the local node topology (whether given to it or self-discovered) with any clients.

PMIX\_USOCK\_DISABLE "pmix.usock.disable" (bool)

Disable legacy UNIX socket (usock) support.

PMIX SOCKET MODE "pmix.sockmode" (uint32 t)

POSIX *mode* t (9 bits valid).

PMIX\_SINGLE\_LISTENER "pmix.sing.listnr" (bool)

Use only one rendezvous socket, letting priorities and/or environment parameters select the active transport.

PMIX\_SERVER\_TOOL\_SUPPORT "pmix.srvr.tool" (bool)

The host RM wants to declare itself as willing to accept tool connection requests.

PMIX SERVER REMOTE CONNECTIONS "pmix.srvr.remote" (bool)

1 2		Allow connections from remote tools. Forces the PMIx server to not exclusively use loopback device.
		PMIX_SERVER_SYSTEM_SUPPORT "pmix.srvr.sys" (bool)
3		The host RM wants to declare itself as being the local system server for PMIx connection
4 5		
		requests.
6 7		PMIX_SERVER_SESSION_SUPPORT "pmix.srvr.sess" (bool)  The best PM wents to declare itself as being the legal session server for PMIx connection
		The host RM wants to declare itself as being the local session server for PMIx connection
8		requests.
9		PMIX_SERVER_START_TIME "pmix.srvr.strtime" (char*)  Time when the server storted i.e. when the server greated it's rendervous file (given in
10 11		Time when the server started - i.e., when the server created it's rendezvous file (given in ctime string format).
12		PMIX_SERVER_TMPDIR "pmix.srvr.tmpdir" (char*)
13		Top-level temporary directory for all client processes connected to this server, and where the
14		PMIx server will place its tool rendezvous point and contact information.
15		PMIX_SYSTEM_TMPDIR "pmix.sys.tmpdir" (char*)
16		Temporary directory for this system, and where a PMIx server that declares itself to be a
17		system-level server will place a tool rendezvous point and contact information.
18		system-rever server with place a tool rendezvous point and contact information.  PMIX_SERVER_ENABLE_MONITORING "pmix.srv.monitor" (bool)
19		Enable PMIx internal monitoring by the PMIx server.
20		PMIX_SERVER_NSPACE "pmix.srv.nspace" (char*)
21		Name of the namespace to use for this PMIx server.
22		PMIX_SERVER_RANK "pmix.srv.rank" (pmix_rank_t)
23		Rank of this PMIx server.
24		PMIX_SERVER_GATEWAY "pmix.srv.gway" (bool)
25		Server is acting as a gateway for PMIx requests that cannot be serviced on backend nodes
26		(e.g., logging to email).
27		PMIX_SERVER_SCHEDULER "pmix.srv.sched" (bool)
28		Server is supporting system scheduler and desires access to appropriate WLM-supporting
29		features. Indicates that the library is to be initialized for scheduler support.
30		PMIX_EXTERNAL_PROGRESS "pmix.evext" (bool)
31		The host shall progress the PMIx library via calls to PMIx_Progress
32		PMIX_HOMOGENEOUS_SYSTEM "pmix.homo" (bool)
33		The nodes comprising the session are homogeneous - i.e., they each contain the same
34		number of identical packages, fabric interfaces, GPUs, and other devices.
	16.2	Sorver Support Functions
35	10.2	Server Support Functions
36		The following APIs allow the RM daemon that hosts the PMIx server library to request specific
37		services from the PMIx library.
38	16.2.1	PMIx_generate_regex
39		Summary

Generate a compressed representation of the input string.

40

CHAPTER 16. SERVER-SPECIFIC INTERFACES

# PMIx v1.0 pmix\_status\_t PMIx\_generate\_regex(const char \*input, char \*\*output); IN input String to process (string) OUT output Compressed representation of input (array of bytes)

Returns **PMIX\_SUCCESS** or a negative value indicating the error.

#### **Description**

Given a comma-separated list of *input* values, generate a reduced size representation of the input that can be passed down to the PMIx server library's **PMIx\_server\_register\_nspace** API for parsing. The order of the individual values in the *input* string is preserved across the operation. The caller is responsible for releasing the returned data.

The precise compressed representations will be implementation specific. The regular expression itself is not required to be a printable string nor to obey typical string constraints (e.g., include a **NULL** terminator byte). However, all PMIx implementations are required to include a colon-delimited **NULL**-terminated string at the beginning of the output representation that can be printed for diagnostic purposes and identifies the method used to generate the representation. The following identifiers are reserved by the PMIx Standard:

- "raw:\0" indicates that the expression following the identifier is simply the comma-delimited input string (no processing was performed).
- "pmix:\0" a PMIx-unique regular expression represented as a NULL-terminated string following the identifier.
- "blob:\0" a PMIx-unique regular expression that is not represented as a **NULL**-terminated string following the identifier. Additional implementation-specific metadata may follow the identifier along with the data itself. For example, a compressed binary array format based on the *zlib* compression package, with the size encoded in the space immediately following the identifier.

Communicating the resulting output should be done by first packing the returned expression using the PMIx\_Data\_pack, declaring the input to be of type PMIX\_REGEX, and then obtaining the resulting blob to be communicated using the PMIX\_DATA\_BUFFER\_UNLOAD macro. The reciprocal method can be used on the remote end prior to passing the regex into PMIx\_server\_register\_nspace. The pack/unpack routines will ensure proper handling of the data based on the regex prefix.

# 16.2.2 PMIx\_generate\_ppn

30

```
Summary
 3
               Generate a compressed representation of the input identifying the processes on each node.
               Format
   PMIx v1.0
5
               pmix_status_t
6
               PMIx_generate_ppn(const char *input, char **ppn);
7
               IN
                    input
                    String to process (string)
8
               OUT ppn
9
10
                    Compressed representation of input (array of bytes)
11
               Returns PMIX SUCCESS or a negative value indicating the error.
12
               Description
               The input shall consist of a semicolon-separated list of ranges representing the ranks of processes
13
               on each node of the job - e.g., "1-4; 2-5; 8, 10, 11, 12; 6, 7, 9". Each field of the input must
14
               correspond to the node name provided at that position in the input to PMIx_generate_regex.
15
16
               Thus, in the example, ranks 1-4 would be located on the first node of the comma-separated list of
17
               names provided to PMIx_generate_regex, and ranks 2-5 would be on the second name in the
               list.
18
               Rules governing the format of the returned regular expression are the same as those specified for
19
20
               PMIx_generate_regex, as detailed here.
    16.2.3
               PMIx server register nspace
22
               Summary
23
               Setup the data about a particular namespace.
               Format
   PMIx v1.0
25
               pmix_status_t
26
               PMIx_server_register_nspace(const pmix_nspace_t nspace,
27
                                                    int nlocalprocs,
                                                    pmix_info_t info[], size_t ninfo,
28
29
                                                    pmix_op_cbfunc_t cbfunc,
```

void \*cbdata);

	_
•	
١.	- 1

1	IN	nenago
2	1114	nspace Character array of maximum size PMIX_MAX_NSLEN containing the namespace identifier
3		(string)
4	IN	nlocalprocs
5		number of local processes (integer)
6	IN	info
7		Array of info structures (array of handles)
8	IN	ninfo
9		Number of elements in the <i>info</i> array (integer)
10	IN	cbfunc
11		Callback function <b>pmix_op_cbfunc_t</b> to be executed upon completion of the operation.
12		A <b>NULL</b> function reference indicates that the function is to be executed as a blocking
13	INI	operation (function reference)
14	IN	cbdata  Deta to be record to the cellback function (mamous reference)
15		Data to be passed to the callback function (memory reference)
16		accessful return indicates that the request is being processed by the host environment and the
17		It will be returned in the provided <i>cbfunc</i> . Note that the library must not invoke the callback
18	func	ction prior to returning from the API. In all other cases, the <i>cbfunc</i> will <i>not</i> be called.
19	Retu	urns PMIX_SUCCESS or one of the following error codes when the condition described occurs:
20 21		MIX_OPERATION_SUCCEEDED, indicating that the request was immediately processed and eturned <i>success</i> - the <i>cbfunc</i> will not be called
22 23		one of the above return codes are appropriate, then an implementation must return either a eral PMIx error code or an implementation defined error code as described in Section 3.1.1.
	<b>—</b> -	Required Attributes
24	The	following attributes are required to be supported by all PMIx libraries:
25	PMI	X_REGISTER_NODATA "pmix.reg.nodata" (bool)
26		Registration is for this namespace only, do not copy job data.
27	DMT	X_SESSION_INFO_ARRAY "pmix.ssn.arr" (pmix_data_array_t)
28	PMI	Provide an array of pmix_info_t containing session-realm information. The
<u> 29</u>	4	PMIX_SESSION_ID attribute is required to be included in the array.
30	PMI	X_JOB_INFO_ARRAY "pmix.job.arr" (pmix_data_array_t)
31		Provide an array of pmix_info_t containing job-realm information. The
32		<b>PMIX_SESSION_ID</b> attribute of the <i>session</i> containing the <i>job</i> is required to be included in
33		the array whenever the PMIx server library may host multiple sessions (e.g., when executing
34		with a host RM daemon). As information is registered one job (aka namespace) at a time via
35		the PMIx_server_register_nspace API, there is no requirement that the array
36		contain either the <b>PMIX_NSPACE</b> or <b>PMIX_JOBID</b> attributes when used in that context

(though either or both of them may be included). At least one of the job identifiers must be provided in all other contexts where the job being referenced is ambiguous.

#### PMIX\_APP\_INFO\_ARRAY "pmix.app.arr" (pmix\_data\_array\_t)

Provide an array of **pmix\_info\_t** containing application-realm information. The **PMIX\_NSPACE** or **PMIX\_JOBID** attributes of the *job* containing the application, plus its **PMIX\_APPNUM** attribute, must to be included in the array when the array is *not* included as part of a call to **PMIx\_server\_register\_nspace** - i.e., when the job containing the application is ambiguous. The job identification is otherwise optional.

#### PMIX\_PROC\_INFO\_ARRAY "pmix.pdata" (pmix\_data\_array\_t)

Provide an array of <code>pmix\_info\_t</code> containing process-realm information. The <code>PMIX\_RANK</code> and <code>PMIX\_NSPACE</code> attributes, or the <code>PMIX\_PROCID</code> attribute, are required to be included in the array when the array is not included as part of a call to <code>PMIx\_server\_register\_nspace</code> - i.e., when the job containing the process is ambiguous. All three may be included if desired. When the array is included in some broader structure that identifies the job, then only the <code>PMIX\_RANK</code> or the <code>PMIX\_PROCID</code> attribute must be included (the others are optional).

#### PMIX\_NODE\_INFO\_ARRAY "pmix.node.arr" (pmix\_data\_array\_t)

Provide an array of **pmix\_info\_t** containing node-realm information. At a minimum, either the **PMIX\_NODEID** or **PMIX\_HOSTNAME** attribute is required to be included in the array, though both may be included.

Host environments are required to provide a wide range of session-, job-, application-, node-, and process-realm information, and may choose to provide a similarly wide range of optional information. The information is broadly separated into categories based on the *data realm* definitions explained in Section 6.1, and retrieved according to the rules detailed in Section 6.2.

Session-realm information may be passed as individual <code>pmix\_info\_t</code> entries, or as part of a <code>pmix\_data\_array\_t</code> using the <code>PMIX\_SESSION\_INFO\_ARRAY</code> attribute. The list of data referenced in this way shall include:

#### • PMIX\_UNIV\_SIZE "pmix.univ.size" (uint32\_t)

Maximum number of process that can be simultaneously executing in a session. Note that this attribute is equivalent to the **PMIX\_MAX\_PROCS** attribute for the *session* realm - it is included in the PMIx Standard for historical reasons.

#### • PMIX MAX PROCS "pmix.max.size" (uint32\_t)

Maximum number of processes that can be executed in the specified realm. Typically, this is a constraint imposed by a scheduler or by user settings in a hostfile or other resource description. Defaults to the *job* realm. Must be provided if **PMIX\_UNIV\_SIZE** is not given. Requires use of the **PMIX\_SESSION\_INFO** attribute to avoid ambiguity when retrieving it.

• PMIX\_SESSION\_ID "pmix.session.id" (uint32\_t)

Session identifier assigned by the scheduler.

plus the following optional information:

#### • PMIX\_CLUSTER\_ID "pmix.clid" (char\*)

A string name for the cluster this allocation is on. As this information is not related to the namespace, it is best passed using the **PMIx\_server\_register\_resources** API.

#### • PMIX ALLOCATED NODELIST "pmix.alist" (char\*)

Comma-delimited list or regular expression of all nodes in the specified realm regardless of whether or not they currently host processes. Defaults to the *job* realm.

#### • PMIX\_RM\_NAME "pmix.rm.name" (char\*)

String name of the RM. As this information is not related to the namespace, it is best passed using the **PMIx\_server\_register\_resources** API.

#### • PMIX\_RM\_VERSION "pmix.rm.version" (char\*)

RM version string. As this information is not related to the namespace, it is best passed using the **PMIx\_server\_register\_resources** API.

#### • PMIX\_SERVER\_HOSTNAME "pmix.srvr.host" (char\*)

Host where target PMIx server is located. As this information is not related to the namespace, it is best passed using the PMIx\_server\_register\_resources API.

Job-realm information may be passed as individual pmix\_info\_t entries, or as part of a pmix\_data\_array\_t using the PMIX\_JOB\_INFO\_ARRAY attribute. The list of data referenced in this way shall include:

#### • PMIX SERVER NSPACE "pmix.srv.nspace" (char\*)

Name of the namespace to use for this PMIx server. Identifies the namespace of the PMIx server itself

#### • PMIX\_SERVER\_RANK "pmix.srv.rank" (pmix\_rank\_t)

Rank of this PMIx server. Identifies the rank of the PMIx server itself.

#### • PMIX NSPACE "pmix.nspace" (char\*)

Namespace of the job - may be a numerical value expressed as a string, but is often an alphanumeric string carrying information solely of use to the system. Required to be unique within the scope of the host environment. Identifies the namespace of the job being registered.

#### • PMIX JOBID "pmix.jobid" (char\*)

Job identifier assigned by the scheduler to the specified job - may be identical to the namespace, but is often a numerical value expressed as a string (e.g., "12345.3").

#### • PMIX\_JOB\_SIZE "pmix.job.size" (uint32\_t)

Total number of processes in the specified job across all contained applications. Note that this value can be different from **PMIX\_MAX\_PROCS**. For example, users may choose to subdivide an allocation (running several jobs in parallel within it), and dynamic

is a constraint imposed by a scheduler or by user settings in a hostfile or other resource description. Defaults to the job realm. Retrieval of this attribute defaults to the job level unless an appropriate specification is given (e.g., PMIX_SESSION_INFO).  **PMIX_NODE_MAP "pmix.nmap" (char*)  Regular expression of nodes currently hosting processes in the specified realm - see 16.2.3.2 for an explanation of its generation. Defaults to the job realm.  **PMIX_PROC_MAP "pmix.pmap" (char*)  Regular expression describing processes on each node in the specified realm - see 16.2.3.2 for an explanation of its generation. Defaults to the job realm.  plus the following optional information:  **PMIX_NPROC_OFFSET "pmix.offset" (pmix_rank_t)  Starting global rank of the specified job.  **PMIX_JOB_NUM_APPS "pmix.job.napps" (uint32_t)  Number of applications in the specified job. This is a required attribute if more than one application is included in the job  **PMIX_MAPBY "pmix.mapby" (char*)  Process mapping policy when accessed using PMIx_Get, use the PMIX_RANK_WILDCARD value for the rank to discover the mapping policy used for the provided namespace. Supported values are launcher specific.  **PMIX_RANK_WILDCARD value for the rank to discover the ranking algorithm used for the provided namespace. Supported values are launcher specific.  **PMIX_RANK_WILDCARD value for the rank to discover the binding policy used for the provided namespace. Supported values are launcher specific.  **PMIX_BINDTO "pmix.bindto" (char*)  Process inding policy - when accessed using PMIx_Get, use the PMIX_RANK_WILDCARD value for the rank to discover the binding policy used for the provided namespace. Supported values are launcher specific.  **PMIX_BINDTO "pmix.bindto" (char*)  Process binding policy - when accessed using PMIx_Get, use the PMIX_RANK_WILDCARD value for the rank to discover the binding policy used for the provided namespace. Supported values are launcher specific.	1 2 3	programming models may support adding and removing processes from a running <i>job</i> on-the-fly. In the latter case, PMIx events may be used to notify processes within the job that the job size has changed.
Regular expression of nodes currently hosting processes in the specified realm - see  16.2.3.2 for an explanation of its generation. Defaults to the job realm.  PMIX_PROC_MAP "pmix.pmap" (char*)  Regular expression describing processes on each node in the specified realm - see 16.2.3.2  for an explanation of its generation. Defaults to the job realm.  plus the following optional information:  PMIX_NPROC_OFFSET "pmix.offset" (pmix_rank_t)  Starting global rank of the specified job.  PMIX_JOB_NUM_APPS "pmix.job.napps" (uint32_t)  Number of applications in the specified job. This is a required attribute if more than one application is included in the job.  PMIX_MAPBY "pmix.mapby" (char*)  Process mapping policy - when accessed using PMIx_Get, use the PMIX_RANK_WILDCARD value for the rank to discover the mapping policy used for the provided namespace. Supported values are launcher specific.  PMIX_RANKBY "pmix.rankby" (char*)  Process ranking policy - when accessed using PMIx_Get, use the PMIX_RANK_WILDCARD value for the rank to discover the ranking algorithm used for the provided namespace. Supported values are launcher specific.  PMIX_BINDTO "pmix.bindto" (char*)  Process binding policy - when accessed using PMIx_Get, use the PMIX_RANK_WILDCARD value for the rank to discover the binding policy used for the provided namespace. Supported values are launcher specific.  PMIX_BINDTO "pmix.bindto" (char*)  Process binding policy - when accessed using PMIx_Get, use the PMIX_RANK_WILDCARD value for the rank to discover the binding policy used for the provided namespace. Supported values are launcher specific.	5 6 7	Maximum number of processes that can be executed in the specified realm. Typically, this is a constraint imposed by a scheduler or by user settings in a hostfile or other resource description. Defaults to the <i>job</i> realm. Retrieval of this attribute defaults to the job level
Regular expression describing processes on each node in the specified realm - see 16.2.3.2 for an explanation of its generation. Defaults to the job realm.  plus the following optional information:  PMIX_NPROC_OFFSET "pmix.offset" (pmix_rank_t) Starting global rank of the specified job.  PMIX_JOB_NUM_APPS "pmix.job.napps" (uint32_t) Number of applications in the specified job. This is a required attribute if more than one application is included in the job.  PMIX_MAPBY "pmix.mapby" (char*) Process mapping policy - when accessed using PMIx_Get, use the PMIX_RANK_WILDCARD value for the rank to discover the mapping policy used for the provided namespace. Supported values are launcher specific.  PMIX_RANKBY "pmix.rankby" (char*) Process ranking policy - when accessed using PMIx_Get, use the PMIX_RANK_WILDCARD value for the rank to discover the ranking algorithm used for the provided namespace. Supported values are launcher specific.  PMIX_BINDTO "pmix.bindto" (char*) Process binding policy - when accessed using PMIx_Get, use the PMIX_RANK_WILDCARD value for the rank to discover the binding policy used for the provided namespace. Supported values are launcher specific.  PMIX_BINDTO "pmix.bindto" (char*) Process mank wildcard value for the rank to discover the binding policy used for the provided namespace. Supported values are launcher specific.  PMIX_HOSTNAME_KEEP_FQDN "pmix.fqdn" (bool) FQDNs are being retained by the PMIx library.  Process map equivalent to PMIX_PROC_MAP expressed in Argonne National	10	Regular expression of nodes currently hosting processes in the specified realm - see
<ul> <li>PMIX_NPROC_OFFSET "pmix.offset" (pmix_rank_t)</li></ul>	13	Regular expression describing processes on each node in the specified realm - see 16.2.3.2
Starting global rank of the specified job.  PMIX_JOB_NUM_APPS "pmix.job.napps" (uint32_t) Number of applications in the specified job. This is a required attribute if more than one application is included in the job.  PMIX_MAPBY "pmix.mapby" (char*) Process mapping policy - when accessed using PMIx_Get, use the PMIX_RANK_WILDCARD value for the rank to discover the mapping policy used for the provided namespace. Supported values are launcher specific.  PMIX_RANKBY "pmix.rankby" (char*) Process ranking policy - when accessed using PMIx_Get, use the PMIX_RANK_WILDCARD value for the rank to discover the ranking algorithm used for the provided namespace. Supported values are launcher specific.  PMIX_BINDTO "pmix.bindto" (char*) Process binding policy - when accessed using PMIx_Get, use the PMIX_BINDTO "pmix.bindto" (char*) Process binding policy - when accessed using PMIx_Get, use the PMIX_RANK_WILDCARD value for the rank to discover the binding policy used for the provided namespace. Supported values are launcher specific.  PMIX_HOSTNAME_KEEP_FQDN "pmix.fqdn" (bool) FQDNs are being retained by the PMIx library.  Process map equivalent to PMIX_PROC_MAP expressed in Argonne National	15	plus the following optional information:
Number of applications in the specified job. This is a required attribute if more than one application is included in the job.  PMIX_MAPBY "pmix.mapby" (char*) Process mapping policy - when accessed using PMIx_Get, use the PMIX_RANK_WILDCARD value for the rank to discover the mapping policy used for the provided namespace. Supported values are launcher specific.  PMIX_RANKBY "pmix.rankby" (char*) Process ranking policy - when accessed using PMIx_Get, use the PMIX_RANK_WILDCARD value for the rank to discover the ranking algorithm used for the provided namespace. Supported values are launcher specific.  PMIX_BINDTO "pmix.bindto" (char*) Process binding policy - when accessed using PMIx_Get, use the PMIX_RANK_WILDCARD value for the rank to discover the binding policy used for the provided namespace. Supported values are launcher specific.  PMIX_RANK_WILDCARD value for the rank to discover the binding policy used for the provided namespace. Supported values are launcher specific.  PMIX_RANK_WILDCARD value for the rank to discover the binding policy used for the provided namespace. Supported values are launcher specific.  PMIX_HOSTNAME_KEEP_FQDN "pmix.fqdn" (bool) FQDNs are being retained by the PMIX library.  Process map equivalent to PMIX_PROC_MAP expressed in Argonne National		
Process mapping policy - when accessed using PMIx_Get, use the PMIX_RANK_WILDCARD value for the rank to discover the mapping policy used for the provided namespace. Supported values are launcher specific.  PMIX_RANKBY "pmix.rankby" (char*) Process ranking policy - when accessed using PMIx_Get, use the PMIX_RANK_WILDCARD value for the rank to discover the ranking algorithm used for the provided namespace. Supported values are launcher specific.  PMIX_BINDTO "pmix.bindto" (char*) Process binding policy - when accessed using PMIx_Get, use the PMIX_RANK_WILDCARD value for the rank to discover the binding policy used for the provided namespace. Supported values are launcher specific.  PMIX_HOSTNAME_KEEP_FQDN "pmix.fqdn" (bool) FQDNs are being retained by the PMIx library.  PMIX_ANL_MAP "pmix.anlmap" (char*) Process map equivalent to PMIX_PROC_MAP expressed in Argonne National	19	Number of applications in the specified job. This is a required attribute if more than one
Process ranking policy - when accessed using PMIx_Get, use the PMIX_RANK_WILDCARD value for the rank to discover the ranking algorithm used for the provided namespace. Supported values are launcher specific.  PMIX_BINDTO "pmix.bindto" (char*)  Process binding policy - when accessed using PMIx_Get, use the PMIX_RANK_WILDCARD value for the rank to discover the binding policy used for the provided namespace. Supported values are launcher specific.  PMIX_HOSTNAME_KEEP_FQDN "pmix.fqdn" (bool) FQDNs are being retained by the PMIx library.  PMIX_ANL_MAP "pmix.anlmap" (char*) Process map equivalent to PMIX_PROC_MAP expressed in Argonne National	22 23	Process mapping policy - when accessed using <b>PMIx_Get</b> , use the <b>PMIX_RANK_WILDCARD</b> value for the rank to discover the mapping policy used for the
Process binding policy - when accessed using PMIx_Get, use the  PMIX_RANK_WILDCARD value for the rank to discover the binding policy used for the provided namespace. Supported values are launcher specific.  PMIX_HOSTNAME_KEEP_FQDN "pmix.fqdn" (bool) FQDNs are being retained by the PMIx library.  PMIX_ANL_MAP "pmix.anlmap" (char*) Process map equivalent to PMIX_PROC_MAP expressed in Argonne National	26 27	Process ranking policy - when accessed using <b>PMIx_Get</b> , use the <b>PMIX_RANK_WILDCARD</b> value for the rank to discover the ranking algorithm used for
FQDNs are being retained by the PMIx library.  • PMIX_ANL_MAP "pmix.anlmap" (char*)  Process map equivalent to PMIX_PROC_MAP expressed in Argonne National	30 31	Process binding policy - when accessed using <b>PMIx_Get</b> , use the <b>PMIX_RANK_WILDCARD</b> value for the rank to discover the binding policy used for the
35 • PMIX_ANL_MAP "pmix.anlmap" (char*) 36 • Process map equivalent to PMIX_PROC_MAP expressed in Argonne National		
Laboratory 81 Wii-1/1 Wii-2 notation. Defaults to the <i>job</i> Teami.	35	• PMIX_ANL_MAP "pmix.anlmap" (char*)

1 2	<ul> <li>PMIX_TDIR_RMCLEAN "pmix.tdir.rmclean" (bool)</li> <li>Resource Manager will cleanup assigned temporary directory trees.</li> </ul>
3	• PMIX_CRYPTO_KEY "pmix.sec.key" (pmix_byte_object_t)  Blob containing crypto key.
5 6 7	If more than one application is included in the namespace, then the host environment is also required to supply data consisting of the following items for each application in the job, passed as a <pre>pmix_data_array_t</pre> using the PMIX_APP_INFO_ARRAY attribute:
8 9 10	• PMIX_APPNUM "pmix.appnum" (uint32_t)  The application number within the job in which the specified process is a member. This attribute must appear at the beginning of the array.
11 12 13	<ul> <li>PMIX_APP_SIZE "pmix.app.size" (uint32_t)</li> <li>Number of processes in the specified application, regardless of their execution state - i.e., this number may include processes that either failed to start or have already terminated.</li> </ul>
14 15 16 17 18	<ul> <li>PMIX_MAX_PROCS "pmix.max.size" (uint32_t)         Maximum number of processes that can be executed in the specified realm. Typically, this is a constraint imposed by a scheduler or by user settings in a hostfile or other resource description. Defaults to the <i>job</i> realm. Requires use of the PMIX_APP_INFO attribute to avoid ambiguity when retrieving it.     </li> </ul>
19 20	• PMIX_APPLDR "pmix.aldr" (pmix_rank_t)  Lowest rank in the specified application.
21 22 23 24	<ul> <li>PMIX_WDIR "pmix.wdir" (char*)</li> <li>Working directory for spawned processes. This attribute is required for all registrations, but may be provided as an individual pmix_info_t entry if only one application is included in the namespace.</li> </ul>
25 26 27 28	• PMIX_APP_ARGV "pmix.app.argv" (char*)  Consolidated argv passed to the spawn command for the given application (e.g., "./myapp arg1 arg2 arg3"). This attribute is required for all registrations, but may be provided as an individual pmix_info_t entry if only one application is included in the namespace.
29	plus the following optional information:
30 31 32	• PMIX_PSET_NAMES "pmix.pset.nms" (pmix_data_array_t*) Returns an array of char* string names of the process sets in which the given process is a member.
33 34 35 36	• PMIX_APP_MAP_TYPE "pmix.apmap.type" (char*)  Type of mapping used to layout the application (e.g., cyclic). This attribute may be provided as an individual pmix_info_t entry if only one application is included in the namespace.
37	• PMIX_APP_MAP_REGEX "pmix.apmap.regex" (char*)

Regular expression describing the result of the process mapping. This attribute may be 1 2 provided as an individual pmix info t entry if only one application is included in the 3 namespace. 4 The data may also include attributes provided by the host environment that identify the programming model (as specified by the user) being executed within the application. The PMIx 5 server library may utilize this information to customize the environment to fit that model (e.g., 6 7 adding environmental variables specified by the corresponding standard for that model): 8 • PMIX PROGRAMMING MODEL "pmix.pgm.model" (char\*) Programming model being initialized (e.g., "MPI" or "OpenMP"). 9 10 • PMIX MODEL LIBRARY NAME "pmix.mdl.name" (char\*) Programming model implementation ID (e.g., "OpenMPI" or "MPICH"). 11 • PMIX MODEL LIBRARY VERSION "pmix.mld.vrs" (char\*) 12 Programming model version string (e.g., "2.1.1"). 13 14 Node-realm information may be passed as individual pmix info t entries if only one node will 15 host processes from the job being registered, or as part of a pmix data array t using the PMIX NODE INFO ARRAY attribute when multiple nodes are involved in the job. The list of data 16 referenced in this way shall include: 17 • PMIX\_NODEID "pmix.nodeid" (uint32\_t) 18 19 Node identifier expressed as the node's index (beginning at zero) in an array of nodes within the active session. The value must be unique and directly correlate to the 20 **PMIX\_HOSTNAME** of the node - i.e., users can interchangeably reference the same 21 22 location using either the PMIX\_HOSTNAME or corresponding PMIX\_NODEID. • PMIX HOSTNAME "pmix.hname" (char\*) 23 24 Name of the host, as returned by the **gethostname** utility or its equivalent. As this information is not related to the namespace, it can be passed using the 25 PMIx\_server\_register\_resources API. However, either it or the 26 27 **PMIX\_NODEID** must be included in the array to properly identify the node. • PMIX\_HOSTNAME\_ALIASES "pmix.alias" (char\*) 28 Comma-delimited list of names by which the target node is known. As this information is 29 not related to the namespace, it is best passed using the 30 PMIx\_server\_register\_resources API. 31 PMIX\_LOCAL\_SIZE "pmix.local.size" (uint32\_t) 32 33 Number of processes in the specified job or application realm on the caller's node. Defaults to job realm unless the PMIX\_APP\_INFO and the PMIX\_APPNUM qualifiers are 34 35 given. 36 • PMIX\_NODE\_SIZE "pmix.node.size" (uint32\_t) Number of processes across all jobs that are executing upon the node. 37

• PMIX\_LOCALLDR "pmix.lldr" (pmix\_rank\_t)

namespace – shortcut for **PMIx\_Resolve\_peers** for the local node. 5 plus the following information for the server's own node: 6 7 • PMIX TMPDIR "pmix.tmpdir" (char\*) Full path to the top-level temporary directory assigned to the session. 8 9 • PMIX NSDIR "pmix.nsdir" (char\*) Full path to the temporary directory assigned to the specified job, under PMIX TMPDIR. 10 • PMIX\_LOCAL\_PROCS "pmix.lprocs" (pmix\_proc\_t array) 11 Array of pmix\_proc\_t of all processes executing on the local node – shortcut for 12 PMIx Resolve peers for the local node and a NULL namespace argument. The 13 process identifier is ignored for this attribute. 14 15 The data may also include the following optional information for the server's own node: • PMIX\_LOCAL\_CPUSETS "pmix.lcpus" (pmix\_data\_array\_t) 16 A pmix data array t array of string representations of the PU binding bitmaps 17 applied to each local peer on the caller's node upon launch. Each string shall begin with 18 19 the name of the library that generated it (e.g., "hwloc") followed by a colon and the bitmap string itself. The array shall be in the same order as the processes returned by 20 PMIX LOCAL PEERS for that namespace. 21 22 • PMIX AVAIL PHYS MEMORY "pmix.pmem" (uint64 t) 23 Total available physical memory on a node. As this information is not related to the namespace, it can be passed using the **PMIx\_server\_register\_resources** API. 24 and the following optional information for other nodes: 25 26 • PMIX MAX PROCS "pmix.max.size" (uint32 t) Maximum number of processes that can be executed in the specified realm. Typically, this 27 is a constraint imposed by a scheduler or by user settings in a hostfile or other resource 28 description. Defaults to the job realm. Requires use of the PMIX\_NODE\_INFO attribute 29 30 to avoid ambiguity when retrieving it.

Process-realm information shall include the following data for each process in the job, passed as a

attribute may be omitted if only one application is present in the namespace.

The application number within the job in which the specified process is a member. This

pmix\_data\_array\_t using the PMIX\_PROC\_INFO\_ARRAY attribute:

PMIX HOSTNAME or PMIX NODEID qualifier).

• PMIX LOCAL PEERS "pmix.lpeers" (char\*)

Lowest rank within the specified job on the node (defaults to current node in absence of

Comma-delimited list of ranks that are executing on the local node within the specified

Process rank within the job, starting from zero.

• PMIX\_RANK "pmix.rank" (pmix\_rank\_t)

• PMIX\_APPNUM "pmix.appnum" (uint32\_t)

31 32

33

34

35 36

37

1

2

31

33 34 35

36 37 38

39

• PMIX\_APP\_RANK "pmix.apprank" (pmix\_rank\_t)

Rank of the specified process within its application. This attribute may be omitted if only one application is present in the namespace.

#### • PMIX\_GLOBAL\_RANK "pmix.grank" (pmix\_rank\_t)

Rank of the specified process spanning across all jobs in this session, starting with zero. Note that no ordering of the jobs is implied when computing this value. As jobs can start and end at random times, this is defined as a continually growing number - i.e., it is not dynamically adjusted as individual jobs and processes are started or terminated.

#### • PMIX\_LOCAL\_RANK "pmix.lrank" (uint16\_t)

Rank of the specified process on its node - refers to the numerical location (starting from zero) of the process on its node when counting only those processes from the same job that share the node, ordered by their overall rank within that job.

#### • PMIX\_NODE\_RANK "pmix.nrank" (uint16\_t)

Rank of the specified process on its node spanning all jobs- refers to the numerical location (starting from zero) of the process on its node when counting all processes (regardless of job) that share the node, ordered by their overall rank within the job. The value represents a snapshot in time when the specified process was started on its node and is not dynamically adjusted as processes from other jobs are started or terminated on the node.

#### • PMIX NODEID "pmix.nodeid" (uint32 t)

Node identifier expressed as the node's index (beginning at zero) in an array of nodes within the active session. The value must be unique and directly correlate to the **PMIX HOSTNAME** of the node - i.e., users can interchangeably reference the same location using either the PMIX\_HOSTNAME or corresponding PMIX\_NODEID.

#### • PMIX REINCARNATION "pmix.reinc" (uint32 t)

Number of times this process has been re-instantiated - i.e., a value of zero indicates that the process has never been restarted. 5

#### • PMIX\_SPAWNED "pmix.spawned" (bool)

true if this process resulted from a call to PMIx Spawn. Lack of inclusion (i.e., a return status of **PMIX ERR NOT FOUND**) corresponds to a value of **false** for this attribute.

plus the following information for processes that are local to the server:

#### • PMIX\_LOCALITY\_STRING "pmix.locstr" (char\*)

String describing a process's bound location - referenced using the process's rank. The string is prefixed by the implementation that created it (e.g., "hwloc") followed by a colon. The remainder of the string represents the corresponding locality as expressed by the underlying implementation. The entire string must be passed to PMIx Get relative locality for processing. Note that hosts are only required to provide locality strings for local client processes - thus, a call to PMIx\_Get for the locality string of a process that returns PMIX\_ERR\_NOT\_FOUND indicates that the process is not executing on the same node.

- PMIX\_PROCDIR "pmix.pdir" (char\*)
  - Full path to the subdirectory under **PMIX\_NSDIR** assigned to the specified process.
- PMIX\_PACKAGE\_RANK "pmix.pkgrank" (uint16\_t)

Rank of the specified process on the *package* where this process resides - refers to the numerical location (starting from zero) of the process on its package when counting only those processes from the same job that share the package, ordered by their overall rank within that job. Note that processes that are not bound to PUs within a single specific package cannot have a package rank.

and the following optional information - note that some of this information can be derived from information already provided by other attributes, but it may be included here for ease of retrieval by users:

- PMIX\_HOSTNAME "pmix.hname" (char\*)
  - Name of the host, as returned by the **gethostname** utility or its equivalent.
- PMIX\_CPUSET "pmix.cpuset" (char\*)

A string representation of the PU binding bitmap applied to the process upon launch. The string shall begin with the name of the library that generated it (e.g., "hwloc") followed by a colon and the bitmap string itself.

- PMIX\_CPUSET\_BITMAP "pmix.bitmap" (pmix\_cpuset\_t\*)
  Bitmap applied to the process upon launch.
- PMIX\_DEVICE\_DISTANCES "pmix.dev.dist" (pmix\_data\_array\_t)
   Return an array of pmix\_device\_distance\_t containing the minimum and maximum distances of the given process location to all devices of the specified type on the local node.

Attributes not directly provided by the host environment may be derived by the PMIx server library from other required information and included in the data made available to the server library's clients.

#### Description

Pass job-related information to the PMIx server library for distribution to local client processes.

#### Advice to PMIx server hosts

Host environments are required to execute this operation prior to starting any local application process within the given namespace.

The PMIx server must register all namespaces that will participate in collective operations with local processes. This means that the server must register a namespace even if it will not host any local processes from within that namespace if any local process of another namespace might at some point perform an operation involving one or more processes from the new namespace. This is necessary so that the collective operation can identify the participants and know when it is locally complete.

The caller must also provide the number of local processes that will be launched within this namespace. This is required for the PMIx server library to correctly handle collectives as a collective operation call can occur before all the local processes have been started.

A **NULL** *cbfunc* reference indicates that the function is to be executed as a blocking operation.

#### Advice to users

The number of local processes for any given namespace is generally fixed at the time of application launch. Calls to **PMIx\_Spawn** result in processes launched in their own namespace, not that of their parent. However, it is possible for processes to *migrate* to another node via a call to **PMIx\_Job\_control\_nb**, thus resulting in a change to the number of local processes on both the initial node and the node to which the process moved. It is therefore critical that applications not migrate processes without first ensuring that PMIx-based collective operations are not in progress, and that no such operations be initiated until process migration has completed.

# 16.2.3.1 Namespace registration attributes

The following attributes are defined specifically for use with the

PMIx\_server\_register\_nspace API: PMIX\_REGISTER\_NODATA

"pmix.reg.nodata" (bool)

Registration is for this namespace only, do not copy job data.

The following attributes are used to assemble information according to its data realm (*session*, *job*, *application*, *node*, or *process* as defined in Section 6.1) for registration where ambiguity may exist see 16.2.3.2 for examples of their use.

PMIX\_SESSION\_INFO\_ARRAY "pmix.ssn.arr" (pmix\_data\_array\_t)

Provide an array of pmix\_info\_t containing session-realm information. The

PMIX\_SESSION\_ID attribute is required to be included in the array.

PMIX\_JOB\_INFO\_ARRAY "pmix.job.arr" (pmix\_data\_array\_t)

Provide an array of pmix\_info\_t containing job-realm information. The

PMIX\_SESSION\_ID attribute of the session containing the job is required to be included in
the array whenever the PMIx server library may host multiple sessions (e.g., when executing
with a host RM daemon). As information is registered one job (aka namespace) at a time via
the PMIx\_server\_register\_nspace API, there is no requirement that the array
contain either the PMIX\_NSPACE or PMIX\_JOBID attributes when used in that context
(though either or both of them may be included). At least one of the job identifiers must be
provided in all other contexts where the job being referenced is ambiguous.

PMIX\_APP\_INFO\_ARRAY "pmix.app.arr" (pmix\_data\_array\_t)

Provide an array of pmix\_info\_t containing application-realm information. The

PMIX\_NSPACE or PMIX\_JOBID attributes of the job containing the application, plus its

PMIX\_APPNUM attribute, must to be included in the array when the array is not included as part of a call to PMIx\_server\_register\_nspace - i.e., when the job containing the application is ambiguous. The job identification is otherwise optional.

PMIX\_PROC\_INFO\_ARRAY "pmix.pdata" (pmix\_data\_array\_t)
Provide an array of pmix\_info\_t containing process-realm information. The
PMIX\_RANK and PMIX\_NSPACE attributes, or the PMIX\_PROCID attribute, are required
to be included in the array when the array is not included as part of a call to
PMIx\_server\_register\_nspace - i.e., when the job containing the process is
ambiguous. All three may be included if desired. When the array is included in some
broader structure that identifies the job, then only the PMIX\_RANK or the PMIX\_PROCID
attribute must be included (the others are optional).

PMIX\_NODE\_INFO\_ARRAY "pmix.node.arr" (pmix\_data\_array\_t)

Provide an array of pmix\_info\_t containing node-realm information. At a minimum, either the PMIX\_NODEID or PMIX\_HOSTNAME attribute is required to be included in the array, though both may be included.

Note that these assemblages can be used hierarchically:

• a PMIX\_JOB\_INFO\_ARRAY might contain multiple PMIX\_APP\_INFO\_ARRAY elements, each describing values for a specific application within the job.

- a PMIX\_JOB\_INFO\_ARRAY could contain a PMIX\_NODE\_INFO\_ARRAY for each node hosting processes from that job, each array describing job-level values for that node.
  - a PMIX\_SESSION\_INFO\_ARRAY might contain multiple PMIX\_JOB\_INFO\_ARRAY
    elements, each describing a job executing within the session. Each job array could, in turn,
    contain both application and node arrays, thus providing a complete picture of the active
    operations within the allocation.

#### Advice to PMIx library implementers

PMIx implementations must be capable of properly parsing and storing any hierarchical depth of information arrays. The resulting stored values are must to be accessible via both **PMIx\_Get** and **PMIx\_Query\_info\_nb** APIs, assuming appropriate directives are provided by the caller.

#### 16.2.3.2 Assembling the registration information

The following description is not intended to represent the actual layout of information in a given PMIx library. Instead, it is describes how information provided in the *info* parameter of the **PMIx\_server\_register\_nspace** shall be organized for proper processing by a PMIx server library. The ordering of the various information elements is arbitrary - they are presented in a top-down hierarchical form solely for clarity in reading.

#### Advice to PMIx server hosts -

Creating the *info* array of data requires knowing in advance the number of elements required for the array. This can be difficult to compute and somewhat fragile in practice. One method for resolving the problem is to create a linked list of objects, each containing a single <code>pmix\_info\_t</code> structure. Allocation and manipulation of the list can then be accomplished using existing standard methods. Upon completion, the final *info* array can be allocated based on the number of elements on the list, and then the values in the list object <code>pmix\_info\_t</code> structures transferred to the corresponding array element utilizing the <code>PMIX\_INFO\_XFER</code> macro.

A common building block used in several areas is the construction of a regular expression identifying the nodes involved in that area - e.g., the nodes in a *session* or *job*. PMIx provides several tools to facilitate this operation, beginning by constructing an argy-like array of node names. This array is then passed to the **PMIx\_generate\_regex** function to create a regular expression parseable by the PMIx server library, as shown below:

```
C
```

```
char **nodes = NULL;
char *nodelist:
char *regex;
size_t n;
pmix_status_t rc;
pmix_info_t info;
/* loop over an array of nodes, adding each
 * name to the array */
for (n=0; n < num_nodes; n++) {
    /* filter the nodes to ignore those not included
     * in the target range (session, job, etc.). In
     * this example, all nodes are accepted */
    PMIX ARGV APPEND(&nodes, node[n]->name);
}
/* join into a comma-delimited string */
nodelist = PMIX ARGV JOIN(nodes, ',');
/* release the array */
PMIX_ARGV_FREE (nodes);
/* generate regex */
rc = PMIx_generate_regex(nodelist, &regex);
/* release list */
free(nodelist);
/* pass the regex as the value to the PMIX_NODE_MAP key */
PMIX_INFO_LOAD(&info, PMIX_NODE_MAP, regex, PMIX_REGEX);
/* release the regex */
free (regex);
```

Changing the filter criteria allows the construction of node maps for any level of information. A description of the returned regular expression is provided here.

A similar method is used to construct the map of processes on each node from the namespace being registered. This may be done for each information level of interest (e.g., to identify the process map for the entire *job* or for each *application* in the job) by changing the search criteria. An example is shown below for the case of creating the process map for a *job*:

1

2

3

4

5

6

7 8

9

10

11

12 13

14 15

16

17

18 19 20

21 22 23

242526

27

28 29

30 31

32

33

34 35

36 37

```
1
            char **ndppn;
2
            char rank[30];
3
            char **ppnarray = NULL;
4
            char *ppn;
5
            char *localranks;
6
            char *regex;
7
            size_t n, m;
8
            pmix_status_t rc;
9
            pmix_info_t info;
10
            /* loop over an array of nodes */
11
            for (n=0; n < num nodes; n++) {
12
13
                /* for each node, construct an array of ranks on that node */
14
                ndppn = NULL;
15
                for (m=0; m < node[n] \rightarrow num procs; m++) {
16
                     /* ignore processes that are not part of the target job */
17
                     if (!PMIX_CHECK_NSPACE(targetjob, node[n]->proc[m].nspace)) {
18
                         continue;
19
                     }
                     snprintf(rank, 30, "%d", node[n]->proc[m].rank);
20
21
                     PMIX_ARGV_APPEND(&ndppn, rank);
22
23
                /* convert the array into a comma-delimited string of ranks */
                localranks = PMIX_ARGV_JOIN(ndppn, ',');
24
                /* release the local array */
25
                PMIX ARGV FREE (ndppn);
26
27
                /* add this node's contribution to the overall array */
28
                PMIX_ARGV_APPEND(&ppnarray, localranks);
29
                /* release the local list */
30
                free (localranks);
31
            }
32
33
            /* join into a semicolon-delimited string */
34
            ppn = PMIX_ARGV_JOIN(ppnarray, ';');
35
            /* release the array */
36
37
            PMIX_ARGV_FREE (ppnarray);
38
39
            /* generate ppn regex */
40
            rc = PMIx_generate_ppn(ppn, &regex);
41
42
            /* release list */
```

```
1
2
3
4
```

```
/* pass the regex as the value to the PMIX_PROC_MAP key */
```

free (ppn);

PMIX\_INFO\_LOAD(&info, PMIX\_PROC\_MAP, regex, PMIX\_REGEX);
/\* release the regex \*/
free(regex);

C

Note that the PMIX\_NODE\_MAP and PMIX\_PROC\_MAP attributes are linked in that the order of entries in the process map must match the ordering of nodes in the node map - i.e., there is no provision in the PMIx process map regular expression generator/parser pair supporting an out-of-order node or a node that has no corresponding process map entry (e.g., a node with no processes on it). Armed with these tools, the registration *info* array can be constructed as follows:

Session-level information includes all session-specific values. In many cases, only two values
 (PMIX\_SESSION\_ID and PMIX\_UNIV\_SIZE) are included in the registration array. Since
 both of these values are session-specific, they can be specified independently - i.e., in their own
 pmix\_info\_t elements of the *info* array. Alternatively, they can be provided as a
 pmix\_data\_array\_t array of pmix\_info\_t using the PMIX\_SESSION\_INFO\_ARRAY
 attribute and identifed by including the PMIX\_SESSION\_ID attribute in the array - this is
 required in cases where non-specific attributes (e.g., PMIX\_NUM\_NODES or
 PMIX\_NODE\_MAP) are passed to describe aspects of the session. Note that the node map can
 include nodes not used by the job being registered as no corresponding process map is specified.

The *info* array at this point might look like (where the labels identify the corresponding attribute - e.g., "Session ID" corresponds to the **PMIX SESSION ID** attribute):




Figure 16.1.: Session-level information elements

Job-level information includes all job-specific values such as PMIX\_JOB\_SIZE,
PMIX\_JOB\_NUM\_APPS, and PMIX\_JOBID. Since each invocation of
PMIx\_server\_register\_nspace describes a single job, job-specific values can be
specified independently - i.e., in their own pmix\_info\_t elements of the info array.
Alternatively, they can be provided as a pmix\_data\_array\_t array of pmix\_info\_t
identified by the PMIX\_JOB\_INFO\_ARRAY attribute - this is required in cases where
non-specific attributes (e.g., PMIX\_NODE\_MAP) are passed to describe aspects of the job. Note

 that since the invocation only involves a single namespace, there is no need to include the **PMIX NSPACE** attribute in the array.

Upon conclusion of this step, the *info* array might look like:




Figure 16.2.: Job-level information elements

Note that in this example, PMIX\_NUM\_NODES is not required as that information is contained in the PMIX\_NODE\_MAP attribute. Similarly, PMIX\_JOB\_SIZE is not technically required as that information is contained in the PMIX\_PROC\_MAP when combined with the corresponding node map - however, there is no issue with including the job size as a separate entry.

The example also illustrates the hierarchical use of the PMIX\_NODE\_INFO\_ARRAY attribute. In this case, we have chosen to pass several job-related values for each node - since those values are non-unique across the job, they must be passed in a node-info container. Note that the choice of what information to pass into the PMIx server library versus what information to derive from other values at time of request is left to the host environment. PMIx implementors in turn may, if they choose, pre-parse registration data to create expanded views (thus enabling faster response to requests at the expense of memory footprint) or to compress views into tighter representations (thus trading minimized footprint for longer response times).

Application-level information includes all application-specific values such as PMIX APP SIZE

and PMIX\_APPLDR. If the *job* contains only a single *application*, then the application-specific values can be specified independently - i.e., in their own pmix\_info\_t elements of the *info* array - or as a pmix\_data\_array\_t array of pmix\_info\_t using the PMIX\_APP\_INFO\_ARRAY attribute and identified by including the PMIX\_APPNUM attribute in the array. Use of the array format is must in cases where non-specific attributes (e.g., PMIX\_NODE\_MAP) are passed to describe aspects of the application.

However, in the case of a job consisting of multiple applications, all application-specific values for each application must be provided using the **PMIX\_APP\_INFO\_ARRAY** format, each identified by its **PMIX\_APPNUM** value.

Upon conclusion of this step, the *info* array might look like that shown in 16.3, assuming there are two applications in the job being registered:




Figure 16.3.: Application-level information elements

- Process-level information includes an entry for each process in the job being registered, each
  entry marked with the PMIX\_PROC\_INFO\_ARRAY attribute. The rank of the process must be
  the first entry in the array this provides efficiency when storing the data. Upon conclusion of
  this step, the info array might look like the diagram in 16.4:
- For purposes of this example, node-level information only includes values describing the local node i.e., it does not include information about other nodes in the job or session. In many cases, the values included in this level are unique to it and can be specified independently i.e., in their own pmix\_info\_t elements of the *info* array. Alternatively, they can be provided as a




Figure 16.4.: Process-level information elements

pmix\_data\_array\_t array of pmix\_info\_t using the PMIX\_NODE\_INFO\_ARRAY
attribute - this is required in cases where non-specific attributes are passed to describe aspects of
the node, or where values for multiple nodes are being provided.

The node-level information requires two elements that must be constructed in a manner similar to that used for the node map. The **PMIX\_LOCAL\_PEERS** value is computed based on the processes on the local node, filtered to select those from the job being registered, as shown below using the tools provided by PMIx:

```
char **ndppn = NULL;
char rank[30];
char *localranks;
size t m;
pmix_info_t info;
for (m=0; m < mynode->num procs; m++) {
    /* ignore processes that are not part of the target job */
    if (!PMIX_CHECK_NSPACE(targetjob, mynode->proc[m].nspace)) {
        continue;
    snprintf(rank, 30, "%d", mynode->proc[m].rank);
    PMIX ARGV APPEND (&ndppn, rank);
/* convert the array into a comma-delimited string of ranks */
localranks = PMIX ARGV JOIN(ndppn, ',');
/* release the local array */
PMIX ARGV FREE (ndppn);
/* pass the string as the value to the PMIX_LOCAL_PEERS key */
PMIX_INFO_LOAD(&info, PMIX_LOCAL_PEERS, localranks, PMIX_STRING);
/* release the list */
free (localranks);
```

The PMIX\_LOCAL\_CPUSETS value is constructed in a similar manner. In the provided example, it is assumed that an Hardware Locality (HWLOC) cpuset representation (a comma-delimited string of processor IDs) of the processors assigned to each process has previously been generated and stored on the process description. Thus, the value can be constructed as shown below:

```
char **ndcpus = NULL;
char *localcpus;
size_t m;
pmix_info_t info;

for (m=0; m < mynode->num_procs; m++) {
    /* ignore processes that are not part of the target job */
    if (!PMIX_CHECK_NSPACE(targetjob,mynode->proc[m].nspace)) {
        continue;
    }
}
```

```
PMIX_ARGV_APPEND(&ndcpus, mynode->proc[m].cpuset);

/* convert the array into a colon-delimited string */
localcpus = PMIX_ARGV_JOIN(ndcpus, ':');
/* release the local array */
PMIX_ARGV_FREE(ndcpus);

/* pass the string as the value to the PMIX_LOCAL_CPUSETS key */
PMIX_INFO_LOAD(&info, PMIX_LOCAL_CPUSETS, localcpus, PMIX_STRING);

/* release the list */
free(localcpus);
```

Note that for efficiency, these two values can be computed at the same time.

The final *info* array might therefore look like the diagram in 16.5:




Figure 16.5.: Final information array

#### 16.2.4 PMIx\_server\_deregister\_nspace Summarv 3 Deregister a namespace. Format <sup>4</sup> *PMIx v1.0* void PMIx\_server\_deregister\_nspace(const pmix\_nspace\_t nspace, 5 6 pmix op cbfunc t cbfunc, void \*cbdata); 7 IN nspace Namespace (string) 8 IN 9 cbfunc Callback function pmix\_op\_cbfunc\_t. A NULL function reference indicates that the 10 11 function is to be executed as a blocking operation. (function reference) 12 IN cbdata Data to be passed to the callback function (memory reference) 13 14 Description 15 Deregister the specified *nspace* and purge all objects relating to it, including any client information from that namespace. This is intended to support persistent PMIx servers by providing an 16 17 opportunity for the host RM to tell the PMIx server library to release all memory for a completed job. Note that the library must not invoke the callback function prior to returning from the API, and 18 that a **NULL** *cbfunc* reference indicates that the function is to be executed as a blocking operation. 19 16.2.5 PMIx server register resources Summary 21 22 Register non-namespace related information with the local PMIx server library. 23 *PMIx v4.0* Format 24 pmix status t PMIx\_server\_register\_resources(pmix\_info\_t info[], size\_t ninfo, 25 26 pmix\_op\_cbfunc\_t cbfunc, 27 void \*cbdata); IN 28 29 Array of info structures (array of handles) IN ninfo 30 31 Number of elements in the *info* array (integer)

	IN	cbfunc
--	----	--------

 Callback function **pmix\_op\_cbfunc\_t**. A **NULL** function reference indicates that the function is to be executed as a blocking operation (function reference)

#### IN cbdata

Data to be passed to the callback function (memory reference)

# Description

Pass information about resources not associated with a given namespace to the PMIx server library for distribution to local client processes. This includes information on fabric devices, GPUs, and other resources. All information provided through this API shall be made available to each job as part of its job-level information. Duplicate information provided with the PMIx\_server\_register\_nspace API shall override any information provided by this function for that namespace, but only for that specific namespace.

Returns **PMIX\_SUCCESS** or a negative value indicating the error.

# Advice to PMIx server hosts

Note that information passed in this manner could also have been included in a call to **PMIx\_server\_register\_nspace** - e.g., as part of a **PMIX\_NODE\_INFO\_ARRAY** array. This API is provided as a logical alternative for code clarity, especially where multiple jobs may be supported by a single PMIx server library instance, to avoid multiple registration of static resource information.

A **NULL** *cbfunc* reference indicates that the function is to be executed as a blocking operation.

# 16.2.6 PMIx\_server\_deregister\_resources

# Summary

Remove specified non-namespace related information from the local PMIx server library.

IN info

6 7

8

9

10

11 12

13 14

15

16

17

18 19

20

21

22 23

24

25

26

27

28

29

30

32 33 Array of info structures (array of handles)

IN ninfo

Number of elements in the *info* array (integer)

IN cbfunc

Callback function **pmix\_op\_cbfunc\_t**. A **NULL** function reference indicates that the function is to be executed as a blocking operation (function reference)

IN cbdata

Data to be passed to the callback function (memory reference)

#### **Description**

Remove information about resources not associated with a given namespace from the PMIx server library. Only the *key* fields of the provided *info* array shall be used for the operation - the associated values shall be ignored except where they serve as qualifiers to the request. For example, to remove a specific fabric device from a given node, the *info* array might include a

**PMIX\_NODE\_INFO\_ARRAY** containing the **PMIX\_NODEID** or **PMIX\_HOSTNAME** identifying the node hosting the device, and the **PMIX\_FABRIC\_DEVICE\_NAME** specifying the device to be removed. Alternatively, the device could be removed using only the **PMIX\_DEVICE\_ID** as this is unique across the overall system.

Returns **PMIX\_SUCCESS** or a negative value indicating the error.

# Advice to PMIx server hosts

As information not related to namespaces is considered *static*, there is no requirement that the host environment deregister resources prior to finalizing the PMIx server library. The server library shall properly cleanup as part of its normal finalize operations. Deregistration of resources is only required, therefore, when the host environment determines that client processes should no longer have access to that information.

A **NULL** *cbfunc* reference indicates that the function is to be executed as a blocking operation.

# 16.2.7 PMIx\_server\_register\_client

# Summary

Register a client process with the PMIx server library.

IN cbfunc

1

2

3

4

5

6

7

8

9

10

11

12

13

14 15

16

17

18

19 20

21

22 23

24

25

26

27

28

29 30

31

32

33 34

35

Callback function **pmix\_op\_cbfunc\_t**. A **NULL** function reference indicates that the function is to be executed as a blocking operation (function reference)

IN cbdata

Data to be passed to the callback function (memory reference)

A successful return indicates that the request is being processed by the host environment and the result will be returned in the provided *cbfunc*. Note that the library must not invoke the callback function prior to returning from the API. In all other cases, the *cbfunc* will *not* be called.

Returns PMIX\_SUCCESS or one of the following error codes when the condition described occurs:

• PMIX\_OPERATION\_SUCCEEDED, indicating that the request was immediately processed and returned *success* - the *cbfunc* will not be called

If none of the above return codes are appropriate, then an implementation must return either a general PMIx error code or an implementation defined error code as described in Section 3.1.1.

# Description

Register a client process with the PMIx server library.

The host server can also, if it desires, provide an object it wishes to be returned when a server function is called that relates to a specific process. For example, the host server may have an object that tracks the specific client. Passing the object to the library allows the library to provide that object to the host server during subsequent calls related to that client, such as a pmix\_server\_client\_connected2\_fn\_t function. This allows the host server to access the object without performing a lookup based on the client's namespace and rank.

#### Advice to PMIx server hosts

Host environments are required to execute this operation prior to starting the client process. The expected user ID and group ID of the child process allows the server library to properly authenticate clients as they connect by requiring the two values to match. Accordingly, the detected user and group ID's of the connecting process are not included in the pmix server client connected2 fn t server module function.

# - Advice to PMIx library implementers

For security purposes, the PMIx server library should check the user and group ID's of a connecting process against those provided for the declared client process identifier via the PMIx\_server\_register\_client prior to completing the connection.

# 16.2.8 PMIx\_server\_deregister\_client

#### Summary

Deregister a client and purge all data relating to it.

# PMIx v1 0 Format

# IIIat

13 void

1

2

4

5

6

7

8

10 11

14

15

16

17 18

19

20

21

22

23

24

25 26

27

28

PMIx\_server\_deregister\_client(const pmix\_proc\_t \*proc,

pmix\_op\_cbfunc\_t cbfunc, void \*cbdata);

IN proc

pmix proc t structure (handle)

IN cbfunc

Callback function **pmix\_op\_cbfunc\_t**. A **NULL** function reference indicates that the function is to be executed as a blocking operation (function reference)

IN cbdata

Data to be passed to the callback function (memory reference)

# Description

The PMIx\_server\_deregister\_nspace API will delete all client information for that namespace. The PMIx server library will automatically perform that operation upon disconnect of all local clients. This API is therefore intended primarily for use in exception cases, but can be called in non-exception cases if desired. Note that the library must not invoke the callback function prior to returning from the API.

# 16.2.9 PMIx\_server\_setup\_fork

#### Summary

2

5

6

7

8

9

10

11

12

13

14

15

16 17

18

19

20

22

23

Setup the environment of a child process to be forked by the host.

#### Format

IN proc

pmix\_proc\_t structure (handle)

IN env

Environment array (array of strings)

Returns **PMIX\_SUCCESS** or a negative value indicating the error.

#### Description

Setup the environment of a child process to be forked by the host so it can correctly interact with the PMIx server.

The PMIx client needs some setup information so it can properly connect back to the server. This function will set appropriate environmental variables for this purpose, and will also provide any environmental variables that were specified in the launch command (e.g., via PMIx\_Spawn) plus other values (e.g., variables required to properly initialize the client's fabric library).

# Advice to PMIx server hosts -

Host environments are required to execute this operation prior to starting the client process.

# 16.2.10 PMIx\_server\_dmodex\_request

# Summary

Define a function by which the host server can request modex data from the local PMIx server.

IN proc

pmix\_proc\_t structure (handle)

IN cbfunc

Callback function pmix\_dmodex\_response\_fn\_t (function reference)

IN cbdata

Data to be passed to the callback function (memory reference)

A successful return indicates that the request is being processed by the host environment and the result will be returned in the provided *cbfunc*. Note that the library must not invoke the callback function prior to returning from the API. In all other cases, the *cbfunc* will *not* be called.

# **Description**

Define a function by which the host server can request modex data from the local PMIx server. Traditional wireup procedures revolve around the per-process posting of data (e.g., location and endpoint information) via the PMIx\_Put and PMIx\_Commit functions followed by a PMIx\_Fence barrier that globally exchanges the posted information. However, the barrier operation represents a significant time impact at large scale.

PMIx supports an alternative wireup method known as *Direct Modex* that replaces the barrier-based exchange of all process-posted information with on-demand fetch of a peer's data. In place of the barrier operation, data posted by each process is cached on the local PMIx server. When a process requests the information posted by a particular peer, it first checks the local cache to see if the data is already available. If not, then the request is passed to the local PMIx server, which subsequently requests that its RM host request the data from the RM daemon on the node where the specified peer process is located. Upon receiving the request, the RM daemon passes the request into its PMIx server library using the PMIx\_server\_dmodex\_request function, receiving the response in the provided *cbfunc* once the indicated process has posted its information. The RM daemon then returns the data to the requesting daemon, who subsequently passes the data to its PMIx server library for transfer to the requesting client.

# Advice to users

While direct modex allows for faster launch times by eliminating the barrier operation, per-peer retrieval of posted information is less efficient. Optimizations can be implemented - e.g., by returning posted information from all processes on a node upon first request - but in general direct modex remains best suited for sparsely connected applications.

# 16.2.10.1 Server Direct Modex Response Callback Function

The PMIx\_server\_dmodex\_request callback function.

#### Summary

Provide a function by which the local PMIx server library can return connection and other data posted by local application processes to the host resource manager.

# PMIx v1.0 Format

2

3

5

8

9

10

11 12

13

14

15 16

17

18

19

20

21 22

23

25

26 27

IN status

Returned status of the request (pmix\_status\_t)

IN data

Pointer to a data "blob" containing the requested information (handle)

IN sz

Number of bytes in the *data* blob (integer)

IN cbdata

Data passed into the initial call to **PMIx** server\_dmodex\_request (memory reference)

# Description

Define a function to be called by the PMIx server library for return of information posted by a local application process (via **PMIx\_Put** with subsequent **PMIx\_Commit**) in response to a request from the host RM. The returned *data* blob is owned by the PMIx server library and will be free'd upon return from the function.

# 24 16.2.11 PMIx\_server\_setup\_application

#### Summary

Provide a function by which a launcher can request application-specific setup data prior to launch of a *job*.

1	Format C	
2	pmix_status_t	
3	PMIx_server_setup_application(const pmix_nspace_t nspace,	
4	pmix_info_t info[], size_t ninfo,	
5	pmix_setup_application_cbfunc_t cbfunc,	
6	<pre>void *cbdata);</pre>	
•	C	
7	IN nspace	
8	namespace (string)	
9	IN info	
0	Array of info structures (array of handles)	
1	IN ninfo	
2	Number of elements in the <i>info</i> array (integer)	
3	IN cbfunc	
4	Callback function <pre>pmix_setup_application_cbfunc_t</pre> (function reference)	
5	IN cbdata	
6	Data to be passed to the <i>cbfunc</i> callback function (memory reference)	
7 8 9	A successful return indicates that the request is being processed by the host environment and the result will be returned in the provided <i>cbfunc</i> . Note that the library must not invoke the callback function prior to returning from the API. In all other cases, the <i>cbfunc</i> will <i>not</i> be called.	
	→	
20	PMIx libraries that support this operation are required to support the following:	
21 22	PMIX_SETUP_APP_ENVARS "pmix.setup.env" (bool)  Harvest and include relevant environmental variables.	
23 24	<pre>PMIX_SETUP_APP_NONENVARS ""pmix.setup.nenv" (bool) Include all relevant data other than environmental variables.</pre>	
25 26	<pre>PMIX_SETUP_APP_ALL "pmix.setup.all" (bool) Include all relevant data.</pre>	
27 28 29 30	PMIX_ALLOC_FABRIC "pmix.alloc.net" (array)  Array of pmix_info_t describing requested fabric resources. This must include at least:  PMIX_ALLOC_FABRIC_ID, PMIX_ALLOC_FABRIC_TYPE, and  PMIX_ALLOC_FABRIC_ENDPTS, plus whatever other descriptors are desired.	
1	<pre>PMIX_ALLOC_FABRIC_ID "pmix.alloc.netid" (char*)</pre>	

1 2 3 4 5 6 7 8 9 10 11 12 13	The key to be used when accessing this requested fabric allocation. The fabric allocation will be returned/stored as a <a href="mix_data_array_t">pmix_info_t</a> whose first element is composed of this key and the allocated resource description. The type of the included value depends upon the fabric support. For example, a TCP allocation might consist of a comma-delimited string of socket ranges such as "32000-32100, 33005, 38123-38146". Additional array entries will consist of any provided resource request directives, along with their assigned values. Examples include:  PMIX_ALLOC_FABRIC_TYPE - the type of resources provided;  PMIX_ALLOC_FABRIC_PLANE - if applicable, what plane the resources were assigned from; PMIX_ALLOC_FABRIC_QOS - the assigned QoS; PMIX_ALLOC_BANDWIDTH - the allocated bandwidth; PMIX_ALLOC_FABRIC_SEC_KEY - a security key for the requested fabric allocation. NOTE: the array contents may differ from those requested, especially if PMIX_INFO_REQD was not set in the request.
14 15	<pre>PMIX_ALLOC_FABRIC_SEC_KEY "pmix.alloc.nsec" (pmix_byte_object_t) Request that the allocation include a fabric security key for the spawned job.</pre>
16 17	<pre>PMIX_ALLOC_FABRIC_TYPE "pmix.alloc.nettype" (char*) Type of desired transport (e.g., "tcp", "udp") being requested in an allocation request.</pre>
18 19	<pre>PMIX_ALLOC_FABRIC_PLANE "pmix.alloc.netplane" (char*) ID string for the fabric plane to be used for the requested allocation.</pre>
20 21	<pre>PMIX_ALLOC_FABRIC_ENDPTS "pmix.alloc.endpts" (size_t) Number of endpoints to allocate per process in the job.</pre>
22 23	<pre>PMIX_ALLOC_FABRIC_ENDPTS_NODE "pmix.alloc.endpts.nd" (size_t) Number of endpoints to allocate per node for the job.</pre>
24 25 26	PMIX_PROC_MAP "pmix.pmap" (char*)  Regular expression describing processes on each node in the specified realm - see 16.2.3.2 for an explanation of its generation. Defaults to the <i>job</i> realm.
27 28 29	PMIX_NODE_MAP "pmix.nmap" (char*)  Regular expression of nodes currently hosting processes in the specified realm - see 16.2.3.2 for an explanation of its generation. Defaults to the <i>job</i> realm.
	Optional Attributes
30	PMIx libraries that support this operation may support the following:
31 32 33	PMIX_ALLOC_BANDWIDTH "pmix.alloc.bw" (float)  Fabric bandwidth (in Megabits[base2]/sec) for the job being requested in an allocation request.
34 35	<pre>PMIX_ALLOC_FABRIC_QOS "pmix.alloc.netqos" (char*) Fabric quality of service level for the job being requested in an allocation request.</pre>

#### 1 PMIX\_SESSION\_INFO "pmix.ssn.info" (bool) 2 Return information regarding the session realm of the target process. In this context, 3 indicates that the information provided in the PMIX NODE MAP is for the entire session and 4 not just the indicated namespace. Thus, subsequent calls to this API may omit node-level 5 information - e.g., the library may not need to include information on the devices on each 6 node in a subsequent call. 7 The following optional attributes may be provided by the host environment to identify the 8 programming model (as specified by the user) being executed within the application. The PMIx 9 server library may utilize this information to harvest/forward model-specific environmental variables, record the programming model associated with the application, etc. 10 • PMIX PROGRAMMING MODEL "pmix.pqm.model" (char\*) 11 12 Programming model being initialized (e.g., "MPI" or "OpenMP"). • PMIX MODEL LIBRARY NAME "pmix.mdl.name" (char\*) 13 Programming model implementation ID (e.g., "OpenMPI" or "MPICH"). 14

# **Description**

15

16

17 18

19

20 21

22

23

24

25

26

27

28 29

30

31

32 33 Provide a function by which the RM can request application-specific setup data (e.g., environmental variables, fabric configuration and security credentials) from supporting PMIx server library subsystems prior to initiating launch of a job.

• PMIX MODEL LIBRARY VERSION "pmix.mld.vrs" (char\*)

Programming model version string (e.g., "2.1.1").

This is defined as a non-blocking operation in case contributing subsystems need to perform some potentially time consuming action (e.g., query a remote service) before responding. The returned data must be distributed by the host environment and subsequently delivered to the local PMIx server on each node where application processes will execute, prior to initiating execution of those processes.

# Advice to PMIx server hosts -

Host environments are required to execute this operation prior to launching a job. In addition to supported directives, the *info* array must include a description of the *job* using the **PMIX\_NODE\_MAP** and **PMIX\_PROC\_MAP** attributes.

Note that the function can be called on a per-application basis if the **PMIX\_PROC\_MAP** and **PMIX\_NODE\_MAP** are provided only for the corresponding application (as opposed to the entire job) each time.

# Advice to PMIx library implementers —

Support for harvesting of environmental variables and providing of local configuration information by the PMIx implementation is optional.

# 16.2.11.1 Server Setup Application Callback Function

The **PMIx\_server\_setup\_application** callback function.

#### Summary

Provide a function by which the resource manager can receive application-specific environmental variables and other setup data prior to launch of an application.

PMIx v2.0

3

5

7

8

9

10

11

12

13

14

15 16

17

18

19 20

21

22

23

24

25

26 27

28

29

31

32

33

34 35

36

```
Format
```

```
IN status
```

returned status of the request (pmix\_status\_t)

IN info

Array of info structures (array of handles)

IN ninfo

Number of elements in the *info* array (integer)

IN provided cbdata

Data originally passed to call to **PMIx\_server\_setup\_application** (memory reference)

IN cbfunc

pmix\_op\_cbfunc\_t function to be called when processing completed (function reference)

IN cbdata

Data to be passed to the *cbfunc* callback function (memory reference)

#### Description

Define a function to be called by the PMIx server library for return of application-specific setup data in response to a request from the host RM. The returned *info* array is owned by the PMIx server library and will be free'd when the provided *cbfunc* is called.

# 16.2.11.2 Server Setup Application Attributes

30 *PMIx v3.0* Attributes specifically defined for controlling contents of application setup data.

```
PMIX_SETUP_APP_ENVARS "pmix.setup.env" (bool)
```

Harvest and include relevant environmental variables.

PMIX\_SETUP\_APP\_NONENVARS ""pmix.setup.nenv" (bool)

Include all relevant data other than environmental variables.

PMIX SETUP APP ALL "pmix.setup.all" (bool)

Include all relevant data.

# 16.2.12 PMIx\_Register\_attributes

#### Summary 3 Register host environment attribute support for a function. Format <sup>4</sup> *PMIx v4.0* 5 pmix\_status\_t 6 PMIx Register attributes (char \*function, 7 pmix\_regattr\_t attrs[], 8 size\_t nattrs); IN function 9 String name of function (string) 10 11 IN attrs 12 Array of **pmix regattr** t describing the supported attributes (handle) IN nattrs 13 14 Number of elements in *attrs* (**size t**) 15 Returns **PMIX SUCCESS** or a negative value indicating the error. **Description** 16 17 The PMIx\_Register\_attributes function is used by the host environment to register with its PMIx server library the attributes it supports for each pmix\_server\_module\_t function. 18 The function is the string name of the server module function (e.g., "register\_events", 19 "validate\_credential", or "allocate") whose attributes are being registered. See the 20 **pmix regattr** t entry for a description of the *attrs* array elements. 21 22 Note that the host environment can also query the library (using the PMIx\_Query\_info\_nb API) for its attribute support both at the server, client, and tool levels once the host has executed 23 **PMIx** server init since the server will internally register those values. 24 Advice to PMIx server hosts -25 Host environments are strongly encouraged to register all supported attributes immediately after initializing the library to ensure that user requests are correctly serviced. 26

# Advice to PMIx library implementers -

PMIx implementations are *required* to register all internally supported attributes for each API during initialization of the library (i.e., when the process calls their respective PMIx init function). Specifically, the implementation *must not* register supported attributes upon first call to a given API as this would prevent users from discovering supported attributes prior to first use of an API.

It is the implementation's responsibility to associate registered attributes for a given **pmix\_server\_module\_t** function with their corresponding user-facing API. Supported attributes *must* be reported to users in terms of their support for user-facing APIs, broken down by the level (see Section 5.4.6) at which the attribute is supported.

Note that attributes can/will be registered on an API for each level. It is *required* that the implementation support user queries for supported attributes on a per-level basis. Duplicate registrations at the *same* level for a function *shall* return an error - however, duplicate registrations at *different* levels *shall* be independently tracked.

# 16.2.12.1 Attribute registration constants

1

2

3

5

6 7

8

9

10

11 12

14

15

16

17 18

27

28 29

30 31 PMIx v4.0

Constants supporting attribute registration.

**PMIX\_ERR\_REPEAT\_ATTR\_REGISTRATION** The attributes for an identical function have already been registered at the specified level (host, server, or client).

# 16.2.12.2 Attribute registration structure

The **pmix\_regattr\_t** structure is used to register attribute support for a PMIx function.

```
19
            typedef struct pmix_regattr {
20
                 char *name;
                 pmix_key_t *string;
21
22
                pmix_data_type_t type;
                pmix_info_t *info;
23
24
                 size_t ninfo;
25
                 char **description;
26
             } pmix regattr t;;
```

Note that in this structure:

- the *name* is the actual name of the attribute e.g., "PMIX\_MAX\_PROCS"
- the *string* is the literal string value of the attribute e.g., "pmix.max.size" for the **PMIX MAX PROCS** attribute
- type must be a PMIx data type identifying the type of data associated with this attribute.

- the info array contains machine-usable information regarding the range of accepted values. This may include entries for PMIX\_MIN\_VALUE, PMIX\_MAX\_VALUE, PMIX\_ENUM\_VALUE, or a combination of them. For example, an attribute that supports all positive integers might delineate it by including a pmix\_info\_t with a key of PMIX\_MIN\_VALUE, type of PMIX\_INT, and value of zero. The lack of an entry for PMIX\_MAX\_VALUE indicates that there is no ceiling to the range of accepted values.
- *ninfo* indicates the number of elements in the *info* array
- The description field consists of a NULL-terminated array of strings describing the attribute, optionally including a human-readable description of the range of accepted values e.g., "ALL POSITIVE INTEGERS", or a comma-delimited list of enum value names. No correlation between the number of entries in the description and the number of elements in the info array is implied or required.

The attribute *name* and *string* fields must be **NULL**-terminated strings composed of standard alphanumeric values supported by common utilities such as *strcmp*.

Although not strictly required, both PMIx library implementers and host environments are strongly encouraged to provide both human-readable and machine-parsable descriptions of supported attributes when registering them.

# 16.2.12.3 Attribute registration structure descriptive attributes

The following attributes relate to the nature of the values being reported in the **pmix\_regattr\_t** structures.

```
PMIX MAX VALUE "pmix.descr.maxval" (varies)
```

Used in **pmix\_regattr\_t** to describe the maximum valid value for the associated attribute.

```
PMIX_MIN_VALUE "pmix.descr.minval" (varies)
```

Used in **pmix\_regattr\_t** to describe the minimum valid value for the associated attribute.

```
PMIX ENUM VALUE "pmix.descr.enum" (char*)
```

Used in **pmix\_regattr\_t** to describe accepted values for the associated attribute. Numerical values shall be presented in a form convertible to the attribute's declared data type. Named values (i.e., values defined by constant names via a typical C-language enum declaration) must be provided as their numerical equivalent.

# 16.2.12.4 Attribute registration structure support macros

The following macros are provided to support the **pmix\_regattr\_t** structure.

# Initialize the regattr structure

Initialize the pmix regattr t fields

PMIx v4.0

		· ·
1		PMIX_REGATTR_CONSTRUCT (m)
		· ·
2		IN m
3		Pointer to the structure to be initialized (pointer to pmix_regattr_t)
1		Destruct the regattr structure
4		
5		Destruct the pmix_regattr_t fields, releasing all strings.
	<i>PMIx v4.0</i>	C
_		DATA DEGLETO DEGENERACIO
6		PMIX_REGATTR_DESTRUCT (m)
		C
7		IN m
8		Pointer to the structure to be destructed (pointer to pmix_regattr_t)
9		Create a regattr array
10		Allocate and initialize an array of <b>pmix_regattr_t</b> structures.
	PMIx v4.0	
	1 11111 14.0	
11		PMIX_REGATTR_CREATE (m, n)
		C
12		INOUT m
13		Address where the pointer to the array of <b>pmix_regattr_t</b> structures shall be stored
14		(handle)
15		IN n
16		Number of structures to be allocated (size_t)
17		Free a regattr array
18		Release an array of pmix_regattr_t structures.
	PMIx v4.0	release an array of participants.
	1 W11x V4.0	
19		PMIX_REGATTR_FREE(m, n)
20		INOUT m
20		
21	•	Pointer to the array of pmix_regattr_t structures (handle)
22		IN n
23		Number of structures in the array (size_t)

```
Load a regattr structure
 1
 2
               Load values into a pmix regattr t structure. The macro can be called multiple times to add as
               many strings as desired to the same structure by passing the same address and a NULL key to the
 3
 4
               macro. Note that the t type value must be given each time.
 5
               PMIX REGATTR LOAD (a, n, k, t, ni, v)
               IN
 6
 7
                    Pointer to the structure to be loaded (pointer to pmix_proc_t)
               IN
 8
 9
                    String name of the attribute (string)
10
               IN
11
                    Key value to be loaded (pmix_key_t)
12
               IN
                    Type of data associated with the provided key (pmix_data_type_t)
13
               IN
14
15
                    Number of pmix_info_t elements to be allocated in info(size_t)
               IN
16
                    One-line description to be loaded (more can be added separately) (string)
17
               Transfer a regattr to another regattr
18
               Non-destructively transfer the contents of a pmix regattr t structure to another one.
19
  PMIx v4.0
20
               PMIX REGATTR XFER (m, n)
               INOUT m
21
22
                    Pointer to the destination pmix regattr t structure (handle)
               IN
23
24
                    Pointer to the source pmix regattr t structure (handle)
    16.2.13
                 PMIx_server_setup_local_support
               Summary
26
27
               Provide a function by which the local PMIx server can perform any application-specific operations
               prior to spawning local clients of a given application.
28
```

1	Format C
2	pmix_status_t
3	PMIx_server_setup_local_support(const pmix_nspace_t nspace,
4	<pre>pmix_info_t info[], size_t ninfo,</pre>
5	pmix_op_cbfunc_t cbfunc,
6	void *cbdata);
	C
7	IN nspace
8	Namespace (string)
9	IN info
10	Array of info structures (array of handles)
11	IN ninfo
12	Number of elements in the <i>info</i> array (size_t)
13	IN cbfunc
14	Callback function pmix_op_cbfunc_t. A NULL function reference indicates that the
15	function is to be executed as a blocking operation (function reference)
16	IN cbdata
17	Data to be passed to the callback function (memory reference)
18 19 20	A successful return indicates that the request is being processed by the host environment and the result will be returned in the provided <i>cbfunc</i> . Note that the library must not invoke the callback function prior to returning from the API. In all other cases, the <i>cbfunc</i> will <i>not</i> be called.
21	Returns PMIX_SUCCESS or one of the following error codes when the condition described occurs:
22 23	• PMIX_OPERATION_SUCCEEDED, indicating that the request was immediately processed and returned <i>success</i> - the <i>cbfunc</i> will not be called
24	If none of the above return codes are appropriate, then an implementation must return either a
25	general PMIx error code or an implementation defined error code as described in Section 3.1.1.
26	Description
27	Provide a function by which the local PMIx server can perform any application-specific operations
28	prior to spawning local clients of a given application. For example, a fabric library might need to
29	setup the local driver for "instant on" addressing. The data provided in the info array is the data
30	returned to the host RM by the callback function executed as a result of a call to
31	PMIx_server_setup_application.
	Advice to PMIx server hosts
32	Host environments are required to execute this operation prior to starting any local application
33	processes from the specified namespace if information was obtained from a call to

PMIx\_server\_setup\_application.

Host environments must register the *nspace* using **PMIx\_server\_register\_nspace** prior to calling this API to ensure that all namespace-related information required to support this function is available to the library. This eliminates the need to include any of the registration information in the *info* array passed to this API.

# 16.2.14 PMIx\_server\_IOF\_deliver

#### Summary

1

2

3 4

6 7

8

Provide a function by which the host environment can pass forwarded Input/Output (IO) to the PMIx server library for distribution to its clients.

```
9 PMIx v3.0
               Format
10
               pmix status t
               PMIx_server_IOF_deliver(const pmix_proc_t *source,
11
12
                                              pmix iof channel t channel,
                                              const pmix_byte_object_t *bo,
13
14
                                              const pmix_info_t info[], size_t ninfo,
                                              pmix op cbfunc t cbfunc, void *cbdata);
15
                                                         C
16
               IN
                    source
                   Pointer to pmix proc t identifying source of the IO (handle)
17
               IN
                    channel
18
                   IO channel of the data (pmix_iof_channel_t)
19
20
               IN
                   Pointer to pmix_byte_object_t containing the payload to be delivered (handle)
21
               IN
                   info
22
23
                   Array of pmix_info_t metadata describing the data (array of handles)
24
               IN
                   Number of elements in the info array (size t)
25
               IN
                   cbfunc
26
                   Callback function pmix_op_cbfunc_t. A NULL function reference indicates that the
27
                   function is to be executed as a blocking operation (function reference)
28
               IN
29
                    cbdata
                   Data to be passed to the callback function (memory reference)
30
               A successful return indicates that the request is being processed by the host environment and the
31
32
```

result will be returned in the provided cbfunc. Note that the library must not invoke the callback function prior to returning from the API. In all other cases, the *cbfunc* will *not* be called.

Returns PMIX\_SUCCESS or one of the following error codes when the condition described occurs:

33

 PMIX\_OPERATION\_SUCCEEDED, indicating that the request was immediately processed and returned success - the cbfunc will not be called

If none of the above return codes are appropriate, then an implementation must return either a general PMIx error code or an implementation defined error code as described in Section 3.1.1.

#### **Description**

1

3

4

5

6

7

8

9

11

12

18

19

20

21

22

23

24 25

26

27

28

PMIx v3.0

Provide a function by which the host environment can pass forwarded IO to the PMIx server library for distribution to its clients. The PMIx server library is responsible for determining which of its clients have actually registered for the provided data and delivering it. The *cbfunc* callback function will be called once the PMIx server library no longer requires access to the provided data.

# 16.2.15 PMIx\_server\_collect\_inventory

#### Summary

Format

Collect inventory of resources on a node.

# pmix\_status\_t PMIx\_server\_collect\_inventory(const pmix\_info\_t directives[], size\_t ndirs, pmix\_info\_cbfunc\_t cbfunc,

#### IN directives

Array of **pmix info** t directing the request (array of handles)

IN ndirs

Number of elements in the *directives* array (size t)

IN cbfunc

Callback function to return collected data (pmix info cbfunc t function reference)

void \*cbdata);

IN cbdata

Data to be passed to the callback function (memory reference)

Returns **PMIX\_SUCCESS** or a negative value indicating the error. In the event the function returns an error, the *cbfunc* will not be called.

# Description

 Provide a function by which the host environment can request its PMIx server library collect an inventory of local resources. Supported resources depends upon the PMIx implementation, but may include the local node topology and fabric interfaces.

#### Advice to PMIx server hosts

This is a non-blocking API as it may involve somewhat lengthy operations to obtain the requested information. Inventory collection is expected to be a rare event – at system startup and upon command from a system administrator. Inventory updates are expected to initiate a smaller operation involving only the changed information. For example, replacement of a node would generate an event to notify the scheduler with an inventory update without invoking a global inventory operation.

# 16.2.16 PMIx\_server\_deliver\_inventory

## Summary

Pass collected inventory to the PMIx server library for storage.

```
14 _{PMIx \ v3.0} Format
```

IN info

Array of pmix\_info\_t containing the inventory (array of handles)

IN ninfo

Number of elements in the *info* array (size t)

IN directives

Array of **pmix\_info\_t** directing the request (array of handles)

IN ndirs

Number of elements in the *directives* array (size\_t)

IN cbfunc

Callback function **pmix\_op\_cbfunc\_t**. A **NULL** function reference indicates that the function is to be executed as a blocking operation (function reference)

IN cbdata

Data to be passed to the callback function (memory reference)

1 Returns one of the following:

2

3

5

6

7

8

9

10

11

12 13

14

15 16

18

19

24

25

26 27

28

29

A successful return indicates that the request is being processed by the host environment and the result will be returned in the provided *cbfunc*. Note that the library must not invoke the callback function prior to returning from the API. In all other cases, the *cbfunc* will *not* be called.

Returns PMIX SUCCESS or one of the following error codes when the condition described occurs:

• **PMIX\_OPERATION\_SUCCEEDED**, indicating that the request was immediately processed and returned *success* - the *cbfunc* will not be called

If none of the above return codes are appropriate, then an implementation must return either a general PMIx error code or an implementation defined error code as described in Section 3.1.1.

# Description

Provide a function by which the host environment can pass inventory information obtained from a node (as a result of a call to <code>PMIx\_server\_collect\_inventory</code>) to the PMIx server library for storage. Inventory data is subsequently used by the PMIx server library for allocations in response to <code>PMIx\_server\_setup\_application</code>, and may be available to the library's host via the <code>PMIx\_Get</code> API (depending upon PMIx implementation). The <code>cbfunc</code> callback function will be called once the PMIx server library no longer requires access to the provided data.

# 7 16.2.17 PMIx\_server\_generate\_locality\_string

#### Summary

Generate a PMIx locality string from a given cpuset.

# PMIx v4.0 pmix\_status\_t PMIx\_server\_generate\_locality\_string(const pmix\_cpuset\_t \*cpuset, char \*\*locality);

#### IN cpuset

Pointer to a pmix cpuset t containing the bitmap of assigned PUs (handle)

#### OUT locality

String representation of the PMIx locality corresponding to the input bitmap (char\*)

A successful return indicates that the returned string contains the generated locality string.

Returns **PMIX SUCCESS** or a negative value indicating the error.

# Description

Provide a function by which the host environment can generate a PMIx locality string for inclusion in the call to PMIx\_server\_register\_nspace. This function shall only be called for local client processes, with the returned locality included in the job-level information (via the PMIX\_LOCALITY\_STRING attribute) provided to local clients. Local clients can use these strings as input to determine the relative locality of their local peers via the PMIx Get relative locality API.

The function is required to return a string prefixed by the *source* field of the provided *cpuset* followed by a colon. The remainder of the string shall represent the corresponding locality as expressed by the underlying implementation.

# 11 16.2.18 PMIx\_server\_generate\_cpuset\_string

#### Summary

Generate a PMIx string representation of the provided cpuset.

# 14 PMIx v4.0 Format

#### IN cpuset

Pointer to a pmix\_cpuset\_t containing the bitmap of assigned PUs (handle)

#### OUT cpuset\_string

String representation of the input bitmap (char\*)

A successful return indicates that the returned string contains the generated cpuset representation string.

Returns **PMIX\_SUCCESS** or a negative value indicating the error.

#### **Description**

Provide a function by which the host environment can generate a string representation of the cpuset bitmap for inclusion in the call to **PMIx\_server\_register\_nspace**. This function shall only be called for local client processes, with the returned string included in the job-level information (via the **PMIX\_CPUSET** attribute) provided to local clients. Local clients can use these strings as input to obtain their PU bindings via the **PMIx\_Parse\_cpuset\_string** API.

The function is required to return a string prefixed by the *source* field of the provided *cpuset* followed by a colon. The remainder of the string shall represent the PUs to which the process is bound as expressed by the underlying implementation.

```
16.2.18.1
                 Cpuset Structure
 2
               The pmix_cpuset_t structure contains a character string identifying the source of the bitmap
 3
               (e.g., "hwloc") and a pointer to the corresponding implementation-specific structure (e.g.,
               hwloc_cpuset_t).
   PMIx v4.0
 5
               typedef struct pmix_cpuset {
 6
                    char *source;
 7
                    void *bitmap;
 8
               } pmix_cpuset_t;
    16.2.18.2 Cpuset support macros
               The following macros support the pmix_cpuset_t structure.
10
               Initialize the cpuset structure
11
12
               Initialize the pmix_cpuset_t fields.
   PMIx v4.0
13
               PMIX CPUSET CONSTRUCT (m)
               IN
14
                    Pointer to the structure to be initialized (pointer to pmix cpuset t)
15
               Destruct the cpuset structure
16
               Destruct the pmix cpuset t fields.
17
   PMIx v4.0
               PMIX CPUSET DESTRUCT (m)
18
               IN
19
                    Pointer to the structure to be destructed (pointer to pmix_cpuset_t)
20
               Create a cpuset array
21
22
               Allocate and initialize a pmix cpuset t array.
   PMIx v4.0
23
               PMIX CPUSET CREATE (m, n)
               INOUT m
24
                    Address where the pointer to the array of pmix_cpuset_t structures shall be stored
25
                    (handle)
26
               IN
27
                    n
28
                    Number of structures to be allocated (size_t)
```

```
Release a cpuset array
 1
2
               Deconstruct and free a pmix cpuset t array.
  PMIx v4.0
 3
               PMIX CPUSET FREE (m, n)
               INOUT m
 4
                    Address the array of pmix_cpuset_t structures to be released (handle)
 5
               IN
6
 7
                    Number of structures in the array (size_t)
    16.2.19
                 PMIx server define process set
8
               Summary
9
10
               Define a PMIx process set.
               Format
  PMIx v4.0
12
               pmix status t
               PMIx server define process set(const pmix proc t members[],
13
14
                                                        size t nmembers,
15
                                                        char *pset name);
               IN
                    members
16
                    Pointer to an array of pmix_proc_t containing the identifiers of the processes in the
17
                    process set (handle)
18
19
               IN
                    nmembers
                    Number of elements in members (integer)
20
               IN
21
                    pset name
                    String name of the process set being defined (char*)
22
               Returns PMIX_SUCCESS or a negative value indicating the error.
23
               Description
24
25
               Provide a function by which the host environment can create a process set. The PMIx server shall
               alert all local clients of the new process set (including process set name and membership) via the
26
               PMIX PROCESS SET DEFINE event.
27
                                     — Advice to PMIx server hosts –
               The host environment is responsible for ensuring:
28
29

    consistent knowledge of process set membership across all involved PMIx servers; and

               • that process set names do not conflict with system-assigned namespaces within the scope of the
30
31
```

# 1 16.2.20 PMIx\_server\_delete\_process\_set

#### Summary 3 Delete a PMIx process set name **Format** PMIx v4.0 5 pmix\_status\_t 6 PMIx server delete process set(char \*pset name); 7 IN pset name String name of the process set being deleted (char\*) 8 9 Returns **PMIX SUCCESS** or a negative value indicating the error. Description 10 Provide a function by which the host environment can delete a process set name. The PMIx server 11 12 shall alert all local clients of the process set name being deleted via the PMIX\_PROCESS\_SET\_DELETE event. Deletion of the name has no impact on the member 13 14 processes. Advice to PMIx server hosts 15 The host environment is responsible for ensuring consistent knowledge of process set membership across all involved PMIx servers. 16

# 7 16.3 Server Function Pointers

18 19

20

21 22

23 24

25

26

27

28

29 30

31

PMIx utilizes a "function-shipping" approach to support for implementing the server-side of the protocol. This method allows RMs to implement the server without being burdened with PMIx internal details. When a request is received from the client, the corresponding server function will be called with the information.

Any functions not supported by the RM can be indicated by a **NULL** for the function pointer. PMIx implementations are required to return a **PMIX\_ERR\_NOT\_SUPPORTED** status to all calls to functions that require host environment support and are not backed by a corresponding server module entry. Host environments may, if they choose, include a function pointer for operations they have not yet implemented and simply return **PMIX\_ERR\_NOT\_SUPPORTED**.

Functions that accept directives (i.e., arrays of <code>pmix\_info\_t</code> structures) must check any provided directives for those marked as <code>required</code> via the <code>PMIX\_INFO\_REQD</code> flag. PMIx client and server libraries are required to mark any such directives with the <code>PMIX\_INFO\_REQD\_PROCESSED</code> flag should they have handled the request. Any required directive that has not been marked therefore becomes the responsibility of the host environment. If a required directive that hasn't been

processed by a lower level cannot be supported by the host, then the

PMIX\_ERR\_NOT\_SUPPORTED error constant must be returned. If the directive can be processed

by the host, then the host shall do so and mark the attribute with the

PMIX\_INFO\_REQD\_PROCESSED flag.

The host RM will provide the function pointers in a **pmix\_server\_module\_t** structure passed to **PMIx\_server\_init**. The module structure and associated function references are defined in this section.

# Advice to PMIx server hosts -

For performance purposes, the host server is required to return as quickly as possible from all functions. Execution of the function is thus to be done asynchronously so as to allow the PMIx server support library to handle multiple client requests as quickly and scalably as possible.

All data passed to the host server functions is "owned" by the PMIX server support library and must not be free'd. Data returned by the host server via callback function is owned by the host server, which is free to release it upon return from the callback

# 16.3.1 pmix\_server\_module\_t Module

#### Summary

1

2

3

5

6

7

8

9

10

11 12

13

15

16

17

List of function pointers that a PMIx server passes to PMIx\_server\_init during startup.

#### **Format**

```
typedef struct pmix server module 4 0 0 t {
18
19
                /* vlx interfaces */
20
                pmix server client connected fn t
                                                      client connected;
                                                                          // DEPRECATED
21
                pmix server client finalized fn t
                                                      client finalized;
                pmix server abort fn t
22
                                                      abort:
                pmix_server_fencenb_fn_t
23
                                                      fence_nb;
24
                pmix_server_dmodex_req_fn_t
                                                      direct_modex;
25
                pmix_server_publish_fn_t
                                                      publish;
26
                pmix_server_lookup_fn_t
                                                      lookup;
27
                pmix_server_unpublish_fn_t
                                                      unpublish;
                pmix_server_spawn_fn_t
28
                                                      spawn;
29
                pmix_server_connect_fn_t
                                                      connect;
30
                pmix server disconnect fn t
                                                      disconnect;
                pmix_server_register_events_fn_t
31
                                                      register_events;
32
                pmix server deregister events fn t
                                                      deregister events;
                pmix_server_listener_fn_t
33
                                                      listener;
34
                /* v2x interfaces */
35
                pmix server notify event fn t
                                                      notify event;
```

```
1
                 pmix_server_query_fn_t
                                                         query;
2
                                                         tool_connected;
                 pmix server tool connection fn t
3
                 pmix server log fn t
                                                         log;
4
                 pmix server alloc fn t
                                                         allocate;
5
                 pmix_server_job_control_fn_t
                                                         job control;
6
                 pmix_server_monitor_fn_t
                                                         monitor;
7
                 /* v3x interfaces */
8
                 pmix server get cred fn t
                                                         get credential;
9
                 pmix server validate cred fn t
                                                         validate credential;
                 pmix_server_iof_fn_t
                                                         iof_pull;
10
                 pmix_server_stdin_fn_t
                                                         push_stdin;
11
                 /* v4x interfaces */
12
13
                 pmix_server_grp_fn_t
                                                         group;
14
                 pmix_server_fabric_fn_t
                                                         fabric;
15
                 pmix_server_client_connected2_fn_t
                                                         client_connected2;
             } pmix_server_module_t;
16

    Advice to PMIx server hosts

17
             Note that some PMIx implementations require the use of C99-style designated initializers to clearly
```

correlate each provided function pointer with the correct member of the

# 16.3.2 pmix\_server\_client\_connected\_fn\_t

# Summary

time.

18 19

20

22

23 24 Notify the host server that a client connected to this server. This function module entry has been **DEPRECATED** in favor of **pmix server client connected2 fn t**.

pmix server module t structure as the location/ordering of struct members may change over

1		Format
2 3 4 5 6		<pre>typedef pmix_status_t (*pmix_server_client_connected_fn_t)(</pre>
7 8 9 10 11 12 13		<pre>IN proc     pmix_proc_t structure (handle) IN server_object     object reference (memory reference) IN cbfunc     Callback function pmix_op_cbfunc_t (function reference) IN cbdata     Data to be passed to the callback function (memory reference)</pre>
15 16 17		Returns one of the following:  • PMIX_SUCCESS, indicating that the request is being processed by the host environment - resul will be returned in the provided <i>cbfunc</i> . Note that the host must not invoke the callback function prior to returning from the API.
19 20 21 22		<ul> <li>PMIX_OPERATION_SUCCEEDED, indicating that the request was immediately processed and returned <i>success</i> - the <i>cbfunc</i> will not be called</li> <li>a PMIx error constant indicating either an error in the input or that the request was immediately processed and failed - the <i>cbfunc</i> will not be called</li> </ul>
23 24 25 26		<b>Description</b> This function module entry has been DEPRECATED in favor of  pmix_server_client_connected2_fn_t. If both functions are provided, the PMIx  library will ignore this function module entry in favor of its replacement.
27 28 29 30 31	16.3.3	<pre>pmix_server_client_connected2_fn_t Summary Notify the host server that a client connected to this server - this version of the original function definition has been extended to include an array of pmix_info_t, thereby allowing the PMIx server library to pass additional information identifying the client to the host environment.</pre>

pmix\_proc\_t structure (handle) IN server object object reference (memory reference) IN info Array of info structures (array of handles) IN ninfo Number of elements in the *info* array (integer) cbfunc IN Callback function **pmix** op **cbfunc t** (function reference) IN cbdata Data to be passed to the callback function (memory reference)

#### Returns one of the following:

1

2

3

4

5

6

7

8

9

10

11 12

13 14

15

16

17

18

19 20

21

22

23 24

25

26

27 28

29 30

31 32

33

34 35

36

37

- PMIX\_SUCCESS, indicating that the request is being processed by the host environment result will be returned in the provided *cbfunc*. Note that the host must not invoke the callback function prior to returning from the API.
- PMIX\_OPERATION\_SUCCEEDED, indicating that the request was immediately processed and returned success - the cbfunc will not be called
- a PMIx error constant indicating either an error in the input or that the request was immediately processed and failed the *cbfunc* will not be called. The PMIx server library is to immediately terminate the connection.

# **Description**

Notify the host environment that a client has called **PMIx\_Init**. Note that the client will be in a blocked state until the host server executes the callback function, thus allowing the PMIx server support library to release the client. The server\_object parameter will be the value of the server\_object parameter passed to **PMIx\_server\_register\_client** by the host server when registering the connecting client. A host server can choose to not be notified when clients connect by setting **pmix server client connected2 fn t** to **NULL**.

It is possible that only a subset of the clients in a namespace call **PMIx\_Init**. The server's **pmix\_server\_client\_connected2\_fn\_t** implementation should therefore not depend on

1 being called once per rank in a namespace or delay calling the callback function until all ranks have 2 connected. However, the host may rely on the pmix server client connected2 fn t function module entry being called for a given rank prior to any other function module entries 3 4 being executed on behalf of that rank. 16.3.4 pmix server client finalized fn t Summarv 6 7 Notify the host environment that a client called **PMIx\_Finalize**. 8 *PMIx v1.0* typedef pmix\_status\_t (\*pmix\_server\_client\_finalized\_fn\_t)( 9 10 const pmix\_proc\_t \*proc, 11 void\* server\_object, 12 pmix\_op\_cbfunc\_t cbfunc, 13 void \*cbdata); IN 14 proc 15 pmix\_proc\_t structure (handle) IN server\_object 16 object reference (memory reference) 17 18 IN cbfunc Callback function pmix\_op\_cbfunc\_t (function reference) 19 IN 20 Data to be passed to the callback function (memory reference) 21 22 Returns one of the following: 23 • PMIX\_SUCCESS, indicating that the request is being processed by the host environment - result will be returned in the provided cbfunc. Note that the host must not invoke the callback function 24 25 prior to returning from the API. 26 • PMIX OPERATION SUCCEEDED, indicating that the request was immediately processed and returned success - the cbfunc will not be called 27 28 • a PMIx error constant indicating either an error in the input or that the request was immediately processed and failed - the cbfunc will not be called 29

#### Description

1

3

5

6

7

8

9

10

11 12

13 14

16

17

Notify the host environment that a client called PMIx\_Finalize. Note that the client will be in a blocked state until the host server executes the callback function, thus allowing the PMIx server support library to release the client. The server\_object parameter will be the value of the server\_object parameter passed to PMIx\_server\_register\_client by the host server when registering the connecting client. If provided, an implementation of pmix\_server\_client\_finalized\_fn\_t is only required to call the callback function designated. A host server can choose to not be notified when clients finalize by setting pmix server client finalized fn t to NULL.

Note that the host server is only being informed that the client has called **PMIx\_Finalize**. The client might not have exited. If a client exits without calling **PMIx\_Finalize**, the server support library will not call the **pmix\_server\_client\_finalized\_fn\_t** implementation.

#### Advice to PMIx server hosts

This operation is an opportunity for a host server to update the status of the tasks it manages. It is also a convenient and well defined time to release resources used to support that client.

# 16.3.5 pmix\_server\_abort\_fn\_t

### Summary

Notify the host environment that a local client called **PMIx\_Abort**.

```
PMIx v1.0 Format
```

```
typedef pmix_status_t (*pmix_server_abort_fn_t)(
19
20
                                           const pmix_proc_t *proc,
21
                                           void *server_object,
22
                                           int status,
23
                                           const char msq[],
                                           pmix_proc_t procs[],
24
                                           size_t nprocs,
25
26
                                           pmix_op_cbfunc_t cbfunc,
27
                                           void *cbdata);
```

31

32

33

1

2

IN proc

pmix\_proc\_t structure identifying the process requesting the abort (handle)

IN server object

object reference (memory reference)

IN status

exit status (integer)

IN msg

exit status message (string)

IN procs

Array of **pmix\_proc\_t** structures identifying the processes to be terminated (array of handles)

IN nprocs

Number of elements in the *procs* array (integer)

IN cbfunc

Callback function **pmix\_op\_cbfunc\_t** (function reference)

IN cbdata

Data to be passed to the callback function (memory reference)

#### Returns one of the following:

- PMIX\_SUCCESS, indicating that the request is being processed by the host environment result will be returned in the provided *cbfunc*. Note that the host must not invoke the callback function prior to returning from the API.
- PMIX\_OPERATION\_SUCCEEDED, indicating that the request was immediately processed and returned *success* the *cbfunc* will not be called
- PMIX\_ERR\_PARAM\_VALUE\_NOT\_SUPPORTED indicating that the host environment supports
  this API, but the request includes processes that the host environment cannot abort e.g., if the
  request is to abort subsets of processes from a namespace, or processes outside of the caller's
  own namespace, and the host environment does not permit such operations. In this case, none of
  the specified processes will be terminated the *cbfunc* will not be called
- PMIX\_ERR\_NOT\_SUPPORTED, indicating that the host environment does not support the request, even though the function entry was provided in the server module the *cbfunc* will not be called
- a PMIx error constant indicating either an error in the input or that the request was immediately processed and failed the *cbfunc* will not be called

```
Description
 1
 2
               A local client called PMIx Abort. Note that the client will be in a blocked state until the host
 3
               server executes the callback function, thus allowing the PMIx server library to release the client.
 4
               The array of procs indicates which processes are to be terminated. A NULL for the procs array
 5
               indicates that all processes in the caller's namespace are to be aborted, including itself - this is the
6
               equivalent of passing a pmix proc t array element containing the caller's namespace and a rank
 7
               value of PMIX RANK WILDCARD.
    16.3.6 pmix_server_fencenb_fn_t
9
               Summary
               At least one client called either PMIx Fence or PMIx Fence nb.
10
               Format
   PMIx v1.0
12
               typedef pmix_status_t (*pmix_server_fencenb_fn_t)(
                                                     const pmix_proc_t procs[],
13
14
                                                      size t nprocs,
15
                                                      const pmix info t info[],
16
                                                      size_t ninfo,
17
                                                      char *data, size_t ndata,
                                                     pmix modex cbfunc t cbfunc,
18
19
                                                      void *cbdata);
                                                          C
               IN
20
                    procs
21
                    Array of pmix proc t structures identifying operation participants (array of handles)
               IN
22
                    nprocs
23
                    Number of elements in the procs array (integer)
               IN
24
25
                    Array of info structures (array of handles)
26
               IN
                    ninfo
27
                    Number of elements in the info array (integer)
28
               IN
                    data
29
                    (string)
               IN
30
                    ndata
                    (integer)
31
32
                    cbfunc
33
                    Callback function pmix_modex_cbfunc_t (function reference)
               IN
34
```

Data to be passed to the callback function (memory reference)

Returns one of the following:

35

1 2 3	• PMIX_SUCCESS, indicating that the request is being processed by the host environment - result will be returned in the provided <i>cbfunc</i> . Note that the host must not invoke the callback function prior to returning from the API.
4 5 6	• PMIX_ERR_NOT_SUPPORTED, indicating that the host environment does not support the request, even though the function entry was provided in the server module - the <i>cbfunc</i> will not be called
7 8	• a PMIx error constant indicating either an error in the input or that the request was immediately processed and failed - the <i>cbfunc</i> will not be called
	▼
9	PMIx libraries are required to pass any provided attributes to the host environment for processing.
10	The following attributes are required to be supported by all host environments:
11 12 13 14 15	PMIX_COLLECT_DATA "pmix.collect" (bool)  Collect all data posted by the participants using PMIx_Put that has been committed via PMIx_Commit, making the collection locally available to each participant at the end of the operation. By default, this will include all job-level information that was locally generated by PMIx servers unless excluded using the PMIX_COLLECT_GENERATED_JOB_INFO attribute.
	▼ Optional Attributes
17	The following attributes are optional for host environments:
18 19 20 21	PMIX_TIMEOUT "pmix.timeout" (int)  Time in seconds before the specified operation should time out (zero indicating infinite) and return the PMIX_ERR_TIMEOUT error. Care should be taken to avoid race conditions caused by multiple layers (client, server, and host) simultaneously timing the operation.
	Advice to PMIx server hosts
22	Host environment are required to return <b>PMIX_ERR_NOT_SUPPORTED</b> if passed an attributed
23	marked as PMIX_INFO_REQD that they do not support, even if support for that attribute is
24	optional.

### Description

All local clients in the provided array of *procs* called either **PMIx\_Fence** or **PMIx\_Fence\_nb**. In either case, the host server will be called via a non-blocking function to execute the specified operation once all participating local processes have contributed. All processes in the specified *procs* array are required to participate in the **PMIx\_Fence/PMIx\_Fence\_nb** operation. The callback is to be executed once every daemon hosting at least one participant has called the host server's **pmix\_server\_fencenb\_fn\_t** function.

The provided data is to be collectively shared with all PMIx servers involved in the fence operation, and returned in the modex *cbfunc*. A **NULL** data value indicates that the local processes had no data to contribute.

The array of *info* structs is used to pass user-requested options to the server. This can include directives as to the algorithm to be used to execute the fence operation. The directives are optional unless the **PMIX\_INFO\_REQD** flag has been set - in such cases, the host RM is required to return an error if the directive cannot be met.

### —— Advice to PMIx library implementers -

The PMIx server library is required to aggregate participation by local clients, passing the request to the host environment once all local participants have executed the API.

# Advice to PMIx server hosts

The host will receive a single call for each collective operation. It is the responsibility of the host to identify the nodes containing participating processes, execute the collective across all participating nodes, and notify the local PMIx server library upon completion of the global collective. Data received from each node must be simply concatenated to form an aggregated unit, as shown in the following example:

```
uint8_t *blob1, *blob2, *total;
size_t sz_blob1, sz_blob2, sz_total;

sz_total = sz_blob1 + sz_blob2;
total = (uint8_t*)malloc(sz_total);
memcpy(total, blob1, sz_blob1);
memcpy(&total[sz_blob1], blob2, sz_blob2);
```

Note that the ordering of the data blobs does not matter. The host is responsible for free'ing the *data* object passed to it by the PMIx server library.

#### 16.3.6.1 Modex Callback Function

```
2
               Summary
 3
               The pmix_modex_cbfunc_t is used by the pmix_server_fencenb_fn_t and
 4
               pmix_server_dmodex_req_fn_t PMIx server operations to return modex Business Card
 5
               Exchange (BCX) data.
  PMIx v1.0
               typedef void (*pmix_modex_cbfunc_t)
6
 7
                     (pmix_status_t status,
8
                     const char *data, size t ndata,
9
                     void *cbdata,
                     pmix_release_cbfunc_t release_fn,
10
                     void *release cbdata);
11
12
               IN
                    status
                    Status associated with the operation (handle)
13
               IN
14
                    data
                    Data to be passed (pointer)
15
16
               IN
                    ndata
                    size of the data (size t)
17
                    cbdata
18
                    Callback data passed to original API call (memory reference)
19
20
               IN
                   release fn
                    Callback for releasing data (function pointer)
21
22
               IN
                    release cbdata
                    Pointer to be passed to release fn (memory reference)
23
               Description
24
               A callback function that is solely used by PMIx servers, and not clients, to return modex BCX data
25
               in response to "fence" and "get" operations. The returned blob contains the data collected from
26
27
               each server participating in the operation.
```

# 16.3.7 pmix server dmodex req fn t

### Summary

Used by the PMIx server to request its local host contact the PMIx server on the remote node that hosts the specified process to obtain and return a direct modex blob for that process.

29 30

1	Format C
2 3 4 5 6 7	<pre>typedef pmix_status_t (*pmix_server_dmodex_req_fn_t)(</pre>
	C
8 9 10	<pre>IN proc     pmix_proc_t structure identifying the process whose data is being requested (handle) IN info</pre>
11 12 13	Array of info structures (array of handles)  IN ninfo  Number of elements in the <i>info</i> array (integer)
14 15 16 17	<ul> <li>IN cbfunc         Callback function pmix_modex_cbfunc_t (function reference)</li> <li>IN cbdata         Data to be passed to the callback function (memory reference)</li> </ul>
18	Returns one of the following:
19 20 21	• <b>PMIX_SUCCESS</b> , indicating that the request is being processed by the host environment - result will be returned in the provided <i>cbfunc</i> . Note that the host must not invoke the callback function prior to returning from the API.
22 23 24	• PMIX_ERR_NOT_SUPPORTED, indicating that the host environment does not support the request, even though the function entry was provided in the server module - the <i>cbfunc</i> will not be called
25 26	• a PMIx error constant indicating either an error in the input or that the request was immediately processed and failed - the <i>cbfunc</i> will not be called
	Required Attributes
27	PMIx libraries are required to pass any provided attributes to the host environment for processing.
28	All host environments are required to support the following attributes:
29 30 31 32	PMIX_REQUIRED_KEY "pmix.req.key" (char*)  Identifies a key that must be included in the requested information. If the specified key is not already available, then the PMIx servers are required to delay response to the dmodex request until either the key becomes available or the request times out.

#### **Optional Attributes** The following attributes are optional for host environments that support this operation: 1 2 PMIX TIMEOUT "pmix.timeout" (int) 3 Time in seconds before the specified operation should time out (zero indicating infinite) and return the PMIX ERR TIMEOUT error. Care should be taken to avoid race conditions 4 caused by multiple layers (client, server, and host) simultaneously timing the operation. 5 **Description** 6 7 Used by the PMIx server to request its local host contact the PMIx server on the remote node that 8 hosts the specified proc to obtain and return any information that process posted via calls to PMIx Put and PMIx Commit. 9 10 The array of *info* structs is used to pass user-requested options to the server. This can include a 11 timeout to preclude an indefinite wait for data that may never become available. The directives are optional unless the mandatory flag has been set - in such cases, the host RM is required to return an 12 error if the directive cannot be met. 13 16.3.7.1 **Dmodex attributes** 14 PMIX REQUIRED KEY "pmix.req.key" (char\*) 15 Identifies a key that must be included in the requested information. If the specified key is not 16 already available, then the PMIx servers are required to delay response to the dmodex 17 request until either the key becomes available or the request times out. 18

# 19 16.3.8 pmix\_server\_publish\_fn\_t

### 20 Summary

Publish data per the PMIx API specification.

```
22 PMIx v1.0
```

```
Format
```

```
typedef pmix_status_t (*pmix_server_publish_fn_t)(
const pmix_proc_t *proc,
const pmix_info_t info[],
const pmix_info_t info[],
size_t ninfo,
pmix_op_cbfunc_t cbfunc,
void *cbdata);
```

1	IN proc
2	<pre>pmix_proc_t structure of the process publishing the data (handle)</pre>
3	IN info
4 5	Array of info structures (array of handles)  IN ninfo
6	Number of elements in the <i>info</i> array (integer)
7	IN cbfunc
8	Callback function <b>pmix_op_cbfunc_t</b> (function reference)
9	IN cbdata
10	Data to be passed to the callback function (memory reference)
11	Returns one of the following:
12 13 14	<ul> <li>PMIX_SUCCESS, indicating that the request is being processed by the host environment - result will be returned in the provided <i>cbfunc</i>. Note that the host must not invoke the callback function prior to returning from the API.</li> </ul>
15 16	• PMIX_OPERATION_SUCCEEDED, indicating that the request was immediately processed and returned <i>success</i> - the <i>cbfunc</i> will not be called
17 18 19	• PMIX_ERR_NOT_SUPPORTED, indicating that the host environment does not support the request, even though the function entry was provided in the server module - the <i>cbfunc</i> will not be called
20 21	• a PMIx error constant indicating either an error in the input or that the request was immediately processed and failed - the <i>cbfunc</i> will not be called
	Required Attributes
22 23	PMIx libraries are required to pass any provided attributes to the host environment for processing. In addition, the following attributes are required to be included in the passed <i>info</i> array:
24 25	PMIX_USERID "pmix.euid" (uint32_t)  Effective user ID of the connecting process.
26 27	PMIX_GRPID "pmix.egid" (uint32_t)  Effective group ID of the connecting process.
28	
29	Host environments that implement this entry point are required to support the following attributes:
30 31 32	PMIX_RANGE "pmix.range" (pmix_data_range_t)  Define constraints on the processes that can access the provided data. Only processes that meet the constraints are allowed to access it.
33	<pre>PMIX_PERSISTENCE "pmix.persist" (pmix_persistence_t)</pre>

Declare how long the datastore shall retain the provided data. The datastore is to delete the 1 2 data upon reaching the persistence criterion. Optional Attributes The following attributes are optional for host environments that support this operation: 3 4 PMIX TIMEOUT "pmix.timeout" (int) 5 Time in seconds before the specified operation should time out (zero indicating infinite) and return the PMIX ERR TIMEOUT error. Care should be taken to avoid race conditions 6 caused by multiple layers (client, server, and host) simultaneously timing the operation. 7 **Description** 8 Publish data per the PMIx\_Publish specification. The callback is to be executed upon 9 completion of the operation. The default data range is left to the host environment, but expected to 10 be PMIX\_RANGE\_SESSION, and the default persistence PMIX\_PERSIST\_SESSION or their 11 12 equivalent. These values can be specified by including the respective attributed in the *info* array. The persistence indicates how long the server should retain the data. 13 Advice to PMIx server hosts The host environment is not required to guarantee support for any specific range - i.e., the 14 15 environment does not need to return an error if the data store doesn't support a specified range so 16 long as it is covered by some internally defined range. However, the server must return an error (a) 17 if the key is duplicative within the storage range, and (b) if the server does not allow overwriting of

published info by the original publisher - it is left to the discretion of the host environment to allow info-key-based flags to modify this behavior.

The PMIX\_USERID and PMIX\_GRPID of the publishing process will be provided to support authorization-based access to published information and must be returned on any subsequent

16.3.9 pmix server lookup fn t

Summary

lookup request.

Lookup published data.

18

19

20

21

22

24

Effective user ID of the connecting process.

#### PMIX\_GRPID "pmix.egid" (uint32\_t) 1 Effective group ID of the connecting process. 2 3 Host environments that implement this entry point are required to support the following attributes: 4 5 PMIX RANGE "pmix.range" (pmix data range t) Define constraints on the processes that can access the provided data. Only processes that 6 7 meet the constraints are allowed to access it. 8 PMIX\_WAIT "pmix.wait" (int) 9 Caller requests that the PMIx server wait until at least the specified number of values are found (a value of zero indicates all and is the default). 10 Optional Attributes The following attributes are optional for host environments that support this operation: 11 12 PMIX\_TIMEOUT "pmix.timeout" (int) Time in seconds before the specified operation should time out (zero indicating infinite) and 13 return the **PMIX\_ERR\_TIMEOUT** error. Care should be taken to avoid race conditions 14 caused by multiple layers (client, server, and host) simultaneously timing the operation. 15 16 **Description** 17 Lookup published data. The host server will be passed a **NULL**-terminated array of string keys identifying the data being requested. 18 19 The array of *info* structs is used to pass user-requested options to the server. The default data range 20 is left to the host environment, but expected to be PMIX RANGE SESSION. This can include a 21 wait flag to indicate that the server should wait for all data to become available before executing the callback function, or should immediately callback with whatever data is available. In addition, a 22 23 timeout can be specified on the wait to preclude an indefinite wait for data that may never be published. 24 Advice to PMIx server hosts — 25 The PMIX\_USERID and PMIX\_GRPID of the requesting process will be provided to support authorization-based access to published information. The host environment is not required to 26 27 guarantee support for any specific range - i.e., the environment does not need to return an error if 28 the data store doesn't support a specified range so long as it is covered by some internally defined

range.

# 1 16.3.10 pmix\_server\_unpublish\_fn\_t

2			mmary
3		Del	ete data from the data store.
4	PMIx v1.0	Fo	rmat C
5 6 7 8 9 10		tyr	<pre>pedef pmix_status_t (*pmix_server_unpublish_fn_t)(</pre>
12 13 14 15 16 17 18 19 20 21 22 23		IN IN IN IN IN IN	<pre>proc pmix_proc_t structure identifying the process making the request (handle) keys (array of strings) info Array of info structures (array of handles) ninfo Number of elements in the info array (integer) cbfunc Callback function pmix_op_cbfunc_t (function reference) cbdata Data to be passed to the callback function (memory reference)</pre>
		Date	
24 25 26 27		• P w p	MIX_SUCCESS, indicating that the request is being processed by the host environment - result vill be returned in the provided <i>cbfunc</i> . Note that the host must not invoke the callback function rior to returning from the API.
28 29			MIX_OPERATION_SUCCEEDED, indicating that the request was immediately processed and eturned <i>success</i> - the <i>cbfunc</i> will not be called
30 31 32		re	MIX_ERR_NOT_SUPPORTED, indicating that the host environment does not support the equest, even though the function entry was provided in the server module - the <i>cbfunc</i> will not e called
33			PMIx error constant indicating either an error in the input or that the request was immediately rocessed and failed - the <i>chiunc</i> will not be called

## Required Attributes

PMIx libraries are required to pass any provided attributes to the host environment for processing. In addition, the following attributes are required to be included in the passed *info* array:

PMIX\_GRPID "pmix.egid" (uint32\_t)

Effective group ID of the connecting process.

Host environments that implement this entry point are required to support the following attributes:

PMIX\_RANGE "pmix.range" (pmix\_data\_range\_t)

Define constraints on the processes that can access the provided data. Only processes that meet the constraints are allowed to access it.

## Optional Attributes

The following attributes are optional for host environments that support this operation:

PMIX\_TIMEOUT "pmix.timeout" (int)

Time in seconds before the specified operation should time out (zero indicating infinite) and return the **PMIX\_ERR\_TIMEOUT** error. Care should be taken to avoid race conditions caused by multiple layers (client, server, and host) simultaneously timing the operation.

## Description

Delete data from the data store. The host server will be passed a **NULL**-terminated array of string keys, plus potential directives such as the data range within which the keys should be deleted. The default data range is left to the host environment, but expected to be **PMIX\_RANGE\_SESSION**. The callback is to be executed upon completion of the delete procedure.

### Advice to PMIx server hosts -

The PMIX\_USERID and PMIX\_GRPID of the requesting process will be provided to support authorization-based access to published information. The host environment is not required to guarantee support for any specific range - i.e., the environment does not need to return an error if the data store doesn't support a specified range so long as it is covered by some internally defined range.

1

2

5

6 7

9

10

11

12

13

14

15

16

17 18

19 20

21

22

23

24 25

# 16.3.11 pmix\_server\_spawn\_fn\_t

#### Summary

2

4

5

6 7

8

9

10

11

12

13

14 15

16

17

18

19 20

21

22

23

24 25

26

27 28

29

30

31 32

33

34

35 36

37

Spawn a set of applications/processes as per the **PMIx\_Spawn** API.

#### **Format**

C

IN proc

pmix\_proc\_t structure of the process making the request (handle)

IN job\_info

Array of info structures (array of handles)

IN ninfo

Number of elements in the *jobinfo* array (integer)

IN apps

Array of pmix\_app\_t structures (array of handles)

IN napps

Number of elements in the *apps* array (integer)

IN cbfunc

Callback function pmix spawn cbfunc t (function reference)

IN cbdata

Data to be passed to the callback function (memory reference)

#### Returns one of the following:

- PMIX\_SUCCESS, indicating that the request is being processed by the host environment result will be returned in the provided *cbfunc*. Note that the host must not invoke the callback function prior to returning from the API.
- PMIX\_OPERATION\_SUCCEEDED, indicating that the request was immediately processed and returned *success* the *cbfunc* will not be called
- PMTX\_ERR\_NOT\_SUPPORTED, indicating that the host environment does not support the request, even though the function entry was provided in the server module the *cbfunc* will not be called
- a PMIx error constant indicating either an error in the input or that the request was immediately processed and failed the *cbfunc* will not be called

# Required Attributes

PMIx server libraries are required to pass any provided attributes to the host environment for processing. In addition, the following attributes are required to be included in the passed *info* array:

PMIX\_SPAWNED "pmix.spawned" (bool)

true if this process resulted from a call to PMIx\_Spawn. Lack of inclusion (i.e., a return status of PMIX\_ERR\_NOT\_FOUND) corresponds to a value of false for this attribute.

PMIX\_PARENT\_ID "pmix.parent" (pmix\_proc\_t)

Process identifier of the parent process of the specified process - typically used to identify the application process that caused the job containing the specified process to be spawned (e.g., the process that called PMIx\_Spawn).

PMIX\_REQUESTOR\_IS\_TOOL "pmix.req.tool" (bool)
The requesting process is a PMIx tool.

PMIX\_REQUESTOR\_IS\_CLIENT "pmix.req.client" (bool)
The requesting process is a PMIx client.

Host environments that provide this module entry point are required to pass the PMIX\_SPAWNED and PMIX\_PARENT\_ID attributes to all PMIx servers launching new child processes so those values can be returned to clients upon connection to the PMIx server. In addition, they are required to support the following attributes when present in either the *job\_info* or the *info* array of an element of the *apps* array:

```
PMIX_WDIR "pmix.wdir" (char*)
```

Working directory for spawned processes.

```
PMIX_SET_SESSION_CWD "pmix.ssncwd" (bool)
```

Set the current working directory to the session working directory assigned by the RM - can be assigned to the entire job (by including attribute in the *job\_info* array) or on a per-application basis in the *info* array for each **pmix\_app\_t**.

```
PMIX_PREFIX "pmix.prefix" (char*)
```

Prefix to use for starting spawned processes - i.e., the directory where the executables can be found.

```
PMIX HOST "pmix.host" (char*)
```

Comma-delimited list of hosts to use for spawned processes.

```
PMIX HOSTFILE "pmix.hostfile" (char*)
```

1	Hostfile to use for spawned processes.
	▼ Optional Attributes
2	The following attributes are optional for host environments that support this operation:
3 4	PMIX_ADD_HOSTFILE "pmix.addhostfile" (char*)  Hostfile containing hosts to add to existing allocation.
5 6	PMIX_ADD_HOST "pmix.addhost" (char*)  Comma-delimited list of hosts to add to the allocation.
7 8	PMIX_PRELOAD_BIN "pmix.preloadbin" (bool)  Preload executables onto nodes prior to executing launch procedure.
9 10	<pre>PMIX_PRELOAD_FILES "pmix.preloadfiles" (char*) Comma-delimited list of files to pre-position on nodes prior to executing launch procedure.</pre>
11 12 13	<pre>PMIX_PERSONALITY "pmix.pers" (char*)     Name of personality corresponding to programming model used by application - supported values depend upon PMIx implementation.</pre>
14 15	PMIX_DISPLAY_MAP "pmix.dispmap" (bool) Display process mapping upon spawn.
16 17	PMIX_PPR "pmix.ppr" (char*)  Number of processes to spawn on each identified resource.
18 19 20 21	<pre>PMIX_MAPBY "pmix.mapby" (char*) Process mapping policy - when accessed using PMIx_Get, use the PMIX_RANK_WILDCARD value for the rank to discover the mapping policy used for the provided namespace. Supported values are launcher specific.</pre>
22 23 24 25	<pre>PMIX_RANKBY "pmix.rankby" (char*) Process ranking policy - when accessed using PMIx_Get, use the PMIX_RANK_WILDCARD value for the rank to discover the ranking algorithm used for the provided namespace. Supported values are launcher specific.</pre>
26 27 28 29	PMIX_BINDTO "pmix.bindto" (char*)  Process binding policy - when accessed using PMIx_Get, use the  PMIX_RANK_WILDCARD value for the rank to discover the binding policy used for the provided namespace. Supported values are launcher specific.
30 31	PMIX_STDIN_TGT "pmix.stdin" (uint32_t)  Spawned process rank that is to receive any forwarded stdin.
32	<pre>PMIX_FWD_STDIN "pmix.fwd.stdin" (pmix_rank_t)</pre>

6 7

9 10 11

12

13

8

14 15 16

17

18

19 20 21

22 23 24

25 26 27

28 29 30

31 32 33

34 35 36

37 38

39

The requester intends to push information from its **stdin** to the indicated process. The local spawn agent should, therefore, ensure that the **stdin** channel to that process remains available. A rank of PMIX RANK WILDCARD indicates that all processes in the spawned job are potential recipients. The requester will issue a call to PMIx IOF push to initiate the actual forwarding of information to specified targets - this attribute simply requests that the IL retain the ability to forward the information to the designated targets.

#### PMIX FWD STDOUT "pmix.fwd.stdout" (bool)

Requests that the ability to forward the **stdout** of the spawned processes be maintained. The requester will issue a call to **PMIx\_IOF\_pull** to specify the callback function and other options for delivery of the forwarded output.

#### PMIX FWD STDERR "pmix.fwd.stderr" (bool)

Requests that the ability to forward the **stderr** of the spawned processes be maintained. The requester will issue a call to PMIx IOF pull to specify the callback function and other options for delivery of the forwarded output.

#### PMIX DEBUGGER DAEMONS "pmix.debugger" (bool)

Included in the pmix info t array of a pmix app t, this attribute declares that the application consists of debugger daemons and shall be governed accordingly. If used as the sole pmix app t in a PMIx Spawn request, then the PMIX DEBUG TARGET attribute must also be provided (in either the job\_info or in the info array of the pmix\_app\_t) to identify the namespace to be debugged so that the launcher can determine where to place the spawned daemons. If neither PMIX DEBUG DAEMONS PER PROC nor PMIX\_DEBUG\_DAEMONS\_PER\_NODE is specified, then the launcher shall default to a placement policy of one daemon per process in the target job.

#### PMIX TAG OUTPUT "pmix.tagout" (bool)

Tag **stdout/stderr** with the identity of the source process - can be assigned to the entire job (by including attribute in the job\_info array) or on a per-application basis in the info array for each pmix\_app\_t.

#### PMIX\_TIMESTAMP\_OUTPUT "pmix.tsout" (bool)

Timestamp output - can be assigned to the entire job (by including attribute in the job\_info array) or on a per-application basis in the *info* array for each **pmix\_app\_t**.

### PMIX\_MERGE\_STDERR\_STDOUT "pmix.mergeerrout" (bool)

Merge **stdout** and **stderr** streams - can be assigned to the entire job (by including attribute in the *job\_info* array) or on a per-application basis in the *info* array for each pmix\_app\_t.

### PMIX\_OUTPUT\_TO\_FILE "pmix.outfile" (char\*)

Direct output (both stdout and stderr) into files of form "<filename>.rank" - can be assigned to the entire job (by including attribute in the job\_info array) or on a per-application basis in the *info* array for each **pmix\_app\_t**.

PMIX\_INDEX\_ARGV "pmix.indxargv" (bool)

Mark the **argv** with the rank of the process. 1 2 PMIX CPUS PER PROC "pmix.cpuperproc" (uint32 t) Number of PUs to assign to each rank - when accessed using PMIx\_Get, use the 3 PMIX\_RANK\_WILDCARD value for the rank to discover the PUs/process assigned to the 4 provided namespace. 5 PMIX NO PROCS ON HEAD "pmix.nolocal" (bool) 6 Do not place processes on the head node. 7 8 PMIX NO OVERSUBSCRIBE "pmix.noover" (bool) Do not oversubscribe the nodes - i.e., do not place more processes than allocated slots on a 9 10 node. PMIX REPORT BINDINGS "pmix.repbind" (bool) 11 12 Report bindings of the individual processes. 13 PMIX CPU LIST "pmix.cpulist" (char\*) 14 List of PUs to use for this job - when accessed using **PMIx\_Get**, use the PMIX\_RANK\_WILDCARD value for the rank to discover the PU list used for the provided 15 namespace. 16 17 PMIX\_JOB\_RECOVERABLE "pmix.recover" (bool) 18 Application supports recoverable operations. 19 PMIX JOB CONTINUOUS "pmix.continuous" (bool) Application is continuous, all failed processes should be immediately restarted. 20 PMIX MAX RESTARTS "pmix.maxrestarts" (uint32 t) 21 Maximum number of times to restart a process - when accessed using PMIx\_Get, use the 22 PMIX\_RANK\_WILDCARD value for the rank to discover the max restarts for the provided 23 24 namespace. PMIX TIMEOUT "pmix.timeout" (int) 25 Time in seconds before the specified operation should time out (zero indicating infinite) and 26 27 return the PMIX ERR TIMEOUT error. Care should be taken to avoid race conditions caused by multiple layers (client, server, and host) simultaneously timing the operation. 28

## Description

29

30

31

32

33

34

35 36

37

Spawn a set of applications/processes as per the PMIx\_Spawn API. Note that applications are not required to be MPI or any other programming model. Thus, the host server cannot make any assumptions as to their required support. The callback function is to be executed once all processes have been started. An error in starting any application or process in this request shall cause all applications and processes in the request to be terminated, and an error returned to the originating caller.

Note that a timeout can be specified in the job\_info array to indicate that failure to start the requested job within the given time should result in termination to avoid hangs.

#### 16.3.11.1 Server spawn attributes 2 PMIX\_REQUESTOR\_IS\_TOOL "pmix.req.tool" (bool) 3 The requesting process is a PMIx tool. PMIX REQUESTOR IS CLIENT "pmix.req.client" (bool) 4 5 The requesting process is a PMIx client. 16.3.12 pmix\_server\_connect\_fn\_t Summarv 7 Record the specified processes as connected. 8 **Format** 9 *PMIx v1.0* typedef pmix\_status\_t (\*pmix\_server\_connect\_fn\_t)( 10 11 const pmix\_proc\_t procs[], 12 size\_t nprocs, const pmix\_info\_t info[], 13 size\_t ninfo, 14 pmix\_op\_cbfunc\_t cbfunc, 15 void \*cbdata); 16 IN procs 17 Array of pmix proc t structures identifying participants (array of handles) 18 IN nprocs 19 Number of elements in the *procs* array (integer) 20 info 21 IN Array of info structures (array of handles) 22 23 IN ninfo Number of elements in the *info* array (integer) 24 25 IN cbfunc Callback function pmix\_op\_cbfunc\_t (function reference) 26 IN 27 cbdata 28 Data to be passed to the callback function (memory reference) Returns one of the following: 29 30 • PMIX\_SUCCESS, indicating that the request is being processed by the host environment - result will be returned in the provided cbfunc. Note that the host must not invoke the callback function 31 32 prior to returning from the API. • PMIX\_OPERATION\_SUCCEEDED, indicating that the request was immediately processed and 33 34 returned *success* - the *cbfunc* will not be called

2	• PMIX_ERR_NOT_SUPPORTED, indicating that the nost environment does not support the request, even though the function entry was provided in the server module - the <i>cbfunc</i> will not be called
4 5	• a PMIx error constant indicating either an error in the input or that the request was immediately processed and failed - the <i>cbfunc</i> will not be called
	▼ Required Attributes
6	PMIx libraries are required to pass any provided attributes to the host environment for processing.
	▼ Optional Attributes
7	The following attributes are optional for host environments that support this operation:
8 9 10 11	PMIX_TIMEOUT "pmix.timeout" (int)  Time in seconds before the specified operation should time out (zero indicating infinite) and return the PMIX_ERR_TIMEOUT error. Care should be taken to avoid race conditions caused by multiple layers (client, server, and host) simultaneously timing the operation.
12 13 14 15 16	Description  Record the processes specified by the <i>procs</i> array as <i>connected</i> as per the PMIx definition. The callback is to be executed once every daemon hosting at least one participant has called the host server's <a href="maik_server_connect_fn_t">pmix_server_connect_fn_t</a> function, and the host environment has completed any supporting operations required to meet the terms of the PMIx definition of <i>connected</i> processes.  Advice to PMIx library implementers
17 18	The PMIx server library is required to aggregate participation by local clients, passing the request to the host environment once all local participants have executed the API.
	Advice to PMIx server hosts
19 20 21	The host will receive a single call for each collective operation. It is the responsibility of the host to identify the nodes containing participating processes, execute the collective across all participating nodes, and notify the local PMIx server library upon completion of the global collective.
22	16.3.13 pmix_server_disconnect_fn_t
23	Summary
24	Disconnect a previously connected set of processes.

PMIx libraries are required to pass any provided attributes to the host environment for processing.

	→ Optional Attributes
1	The following attributes are optional for host environments that support this operation:
2	PMIX_TIMEOUT "pmix.timeout" (int)
3	Time in seconds before the specified operation should time out (zero indicating infinite) and
4	return the PMIX_ERR_TIMEOUT error. Care should be taken to avoid race conditions
5	caused by multiple layers (client, server, and host) simultaneously timing the operation.
	<b>A-</b>
6	Description
7	Disconnect a previously connected set of processes. The callback is to be executed once every
8	daemon hosting at least one participant has called the host server's has called the
9	<pre>pmix_server_disconnect_fn_t function, and the host environment has completed any</pre>
0	required supporting operations.
	Advice to PMIx library implementers
1	The PMIx server library is required to aggregate participation by local clients, passing the request
2	to the host environment once all local participants have executed the API.
	Advice to PMIx server hosts
3	The host will receive a single call for each collective operation. It is the responsibility of the host to
4	identify the nodes containing participating processes, execute the collective across all participating
5	nodes, and notify the local PMIx server library upon completion of the global collective.
6	A PMIX_ERR_INVALID_OPERATION error must be returned if the specified set of procs was
7	not previously <i>connected</i> via a call to the <b>pmix_server_connect_fn_t</b> function.

# 18 16.3.14 pmix\_server\_register\_events\_fn\_t

# Summary

19 20

Register to receive notifications for the specified events.

Effective user ID of the connecting process.

1 2	PMIX_GRPID "pmix.egid" (uint32_t)  Effective group ID of the connecting process.
3	Description
4 5	Register to receive notifications for the specified status codes. The <i>info</i> array included in this API is reserved for possible future directives to further steer notification.
	Advice to PMIx library implementers
6 7	The PMIx server library must track all client registrations for subsequent notification. This module function shall only be called when:
8 9 0	<ul> <li>the client has requested notification of an environmental code (i.e., a PMIx codes in the range between PMIX_EVENT_SYS_BASE and PMIX_EVENT_SYS_OTHER, inclusive) or codes that lies outside the defined PMIx range of constants; and</li> </ul>
1 2	• the PMIx server library has not previously requested notification of that code - i.e., the host environment is to be contacted only once a given unique code value
	Advice to PMIx server hosts
3	The host environment is required to pass to its PMIx server library all non-environmental events
4	that directly relate to a registered namespace without the PMIx server library explicitly requesting
5	them. Environmental events are to be translated to their nearest PMIx equivalent code as defined in
6	the range between PMIX_EVENT_SYS_BASE and PMIX_EVENT_SYS_OTHER (inclusive).

# 17 16.3.15 pmix\_server\_deregister\_events\_fn\_t

# Summary

18

19

Deregister to receive notifications for the specified events.

• the library is deregistering environmental codes (i.e., a PMIx codes in the range between

PMIX\_EVENT\_SYS\_BASE and PMIX\_EVENT\_SYS\_OTHER, inclusive) or codes that lies

31

32

33

outside the defined PMIx range of constants; and

• no client (including the server library itself) remains registered for notifications on any included code - i.e., a code should be included in this call only when no registered notifications against it remain.

#### 16.3.16 pmix\_server\_notify\_event\_fn\_t

# Summary

Format

1

2

3

5 6

16

17

18 19

20

21

22

23 24

25

26 27

28

29

30 31

32

33

34

Notify the specified processes of an event.

```
PMIx v2 0
8
            typedef pmix_status_t (*pmix_server_notify_event_fn_t)(
                                           pmix status t code,
9
10
                                           const pmix_proc_t *source,
                                           pmix_data_range_t range,
11
12
                                           pmix_info_t info[],
13
                                           size_t ninfo,
14
                                           pmix_op_cbfunc_t cbfunc,
15
                                           void *cbdata);
```

IN code

The pmix\_status\_t event code being referenced structure (handle)

IN source

pmix\_proc\_t of process that generated the event (handle)

IN range

pmix\_data\_range\_t range over which the event is to be distributed (handle)

IN info

> Optional array of pmix info t structures containing additional information on the event (array of handles)

IN ninfo

Number of elements in the *info* array (integer)

IN

Callback function pmix op cbfunc t (function reference)

cbdata

Data to be passed to the callback function (memory reference)

Returns one of the following:

• PMIX SUCCESS, indicating that the request is being processed by the host environment - result will be returned in the provided *cbfunc*. Note that the host must not invoke the callback function prior to returning from the API.

1	<ul> <li>PMIX_OPERATION_SUCCEEDED, indicating that the request was immediately processed and returned success - the cbfunc will not be called</li> </ul>
3 4 5	• PMIX_ERR_NOT_SUPPORTED, indicating that the host environment does not support the request, even though the function entry was provided in the server module - the <i>cbfunc</i> will not be called
6 7	• a PMIx error constant indicating either an error in the input or that the request was immediately processed and failed - the <i>cbfunc</i> will not be called
	Required Attributes
8	PMIx libraries are required to pass any provided attributes to the host environment for processing.
9 10	Host environments that provide this module entry point are required to support the following attributes:
11 12 13	PMIX_RANGE "pmix.range" (pmix_data_range_t)  Define constraints on the processes that can access the provided data. Only processes that meet the constraints are allowed to access it.
14 15 16 17	<b>Description</b> Notify the specified processes (described through a combination of <i>range</i> and attributes provided in the <i>info</i> array) of an event generated either by the PMIx server itself or by one of its local clients. The process generating the event is provided in the <i>source</i> parameter, and any further descriptive information is included in the <i>info</i> array.
19 20 21	Note that the PMIx server library is not allowed to echo any event given to it by its host via the  PMIx_Notify_event API back to the host through the  pmix_server_notify_event_fn_t server module function.  Advice to PMIx server hosts
22 23 24	The callback function is to be executed once the host environment no longer requires that the PMIx server library maintain the provided data structures. It does not necessarily indicate that the event has been delivered to any process, nor that the event has been distributed for delivery

# 16.3.17 pmix\_server\_listener\_fn\_t

# **Summary**

Register a socket the host server can monitor for connection requests.

26

```
Format
 1
 2
               typedef pmix status t (*pmix server listener fn t)(
 3
                                                       int listening sd,
                                                       pmix connection cbfunc t cbfunc,
 4
 5
                                                       void *cbdata);
               IN
 6
                     incoming sd
 7
                    (integer)
 8
               IN
                     cbfunc
 9
                    Callback function pmix connection cbfunc t (function reference)
10
               IN
                     cbdata
11
                    (memory reference)
12
               Returns PMIX SUCCESS indicating that the request is accepted, or a negative value corresponding
               to a PMIx error constant indicating that the request has been rejected.
13
14
               Description
15
               Register a socket the host environment can monitor for connection requests, harvest them, and then
               call the PMIx server library's internal callback function for further processing. A listener thread is
16
               essential to efficiently harvesting connection requests from large numbers of local clients such as
17
18
               occur when running on large SMPs. The host server listener is required to call accept on the
               incoming connection request, and then pass the resulting socket to the provided cbfunc. A NULL
19
               for this function will cause the internal PMIx server to spawn its own listener thread.
20
    16.3.17.1
                  PMIx Client Connection Callback Function
21
22
               Summary
23
               Callback function for incoming connection request from a local client.
               Format
   PMIx v1.0
25
               typedef void (*pmix_connection_cbfunc_t)(
                                           int incoming sd, void *cbdata);
26
               IN
27
                     incoming_sd
28
                    (integer)
29
                     cbdata
                     (memory reference)
30
31
               Description
32
               Callback function for incoming connection requests from local clients - only used by host
33
               environments that wish to directly handle socket connection requests.
```

# 16.3.18 pmix\_server\_query\_fn\_t

#### Summarv 3 Query information from the resource manager. **Format** <sup>4</sup> *PMIx v2.0* 5 typedef pmix\_status\_t (\*pmix\_server\_query\_fn\_t)( pmix\_proc\_t \*proct, 6 7 pmix\_query\_t \*queries, 8 size\_t nqueries, 9 pmix\_info\_cbfunc\_t cbfunc 10 void \*cbdata); IN 11 proct 12 pmix proc t structure of the requesting process (handle) IN 13 queries Array of pmix\_query\_t structures (array of handles) 14 15 IN nqueries 16 Number of elements in the *queries* array (integer) 17 IN cbfunc Callback function pmix\_info\_cbfunc\_t (function reference) 18 IN 19 cbdata 20 Data to be passed to the callback function (memory reference) Returns one of the following: 21 22 • PMIX\_SUCCESS, indicating that the request is being processed by the host environment - result will be returned in the provided cbfunc. Note that the host must not invoke the callback function 23 24 prior to returning from the API. 25 • PMIX OPERATION SUCCEEDED, indicating that the request was immediately processed and 26 returned success - the cbfunc will not be called 27 • PMIX ERR NOT SUPPORTED, indicating that the host environment does not support the 28 request, even though the function entry was provided in the server module - the cbfunc will not 29 be called 30 a PMIx error constant indicating either an error in the input or that the request was immediately 31 processed and failed - the cbfunc will not be called

	▼ Required Attributes
1 2	PMIx libraries are required to pass any provided attributes to the host environment for processing. In addition, the following attributes are required to be included in the passed <i>info</i> array:
3 4	PMIX_USERID "pmix.euid" (uint32_t)  Effective user ID of the connecting process.
5 6	PMIX_GRPID "pmix.egid" (uint32_t)  Effective group ID of the connecting process.
	▼ Optional Attributes
7	The following attributes are optional for host environments that support this operation:
8 9	<pre>PMIX_QUERY_NAMESPACES "pmix.qry.ns" (char*) Request a comma-delimited list of active namespaces. NO QUALIFIERS.</pre>
10 11 12	<pre>PMIX_QUERY_JOB_STATUS "pmix.qry.jst" (pmix_status_t) Status of a specified, currently executing job. REQUIRED QUALIFIER: PMIX_NSPACE indicating the namespace whose status is being queried.</pre>
13 14	<pre>PMIX_QUERY_QUEUE_LIST "pmix.qry.qlst" (char*) Request a comma-delimited list of scheduler queues. NO QUALIFIERS.</pre>
15 16 17 18	<pre>PMIX_QUERY_QUEUE_STATUS "pmix.qry.qst" (char*) Returns status of a specified scheduler queue, expressed as a string. OPTIONAL QUALIFIERS: PMIX_ALLOC_QUEUE naming specific queue whose status is being requested.</pre>
19 20 21 22	PMIX_QUERY_PROC_TABLE "pmix.qry.ptable" (char*)  Returns a (pmix_data_array_t) array of pmix_proc_info_t, one entry for each process in the specified namespace, ordered by process job rank. REQUIRED QUALIFIER: PMIX_NSPACE indicating the namespace whose process table is being queried.
23 24 25 26 27 28 29	PMIX_QUERY_LOCAL_PROC_TABLE "pmix.qry.lptable" (char*)  Returns a (pmix_data_array_t) array of pmix_proc_info_t, one entry for each process in the specified namespace executing on the same node as the requester, ordered by process job rank. REQUIRED QUALIFIER: PMIX_NSPACE indicating the namespace whose local process table is being queried. OPTIONAL QUALIFIER: PMIX_HOSTNAME indicating the host whose local process table is being queried. By default, the query assumes that the host upon which the request was made is to be used.
30 31	<pre>PMIX_QUERY_SPAWN_SUPPORT "pmix.qry.spawn" (bool) Return a comma-delimited list of supported spawn attributes. NO QUALIFIERS.</pre>
32 33	<pre>PMIX_QUERY_DEBUG_SUPPORT "pmix.qry.debug" (bool) Return a comma-delimited list of supported debug attributes. NO QUALIFIERS.</pre>

1 2 3 4	PMIX_QUERY_MEMORY_USAGE "pmix.qry.mem" (bool)  Return information on memory usage for the processes indicated in the qualifiers.  OPTIONAL QUALIFIERS: PMIX_NSPACE and PMIX_RANK, or PMIX_PROCID of specific process(es) whose memory usage is being requested.
5 6	PMIX_QUERY_LOCAL_ONLY "pmix.qry.local" (bool)  Constrain the query to local information only. NO QUALIFIERS.
7 8	PMIX_QUERY_REPORT_AVG "pmix.qry.avg" (bool) Report only average values for sampled information. NO QUALIFIERS.
9 10	PMIX_QUERY_REPORT_MINMAX "pmix.qry.minmax" (bool) Report minimum and maximum values. NO QUALIFIERS.
11 12	<pre>PMIX_QUERY_ALLOC_STATUS "pmix.query.alloc" (char*)     String identifier of the allocation whose status is being requested. NO QUALIFIERS.</pre>
13 14 15 16	PMIX_TIME_REMAINING "pmix.time.remaining" (char*)  Query number of seconds (uint32_t) remaining in allocation for the specified namespace OPTIONAL QUALIFIERS: PMIX_NSPACE of the namespace whose info is being requested (defaults to allocation containing the caller).
17 18 19 20	Description  Query information from the host environment. The query will include the namespace/rank of the process that is requesting the info, an array of pmix_query_t describing the request, and a callback function/data for the return.  Advice to PMIx library implementers
21 22	The PMIx server library should not block in this function as the host environment may, depending upon the information being requested, require significant time to respond.
23 <b>16.3.1</b>	9 pmix_server_tool_connection_fn_t

24

25

Summary

Register that a tool has connected to the server.

```
Format
 1
2
              typedef void (*pmix server tool connection fn t)(
 3
                                                   pmix info t info[], size t ninfo,
                                                   pmix_tool_connection_cbfunc_t cbfunc,
 4
5
                                                   void *cbdata);
              IN
6
                   info
 7
                   Array of pmix info t structures (array of handles)
8
                  ninfo
9
                   Number of elements in the info array (integer)
10
              IN cbfunc
                   Callback function pmix tool connection cbfunc t (function reference)
11
              IN cbdata
12
                   Data to be passed to the callback function (memory reference)
13
                                              Required Attributes
              PMIx libraries are required to pass the following attributes in the info array:
14
              PMIX_USERID "pmix.euid" (uint32_t)
15
                    Effective user ID of the connecting process.
16
17
              PMIX GRPID "pmix.egid" (uint32 t)
                    Effective group ID of the connecting process.
18
              PMIX TOOL NSPACE "pmix.tool.nspace" (char*)
19
20
                    Name of the namespace to use for this tool. This must be included only if the tool already
                    has an assigned namespace.
21
              PMIX TOOL RANK "pmix.tool.rank" (uint32 t)
22
                    Rank of this tool. This must be included only if the tool already has an assigned rank.
23
24
              PMIX CREDENTIAL "pmix.cred" (char*)
                    Security credential assigned to the process.
25
```

### Optional Attributes

The following attributes are optional for host environments that support this operation:

#### PMIX\_FWD\_STDOUT "pmix.fwd.stdout" (bool)

Requests that the ability to forward the **stdout** of the spawned processes be maintained. The requester will issue a call to **PMIx\_IOF\_pull** to specify the callback function and other options for delivery of the forwarded output.

#### PMIX\_FWD\_STDERR "pmix.fwd.stderr" (bool)

Requests that the ability to forward the **stderr** of the spawned processes be maintained. The requester will issue a call to **PMIx\_IOF\_pull** to specify the callback function and other options for delivery of the forwarded output.

#### PMIX\_FWD\_STDIN "pmix.fwd.stdin" (pmix\_rank\_t)

The requester intends to push information from its **stdin** to the indicated process. The local spawn agent should, therefore, ensure that the **stdin** channel to that process remains available. A rank of **PMIX\_RANK\_WILDCARD** indicates that all processes in the spawned job are potential recipients. The requester will issue a call to **PMIX\_IOF\_push** to initiate the actual forwarding of information to specified targets - this attribute simply requests that the IL retain the ability to forward the information to the designated targets.

#### PMIX VERSION INFO "pmix.version" (char\*)

PMIx version of the library being used by the connecting process.

### Description

Register that a tool has connected to the server, possibly requesting that the tool be assigned a namespace/rank identifier for further interactions. The <code>pmix\_info\_t</code> array is used to pass qualifiers for the connection request, including the effective uid and gid of the calling tool for authentication purposes.

If the tool already has an assigned process identifier, then this must be indicated in the *info* array. The host is responsible for checking that the provided namespace does not conflict with any currently known assignments, returning an appropriate error in the callback function if a conflict is found.

The host environment is solely responsible for authenticating and authorizing the connection using whatever means it deems appropriate. If certificates or other authentication information are required, then the tool must provide them. The conclusion of those operations shall be communicated back to the PMIx server library via the callback function.

Approval or rejection of the connection request shall be returned in the *status* parameter of the **pmix\_tool\_connection\_cbfunc\_t**. If the connection is refused, the PMIx server library must terminate the connection attempt. The host must not execute the callback function prior to returning from the API.

```
16.3.19.1
                 Tool connection attributes
 2
               Attributes associated with tool connections.
               PMIX USERID "pmix.euid" (uint32 t)
 3
                    Effective user ID of the connecting process.
 4
 5
               PMIX GRPID "pmix.egid" (uint32 t)
                    Effective group ID of the connecting process.
6
               PMIX VERSION INFO "pmix.version" (char*)
 7
                    PMIx version of the library being used by the connecting process.
8
                 PMIx Tool Connection Callback Function
    16.3.19.2
9
               Summary
10
               Callback function for incoming tool connections.
11
               Format
   PMIx v2.0
               typedef void (*pmix_tool_connection_cbfunc_t)(
13
14
                                        pmix status t status,
15
                                        pmix_proc_t *proc, void *cbdata);
               IN
                   status
16
                   pmix_status_t value (handle)
17
               IN
18
                  proc
19
                   pmix_proc_t structure containing the identifier assigned to the tool (handle)
               IN
20
                   cbdata
                   Data to be passed (memory reference)
21
               Description
22
               Callback function for incoming tool connections. The host environment shall provide a
23
               namespace/rank identifier for the connecting tool.
24
                                         Advice to PMIx server hosts -
25
               It is assumed that rank=0 will be the normal assignment, but allow for the future possibility of a
26
               parallel set of tools connecting, and thus each process requiring a unique rank.
    16.3.20
                 pmix_server_log_fn_t
```

#### Summary

28 29

Log data on behalf of a client.

```
Format
 1
 2
               typedef void (*pmix server log fn t) (
 3
                                         const pmix proc t *client,
                                        const pmix_info_t data[], size_t ndata,
 4
 5
                                        const pmix_info_t directives[], size_t ndirs,
                                        pmix op cbfunc t cbfunc, void *cbdata);
6
               IN
7
                   client
 8
                   pmix_proc_t structure (handle)
9
               IN
                    data
10
                   Array of info structures (array of handles)
               IN
                   ndata
11
                   Number of elements in the data array (integer)
12
               IN
                   directives
13
14
                   Array of info structures (array of handles)
15
               IN
                  ndirs
                   Number of elements in the directives array (integer)
16
17
               IN
                   cbfunc
                   Callback function pmix_op_cbfunc_t (function reference)
18
19
               IN
                    cbdata
                   Data to be passed to the callback function (memory reference)
20
                                               Required Attributes
21
               PMIx libraries are required to pass any provided attributes to the host environment for processing.
22
               In addition, the following attributes are required to be included in the passed info array:
23
               PMIX USERID "pmix.euid" (uint32 t)
24
                    Effective user ID of the connecting process.
               PMIX GRPID "pmix.egid" (uint32_t)
25
26
                    Effective group ID of the connecting process.
27
               Host environments that provide this module entry point are required to support the following
28
29
               attributes:
               PMIX_LOG_STDERR "pmix.log.stderr" (char*)
30
                    Log string to stderr.
31
32
               PMIX LOG STDOUT "pmix.log.stdout" (char*)
33
                    Log string to stdout.
               PMIX_LOG_SYSLOG "pmix.log.syslog" (char*)
34
```

Log data to syslog. Defaults to **ERROR** priority. Will log to global syslog if available, 1 2 otherwise to local syslog. Optional Attributes The following attributes are optional for host environments that support this operation: 3 4 PMIX LOG MSG "pmix.log.msg" (pmix byte object t) Message blob to be sent somewhere. 5 PMIX\_LOG\_EMAIL "pmix.log.email" (pmix\_data\_array\_t) 6 Log via email based on **pmix\_info\_t** containing directives. 7 8 PMIX LOG EMAIL ADDR "pmix.log.emaddr" (char\*) Comma-delimited list of email addresses that are to receive the message. 9 PMIX\_LOG\_EMAIL\_SUBJECT "pmix.log.emsub" (char\*) 10 11 Subject line for email. PMIX\_LOG\_EMAIL\_MSG "pmix.log.emmsg" (char\*) 12 Message to be included in email. 13 **Description** 14 Log data on behalf of a client. This function is not intended for output of computational results, but 15 16 rather for reporting status and error messages. The host must not execute the callback function prior to returning from the API. 17 16.3.21 pmix\_server\_alloc\_fn\_t 18 Summary 19 20 Request allocation operations on behalf of a client.

2

3

4

5

6 7

8

9

10

11 12

13 14

15

16

17

18 19

20

21

22

23 24

25

26

27

28 29

30

31

32 33

34

1 2	PMIX_GRPID "pmix.egid" (uint32_t)  Effective group ID of the connecting process.
3	
4 5	Host environments that provide this module entry point are required to support the following attributes:
6 7 8	<pre>PMIX_ALLOC_ID "pmix.alloc.id" (char*) A string identifier (provided by the host environment) for the resulting allocation which can later be used to reference the allocated resources in, for example, a call to PMIx_Spawn.</pre>
9 0	<pre>PMIX_ALLOC_NUM_NODES "pmix.alloc.nnodes" (uint64_t) The number of nodes being requested in an allocation request.</pre>
1 2	<pre>PMIX_ALLOC_NUM_CPUS "pmix.alloc.ncpus" (uint64_t) Number of PUs being requested in an allocation request.</pre>
3 4	PMIX_ALLOC_TIME "pmix.alloc.time" (uint32_t)  Total session time (in seconds) being requested in an allocation request.
	→ Optional Attributes
5	The following attributes are optional for host environments that support this operation:
6 7	<pre>PMIX_ALLOC_NODE_LIST "pmix.alloc.nlist" (char*) Regular expression of the specific nodes being requested in an allocation request.</pre>
8 9 20	<pre>PMIX_ALLOC_NUM_CPU_LIST "pmix.alloc.ncpulist" (char*) Regular expression of the number of PUs for each node being requested in an allocation request.</pre>
?1 ?2	<pre>PMIX_ALLOC_CPU_LIST "pmix.alloc.cpulist" (char*) Regular expression of the specific PUs being requested in an allocation request.</pre>
23 24 25	<pre>PMIX_ALLOC_MEM_SIZE "pmix.alloc.msize" (float) Number of Megabytes[base2] of memory (per process) being requested in an allocation request.</pre>
26 27 28	PMIX_ALLOC_FABRIC "pmix.alloc.net" (array)  Array of pmix_info_t describing requested fabric resources. This must include at least:  PMIX_ALLOC_FABRIC_ID, PMIX_ALLOC_FABRIC_TYPE, and  PMIX_ALLOC_FABRIC_ENDPTS, plus whatever other descriptors are desired.
20	DMIV ALLOC FARRIC ID "priv allog notid" (chart)

1 The key to be used when accessing this requested fabric allocation. The fabric allocation 2 will be returned/stored as a pmix data array t of pmix info t whose first element is composed of this key and the allocated resource description. The type of the 3 4 included value depends upon the fabric support. For example, a TCP allocation might 5 consist of a comma-delimited string of socket ranges such as "32000-32100, 6 33005, 38123-38146". Additional array entries will consist of any provided resource 7 request directives, along with their assigned values. Examples include: PMIX ALLOC FABRIC TYPE - the type of resources provided; 8 9 PMIX ALLOC FABRIC PLANE - if applicable, what plane the resources were assigned 10 from; PMIX\_ALLOC\_FABRIC\_QOS - the assigned QoS; PMIX\_ALLOC\_BANDWIDTH the allocated bandwidth; **PMIX\_ALLOC\_FABRIC\_SEC\_KEY** - a security key for the 11 requested fabric allocation. NOTE: the array contents may differ from those requested, 12 13 especially if **PMIX INFO REOD** was not set in the request.

#### PMIX\_ALLOC\_BANDWIDTH "pmix.alloc.bw" (float)

Fabric bandwidth (in Megabits[base2]/sec) for the job being requested in an allocation request.

PMIX\_ALLOC\_FABRIC\_QOS "pmix.alloc.netqos" (char\*)

Fabric quality of service level for the job being requested in an allocation request.

### **Description**

Request new allocation or modifications to an existing allocation on behalf of a client. Several broad categories are envisioned, including the ability to:

- Request allocation of additional resources, including memory, bandwidth, and compute for an existing allocation. Any additional allocated resources will be considered as part of the current allocation, and thus will be released at the same time.
- Request a new allocation of resources. Note that the new allocation will be disjoint from (i.e., not
  affiliated with) the allocation of the requestor thus the termination of one allocation will not
  impact the other.
- Extend the reservation on currently allocated resources, subject to scheduling availability and priorities.
- Return no-longer-required resources to the scheduler. This includes the *loan* of resources back to the scheduler with a promise to return them upon subsequent request.

The callback function provides a *status* to indicate whether or not the request was granted, and to provide some information as to the reason for any denial in the **pmix\_info\_cbfunc\_t** array of **pmix\_info\_t** structures.

## 16.3.22 pmix\_server\_job\_control\_fn\_t

### Summary

Execute a job control action on behalf of a client.

14

15 16

17

18

19

20

21 22

23

24 25

26 27

28 29

30

31 32

33

34

35

36

- will be returned in the provided cbfunc. Note that the host must not invoke the callback function
- PMIX ERR NOT SUPPORTED, indicating that the host environment does not support the request, even though the function entry was provided in the server module - the cbfunc will not be called

32 33

34

• a PMIx error constant indicating either an error in the input or that the request was immediately processed and failed - the cbfunc will not be called

#### Required Attributes PMIx libraries are required to pass any attributes provided by the client to the host environment for 1 processing. In addition, the following attributes are required to be included in the passed *info* array: 2 3 PMIX USERID "pmix.euid" (uint32 t) Effective user ID of the connecting process. 4 5 PMIX GRPID "pmix.eqid" (uint32 t) Effective group ID of the connecting process. 6 7 Host environments that provide this module entry point are required to support the following 8 9 attributes: 10 PMIX JOB CTRL ID "pmix.jctrl.id" (char\*) 11 Provide a string identifier for this request. The user can provide an identifier for the requested operation, thus allowing them to later request status of the operation or to 12 terminate it. The host, therefore, shall track it with the request for future reference. 13 PMIX JOB CTRL PAUSE "pmix.jctrl.pause" (bool) 14 Pause the specified processes. 15 16 PMIX JOB CTRL RESUME "pmix.jctrl.resume" (bool) Resume ("un-pause") the specified processes. 17 18 PMIX JOB CTRL KILL "pmix.jctrl.kill" (bool) Forcibly terminate the specified processes and cleanup. 19 PMIX\_JOB\_CTRL\_SIGNAL "pmix.jctrl.sig" (int) 20 Send given signal to specified processes. 21 22 PMIX JOB CTRL TERMINATE "pmix.jctrl.term" (bool) Politely terminate the specified processes. 23 Optional Attributes The following attributes are optional for host environments that support this operation: 24 25 PMIX\_JOB\_CTRL\_CANCEL "pmix.jctrl.cancel" (char\*) Cancel the specified request - the provided request ID must match the 26 PMIX JOB\_CTRL\_ID provided to a previous call to PMIx\_Job\_control. An ID of 27 **NULL** implies cancel all requests from this requestor. 28 PMIX\_JOB\_CTRL\_RESTART "pmix.jctrl.restart" (char\*) 29 Restart the specified processes using the given checkpoint ID. 30 PMIX JOB CTRL CHECKPOINT "pmix.jctrl.ckpt" (char\*) 31 Checkpoint the specified processes and assign the given ID to it. 32

```
PMIX_JOB_CTRL_CHECKPOINT_EVENT "pmix.jctrl.ckptev" (bool)
 1
 2
                     Use event notification to trigger a process checkpoint.
 3
               PMIX_JOB_CTRL_CHECKPOINT_SIGNAL "pmix.jctrl.ckptsig" (int)
                     Use the given signal to trigger a process checkpoint.
 4
               PMIX_JOB_CTRL_CHECKPOINT_TIMEOUT "pmix.jctrl.ckptsig" (int)
 5
 6
                     Time in seconds to wait for a checkpoint to complete.
 7
               PMIX JOB CTRL CHECKPOINT METHOD
8
               "pmix.jctrl.ckmethod" (pmix_data_array_t)
9
                     Array of pmix_info_t declaring each method and value supported by this application.
10
               PMIX_JOB_CTRL_PROVISION "pmix.jctrl.pvn" (char*)
11
                     Regular expression identifying nodes that are to be provisioned.
               PMIX_JOB_CTRL_PROVISION_IMAGE "pmix.jctrl.pvnimg" (char*)
12
13
                     Name of the image that is to be provisioned.
               PMIX_JOB_CTRL_PREEMPTIBLE "pmix.jctrl.preempt" (bool)
14
15
                     Indicate that the job can be pre-empted.
               Description
16
17
               Execute a job control action on behalf of a client. The targets array identifies the processes to
               which the requested job control action is to be applied. A NULL value can be used to indicate all
18
19
               processes in the caller's namespace. The use of PMIX RANK WILDCARD can also be used to
               indicate that all processes in the given namespace are to be included.
20
21
               The directives are provided as pmix info t structures in the directives array. The callback
22
               function provides a status to indicate whether or not the request was granted, and to provide some
23
               information as to the reason for any denial in the pmix info cbfunc t array of
               pmix_info_t structures.
24
```

# 5 16.3.23 pmix\_server\_monitor\_fn\_t

### Summary

26

27

Request that a client be monitored for activity.

- IN requestor
- pmix proc t structure of requesting process (handle)
- IN monitor

11

12

13 14

15

16 17

18

19 20

21

22

23 24

25

26

27

28 29

30

31

32

33

34

35 36

- pmix\_info\_t identifying the type of monitor being requested (handle)
- IN error
  - Status code to use in generating event if alarm triggers (integer)
- IN directives
  - Array of info structures (array of handles)
- IN ndirs
  - Number of elements in the *info* array (integer)
- IN cbfunc
  - Callback function **pmix** info **cbfunc** t (function reference)
- IN cbdata
  - Data to be passed to the callback function (memory reference)

Returns one of the following:

- PMIX\_SUCCESS, indicating that the request is being processed by the host environment result will be returned in the provided *cbfunc*. Note that the host must not invoke the callback function prior to returning from the API.
- **PMIX\_OPERATION\_SUCCEEDED**, indicating that the request was immediately processed and returned *success* the *cbfunc* will not be called
- PMIX\_ERR\_NOT\_SUPPORTED, indicating that the host environment does not support the request, even though the function entry was provided in the server module the *cbfunc* will not be called
- a PMIx error constant indicating either an error in the input or that the request was immediately processed and failed the *cbfunc* will not be called

This entry point is only called for monitoring requests that are not directly supported by the PMIx server library itself.

Required Attributes
If supported by the PMIx server library, then the library must not pass any supported attributes to the host environment. Any attributes provided by the client that are not directly supported by the server library must be passed to the host environment if it provides this module entry. In addition, the following attributes are required to be included in the passed <i>info</i> array:
PMIX_USERID "pmix.euid" (uint32_t) Effective user ID of the connecting process.
PMIX_GRPID "pmix.egid" (uint32_t)  Effective group ID of the connecting process.
Host environments are not required to support any specific monitoring attributes.
▼ Optional Attributes
The following attributes may be implemented by a host environment.
PMIX_MONITOR_ID "pmix.monitor.id" (char*) Provide a string identifier for this request.
<pre>PMIX_MONITOR_CANCEL "pmix.monitor.cancel" (char*)     Identifier to be canceled (NULL means cancel all monitoring for this process).</pre>
PMIX_MONITOR_APP_CONTROL "pmix.monitor.appctrl" (bool)  The application desires to control the response to a monitoring event - i.e., the application is requesting that the host environment not take immediate action in response to the event (e.g., terminating the job).
PMIX_MONITOR_HEARTBEAT "pmix.monitor.mbeat" (void) Register to have the PMIx server monitor the requestor for heartbeats.
<pre>PMIX_MONITOR_HEARTBEAT_TIME "pmix.monitor.btime" (uint32_t) Time in seconds before declaring heartbeat missed.</pre>
<pre>PMIX_MONITOR_HEARTBEAT_DROPS "pmix.monitor.bdrop" (uint32_t) Number of heartbeats that can be missed before generating the event.</pre>
<pre>PMIX_MONITOR_FILE "pmix.monitor.fmon" (char*) Register to monitor file for signs of life.</pre>
PMIX_MONITOR_FILE_SIZE "pmix.monitor.fsize" (bool)  Monitor size of given file is growing to determine if the application is running.
PMIX_MONITOR_FILE_ACCESS "pmix.monitor.faccess" (char*)  Monitor time since last access of given file to determine if the application is running.
<pre>PMIX_MONITOR_FILE_MODIFY "pmix.monitor.fmod" (char*)  Monitor time since last modified of given file to determine if the application is running.</pre>

```
PMIX_MONITOR_FILE_CHECK_TIME "pmix.monitor.ftime" (uint32_t)
 1
 2
                     Time in seconds between checking the file.
               PMIX_MONITOR_FILE_DROPS "pmix.monitor.fdrop" (uint32_t)
 3
                     Number of file checks that can be missed before generating the event.
 4
               Description
 5
               Request that a client be monitored for activity.
 6
    16.3.24
                 pmix server get cred fn t
               Summary
8
9
               Request a credential from the host environment.
               Format
^{10} PMIx v3.0
11
               typedef pmix_status_t (*pmix_server_get_cred_fn_t)(
12
                                                     const pmix_proc_t *proc,
                                                     const pmix_info_t directives[],
13
14
                                                     size_t ndirs,
                                                     pmix_credential_cbfunc_t cbfunc,
15
16
                                                     void *cbdata);
17
               IN
                    proc
18
                    pmix proc t structure of requesting process (handle)
19
               IN
                    directives
                    Array of info structures (array of handles)
20
               IN
                   ndirs
21
22
                    Number of elements in the info array (integer)
               IN cbfunc
23
24
                    Callback function to return the credential (pmix credential cbfunc t function
                    reference)
25
26
               IN
                    cbdata
27
                    Data to be passed to the callback function (memory reference)
28
               • PMIX_SUCCESS, indicating that the request is being processed by the host environment - result
                 will be returned in the provided cbfunc
29
30
               • PMIX ERR NOT SUPPORTED, indicating that the host environment does not support the
                 request, even though the function entry was provided in the server module - the cbfunc will not
31
                 be called
32
33
               • a PMIx error constant indicating either an error in the input or that the request was immediately
34
                 processed and failed - the cbfunc will not be called
```

#### Required Attributes If the PMIx library does not itself provide the requested credential, then it is required to pass any 1 attributes provided by the client to the host environment for processing. In addition, it must include 2 the following attributes in the passed *info* array: 3 PMIX USERID "pmix.euid" (uint32 t) 4 Effective user ID of the connecting process. 5 6 PMIX GRPID "pmix.eqid" (uint32 t) 7 Effective group ID of the connecting process. **Optional Attributes** The following attributes are optional for host environments that support this operation: 8 9 PMIX CRED TYPE "pmix.sec.ctype" (char\*) When passed in PMIx\_Get\_credential, a prioritized, comma-delimited list of desired 10 credential types for use in environments where multiple authentication mechanisms may be 11 available. When returned in a callback function, a string identifier of the credential type. 12 PMIX\_TIMEOUT "pmix.timeout" (int) 13 Time in seconds before the specified operation should time out (zero indicating infinite) and 14 return the PMIX ERR TIMEOUT error. Care should be taken to avoid race conditions 15 16 caused by multiple layers (client, server, and host) simultaneously timing the operation. Description 17 Request a credential from the host environment. 18 16.3.24.1 Credential callback function 19 Summary 20 21 Callback function to return a requested security credential

#### Format 1 typedef void (\*pmix credential cbfunc t)( 2 3 pmix status t status, 4 pmix byte object t \*credential, pmix\_info\_t info[], size\_t ninfo, 5 void \*cbdata); 6 IN 7 status 8 pmix status t value (handle) 9 IN credential 10 pmix\_byte\_object\_t structure containing the security credential (handle) IN info 11 12 Array of provided by the system to pass any additional information about the credential - e.g., the identity of the issuing agent. (handle) 13 14 IN ninfo 15 Number of elements in *info* (size t) 16 IN 17 Object passed in original request (memory reference) 18 Description 19 Define a callback function to return a requested security credential. Information provided by the issuing agent can subsequently be used by the application for a variety of purposes. Examples 20 21 include: 22 • checking identified authorizations to determine what requests/operations are feasible as a means 23 to steering workflows • compare the credential type to that of the local SMS for compatibility 24 Advice to users — 25 The credential is opaque and therefore understandable only by a service compatible with the issuer. The *info* array is owned by the PMIx library and is not to be released or altered by the receiving 26 27 party.

## 16.3.25 pmix\_server\_validate\_cred\_fn\_t

### Summary

Request validation of a credential.

Effective user ID of the connecting process.

1 2	PMIX_GRPID "pmix.egid" (uint32_t)  Effective group ID of the connecting process.
3	
4	Host environments are not required to support any specific attributes.
	▼ Optional Attributes
5	The following attributes are optional for host environments that support this operation:
6 7 8 9	PMIX_TIMEOUT "pmix.timeout" (int)  Time in seconds before the specified operation should time out (zero indicating infinite) and return the PMIX_ERR_TIMEOUT error. Care should be taken to avoid race conditions caused by multiple layers (client, server, and host) simultaneously timing the operation.
10 11 12	<b>Description</b> Request validation of a credential obtained from the host environment via a prior call to the  pmix_server_get_cred_fn_t module entry.
13	16.3.26 Credential validation callback function

Summary

Callback function for security credential validation.

#### **Format** 1 typedef void (\*pmix validation cbfunc t) ( 2 3 pmix status t status, pmix\_info\_t info[], size\_t ninfo, 4 5 void \*cbdata); IN 6 status 7 pmix status t value (handle) 8 IN info 9 Array of pmix info t provided by the system to pass any additional information about the 10 authentication - e.g., the effective userid and group id of the certificate holder, and any related authorizations (handle) 11 12 ninfo Number of elements in *info* (size t) 13 14 IN cbdata 15 Object passed in original request (memory reference) 16 The returned status shall be one of the following: 17 • PMIX SUCCESS, indicating that the request was processed and returned success (i.e., the credential was both valid and any information it contained was successfully processed). Details 18 19 of the result will be returned in the *info* array 20 • a PMIx error constant indicating either an error in the parsing of the credential or that the request was refused 21 **Description** 22 Define a validation callback function to indicate if a provided credential is valid, and any 23 corresponding information regarding authorizations and other security matters. 24 Advice to users 25 The precise contents of the array will depend on the host environment and its associated security system. At the minimum, it is expected (but not required) that the array will contain entries for the 26 27 **PMIX USERID** and **PMIX GRPID** of the client described in the credential. The *info* array is

# 16.3.27 pmix\_server\_iof\_fn\_t

### Summary

28

30 31

Request the specified IO channels be forwarded from the given array of processes.

owned by the PMIx library and is not to be released or altered by the receiving party.

Effective user ID of the connecting process. PMIX GRPID "pmix.egid" (uint32 t) Effective group ID of the connecting process. Host environments that provide this module entry point are required to support the following attributes: PMIX IOF CACHE SIZE "pmix.iof.csize" (uint32 t) The requested size of the PMIx server cache in bytes for each specified channel. By default, the server is allowed (but not required) to drop all bytes received beyond the max size. PMIX IOF DROP OLDEST "pmix.iof.old" (bool) In an overflow situation, the PMIx server is to drop the oldest bytes to make room in the cache. PMIX IOF DROP NEWEST "pmix.iof.new" (bool) In an overflow situation, the PMIx server is to drop any new bytes received until room becomes available in the cache (default). Optional Attributes The following attributes may be supported by a host environment. PMIX\_IOF\_BUFFERING\_SIZE "pmix.iof.bsize" (uint32\_t) Requests that IO on the specified channel(s) be aggregated in the PMIx tool library until the specified number of bytes is collected to avoid being called every time a block of IO arrives. The PMIx tool library will execute the callback and reset the collection counter whenever the specified number of bytes becomes available. Any remaining buffered data will be flushed to the callback upon a call to deregister the respective channel. PMIX\_IOF\_BUFFERING\_TIME "pmix.iof.btime" (uint32\_t) Max time in seconds to buffer IO before delivering it. Used in conjunction with buffering size, this prevents IO from being held indefinitely while waiting for another payload to arrive.

1

2

3

5

6

7

8

9

10

11

12

13 14

15

16

17

18

19 20

21

22

23

24

#### Description 1 2 Request the specified IO channels be forwarded from the given array of processes. An error shall be returned in the callback function if the requested service from any of the requested processes cannot 3 4 be provided. Advice to PMIx library implementers -5 The forwarding of stdin is a *push* process - processes cannot request that it be *pulled* from some other source. Requests including the PMIX\_FWD\_STDIN\_CHANNEL channel will return a 6 7 PMIX ERR NOT SUPPORTED error. **IOF** delivery function 16.3.27.1 Summary 9 Callback function for delivering forwarded IO to a process. 10 **Format** <sup>11</sup> *PMIx v3.0* 12 typedef void (\*pmix\_iof\_cbfunc\_t)( 13 size\_t iofhdlr, pmix\_iof\_channel\_t channel, pmix\_proc\_t \*source, char \*payload, 14 15 pmix\_info\_t info[], size\_t ninfo); IN iofhdlr 16 Registration number of the handler being invoked (size\_t) 17 18 IN channel bitmask identifying the channel the data arrived on (pmix\_iof\_channel\_t) 19 IN 20 source 21 Pointer to a pmix proc t identifying the namespace/rank of the process that generated the 22 data (char\*) 23 IN payload

Array of pmix info t provided by the source containing metadata about the payload. This

IN

info

Pointer to character array containing the data.

could include **PMIX IOF COMPLETE** (handle)

24 25

26

#### Description

1

3

4 5

6

8

9

19

20

21

22 23

24

25

26 27

28

29 30

31

32

33

34

Define a callback function for delivering forwarded IO to a process. This function will be called whenever data becomes available, or a specified buffering size and/or time has been met.

#### Advice to users

Multiple strings may be included in a given *payload*, and the *payload* may *not* be **NULL** terminated. The user is responsible for releasing the *payload* memory. The *info* array is owned by the PMIx library and is not to be released or altered by the receiving party.

### 16.3.28 pmix\_server\_stdin\_fn\_t

#### Summary

Pass standard input data to the host environment for transmission to specified recipients.

```
Format
  PMIx v3.0
            typedef pmix_status_t (*pmix_server_stdin_fn_t)(
11
12
                                         const pmix_proc_t *source,
13
                                         const pmix_proc_t targets[],
14
                                         size_t ntargets,
                                         const pmix_info_t directives[],
15
                                         size_t ndirs,
16
17
                                         const pmix_byte_object_t *bo,
                                         pmix op cbfunc t cbfunc, void *cbdata);
18
```

IN source
 pmix\_proc\_t structure of source process (handle)
IN targets
 Array of pmix\_proc\_t target identifiers (handle)
IN ntargets
 Number of elements in the targets array (integer)

IN directives

Array of info structures (array of handles)

N ndirs

Number of elements in the *info* array (integer)

IN bo

Pointer to pmix byte object t containing the payload (handle)

IN cbfunc

Callback function **pmix** op **cbfunc t** (function reference)

IN cbdata

Data to be passed to the callback function (memory reference)

#### Returns one of the following: 1 • PMIX SUCCESS, indicating that the request is being processed by the host environment - result 2 will be returned in the provided cbfunc. Note that the library must not invoke the callback 3 4 function prior to returning from the API. 5 • PMIX OPERATION SUCCEEDED, indicating that the request was immediately processed and returned success - the cbfunc will not be called 6 7 • PMIX ERR NOT SUPPORTED, indicating that the host environment does not support the request, even though the function entry was provided in the server module - the *cbfunc* will not 8 be called 9 • a PMIx error constant indicating either an error in the input or that the request was immediately 10 processed and failed - the cbfunc will not be called 11 Required Attributes The following attributes are required to be included in the passed *info* array: 12 13 PMIX USERID "pmix.euid" (uint32 t) Effective user ID of the connecting process. 14 15 PMIX GRPID "pmix.eqid" (uint32 t) Effective group ID of the connecting process. 16

## Description

Passes stdin to the host environment for transmission to specified recipients. The host environment is responsible for forwarding the data to all locations that host the specified *targets* and delivering the payload to the PMIx server library connected to those clients.

## 16.3.29 pmix server grp fn t

### Summary

Request group operations (construct, destruct, etc.) on behalf of a set of processes.

17

18

19

20

22

Returns one of the following:

29

30

31

32 33

34

35

36 37

- PMIX SUCCESS, indicating that the request is being processed by the host environment result will be returned in the provided *cbfunc*. Note that the library must not invoke the callback function prior to returning from the API.
- PMIX\_OPERATION\_SUCCEEDED, indicating that the request was immediately processed and returned success - the cbfunc will not be called
- PMIX ERR\_NOT\_SUPPORTED, indicating that the host environment does not support the request, even though the function entry was provided in the server module - the cbfunc will not be called
- a PMIx error constant indicating either an error in the input or that the request was immediately processed and failed - the cbfunc will not be called

<b>Optional Attributes</b>
----------------------------

The following attributes may be supported by a host environment.

#### PMIX\_GROUP\_ASSIGN\_CONTEXT\_ID "pmix.grp.actxid" (bool)

Requests that the RM assign a new context identifier to the newly created group. The identifier is an unsigned, <code>size\_t</code> value that the RM guarantees to be unique across the range specified in the request. Thus, the value serves as a means of identifying the group within that range. If no range is specified, then the request defaults to <code>PMIX\_RANGE\_SESSION</code>.

### PMIX\_GROUP\_LOCAL\_ONLY "pmix.grp.lcl" (bool)

Group operation only involves local processes. PMIx implementations are *required* to automatically scan an array of group members for local vs remote processes - if only local processes are detected, the implementation need not execute a global collective for the operation unless a context ID has been requested from the host environment. This can result in significant time savings. This attribute can be used to optimize the operation by indicating whether or not only local processes are represented, thus allowing the implementation to bypass the scan.

### PMIX\_GROUP\_ENDPT\_DATA "pmix.grp.endpt" (pmix\_byte\_object\_t)

Data collected during group construction to ensure communication between group members is supported upon completion of the operation.

### PMIX\_GROUP\_OPTIONAL "pmix.grp.opt" (bool)

Participation is optional - do not return an error if any of the specified processes terminate without having joined. The default is **false**.

#### PMIX RANGE "pmix.range" (pmix data range t)

Define constraints on the processes that can access the provided data. Only processes that meet the constraints are allowed to access it.

The following attributes may be included in the host's response:

```
PMIX_GROUP_ID "pmix.grp.id" (char*)
```

User-provided group identifier - as the group identifier may be used in PMIx operations, the user is required to ensure that the provided ID is unique within the scope of the host environment (e.g., by including some user-specific or application-specific prefix or suffix to the string).

```
PMIX_GROUP_MEMBERSHIP "pmix.grp.mbrs" (pmix_data_array_t*)
```

Array pmix\_proc\_t identifiers identifying the members of the specified group.

```
PMIX_GROUP_CONTEXT_ID "pmix.grp.ctxid" (size_t)
```

Context identifier assigned to the group by the host RM.

```
PMIX GROUP_ENDPT_DATA "pmix.grp.endpt" (pmix_byte_object_t)
```

Data collected during group construction to ensure communication between group members is supported upon completion of the operation.

Description 1 2 Perform the specified operation across the identified processes, plus any special actions included in the directives. Return the result of any special action requests in the callback function when the 3 operation is completed. Actions may include a request (PMIX GROUP ASSIGN CONTEXT ID) 4 5 that the host assign a unique numerical (size t) ID to this group - if given, the PMIX RANGE attribute will specify the range across which the ID must be unique (default to 6 7 PMIX RANGE SESSION). **Group Operation Constants** 16.3.29.1 8 PMIx v4.0 The pmix\_group\_operation\_t structure is a uint8\_t value for specifying group operations. All values were originally defined in version 4 of the standard unless otherwise marked. 10 11 PMIX\_GROUP\_CONSTRUCT Construct a group composed of the specified processes - used by 12 a PMIx server library to direct host operation. PMIX\_GROUP\_DESTRUCT 13 Destruct the specified group - used by a PMIx server library to 14 direct host operation. 16.3.30 pmix server fabric fn t 15 Summary 16 Request fabric-related operations (e.g., information on a fabric) on behalf of a tool or other process. 17 **Format** PMIx v4 0 typedef pmix status t (\*pmix server fabric fn t) ( 19 20 const pmix proc t \*requestor, pmix\_fabric\_operation\_t op, 21 22 const pmix info t directives[], 23 size t ndirs, pmix info cbfunc t cbfunc, 24 25 void \*cbdata); IN 26 requestor pmix\_proc\_t identifying the requestor (handle) 27 IN 28 29 pmix fabric operation t value indicating operation the host is requested to perform (integer) 30 directives 31 32 Array of info structures (array of handles) IN 33 ndirs 34 Number of elements in the *info* array (integer)

1	IN cbfunc
2	Callback function pmix_info_cbfunc_t (function reference)
3 4	IN cbdata  Data to be passed to the callback function (memory reference)
-	
5	Returns one of the following:
6 7 8	• PMIX_SUCCESS, indicating that the request is being processed by the host environment - result will be returned in the provided <i>cbfunc</i> . Note that the library must not invoke the callback function prior to returning from the API.
9 10	<ul> <li>PMIX_OPERATION_SUCCEEDED, indicating that the request was immediately processed and returned success - the cbfunc will not be called</li> </ul>
11 12 13	• PMIX_ERR_NOT_SUPPORTED, indicating that the host environment does not support the request, even though the function entry was provided in the server module - the <i>cbfunc</i> will not be called
14 15	• a PMIx error constant indicating either an error in the input or that the request was immediately processed and failed - the <i>cbfunc</i> will not be called
	▼ Required Attributes
16 17	The following directives are required to be supported by all hosts to aid users in identifying the fabric and (if applicable) the device to whom the operation references:
18 19	<pre>PMIX_FABRIC_VENDOR "pmix.fab.vndr" (string) Name of the vendor (e.g., Amazon, Mellanox, HPE, Intel) for the specified fabric.</pre>
20 21	PMIX_FABRIC_IDENTIFIER "pmix.fab.id" (string)  An identifier for the specified fabric (e.g., MgmtEthernet, Slingshot-11, OmniPath-1).
22 23	PMIX_FABRIC_PLANE "pmix.fab.plane" (string)  ID string of a fabric plane (e.g., CIDR for Ethernet). When used as a modifier in a request
24	for information, specifies the plane whose information is to be returned. When used directly
25 26	as a key in a request, returns a <b>pmix_data_array_t</b> of string identifiers for all fabric planes in the overall system.
27 28	PMIX_FABRIC_DEVICE_INDEX "pmix.fabdev.idx" (uint32_t)  Index of the device within an associated communication cost matrix.
_0	A control and device within an associated confinement of cost matrix.
29	Description
30	Perform the specified operation. Return the result of any requests in the callback function when the
31	operation is completed. Operations may, for example, include a request for fabric information. See

Perform the specified operation. Return the result of any requests in the callback function when the operation is completed. Operations may, for example, include a request for fabric information. See <code>pmix\_fabric\_t</code> for a list of expected information to be included in the response. Note that requests for device index are to be returned in the callback function's array of <code>pmix\_info\_t</code> using the <code>PMIX\_FABRIC\_DEVICE\_INDEX</code> attribute.

#### **CHAPTER 17**

# **Tools and Debuggers**

The term *tool* widely refers to programs executed by the user or system administrator on a command line. Tools frequently interact with either the SMS, user applications, or both to perform administrative and support functions. For example, a debugger tool might be used to remotely control the processes of a parallel application, monitoring their behavior on a step-by-step basis. Historically, such tools were custom-written for each specific host environment due to the customized and/or proprietary nature of the environment's interfaces.

The advent of PMIx offers the possibility for creating portable tools capable of interacting with multiple RMs without modification. Possible use-cases include:

- querying the status of scheduling queues and estimated allocation time for various resource options
- job submission and allocation requests
- querying job status for executing applications
- launching, monitoring, and debugging applications

Enabling these capabilities requires some extensions to the PMIx Standard (both in terms of APIs and attributes), and utilization of client-side APIs for more tool-oriented purposes.

This chapter defines specific APIs related to tools, provides tool developers with an overview of the support provided by PMIx, and serves to guide RM vendors regarding roles and responsibilities of RMs to support tools. As the number of tool-specific APIs and attributes is fairly small, the bulk of the chapter serves to provide a "theory of operation" for tools and debuggers. Description of the APIs themselves is therefore deferred to the Section 17.5 later in the chapter.

# 17.1 Connection Mechanisms

The key to supporting tools lies in providing mechanisms by which a tool can connect to a PMIx server. Application processes are able to connect because their local RM daemon provides them with the necessary contact information upon execution. A command-line tool, however, isn't spawned by an RM daemon, and therefore lacks the information required for rendezvous with a PMIx server.

Once a tool has started, it initializes PMIx as a tool (via PMIx\_tool\_init) if its access is restricted to PMIx-based informational services such as PMIx\_Query\_info. However, if the

tool intends to start jobs, then it must include the **PMIX\_LAUNCHER** attribute to inform the library of that intent so that the library can initialize and provide access to the corresponding support.

Support for tools requires that the PMIx server be initialized with an appropriate attribute indicating that tool connections are to be allowed. Separate attributes are provided to "fine-tune" this permission by allowing the environment to independently enable (or disable) connections from tools executing on nodes other than the one hosting the server itself. The PMIx server library shall provide an opportunity for the host environment to authenticate and approve each connection request from a specific tool by calling the <code>pmix\_server\_tool\_connection\_fn\_t</code> "hook" provided in the server module for that purpose. Servers in environments that do not provide this "hook" shall automatically reject all tool connection requests.

Tools can connect to any local or remote PMIx server provided they are either explicitly given the required connection information, or are able to discover it via one of several defined rendezvous protocols. Connection discovery centers around the existence of *rendezvous files* containing the necessary connection information, as illustrated in Fig. 17.1.




Figure 17.1.: Tool rendezvous files

The contents of each rendezvous file are specific to a given PMIx implementation, but should at least contain the namespace and rank of the server along with its connection URI. Note that tools linked to one PMIx implementation are therefore unlikely to successfully connect to PMIx server libraries from another implementation.

The top of the directory tree is defined by either the PMIX\_SYSTEM\_TMPDIR attribute (if given) or the TMPDIR environmental variable. PMIx servers that are designated as *system servers* by including the PMIX\_SERVER\_SYSTEM\_SUPPORT attribute when calling PMIX\_SERVER\_SYSTEM\_SUPPORT attribute when calling PMIX\_server\_init will create a rendezvous file in this top-level directory. The filename will be of the form *pmix.sys.hostname*, where *hostname* is the string returned by the gethostname system call. Note that only one PMIx server on a node can be designated as the system server.

Non-system PMIx servers will create a set of three rendezvous files in the directory defined by either the **PMIX\_SERVER\_TMPDIR** attribute or the **TMPDIR** environmental variable:

- *pmix.host.tool.nspace* where *host* is the string returned by the **gethostname** system call and *nspace* is the namespace of the server.
- *pmix.host.tool.pid* where *host* is the string returned by the **gethostname** system call and *pid* is the PID of the server.
- pmix.host.tool where host is the string returned by the **gethostname** system call. Note that servers which are not given a namespace-specific **PMIX\_SERVER\_TMPDIR** attribute may not generate this file due to conflicts should multiple servers be present on the node.

The files are identical and may be implemented as symlinks to a single instance. The individual file names are composed so as to aid the search process should a tool wish to connect to a server identified by its namespace or PID.

Servers will additionally provide a rendezvous file in any given location if the path (either absolute or relative) and filename is specified either during <code>PMIx\_server\_init</code> using the <code>PMIX\_LAUNCHER\_RENDEZVOUS\_FILE</code> attribute, or by the <code>PMIX\_LAUNCHER\_RNDZ\_FILE</code> environmental variable prior to executing the process containing the server. This latter mechanism may be the preferred mechanism for tools such as debuggers that need to fork/exec a launcher (e.g., "mpiexec") and then rendezvous with it. This is described in more detail in Section 17.2.2.

Rendezvous file ownerships are set to the UID and GID of the server that created them, with permissions set according to the desires of the implementation and/or system administrator policy. All connection attempts are first governed by read access privileges to the target rendezvous file - thus, the combination of permissions, UID, and GID of the rendezvous files act as a first-level of security for tool access.

A tool may connect to as many servers at one time as the implementation supports, but is limited to designating only one such connection as its *primary* server. This is done to avoid confusion when the tool calls an API as to which server should service the request. The first server the tool connects to is automatically designated as the *primary* server.

Tools are allowed to change their primary server at any time via the PMIx\_tool\_set\_server API, and to connect/disconnect from a server as many times as desired. Note that standing requests (e.g., event registrations) with the current primary server may be lost and/or may not be transferred when transitioning to another primary server - PMIx implementors are not required to maintain or transfer state across tool-server connections.

Tool process identifiers are assigned by one of the following methods:

- If PMIX\_TOOL\_NSPACE is given, then the namespace of the tool will be assigned that value.
  - If PMIX\_TOOL\_RANK is also given, then the rank of the tool will be assigned that value.
  - If **PMIX\_TOOL\_RANK** is not given, then the rank will be set to a default value of zero.
- If a process ID is not provided and the tool connects to a server, then one will be assigned by the host environment upon connection to that server.

• If a process ID is not provided and the tool does not connect to a server (e.g., if **PMIX\_TOOL\_DO\_NOT\_CONNECT** is given), then the tool shall self-assign a unique identifier. This is often done using some combination involving hostname and PID.

Tool process identifiers remain constant across servers. Thus, it is critical that a system-wide unique namespace be provided if the tool itself sets the identifier, and that host environments provide a system-wide unique identifier in the case where the identifier is set by the server upon connection. The host environment is required to reject any connection request that fails to meet this criterion.

For simplicity, the following descriptions will refer to the:

- PMIX\_SYSTEM\_TMPDIR as the directory specified by either the PMIX\_SYSTEM\_TMPDIR attribute (if given) or the TMPDIR environmental variable.
- PMIX\_SERVER\_TMPDIR as the directory specified by either the PMIX\_SERVER\_TMPDIR attribute or the TMPDIR environmental variable.

The rendezvous methods are automatically employed for the initial tool connection during PMIx\_tool\_init unless the PMIX\_TOOL\_DO\_NOT\_CONNECT attribute is specified, and on all subsequent calls to PMIx\_tool\_attach\_to\_server.

# 17.1.1 Rendezvousing with a local server

Connection to a local PMIx server is pursued according to the following precedence chain based on attributes contained in the call to the PMIx\_tool\_init or PMIx\_tool\_attach\_to\_server APIs. Servers to which the tool already holds a connection will be ignored. Except where noted, the PMIx library will return an error if the specified file cannot be found, the caller lacks permissions to read it, or the server specified within the file does not respond to or accept the connection — the library will not proceed to check for other connection options as the user specified a particular one to use.

Note that the PMIx implementation may choose to introduce a "delayed connection" protocol between steps in the precedence chain - i.e., the library may cycle several times, checking for creation of the rendezvous file each time after a delay of some period of time, thereby allowing the tool to wait for the server to create the rendezvous file before either returning an error or continuing to the next step in the chain.

- If PMIX\_TOOL\_ATTACHMENT\_FILE is given, then the tool will attempt to read the specified file and connect to the server based on the information contained within it. The format of the attachment file is identical to the rendezvous files described in earlier in this section. An error will be returned if the specified file cannot be found.
- If PMIX\_SERVER\_URI or PMIX\_TCP\_URI is given, then connection will be attempted to the server at the specified URI. Note that it is an error for both of these attributes to be specified.
   PMIX\_SERVER\_URI is the preferred method as it is more generalized PMIX\_TCP\_URI is provided for those cases where the user specifically wants to use a TCP transport for the connection and wants to error out if one isn't available or cannot be used.

- If PMIX\_SERVER\_PIDINFO was provided, then the tool will search for a rendezvous file
  created by a PMIx server of the given PID in the PMIX\_SERVER\_TMPDIR directory. An error
  will be returned if a matching rendezvous file cannot be found.
  - If **PMIX\_SERVER\_NSPACE** is given, then the tool will search for a rendezvous file created by a PMIx server of the given namespace in the **PMIX\_SERVER\_TMPDIR** directory. An error will be returned if a matching rendezvous file cannot be found.
  - If **PMIX\_CONNECT\_TO\_SYSTEM** is given, then the tool will search for a system-level rendezvous file created by a PMIx server in the **PMIX\_SYSTEM\_TMPDIR** directory. An error will be returned if a matching rendezvous file cannot be found.
  - If **PMIX\_CONNECT\_SYSTEM\_FIRST** is given, then the tool will look for a system-level rendezvous file created by a PMIx server in the **PMIX\_SYSTEM\_TMPDIR** directory. If found, then the tool will attempt to connect to it. In this case, no error will be returned if the rendezvous file is not found or connection is refused the PMIx library will silently continue to the next option.
  - By default, the tool will search the directory tree under the PMIX\_SERVER\_TMPDIR directory
    for rendezvous files of PMIx servers, attempting to connect to each it finds until one accepts the
    connection. If no rendezvous files are found, or all contacted servers refuse connection, then the
    PMIx library will return an error. No "delayed connection" protocols may be utilized at this point.

Note that there can be multiple local servers - one from the system plus others from launchers and active jobs. The PMIx tool connection search method is not guaranteed to pick a particular server unless directed to do so. Tools can obtain a list of servers available on their local node using the PMIx\_Query\_info APIs with the PMIX\_QUERY\_AVAIL\_SERVERS key.

# 17.1.2 Connecting to a remote server

Connecting to remote servers is complicated due to the lack of access to the previously-described rendezvous files. Two methods are required to be supported, both based on the caller having explicit knowledge of either connection information or a path to a local file that contains such information:

- If **PMIX\_TOOL\_ATTACHMENT\_FILE** is given, then the tool will attempt to read the specified file and connect to the server based on the information contained within it. The format of the attachment file is identical to the rendezvous files described in earlier in this section.
- If PMIX\_SERVER\_URI or PMIX\_TCP\_URI is given, then connection will be attempted to the server at the specified URI. Note that it is an error for both of these attributes to be specified.

  PMIX\_SERVER\_URI is the preferred method as it is more generalized PMIX\_TCP\_URI is provided for those cases where the user specifically wants to use the TCP transport for the connection and wants to error out if it isn't available or cannot be used.

Additional methods may be provided by particular PMIx implementations. For example, the tool may use *ssh* to launch a *probe* process onto the remote node so that the probe can search the **PMIX\_SYSTEM\_TMPDIR** and **PMIX\_SERVER\_TMPDIR** directories for rendezvous files,

relaying the discovered information back to the requesting tool. If sufficient information is found to allow for remote connection, then the tool can use it to establish the connection. Note that this method is not required to be supported - it is provided here as an example and left to the discretion of PMIx implementors.

#### 17.1.3 Attaching to running jobs

1

2

3

4

6 7

8

9

10

11

12 13

14

15

16 17

18

19 20

21

22

23

24 25

26 27

28 29

30

31

33

34 35 When attaching to a running job, the tool must connect to a PMIx server that is associated with that job - e.g., a server residing in the host environment's local daemon that spawned one or more of the job's processes, or the server residing in the launcher that is overseeing the job. Identifying an appropriate server can sometimes prove challenging, particularly in an environment where multiple job launchers may be in operation, possibly under control of the same user.

In cases where the user has only the one job of interest in operation on the local node (e.g., when engaged in an interactive session on the node from which the launcher was executed), the normal rendezvous file discovery method can often be used to successfully connect to the target job, even in the presence of jobs executed by other users. The permissions and security authorizations can, in many cases, reliably ensure that only the one connection can be made. However, this is not guaranteed in all cases.

The most common method, therefore, for attaching to a running job is to specify either the PID of the job's launcher or the namespace of the launcher's job (note that the launcher's namespace frequently differs from the namespace of the job it has launched). Unless the application processes themselves act as PMIx servers, connection must be to the servers in the daemons that oversee the application. This is typically either daemons specifically started by the job's launcher process, or daemons belonging to the host environment, that are responsible for starting the application's processes and oversee their execution.

Identifying the correct PID or namespace can be accomplished in a variety of ways, including:

- Using typical OS or host environment tools to obtain a listing of active jobs and perusing those to find the target launcher.
- Using a PMIx-based tool attached to a system-level server to query the active jobs and their command lines, thereby identifying the application of interest and its associated launcher.
- Manually recording the PID of the launcher upon starting the job.

Once the namespace and/or PID of the target server has been identified, either of the previous methods can be used to connect to it.

## 17.1.4 Tool initialization attributes

The following attributes are passed to the **PMIx\_tool\_init** API for use when initializing the PMIx library.

PMIX TOOL NSPACE "pmix.tool.nspace" (char\*)

1		Name of the namespace to use for this tool.
2		<pre>PMIX_TOOL_RANK "pmix.tool.rank" (uint32_t)</pre>
3		Rank of this tool.
4		PMIX_LAUNCHER "pmix.tool.launcher" (bool)
5		Tool is a launcher and needs to create rendezvous files.
6	17.1.5	Tool initialization environmental variables
7 8 9		The following environmental variables are used during <b>PMIx_tool_init</b> and <b>PMIx_server_init</b> to control various rendezvous-related operations when the process is started manually (e.g., on a command line) or by a fork/exec-like operation.
10 11 12 13 14 15 16 17 18		PMIX_LAUNCHER_RNDZ_URI  The spawned tool is to be connected back to the spawning tool using the given URI so that the spawning tool can provide directives (e.g., a PMIx_Spawn command) to it.  PMIX_LAUNCHER_RNDZ_FILE  If the specified file does not exist, this variable contains the absolute path of the file where the spawned tool is to store its connection information so that the spawning tool can connect to it. If the file does exist, it contains the information specifying the server to which the spawned tool is to connect.  PMIX_KEEPALIVE_PIPE  An integer read-end of a POSIX pipe that the tool should monitor for closure, thereby indicating that the parent tool has terminated. Used. for example, when a tool fork/exec's an
21 22 23		intermediate launcher that should self-terminate if the originating tool exits.  Note that these environmental variables should be cleared from the environment after use and prior to forking child processes to avoid potentially unexpected behavior by the child processes.
24	17.1.6	Tool connection attributes
25 26 27		These attributes are defined to assist PMIx-enabled tools to connect with a PMIx server by passing them into either the PMIx_tool_init or the PMIx_tool_attach_to_server APIs - thus, they are not typically accessed via the PMIx_Get API.
28 29 30 31 32		PMIX_SERVER_PIDINFO "pmix.srvr.pidinfo" (pid_t) PID of the target PMIx server for a tool.  PMIX_CONNECT_TO_SYSTEM "pmix.cnct.sys" (bool) The requester requires that a connection be made only to a local, system-level PMIx server.  PMIX_CONNECT_SYSTEM_FIRST "pmix.cnct.sys.first" (bool) Preferentially, look for a system-level PMIx server first.
34 35 36		PMIX_SERVER_URI "pmix.srvr.uri" (char*)  URI of the PMIx server to be contacted.  PMIX_SERVER_HOSTNAME "pmix.srvr.host" (char*)
37 38		Host where target PMIx server is located.  PMIX CONNECT MAX RETRIES "pmix.tool.mretries" (uint32 t)

1	Maximum number of times to try to connect to PMIx server - the default value is
2	implementation specific.
3	<pre>PMIX_CONNECT_RETRY_DELAY "pmix.tool.retry" (uint32_t)</pre>
4	Time in seconds between connection attempts to a PMIx server - the default value is
5	implementation specific.
6	PMIX_TOOL_DO_NOT_CONNECT "pmix.tool.nocon" (bool)
7	The tool wants to use internal PMIx support, but does not want to connect to a PMIx serve
8	PMIX_TOOL_CONNECT_OPTIONAL "pmix.tool.conopt" (bool)
9	The tool shall connect to a server if available, but otherwise continue to operate unconnect
0	<pre>PMIX_TOOL_ATTACHMENT_FILE "pmix.tool.attach" (char*)</pre>
1	Pathname of file containing connection information to be used for attaching to a specific
2	server.
3	<pre>PMIX_LAUNCHER_RENDEZVOUS_FILE "pmix.tool.lncrnd" (char*)</pre>
4	Pathname of file where the launcher is to store its connection information so that the
5	spawning tool can connect to it.
6	PMIX_PRIMARY_SERVER "pmix.pri.srvr" (bool)
7	The server to which the tool is connecting shall be designated the primary server once
8	connection has been accomplished.
9	PMIX_WAIT_FOR_CONNECTION "pmix.wait.conn" (bool)
20	Wait until the specified process has connected to the requesting tool or server, or the
1	operation times out (if the <b>PMTY_TIMEOUT</b> directive is included in the request)

# 17.2 Launching Applications with Tools

Tool-directed launches require that the tool include the **PMIX\_LAUNCHER** attribute when calling **PMIx\_tool\_init**. Two launch modes are supported:

- Direct launch where the tool itself is directly responsible for launching all processes, including debugger daemons, using either the RM or daemons launched by the tool i.e., there is no intermediate launcher (IL) such as mpiexec. The case where the tool is self-contained (i.e., uses its own daemons without interacting with an external entity such as the RM) lies outside the scope of this Standard; and
- *Indirect launch* where all processes are started via an IL such as *mpiexec* and the tool itself is not directly involved in launching application processes or debugger daemons. Note that the IL may utilize the RM to launch processes and/or daemons under the tool's direction.

Either of these methods can be executed interactively or by a batch script. Note that not all host environments may support the direct launch method.

### 17.2.1 Direct launch

In the direct-launch use-case (Fig. 17.2), the tool itself performs the role of the launcher. Once invoked, the tool connects to an appropriate PMIx server - e.g., a system-level server hosted by the

RM. The tool is responsible for assembling the description of the application to be launched (e.g., by parsing its command line) into a spawn request containing an array of <code>pmix\_app\_t</code> applications and <code>pmix\_info\_t</code> job-level information. An allocation of resources may or may not have been made in advance – if not, then the spawn request must include allocation request information.




Figure 17.2.: Direct Launch

In addition to the attributes described in **PMIx\_Spawn**, the tool may optionally wish to include the following tool-specific attributes in the *job\_info* argument to that API (the debugger-related attributes are discussed in more detail in Section 17.4):

- PMIX\_FWD\_STDIN "pmix.fwd.stdin" (pmix\_rank\_t)
  - The requester intends to push information from its **stdin** to the indicated process. The local spawn agent should, therefore, ensure that the **stdin** channel to that process remains available. A rank of **PMIX\_RANK\_WILDCARD** indicates that all processes in the spawned job are potential recipients. The requester will issue a call to **PMIx\_IOF\_push** to initiate the actual forwarding of information to specified targets this attribute simply requests that the IL retain the ability to forward the information to the designated targets.
- PMIX\_FWD\_STDOUT "pmix.fwd.stdout" (bool)

  Requests that the ability to forward the stdout of the spawned processes be maintained.

  The requester will issue a call to PMIx\_IOF\_pull to specify the callback function and other options for delivery of the forwarded output.
- PMIX\_FWD\_STDERR "pmix.fwd.stderr" (bool)
   Requests that the ability to forward the stderr of the spawned processes be maintained.
   The requester will issue a call to PMIx\_IOF\_pull to specify the callback function and

1	other options for delivery of the forwarded output.
2 3 4 5	<ul> <li>PMIX_FWD_STDDIAG "pmix.fwd.stddiag" (bool)         Requests that the ability to forward the diagnostic channel (if it exists) of the spawned processes be maintained. The requester will issue a call to PMIx_IOF_pull to specify the callback function and other options for delivery of the forwarded output.     </li> </ul>
6 7 8 9	• PMIX_IOF_CACHE_SIZE "pmix.iof.csize" (uint32_t)  The requested size of the PMIx server cache in bytes for each specified channel. By default, the server is allowed (but not required) to drop all bytes received beyond the max size.
10 11 12	• PMIX_IOF_DROP_OLDEST "pmix.iof.old" (bool)  In an overflow situation, the PMIx server is to drop the oldest bytes to make room in the cache.
13 14 15	<ul> <li>PMIX_IOF_DROP_NEWEST "pmix.iof.new" (bool)</li> <li>In an overflow situation, the PMIx server is to drop any new bytes received until room becomes available in the cache (default).</li> </ul>
16 17 18 19 20 21	• PMIX_IOF_BUFFERING_SIZE "pmix.iof.bsize" (uint32_t) Requests that IO on the specified channel(s) be aggregated in the PMIx tool library until the specified number of bytes is collected to avoid being called every time a block of IO arrives. The PMIx tool library will execute the callback and reset the collection counter whenever the specified number of bytes becomes available. Any remaining buffered data will be <i>flushed</i> to the callback upon a call to deregister the respective channel.
22 23 24 25	<ul> <li>PMIX_IOF_BUFFERING_TIME "pmix.iof.btime" (uint32_t)</li> <li>Max time in seconds to buffer IO before delivering it. Used in conjunction with buffering size, this prevents IO from being held indefinitely while waiting for another payload to arrive.</li> </ul>
26 27 28	<ul> <li>PMIX_IOF_TAG_OUTPUT "pmix.iof.tag" (bool)</li> <li>Requests that output be prefixed with the nspace, rank of the source and a string identifying the channel (stdout, stderr, etc.).</li> </ul>
29 30 31	• PMIX_IOF_TIMESTAMP_OUTPUT "pmix.iof.ts" (bool)  Requests that output be marked with the time at which the data was received by the tool - note that this will differ from the time at which the data was collected from the source.
32 33	• PMIX_IOF_XML_OUTPUT "pmix.iof.xml" (bool)  Requests that output be formatted in XML.

• PMIX\_NOHUP "pmix.nohup" (bool)

Any processes started on behalf of the calling tool (or the specified namespace, if such specification is included in the list of attributes) should continue after the tool disconnects from its server.

• PMIX\_NOTIFY\_JOB\_EVENTS "pmix.note.jev" (bool)

 Requests that the launcher generate the PMIX\_EVENT\_JOB\_START,
PMIX\_LAUNCH\_COMPLETE, and PMIX\_EVENT\_JOB\_END events. Each event is to
include at least the namespace of the corresponding job and a

PMIX\_EVENT\_TIMESTAMP indicating the time the event occurred. Note that the
requester must register for these individual events, or capture and process them by
registering a default event handler instead of individual handlers and then process the
events based on the returned status code. Another common method is to register one event
handler for all job-related events, with a separate handler for non-job events - see
PMIX Register event handler for details.

### • PMIX\_NOTIFY\_COMPLETION "pmix.notecomp" (bool)

Requests that the launcher generate the PMIX\_EVENT\_JOB\_END event for normal or abnormal termination of the spawned job. The event shall include the returned status code (PMIX\_JOB\_TERM\_STATUS) for the corresponding job; the identity (PMIX\_PROCID) and exit status (PMIX\_EXIT\_CODE) of the first failed process, if applicable; and a PMIX\_EVENT\_TIMESTAMP indicating the time the termination occurred. Note that the requester must register for the event or capture and process it within a default event handler.

- PMIX\_LOG\_JOB\_EVENTS "pmix.log.jev" (bool)
   Requests that the launcher log the PMIX\_EVENT\_JOB\_START,
   PMIX\_LAUNCH\_COMPLETE, and PMIX\_EVENT\_JOB\_END events using PMIx\_Log,
   subject to the logging attributes of Section 12.4.3.
- PMIX\_LOG\_COMPLETION "pmix.logcomp" (bool)
  Requests that the launcher log the PMIX\_EVENT\_JOB\_END event for normal or abnormal termination of the spawned job using PMIx\_Log, subject to the logging attributes of Section 12.4.3. The event shall include the returned status code (PMIX\_JOB\_TERM\_STATUS) for the corresponding job; the identity (PMIX\_PROCID) and exit status (PMIX\_EXIT\_CODE) of the first failed process, if applicable; and a PMIX\_EVENT\_TIMESTAMP indicating the time the termination occurred.
- PMIX\_DEBUG\_STOP\_ON\_EXEC "pmix.dbg.exec" (bool)

  Included in either the pmix\_info\_t array in a pmix\_app\_t description (if the directive applies only to that application) or in the job\_info array if it applies to all applications in the given spawn request. Indicates that the application is being spawned under a debugger, and that the local launch agent is to pause the resulting application processes on first instruction for debugger attach. The launcher (RM or IL) is to generate the PMIX LAUNCH COMPLETE event when all processes are stopped at the exec point.
- PMIX\_DEBUG\_STOP\_IN\_INIT "pmix.dbg.init" (bool)

  Included in either the pmix\_info\_t array in a pmix\_app\_t description (if the directive applies only to that application) or in the job\_info array if it applies to all applications in the given spawn request. Indicates that the specified application is being spawned under a debugger. The PMIx client library in each resulting application process shall notify its PMIx server that it is pausing and then pause during PMIx\_Init of the

spawned processes until either released by debugger modification of an appropriate variable or receipt of the **PMIX\_DEBUGGER\_RELEASE** event. The launcher (RM or IL) is responsible for generating the **PMIX\_DEBUG\_WAITING\_FOR\_NOTIFY** event when all processes have reached the pause point.

#### • PMIX\_DEBUG\_WAIT\_FOR\_NOTIFY "pmix.dbg.notify" (bool)

Included in either the <code>pmix\_info\_t</code> array in a <code>pmix\_app\_t</code> description (if the directive applies only to that application) or in the <code>job\_info</code> array if it applies to all applications in the given spawn request. Indicates that the specified application is being spawned under a debugger. The resulting application processes are to notify their server (by generating the <code>PMIX\_DEBUG\_WAITING\_FOR\_NOTIFY</code> event) when they reach some application-determined location and pause at that point until either released by debugger modification of an appropriate variable or receipt of the <code>PMIX\_DEBUGGER\_RELEASE</code> event. The launcher (RM or IL) is responsible for generating the <code>PMIX\_DEBUG\_WAITING\_FOR\_NOTIFY</code> event when all processes have indicated they are at the pause point.

The tool then calls the **PMIx\_Spawn** API so that the PMIx library can communicate the spawn request to the server.

Upon receipt, the PMIx server library passes the spawn request to its host RM daemon for processing via the <code>pmix\_server\_spawn\_fn\_t</code> server module function. If this callback was not provided, then the PMIx server library will return the <code>PMIX\_ERR\_NOT\_SUPPORTED</code> error status.

If an allocation must be made, then the host environment is responsible for communicating the request to its associated scheduler. Once resources are available, the host environment initiates the launch process to start the job. The host environment must parse the spawn request for relevant directives, returning an error if any required directive cannot be supported. Optional directives may be ignored if they cannot be supported.

Any error while executing the spawn request must be returned by **PMIx\_Spawn** to the requester. Once the spawn request has succeeded in starting the specified processes, the request will return **PMIX\_SUCCESS** back to the requester along with the namespace of the started job. Upon termination of the spawned job, the host environment must generate a **PMIX\_EVENT\_JOB\_END** event for normal or abnormal termination if requested to do so. The event shall include:

- the returned status code (PMIX JOB TERM STATUS) for the corresponding job;
- the identity (PMIX\_PROCID) and exit status (PMIX\_EXIT\_CODE) of the first failed process, if applicable;
- a PMIX\_EVENT\_TIMESTAMP indicating the time the termination occurred; plus
- any other info provided by the host environment.

## 17.2.2 Indirect launch

In the indirect launch use-case, the application processes are started via an intermediate launcher (e.g., *mpiexec*) that is itself started by the tool (see Fig 17.3). Thus, at a high level, this is a

two-stage launch procedure to start the application: the tool (henceforth referred to as the *initiator*) starts the IL, which then starts the applications. In practice, additional steps may be involved if, for example, the IL starts its own daemons to shepherd the application processes.

A key aspect of this operational mode is the avoidance of any requirement that the initiator parse and/or understand the command line of the IL. Instead, the indirect launch procedure supports either of two methods: one where the initiator assumes responsibility for parsing its command line to obtain the application as well as the IL and its options, and another where the initiator defers the command line parsing to the IL. Both of these methods are described in the following sections.

## 17.2.2.1 Initiator-based command line parsing

This method utilizes a first call to the **PMIx\_Spawn** API to start the IL itself, and then uses a second call to **PMIx\_Spawn** to request that the IL spawn the actual job. The burden of analyzing the initial command line to separately identify the IL's command line from the application itself falls upon the initiator. An example is provided below:

```
$ initiator --launcher "mpiexec --verbose" -n 3 ./app <appoptions>
```

The initiator spawns the IL using the same procedure for launching an application - it begins by assembling the description of the IL into a spawn request containing an array of <code>pmix\_app\_t</code> and <code>pmix\_info\_t</code> job-level information. Note that this step does not include any information regarding the application itself - only the launcher is included. In addition, the initiator must include the rendezvous URI in the environment so the IL knows how to connect back to it.

An allocation of resources for the IL itself may or may not be required – if it is, then the allocation must be made in advance or the spawn request must include allocation request information.




Figure 17.3.: Indirect launch procedure

The initiator may optionally wish to include the following tool-specific attributes in the *job\_info* argument to **PMIx\_Spawn** - note that these attributes refer only to the behavior of the IL itself and not the eventual job to be launched:

• PMIX\_FWD\_STDIN "pmix.fwd.stdin" (pmix\_rank\_t)

13

14

7

17

18

23 24

25

22

26 27 28

29

34 35 36

37 38

39

The requester intends to push information from its **stdin** to the indicated process. The local spawn agent should, therefore, ensure that the **stdin** channel to that process remains available. A rank of PMIX RANK WILDCARD indicates that all processes in the spawned job are potential recipients. The requester will issue a call to PMIx IOF push to initiate the actual forwarding of information to specified targets - this attribute simply requests that the IL retain the ability to forward the information to the designated targets.

#### • PMIX FWD STDOUT "pmix.fwd.stdout" (bool)

Requests that the ability to forward the **stdout** of the spawned processes be maintained. The requester will issue a call to **PMIx\_IOF\_pull** to specify the callback function and other options for delivery of the forwarded output.

### • PMIX FWD STDERR "pmix.fwd.stderr" (bool)

Requests that the ability to forward the **stderr** of the spawned processes be maintained. The requester will issue a call to PMIx IOF pull to specify the callback function and other options for delivery of the forwarded output.

### • PMIX FWD STDDIAG "pmix.fwd.stddiag" (bool)

Requests that the ability to forward the diagnostic channel (if it exists) of the spawned processes be maintained. The requester will issue a call to PMIx IOF pull to specify the callback function and other options for delivery of the forwarded output.

#### • PMIX\_IOF\_CACHE\_SIZE "pmix.iof.csize" (uint32\_t)

The requested size of the PMIx server cache in bytes for each specified channel. By default, the server is allowed (but not required) to drop all bytes received beyond the max size.

## • PMIX\_IOF\_DROP\_OLDEST "pmix.iof.old" (bool)

In an overflow situation, the PMIx server is to drop the oldest bytes to make room in the cache.

## • PMIX\_IOF\_DROP\_NEWEST "pmix.iof.new" (bool)

In an overflow situation, the PMIx server is to drop any new bytes received until room becomes available in the cache (default).

### • PMIX IOF BUFFERING\_SIZE "pmix.iof.bsize" (uint32\_t)

Requests that IO on the specified channel(s) be aggregated in the PMIx tool library until the specified number of bytes is collected to avoid being called every time a block of IO arrives. The PMIx tool library will execute the callback and reset the collection counter whenever the specified number of bytes becomes available. Any remaining buffered data will be *flushed* to the callback upon a call to deregister the respective channel.

#### • PMIX\_IOF\_BUFFERING\_TIME "pmix.iof.btime" (uint32\_t)

Max time in seconds to buffer IO before delivering it. Used in conjunction with buffering size, this prevents IO from being held indefinitely while waiting for another payload to arrive.

• PMIX\_IOF\_TAG\_OUTPUT "pmix.iof.tag" (bool)

Requests that output be prefixed with the nspace, rank of the source and a string identifying the channel (**stdout**, **stderr**, etc.).

### • PMIX\_IOF\_TIMESTAMP\_OUTPUT "pmix.iof.ts" (bool)

Requests that output be marked with the time at which the data was received by the tool - note that this will differ from the time at which the data was collected from the source.

- PMIX\_IOF\_XML\_OUTPUT "pmix.iof.xml" (bool)

  Requests that output be formatted in XML.
- PMIX NOHUP "pmix.nohup" (bool)

Any processes started on behalf of the calling tool (or the specified namespace, if such specification is included in the list of attributes) should continue after the tool disconnects from its server.

### • PMIX\_LAUNCHER\_DAEMON "pmix.lnch.dmn" (char\*)

Path to executable that is to be used as the backend daemon for the launcher. This replaces the launcher's own daemon with the specified executable. Note that the user is therefore responsible for ensuring compatibility of the specified executable and the host launcher.

## • PMIX\_FORKEXEC\_AGENT "pmix.frkex.agnt" (char\*)

Path to executable that the launcher's backend daemons are to fork/exec in place of the actual application processes. The fork/exec agent shall connect back (as a PMIx tool) to the launcher's daemon to receive its spawn instructions, and is responsible for starting the actual application process it replaced. See Section 17.4.3 for details.

## • PMIX\_EXEC\_AGENT "pmix.exec.agnt" (char\*)

Path to executable that the launcher's backend daemons are to fork/exec in place of the actual application processes. The launcher's daemon shall pass the full command line of the application on the command line of the exec agent, which shall not connect back to the launcher's daemon. The exec agent is responsible for exec'ing the specified application process in its own place. See Section 17.4.3 for details.

#### • PMIX\_DEBUG\_STOP\_IN\_INIT "pmix.dbg.init" (bool)

Included in either the <code>pmix\_info\_t</code> array in a <code>pmix\_app\_t</code> description (if the directive applies only to that application) or in the <code>job\_info</code> array if it applies to all applications in the given spawn request. Indicates that the specified application is being spawned under a debugger. The PMIx client library in each resulting application process shall notify its PMIx server that it is pausing and then pause during <code>PMIx\_Init</code> of the spawned processes until either released by debugger modification of an appropriate variable or receipt of the <code>PMIX\_DEBUGGER\_RELEASE</code> event. The launcher (RM or IL) is responsible for generating the <code>PMIX\_DEBUG\_WAITING\_FOR\_NOTIFY</code> event when all processes have reached the pause point. In this context, the initiator is directing the IL to stop in <code>PMIx\_tool\_init</code>. This gives the initiator a chance to connect to the IL and register for events prior to the IL launching the application job.

and the following optional variables in the environment of the IL:

• PMIX\_KEEPALIVE\_PIPE - an integer read-end of a POSIX pipe that the IL should monitor for closure, thereby indicating that the initiator has terminated.

The initiator then calls the **PMIx\_Spawn** API so that the PMIx library can either communicate the spawn request to a server (if connected to one), or locally spawn the IL itself if not connected to a server and the PMIx implementation includes self-spawn support. **PMIx\_Spawn** shall return an error if neither of these conditions is met.

When initialized by the IL, the **PMIx\_tool\_init** function must perform two operations:

- check for the presence of the PMIX\_KEEPALIVE\_PIPE environmental variable if provided, then the library shall monitor the pipe for closure, providing a PMIX\_EVENT\_JOB\_END event when the pipe closes (thereby indicating the termination of the initiator). The IL should register for this event after completing PMIx\_tool\_init the initiator's namespace can be obtained via a call to PMIx\_Get with the PMIX\_PARENT\_ID key. Note that this feature will only be available if the spawned IL is local to the initiator.
- check for the PMIX\_LAUNCHER\_RNDZ\_URI environmental parameter if found, the library shall connect back to the initiator using the PMIx\_tool\_attach\_to\_server API, retaining its current server as its primary server.

Once the IL completes **PMIx\_tool\_init**, it must register for the **PMIX\_EVENT\_JOB\_END** termination event and then idle until receiving that event - either directly from the initiator, or from the PMIx library upon detecting closure of the keepalive pipe. The IL idles in the intervening time as it is solely acting as a relay (if connected to a server that is performing the actual application launch) or as a PMIx server responding to spawn requests.

Upon return from the **PMIx\_Spawn** API, the initiator should set the spawned IL as its primary server using the **PMIx\_tool\_set\_server** API with the nspace returned by **PMIx\_Spawn** and any valid rank (a rank of zero would ordinarily be used as only one IL process is typically started). It is advisable to set a connection timeout value when calling this function. The initiator can then proceed to spawn the actual application according to the procedure described in Section 17.2.1.

## 17.2.2.2 IL-based command line parsing

In the case where the initiator cannot parse its command line, it must defer that parsing to the IL. A common example is provided below:

```
$ initiator mpiexec --verbose -n 3 ./app <appoptions>
```

For this situation, the initiator proceeds as above with only one notable exception: instead of calling **PMIx\_Spawn** twice (once to start the IL and again to start the actual application), the initiator only calls that API one time:

- The *app* parameter passed to the spawn request contains only one **pmix\_app\_t** that contains the entire command line, including both launcher and application(s).
- The launcher executable must be in the *app.cmd* field and in *app.argv[0]*, with the rest of the command line appended to the *app.argv* array.

- Any job-level directives for the IL itself (e.g., PMIX\_FORKEXEC\_AGENT or
   PMIX\_FWD\_STDOUT) are included in the job\_info parameter of the call to PMIx\_Spawn.
  - The job-level directives must include both the PMIX\_SPAWN\_TOOL attribute indicating that the initiator is spawning a tool, and the PMIX\_DEBUG\_STOP\_IN\_INIT attribute directing the IL to stop during the call to PMIx\_tool\_init. The latter directive allows the initiator to connect to the IL prior to launch of the application.
  - The PMIX\_LAUNCHER\_RNDZ\_URI and PMIX\_KEEPALIVE\_PIPE environmental variables are provided to the launcher in its environment via the *app.env* field.
  - The IL must use PMIx\_Get with the PMIX\_LAUNCH\_DIRECTIVES key to obtain any initiator-provided directives (e.g., PMIX\_DEBUG\_STOP\_IN\_INIT or PMIX\_DEBUG\_STOP\_ON\_EXEC) aimed at the application(s) it will spawn.

Upon return from **PMIx\_Spawn**, the initiator must:

- use the **PMIx\_tool\_set\_server** API to set the spawned IL as its primary server
- register with that server to receive the **PMIX\_LAUNCH\_COMPLETE** event. This allows the initiator to know when the IL has completed launch of the application
- release the IL from its "hold" in PMIx\_tool\_init by issuing the
   PMIX\_DEBUGGER\_RELEASE event, specifying the IL as the custom range. Upon receipt of the
   event, the IL is free to parse its command line, apply any provided directives, and execute the
   application.

Upon receipt of the **PMIX\_LAUNCH\_COMPLETE** event, the initiator should register to receive notification of completion of the returned namespace of the application. Receipt of the **PMIX\_EVENT\_JOB\_END** event provides a signal that the initiator may itself terminate.

## 17.2.3 Tool spawn-related attributes

Tools are free to utilize the spawn attributes available to applications (see 11.2.4) when constructing a spawn request, but can also utilize the following attributes that are specific to tool-based spawn operations:

## PMIX FWD\_STDIN "pmix.fwd.stdin" (pmix\_rank\_t)

The requester intends to push information from its **stdin** to the indicated process. The local spawn agent should, therefore, ensure that the **stdin** channel to that process remains available. A rank of **PMIX\_RANK\_WILDCARD** indicates that all processes in the spawned job are potential recipients. The requester will issue a call to **PMIx\_IOF\_push** to initiate the actual forwarding of information to specified targets - this attribute simply requests that the IL retain the ability to forward the information to the designated targets.

### PMIX FWD STDOUT "pmix.fwd.stdout" (bool)

Requests that the ability to forward the **stdout** of the spawned processes be maintained. The requester will issue a call to **PMIx\_IOF\_pull** to specify the callback function and other options for delivery of the forwarded output.

## PMIX\_FWD\_STDERR "pmix.fwd.stderr" (bool)

Requests that the ability to forward the **stderr** of the spawned processes be maintained. The requester will issue a call to **PMIx\_IOF\_pull** to specify the callback function and other options for delivery of the forwarded output.

## PMIX\_FWD\_STDDIAG "pmix.fwd.stddiag" (bool)

Requests that the ability to forward the diagnostic channel (if it exists) of the spawned processes be maintained. The requester will issue a call to **PMIx\_IOF\_pull** to specify the callback function and other options for delivery of the forwarded output.

## PMIX\_NOHUP "pmix.nohup" (bool)

Any processes started on behalf of the calling tool (or the specified namespace, if such specification is included in the list of attributes) should continue after the tool disconnects from its server.

## PMIX\_LAUNCHER\_DAEMON "pmix.lnch.dmn" (char\*)

Path to executable that is to be used as the backend daemon for the launcher. This replaces the launcher's own daemon with the specified executable. Note that the user is therefore responsible for ensuring compatibility of the specified executable and the host launcher.

### PMIX FORKEXEC AGENT "pmix.frkex.agnt" (char\*)

Path to executable that the launcher's backend daemons are to fork/exec in place of the actual application processes. The fork/exec agent shall connect back (as a PMIx tool) to the launcher's daemon to receive its spawn instructions, and is responsible for starting the actual application process it replaced. See Section 17.4.3 for details.

### PMIX\_EXEC\_AGENT "pmix.exec.agnt" (char\*)

Path to executable that the launcher's backend daemons are to fork/exec in place of the actual application processes. The launcher's daemon shall pass the full command line of the application on the command line of the exec agent, which shall not connect back to the launcher's daemon. The exec agent is responsible for exec'ing the specified application process in its own place. See Section 17.4.3 for details.

PMIX\_LAUNCH\_DIRECTIVES "pmix.lnch.dirs" (pmix\_data\_array\_t\*)

Array of pmix\_info\_t containing directives for the launcher - a convenience attribute for retrieving all directives with a single call to PMIx\_Get.

## 17.2.4 Tool rendezvous-related events

The following constants refer to events relating to rendezvous of a tool and launcher during spawn of the IL.

PMIX\_LAUNCHER\_READY An application launcher (e.g., *mpiexec*) shall generate this event to signal a tool that started it that the launcher is ready to receive directives/commands (e.g., PMIx\_Spawn). This is only used when the initiator is able to parse the command line itself, or the launcher is started as a persistent Distributed Virtual Machine (DVM).

# 17.3 IO Forwarding

Underlying the operation of many tools is a common need to forward **stdin** from the tool to targeted processes, and to return **stdout/stderr** from those processes to the tool (e.g., for

display on the user's console). Historically, each tool developer was responsible for creating their own IO forwarding subsystem. However, the introduction of PMIx as a standard mechanism for interacting between applications and the host environment has made it possible to relieve tool developers of this burden.

This section defines functions by which tools can request forwarding of input/output to/from other processes and serves as a design guide to:

- provide tool developers with an overview of the expected behavior of the PMIx IO forwarding support;
- guide RM vendors regarding roles and responsibilities expected of the RM to support IO forwarding; and
- provide insight into the thinking of the PMIx community behind the definition of the PMIx IO forwarding APIs.

Note that the forwarding of IO via PMIx requires that both the host environment and the tool support PMIx, but does not impose any similar requirements on the application itself.

The responsibility of the host environment in forwarding of IO falls into the following areas:

- Capturing output from specified processes.
- Forwarding that output to the host of the PMIx server library that requested it.
- Delivering that payload to the PMIx server library via the **PMIx\_server\_IOF\_deliver** API for final dispatch to the requesting tool.

It is the responsibility of the PMIx library to buffer, format, and deliver the payload to the requesting client. This may require caching of output until a forwarding registration is received, as governed by the corresponding IO forwarding attributes of Section 17.3.5 that are supported by the implementation.

## 17.3.1 Forwarding stdout/stderr

At an appropriate point in its operation (usually during startup), a tool will utilize the **PMIx\_tool\_init** function to connect to a PMIx server. The PMIx server can be hosted by an RM daemon or could be embedded in a library-provided starter program such as *mpiexec* - in terms of IO forwarding, the operations remain the same either way. For purposes of this discussion, we will assume the server is in an RM daemon and that the application processes are directly launched by the RM, as shown in Fig 17.4.

Once the tool has connected to the target server, it can request that processes be spawned on its behalf or that output from a specified set of existing processes in a given executing application be forwarded to it. Requests to spawn processes should include the PMIX\_FWD\_STDIN,
PMIX\_FWD\_STDOUT, and/or PMIX\_FWD\_STDERR attributes if the tool intends to request that the corresponding streams be forwarded at some point during execution.






Figure 17.4.: Forwarding stdout/stderr

Note that requests to capture output from existing processes via the **PMIx\_IOF\_pull** API, and/or to forward input to specified processes via the **PMIx\_IOF\_push** API, can only succeed if the required attributes to retain that ability were passed when the corresponding job was spawned. The host is required to return an error for all such requests in cases where this condition is not met.

Two modes are supported when requesting that the host forward standard output/error via the **PMIx\_IOF\_pull** API - these can be controlled by including one of the following attributes in the *info* array passed to that function:

## • PMIX\_IOF\_COPY "pmix.iof.cpy" (bool)

Requests that the host environment deliver a copy of the specified output stream(s) to the tool, letting the stream(s) continue to also be delivered to the default location. This allows the tool to tap into the output stream(s) without redirecting it from its current final destination.

#### • PMIX IOF REDIRECT "pmix.iof.redir" (bool)

Requests that the host environment intercept the specified output stream(s) and deliver it to the requesting tool instead of its current final destination. This might be used, for example, during a debugging procedure to avoid injection of debugger-related output into the application's results file. The original output stream(s) destination is restored upon termination of the tool. This is the default mode of operation.

When requesting to forward **stdout/stderr**, the tool can specify several formatting options to be used on the resulting output stream. These include:

• PMIX\_IOF\_TAG\_OUTPUT "pmix.iof.tag" (bool)

Requests that output be prefixed with the nspace, rank of the source and a string identifying the channel (**stdout**, **stderr**, etc.).

- PMIX\_IOF\_TIMESTAMP\_OUTPUT "pmix.iof.ts" (bool)
   Requests that output be marked with the time at which the data was received by the tool note that this will differ from the time at which the data was collected from the source.
- PMIX\_IOF\_XML\_OUTPUT "pmix.iof.xml" (bool)
  Requests that output be formatted in XML.

The PMIx client in the tool is responsible for formatting the output stream. Note that output from multiple processes will often be interleaved due to variations in arrival time - ordering of output is not guaranteed across processes and/or nodes.

# 17.3.2 Forwarding stdin

A tool is not necessarily a child of the RM as it may have been started directly from the command line. Thus, provision must be made for the tool to collect its **stdin** and pass it to the host RM (via the PMIx server) for forwarding. Two methods of support for forwarding of **stdin** are defined:




Figure 17.5.: Forwarding stdin

• internal collection by the PMIx tool library itself. This is requested via the PMIX\_IOF\_PUSH\_STDIN attribute in the PMIx\_IOF\_push call. When this mode is selected, the tool library begins collecting all stdin data and internally passing it to the local

- server for distribution to the specified target processes. All collected data is sent to the same targets until **stdin** is closed, or a subsequent call to **PMIx\_IOF\_push** is made that includes the **PMIX\_IOF\_COMPLETE** attribute indicating that forwarding of **stdin** is to be terminated.
- external collection directly by the tool. It is assumed that the tool will provide its own code/mechanism for collecting its stdin as the tool developers may choose to insert some filtering and/or editing of the stream prior to forwarding it. In addition, the tool can directly control the targets for the data on a per-call basis i.e., each call to PMIx\_IOF\_push can specify its own set of target recipients for that particular blob of data. Thus, this method provides maximum flexibility, but requires that the tool developer provide their own code to capture stdin.

Note that it is the responsibility of the RM to forward data to the host where the target process(es) are executing, and for the host daemon on that node to deliver the data to the **stdin** of target process(es). The PMIx server on the remote node is not involved in this process. Systems that do not support forwarding of **stdin** shall return **PMIX\_ERR\_NOT\_SUPPORTED** in response to a forwarding request.

## Advice to users

Scalable forwarding of **stdin** represents a significant challenge. Most environments will at least handle a *send-to-1* model whereby **stdin** is forwarded to a single identified process, and occasionally an additional *send-to-all* model where **stdin** is forwarded to all processes in the application. Users are advised to check their host environment for available support as the distribution method lies outside the scope of PMIx.

**Stdin** buffering by the RM and/or PMIx library can be problematic. If any targeted recipient is slow reading data (or decides never to read data), then the data must be buffered in some intermediate daemon or the PMIx tool library itself. Thus, piping a large amount of data into **stdin** can result in a very large memory footprint in the system management stack or the tool. Best practices, therefore, typically focus on reading of input files by application processes as opposed to forwarding of **stdin**.

# 17.3.3 IO Forwarding Channels

*PMIx v3.0* The **pmix\_iof\_channel\_t** structure is a **uint16\_t** type that defines a set of bit-mask flags for specifying IO forwarding channels. These can be bitwise OR'd together to reference multiple channels. PMIX FWD NO CHANNELS Forward no channels. Forward stdin. PMIX\_FWD\_STDIN\_CHANNEL PMIX FWD STDOUT CHANNEL Forward **stdout**. Forward stderr.

34 PMIX\_FWD\_STDERR\_CHANNEL Forward stderr.
35 PMIX\_FWD\_STDDIAG\_CHANNEL Forward stddiag, if available.
36 PMIX FWD ALL CHANNELS Forward all available channels.

## 17.3.4 IO Forwarding constants

1	17.3.4	io Forwarding constants
2 3 4 5		PMIX_ERR_IOF_FAILURE An IO forwarding operation failed - the affected channel will be included in the notification.  PMIX_ERR_IOF_COMPLETE IO forwarding of the standard input for this process has completed - i.e., the stdin file descriptor has closed.
6	17.3.5	IO Forwarding attributes
7 8 9		The following attributes are used to control IO forwarding behavior at the request of tools. Use of the attributes is optional - any option not provided will revert to some implementation-specific value.
10 11 12 13		PMIX_IOF_CACHE_SIZE "pmix.iof.csize" (uint32_t)  The requested size of the PMIx server cache in bytes for each specified channel. By default, the server is allowed (but not required) to drop all bytes received beyond the max size.  PMIX_IOF_DROP_OLDEST "pmix.iof.old" (bool)  In an overflow situation, the PMIx server is to drop the oldest bytes to make room in the
15 16 17 18		cache.  PMIX_IOF_DROP_NEWEST "pmix.iof.new" (bool)  In an overflow situation, the PMIx server is to drop any new bytes received until room becomes available in the cache (default).
19 20 21 22 23		PMIX_IOF_BUFFERING_SIZE "pmix.iof.bsize" (uint32_t)  Requests that IO on the specified channel(s) be aggregated in the PMIx tool library until the specified number of bytes is collected to avoid being called every time a block of IO arrives. The PMIx tool library will execute the callback and reset the collection counter whenever the specified number of bytes becomes available. Any remaining buffered data will be <i>flushed</i> to the callback upon a call to deregister the respective channel.
25 26 27		PMIX_IOF_BUFFERING_TIME "pmix.iof.btime" (uint32_t)  Max time in seconds to buffer IO before delivering it. Used in conjunction with buffering size, this prevents IO from being held indefinitely while waiting for another payload to arrive
28 29 30		PMIX_IOF_COMPLETE "pmix.iof.cmp" (bool)  Indicates that the specified IO channel has been closed by the source.  PMIX_IOF_TAG_OUTPUT "pmix.iof.tag" (bool)
31 32		Requests that output be prefixed with the nspace, rank of the source and a string identifying the channel (stdout, stderr, etc.).
33 34 35		PMIX_IOF_TIMESTAMP_OUTPUT "pmix.iof.ts" (bool)  Requests that output be marked with the time at which the data was received by the tool - note that this will differ from the time at which the data was collected from the source.
36 37		PMIX_IOF_XML_OUTPUT "pmix.iof.xml" (bool) Requests that output be formatted in XML.
38		PMIX_IOF_PUSH_STDIN "pmix.iof.stdin" (bool)

1

6 7 8

10 11

9

13 14

12

15

16

18 19 20

17

21 22

23 24

25 26 27

28 29 30

31 32

33 34 35

36 37

38

Requests that the PMIx library collect the **stdin** of the requester and forward it to the processes specified in the PMIx IOF push call. All collected data is sent to the same targets until **stdin** is closed, or a subsequent call to **PMIx IOF push** is made that includes the **PMIX IOF COMPLETE** attribute indicating that forwarding of **stdin** is to be terminated.

### PMIX\_IOF\_COPY "pmix.iof.cpy" (bool)

Requests that the host environment deliver a copy of the specified output stream(s) to the tool, letting the stream(s) continue to also be delivered to the default location. This allows the tool to tap into the output stream(s) without redirecting it from its current final destination.

## PMIX IOF REDIRECT "pmix.iof.redir" (bool)

Requests that the host environment intercept the specified output stream(s) and deliver it to the requesting tool instead of its current final destination. This might be used, for example, during a debugging procedure to avoid injection of debugger-related output into the application's results file. The original output stream(s) destination is restored upon termination of the tool.

#### 17.4 **Debugger Support**

Debuggers are a class of tool that merits special consideration due to their particular requirements for access to job-related information and control over process execution. The primary advantage of using PMIx for these purposes lies in the resulting portability of the debugger as it can be used with any system and/or programming model that supports PMIx. In addition to the general tool support described above, debugger support includes:

- Co-location, co-spawn, and communication wireup of debugger daemons for scalable launch. This includes providing debugger daemons with endpoint connection information across the daemons themselves.
- Identification of the job that is to be debugged. This includes automatically providing debugger daemons with the job-level information for their target job.

Debuggers can also utilize the options in the PMIx\_Spawn API to exercise a degree of control over spawned jobs for debugging purposes. For example, a debugger can utilize the environmental parameter attributes of Section 11.2.4 to request LD\_PRELOAD of a memory interceptor library prior to spawning an application process, or interject a custom fork/exec agent to shepherd the application process.

A key element of the debugging process is the ability of the debugger to require that processes pause at some well-defined point, thereby providing the debugger with an opportunity to attach and control execution. The actual implementation of the pause lies outside the scope of PMIx - it typically requires either the launcher or the application itself to implement the necessary operations. However, PMIx does provide several standard attributes by which the debugger can specify the desired attach point:

• PMIX DEBUG STOP ON EXEC "pmix.dbg.exec" (bool)

Included in either the <code>pmix\_info\_t</code> array in a <code>pmix\_app\_t</code> description (if the directive applies only to that application) or in the <code>job\_info</code> array if it applies to all applications in the given spawn request. Indicates that the application is being spawned under a debugger, and that the local launch agent is to pause the resulting application processes on first instruction for debugger attach. The launcher (RM or IL) is to generate the <code>PMIX\_LAUNCH\_COMPLETE</code> event when all processes are stopped at the exec point. Launchers that cannot support this operation shall return an error from the <code>PMIx\_Spawn</code> API if this behavior is requested.

#### • PMIX DEBUG STOP IN INIT "pmix.dbg.init" (bool)

Included in either the <code>pmix\_info\_t</code> array in a <code>pmix\_app\_t</code> description (if the directive applies only to that application) or in the <code>job\_info</code> array if it applies to all applications in the given spawn request. Indicates that the specified application is being spawned under a debugger. The PMIx client library in each resulting application process shall notify its PMIx server that it is pausing and then pause during <code>PMIx\_Init</code> of the spawned processes until either released by debugger modification of an appropriate variable or receipt of the <code>PMIX\_DEBUGGER\_RELEASE</code> event. The launcher (RM or IL) is responsible for generating the <code>PMIX\_DEBUG\_WAITING\_FOR\_NOTIFY</code> event when all processes have reached the pause point. <code>PMIx</code> implementations that do not support this operation shall return an error from <code>PMIx\_Init</code> if this behavior is requested. Launchers that cannot support this operation shall return an error from the <code>PMIx\_Spawn</code> API if this behavior is requested.

## • PMIX\_DEBUG\_WAIT\_FOR\_NOTIFY "pmix.dbg.notify" (bool)

Included in either the <code>pmix\_info\_t</code> array in a <code>pmix\_app\_t</code> description (if the directive applies only to that application) or in the <code>job\_info</code> array if it applies to all applications in the given spawn request. Indicates that the specified application is being spawned under a debugger. The resulting application processes are to notify their server (by generating the <code>PMIX\_DEBUG\_WAITING\_FOR\_NOTIFY</code> event) when they reach some application-determined location and pause at that point until either released by debugger modification of an appropriate variable or receipt of the <code>PMIX\_DEBUGGER\_RELEASE</code> event. The launcher (RM or IL) is responsible for generating the <code>PMIX\_DEBUG\_WAITING\_FOR\_NOTIFY</code> event when all processes have indicated they are at the pause point. Launchers that cannot support this operation shall return an error from the <code>PMIx\_Spawn</code> API if this behavior is requested.

Note that there is no mechanism by which the PMIx library or the launcher can verify that an application will recognize and support the **PMIX\_DEBUG\_WAIT\_FOR\_NOTIFY** request. Debuggers utilizing this attachment method must, therefore, be prepared to deal with the case where the application fails to recognize and/or honor the request.

If the PMIx implementation and/or the host environment support it, debuggers can utilize the PMIx\_Query\_info API to determine which features are available via the PMIX QUERY ATTRIBUTE SUPPORT attribute.

• PMIX\_DEBUG\_STOP\_IN\_INIT by checking PMIX\_CLIENT\_ATTRIBUTES for the

PMIx Init API.

• PMIX\_DEBUG\_STOP\_ON\_EXEC by checking PMIX\_HOST\_ATTRIBUTES for the PMIX\_Spawn API.

The target namespace or process (as given by the debugger in the spawn request) shall be provided to each daemon in its job-level information via the PMIX\_DEBUG\_TARGET attribute. Debugger daemons are responsible for self-determining their specific target process(es), and can then utilize the PMIx\_Query\_info API to obtain information about them (see Fig 17.6) - e.g., to obtain the PIDs of the local processes to which they need to attach. PMIx provides the pmix\_proc\_info\_t structure for organizing information about a process' PID, location, and state. Debuggers may request information on a given job at two levels:

- PMIX\_QUERY\_PROC\_TABLE "pmix.qry.ptable" (char\*)
   Returns a (pmix\_data\_array\_t) array of pmix\_proc\_info\_t, one entry for each process in the specified namespace, ordered by process job rank. REQUIRED QUALIFIER: PMIX\_NSPACE indicating the namespace whose process table is being queried.
- PMIX\_QUERY\_LOCAL\_PROC\_TABLE "pmix.qry.lptable" (char\*)
  Returns a (pmix\_data\_array\_t) array of pmix\_proc\_info\_t, one entry for each process in the specified namespace executing on the same node as the requester, ordered by process job rank. REQUIRED QUALIFIER: PMIX\_NSPACE indicating the namespace whose local process table is being queried. OPTIONAL QUALIFIER: PMIX\_HOSTNAME indicating the host whose local process table is being queried. By default, the query assumes that the host upon which the request was made is to be used.

Note that the information provided in the returned proctable represents a snapshot in time. Any process, regardless of role (tool, client, debugger, etc.) can obtain the proctable of a given namespace so long as it has the system-determined authorizations to do so. The list of namespaces available via a given server can be obtained using the **PMIx\_Query\_info** API with the **PMIX\_QUERY\_NAMESPACES** key.

Debugger daemons can be started in two ways - either at the same time the application is spawned, or separately at a later time.

## 17.4.1 Co-Location of Debugger Daemons

Debugging operations typically require the use of daemons that are located on the same node as the processes they are attempting to debug. The debugger can, of course, specify its own mapping method when issuing its spawn request or utilize its own internal launcher to place the daemons. However, when attaching to a running job, PMIx provides debuggers with a simplified method for requesting that the launcher associated with the job *co-locate* the required daemons. Debuggers can request *co-location* of their daemons by adding the following attributes to the **PMIx\_Spawn** used to spawn them:




Figure 17.6.: Obtaining proctables

 PMIX\_DEBUGGER\_DAEMONS - indicating that the launcher is being asked to spawn debugger daemons.

- PMIX\_DEBUG\_TARGET indicating the job or process that is to be debugged. This allows the launcher to identify the processes to be debugged and their location. Note that the debugger job shall be assigned its own namespace (different from that of the job it is being spawned to debug) and each daemon will be assigned a unique rank within that namespace.
- PMIX\_DEBUG\_DAEMONS\_PER\_PROC specifies the number of debugger daemons to be co-located per target process.
- PMIX\_DEBUG\_DAEMONS\_PER\_NODE specifies the number of debugger daemons to be co-located per node where at least one target process is executing.

Debugger daemons spawned in this manner shall be provided with the typical PMIx information for their own job plus the target they are to debug via the PMIX\_DEBUG\_TARGET attribute. The debugger daemons spawned on a given node are responsible for self-determining their specific target process(es) - e.g., by referencing their own PMIX\_LOCAL\_RANK in the daemon debugger job versus the corresponding PMIX\_LOCAL\_RANK of the target processes on the node. Note that the debugger will be attaching to the application processes at some arbitrary point in the application's execution unless some method for pausing the application (e.g., by providing a PMIx directive at time of launch, or via a tool using the PMIx\_Job\_control API to direct that the process be paused) has been employed.

#### Advice to users

Note that the tool calling **PMIx\_Spawn** to request the launch of the debugger daemons is *not* included in the resulting job - i.e., the debugger daemons do not inherit the namespace of the tool.

# 17.4.2 Co-Spawn of Debugger Daemons

In the case where a job is being spawned under the control of a debugger, PMIx provides a shortcut method for spawning the debugger's daemons in parallel with the job. This requires that the debugger be specified as one of the <code>pmix\_app\_t</code> in the same spawn command used to start the job. The debugger application must include at least the <code>PMIX\_DEBUGGER\_DAEMONS</code> attribute identifying itself as a debugger, and may utilize either a mapping option to direct daemon placement, or one of the <code>PMIX\_DEBUG\_DAEMONS\_PER\_PROC</code> or <code>PMIX\_DEBUG\_DAEMONS\_PER\_PROC</code> or <code>PMIX\_DEBUG\_DAEMONS\_PER\_NODE</code> directives.

The launcher must not include information regarding the debugger daemons in the job-level info provided to the rest of the <code>pmix\_app\_ts</code>, nor in any calculated rank values (e.g., <code>PMIX\_NODE\_RANK</code> or <code>PMIX\_LOCAL\_RANK</code>) in those applications. The debugger job is to be assigned its own namespace and each debugger daemon shall receive a unique rank - i.e., the debugger application is to be treated as a completely separate PMIx job that is simply being started in parallel with the user's applications. The launcher is free to implement the launch as a single operation for both the applications and debugger daemons (preferred), or may stage the launches as required. The launcher shall not return from the <code>PMIx\_Spawn</code> command until all included applications and the debugger daemons have been started.

Attributes that apply to both the debugger daemons and the application processes can be specified in the *job\_info* array passed into the **PMIx\_Spawn** API. Attributes that either (a) apply solely to the debugger daemons or to one of the applications included in the spawn request, or (b) have values that differ from those provided in the *job\_info* array, should be specified in the *info* array in the corresponding **pmix\_app\_t**. Note that PMIx job *pause* attributes (e.g., **PMIX\_DEBUG\_STOP\_IN\_INIT**) do not apply to applications (defined in **pmix\_app\_t**) where the **PMIX\_DEBUGGER\_DAEMONS** attribute is set to **true**.

Debugger daemons spawned in this manner shall be provided with the typical PMIx information for their own job plus the target they are to debug via the **PMIX\_DEBUG\_TARGET** attribute. The debugger daemons spawned on a given node are responsible for self-determining their specific target process(es) - e.g., by referencing their own **PMIX\_LOCAL\_RANK** in the daemon debugger job versus the corresponding **PMIX\_LOCAL\_RANK** of the target processes on the node.

## Advice to users

Note that the tool calling **PMIx\_Spawn** to request the launch of the debugger daemons is *not* included in the resulting job - i.e., the debugger daemons do not inherit the namespace of the tool. Thus, collective operations and notifications that target the debugger daemon job will not include the tool unless the namespace/rank of the tool is explicitly included.

The PMIx\_Spawn API only supports the return of a single namespace resulting from the spawn request. In the case where the debugger job is co-spawned with the application, the spawn function shall return the namespace of the application and not the debugger job. Tools requiring access to the namespace of the debugger job must query the launcher for the spawned namespaces to find the one belonging to the debugger job.

# 17.4.3 Debugger Agents

Individual debuggers may, depending upon implementation, require varying degrees of control over each application process when it is started beyond those available via directives to **PMIx\_Spawn**. PMIx offers two mechanisms to help provide a means of meeting these needs.

The PMIX\_FORKEXEC\_AGENT attribute allows the debugger to specify an intermediate process (the Fork/Exec Agent (FEA)) for spawning the actual application process (see Fig. 17.7a), thereby interposing the debugger daemon between the application process and the launcher's daemon. Instead of spawning the application process, the launcher will spawn the FEA, which will connect back to the PMIx server as a tool to obtain the spawn description of the application process it is to spawn. The PMIx server in the launcher's daemon shall not register the fork/exec agent as a local client process, nor shall the launcher include the agent in any of the job-level values (e.g., PMIX\_RANK within the job or PMIX\_LOCAL\_RANK on the node) provided to the application process. The launcher shall treat the collection of FEAs as a debugger job equivalent to the co-spawn use-case described in Section 17.4.2.

In contrast, the **PMIX\_EXEC\_AGENT** attribute (Fig. 17.7b) allows the debugger to specify an agent that will perform some preparatory actions and then exec the eventual application process to replace itself. In this scenario, the exec agent is provided with the application process' command line as arguments on its command line (e.g., "./agent appargv[0] appargv[1]") and does not connect back to the host's PMIx server. It is the responsibility of the exec agent to properly separate its own command line arguments (if any) from the application description.




Figure 17.7.: Intermediate agents

# 17.4.4 Tracking the job lifecycle

There are a wide range of events a debugger can register to receive, but three are specifically defined for tracking a job's progress:

- PMIX\_EVENT\_JOB\_START indicates when the first process in the job has been spawned.
- PMIX LAUNCH COMPLETE indicates when the last process in the job has been spawned.
- PMIX EVENT JOB END indicates that all processes have terminated.

Each event is required to contain at least the namespace of the corresponding job and a <code>PMIX\_EVENT\_TIMESTAMP</code> indicating the time the event occurred. In addition, the <code>PMIX\_EVENT\_JOB\_END</code> event shall contain the returned status code (<code>PMIX\_JOB\_TERM\_STATUS</code>) for the corresponding job, plus the identity (<code>PMIX\_PROCID</code>) and exit status (<code>PMIX\_EXIT\_CODE</code>) of the first failed process, if applicable. Generation of these events by the launcher can be requested by including the <code>PMIX\_NOTIFY\_JOB\_EVENTS</code> attributes in the spawn request. Note that these events can be logged via the <code>PMIX\_Log</code> API by including the <code>PMIX\_LOG\_JOB\_EVENTS</code> attribute - this can be done either in conjunction with generated events, or in place of them.

Alternatively, if the debugger or tool solely wants to be alerted to job termination, then including the PMIX\_NOTIFY\_COMPLETION attribute in the spawn request would suffice. This attribute directs the launcher to provide just the PMIX\_EVENT\_JOB\_END event. Note that this event can be logged via the PMIX\_LOG\_API by including the PMIX\_LOG\_COMPLETION attribute - this can be done either in conjunction with the generated event, or in place of it.

#### Advice to users

The PMIx server is required to cache events in order to avoid race conditions - e.g., when a tool is trying to register for the **PMIX\_EVENT\_JOB\_END** event from a very short-lived job. Accordingly, registering for job-related events can result in receiving events relating to jobs other than the one of interest.

Users are therefore advised to specify the job whose events are of interest by including the **PMIX\_EVENT\_AFFECTED\_PROC** or **PMIX\_EVENT\_AFFECTED\_PROCS** attribute in the *info* array passed to the **PMIx\_Register\_event\_handler** API.

## 17.4.4.1 Job lifecycle events

 PMIX\_EVENT\_JOB\_START The first process in the job has been spawned - includes

PMIX\_EVENT\_TIMESTAMP as well as the PMIX\_JOBID and/or PMIX\_NSPACE of the job.

PMIX\_LAUNCH\_COMPLETE All processes in the job have been spawned - includes

PMIX\_EVENT\_TIMESTAMP as well as the PMIX\_JOBID and/or PMIX\_NSPACE of the job.

PMIX\_EVENT\_JOB\_END All processes in the job have terminated - includes

PMIX\_EVENT\_TIMESTAMP when the last process terminated as well as the PMIX\_JOBID and/or PMIX\_NSPACE of the job.

PMIX\_EVENT\_SESSION\_START The allocation has been instantiated and is ready for use -

includes **PMIX\_EVENT\_TIMESTAMP** as well as the **PMIX\_SESSION\_ID** of the allocation. This event is issued after any system-controlled prologue has completed, but before any user-specified actions are taken.

PMIX\_EVENT\_SESSION\_END The allocation has terminated - includes
PMIX\_EVENT\_TIMESTAMP as well as the PMIX\_SESSION\_ID of the allocation. This event is issued after any user-specified actions have completed, but before any system-controlled epilogue is performed.

The following events relate to processes within a job:

**PMIX\_EVENT\_PROC\_TERMINATED** The specified process(es) terminated - normal or abnormal termination will be indicated by the **PMIX\_PROC\_TERM\_STATUS** in the *info* array of the notification. Note that a request for individual process events can generate a significant event volume from large-scale jobs.

The following constants may be included via the **PMIX\_JOB\_TERM\_STATUS** attributed in the *info* array in the **PMIX\_EVENT\_JOB\_END** event notification to provide more detailed information regarding the reason for job abnormal termination:

PMIX\_ERR\_JOB\_CANCELED The job was canceled by the host environment.
 PMIX\_ERR\_JOB\_ABORTED One or more processes in the job called abort, causing the job to be terminated.

PMIX\_ERR\_JOB\_KILLED\_BY\_CMD The job was killed by user command.

PMIX ERR JOB ABORTED BY SIG The job was aborted due to receipt of an error signal

(e.g., SIGKILL).

1 PMIX\_ERR\_JOB\_TERM\_WO\_SYNC The job was terminated due to at least one process terminating without calling PMIx\_Finalize, or was a member of an assemblage formed 2 3 via PMIx Connect and terminated or called PMIx Finalize without first calling 4 **PMIx Disconnect** (or its non-blocking form) from that assemblage. 5 PMIX ERR JOB SENSOR BOUND EXCEEDED The job was terminated due to one or more 6 processes exceeding a specified sensor limit. 7 PMIX ERR JOB NON ZERO TERM The job was terminated due to one or more processes 8 exiting with a non-zero status. 9 PMIX\_ERR\_JOB\_ABORTED\_BY\_SYS\_EVENT The job was aborted due to receipt of a 10 system event. 17.4.4.2 Job lifecycle attributes 11 12 PMIX JOB TERM STATUS "pmix.job.term.status" (pmix status t) 13 Status returned by job upon its termination. The status will be communicated as part of a 14 PMIx event payload provided by the host environment upon termination of a job. Note that generation of the PMIX EVENT JOB END event is optional and host environments may 15 choose to provide it only upon request. 16 17 PMIX PROC STATE STATUS "pmix.proc.state" (pmix proc state t) 18 State of the specified process as of the last report - may not be the actual current state based 19 on update rate. 20 PMIX PROC TERM STATUS "pmix.proc.term.status" (pmix status t) Status returned by a process upon its termination. The status will be communicated as part 21 of a PMIx event payload provided by the host environment upon termination of a process. 22 23 Note that generation of the PMIX EVENT PROC TERMINATED event is optional and host 24 environments may choose to provide it only upon request. 17.4.5 Debugger-related constants 25 26 The following constants are used in events used to coordinate applications and the debuggers 27 attaching to them. PMIX DEBUG WAITING FOR NOTIFY 28 All processes in the job to be debugged are paused waiting for a release at some point within the application. The application shall remain in a 29 30 paused state awaiting release until receipt of the PMIX DEBUGGER RELEASE. 31 PMIX DEBUGGER RELEASE Release processes that are paused at the 32 PMIX DEBUG WAIT FOR NOTIFY point in the target application. Debugger attributes 17.4.6 33 34 Attributes used to assist debuggers - these are values that can either be passed to the PMIx Spawn 35 APIs or accessed by a debugger itself using the **PMIx** Get API with the PMIX RANK WILDCARD rank. 36 37 PMIX DEBUG STOP ON EXEC "pmix.dbq.exec" (bool)

 Included in either the <code>pmix\_info\_t</code> array in a <code>pmix\_app\_t</code> description (if the directive applies only to that application) or in the <code>job\_info</code> array if it applies to all applications in the given spawn request. Indicates that the application is being spawned under a debugger, and that the local launch agent is to pause the resulting application processes on first instruction for debugger attach. The launcher (RM or IL) is to generate the

**PMIX LAUNCH COMPLETE** event when all processes are stopped at the exec point.

## PMIX DEBUG STOP IN INIT "pmix.dbg.init" (bool)

Included in either the <code>pmix\_info\_t</code> array in a <code>pmix\_app\_t</code> description (if the directive applies only to that application) or in the <code>job\_info</code> array if it applies to all applications in the given spawn request. Indicates that the specified application is being spawned under a debugger. The PMIx client library in each resulting application process shall notify its PMIx server that it is pausing and then pause during <code>PMIx\_Init</code> of the spawned processes until either released by debugger modification of an appropriate variable or receipt of the <code>PMIX\_DEBUGGER\_RELEASE</code> event. The launcher (RM or IL) is responsible for generating the <code>PMIX\_DEBUG\_WAITING\_FOR\_NOTIFY</code> event when all processes have reached the pause point.

### PMIX\_DEBUG\_WAIT\_FOR\_NOTIFY "pmix.dbg.notify" (bool)

Included in either the <code>pmix\_info\_t</code> array in a <code>pmix\_app\_t</code> description (if the directive applies only to that application) or in the <code>job\_info</code> array if it applies to all applications in the given spawn request. Indicates that the specified application is being spawned under a debugger. The resulting application processes are to notify their server (by generating the <code>PMIX\_DEBUG\_WAITING\_FOR\_NOTIFY</code> event) when they reach some application-determined location and pause at that point until either released by debugger modification of an appropriate variable or receipt of the <code>PMIX\_DEBUGGER\_RELEASE</code> event. The launcher (RM or IL) is responsible for generating the <code>PMIX\_DEBUG\_WAITING\_FOR\_NOTIFY</code> event when all processes have indicated they are at the pause point.

## PMIX\_DEBUG\_TARGET "pmix.dbg.tgt" (pmix\_proc\_t\*)

Identifier of process(es) to be debugged - a rank of **PMIX\_RANK\_WILDCARD** indicates that all processes in the specified namespace are to be included.

### PMIX DEBUGGER DAEMONS "pmix.debugger" (bool)

Included in the <code>pmix\_info\_t</code> array of a <code>pmix\_app\_t</code>, this attribute declares that the application consists of debugger daemons and shall be governed accordingly. If used as the sole <code>pmix\_app\_t</code> in a <code>PMIx\_Spawn</code> request, then the <code>PMIX\_DEBUG\_TARGET</code> attribute must also be provided (in either the <code>job\_info</code> or in the <code>info</code> array of the <code>pmix\_app\_t</code>) to identify the namespace to be debugged so that the launcher can determine where to place the spawned daemons. If neither <code>PMIX\_DEBUG\_DAEMONS\_PER\_PROC</code> nor <code>PMIX\_DEBUG\_DAEMONS\_PER\_NODE</code> is specified, then the launcher shall default to a placement policy of one daemon per process in the target job.

### PMIX COSPAWN APP "pmix.cospawn" (bool)

Designated application is to be spawned as a disconnected job - i.e., the launcher shall not include the application in any of the job-level values (e.g., **PMIX\_RANK** within the job) provided to any other application process generated by the same spawn request. Typically

used to cospawn debugger daemons alongside an application.

#### PMIX\_DEBUG\_DAEMONS\_PER\_PROC "pmix.dbg.dpproc" (uint16\_t)

Number of debugger daemons to be spawned per application process. The launcher is to pass the identifier of the namespace to be debugged by including the PMIX\_DEBUG\_TARGET attribute in the daemon's job-level information. The debugger daemons spawned on a given node are responsible for self-determining their specific target process(es) - e.g., by referencing their own PMIX\_LOCAL\_RANK in the daemon debugger job versus the corresponding PMIX\_LOCAL\_RANK of the target processes on the node.

## PMIX\_DEBUG\_DAEMONS\_PER\_NODE "pmix.dbg.dpnd" (uint16\_t)

Number of debugger daemons to be spawned on each node where the target job is executing. The launcher is to pass the identifier of the namespace to be debugged by including the **PMIX\_DEBUG\_TARGET** attribute in the daemon's job-level information. The debugger daemons spawned on a given node are responsible for self-determining their specific target process(es) - e.g., by referencing their own **PMIX\_LOCAL\_RANK** in the daemon debugger job versus the corresponding **PMIX\_LOCAL\_RANK** of the target processes on the node.

#### PMIX\_QUERY\_PROC\_TABLE "pmix.qry.ptable" (char\*)

Returns a (pmix\_data\_array\_t) array of pmix\_proc\_info\_t, one entry for each process in the specified namespace, ordered by process job rank. REQUIRED QUALIFIER: PMIX\_NSPACE indicating the namespace whose process table is being queried.

#### PMIX\_QUERY\_LOCAL\_PROC\_TABLE "pmix.qry.lptable" (char\*)

Returns a (pmix\_data\_array\_t) array of pmix\_proc\_info\_t, one entry for each process in the specified namespace executing on the same node as the requester, ordered by process job rank. REQUIRED QUALIFIER: PMIX\_NSPACE indicating the namespace whose local process table is being queried. OPTIONAL QUALIFIER: PMIX\_HOSTNAME indicating the host whose local process table is being queried. By default, the query assumes that the host upon which the request was made is to be used.

# 17.5 Tool-Specific APIs

PMIx-based tools automatically have access to all PMIx client functions. Tools designated as a *launcher* or a *server* will also have access to all PMIx server functions. There are, however, an additional set of functions (described in this section) that are specific to a PMIx tool. Access to those functions require use of the tool initialization routine.

# 17.5.1 PMIx tool\_init

## Summary

Initialize the PMIx library for operating as a tool, optionally connecting to a specified PMIx server.

# $5_{PMIx v2.0}$ Format

```
1
              pmix status t
 2
              PMIx_tool_init(pmix_proc_t *proc,
 3
                                 pmix_info_t info[], size_t ninfo);
              INOUT proc
 4
 5
                   pmix proc t structure (handle)
6
              IN
7
                   Array of pmix info t structures (array of handles)
8
                  ninfo
9
                   Number of elements in the info array (size_t)
              Returns PMIX SUCCESS or a negative value indicating the error.
10
                                             Required Attributes
              The following attributes are required to be supported by all PMIx libraries:
11
              PMIX_TOOL_NSPACE "pmix.tool.nspace" (char*)
12
                    Name of the namespace to use for this tool.
13
              PMIX_TOOL_RANK "pmix.tool.rank" (uint32_t)
14
                    Rank of this tool.
15
              PMIX_TOOL_DO_NOT_CONNECT "pmix.tool.nocon" (bool)
16
17
                    The tool wants to use internal PMIx support, but does not want to connect to a PMIx server.
              PMIX TOOL ATTACHMENT FILE "pmix.tool.attach" (char*)
18
19
                    Pathname of file containing connection information to be used for attaching to a specific
20
                    server.
              PMIX SERVER URI "pmix.srvr.uri" (char*)
21
22
                    URI of the PMIx server to be contacted.
23
              PMIX_TCP_URI "pmix.tcp.uri" (char*)
                    The URI of the PMIx server to connect to, or a file name containing it in the form of
24
25
                    file: <name of file containing it>.
26
              PMIX SERVER PIDINFO "pmix.srvr.pidinfo" (pid t)
                    PID of the target PMIx server for a tool.
27
28
              PMIX SERVER NSPACE "pmix.srv.nspace" (char*)
29
                    Name of the namespace to use for this PMIx server.
30
              PMIX CONNECT TO SYSTEM "pmix.cnct.sys" (bool)
31
                    The requester requires that a connection be made only to a local, system-level PMIx server.
              PMIX CONNECT SYSTEM FIRST "pmix.cnct.sys.first" (bool)
32
```

1	Preferentially, look for a system-level PMIx server first.
	▼ Optional Attributes
2	The following attributes are optional for implementers of PMIx libraries:
3 4 5	PMIX_CONNECT_RETRY_DELAY "pmix.tool.retry" (uint32_t)  Time in seconds between connection attempts to a PMIx server - the default value is implementation specific.
6 7 8	<pre>PMIX_CONNECT_MAX_RETRIES "pmix.tool.mretries" (uint32_t)     Maximum number of times to try to connect to PMIx server - the default value is implementation specific.</pre>
9 10 11	PMIX_SOCKET_MODE "pmix.sockmode" (uint32_t) POSIX mode_t (9 bits valid). If the library supports socket connections, this attribute may be supported for setting the socket mode.
12 13 14 15	<pre>PMIX_TCP_REPORT_URI "pmix.tcp.repuri" (char*) If provided, directs that the TCP URI be reported and indicates the desired method of reporting: '-' for stdout, '+' for stderr, or filename. If the library supports TCP socket connections, this attribute may be supported for reporting the URI.</pre>
16 17 18 19	<pre>PMIX_TCP_IF_INCLUDE "pmix.tcp.ifinclude" (char*) Comma-delimited list of devices and/or CIDR notation to include when establishing the TCP connection. If the library supports TCP socket connections, this attribute may be supported for specifying the interfaces to be used.</pre>
20 21 22 23	<pre>PMIX_TCP_IF_EXCLUDE "pmix.tcp.ifexclude" (char*) Comma-delimited list of devices and/or CIDR notation to exclude when establishing the TCP connection. If the library supports TCP socket connections, this attribute may be supported for specifying the interfaces that are not to be used.</pre>
24 25 26	PMIX_TCP_IPV4_PORT "pmix.tcp.ipv4" (int)  The IPv4 port to be used If the library supports IPV4 connections, this attribute may be supported for specifying the port to be used.
27 28 29	<pre>PMIX_TCP_IPV6_PORT "pmix.tcp.ipv6" (int) The IPv6 port to be used. If the library supports IPV6 connections, this attribute may be supported for specifying the port to be used.</pre>
30 31 32	PMIX_TCP_DISABLE_IPV4 "pmix.tcp.disipv4" (bool)  Set to true to disable IPv4 family of addresses. If the library supports IPV4 connections, this attribute may be supported for disabling it.
33 34 35	PMIX_TCP_DISABLE_IPV6 "pmix.tcp.disipv6" (bool)  Set to true to disable IPv6 family of addresses. If the library supports IPV6 connections, this attribute may be supported for disabling it.

#### PMIX\_EXTERNAL\_PROGRESS "pmix.evext" (bool)

The host shall progress the PMIx library via calls to PMIx Progress

### PMIX\_EVENT\_BASE "pmix.evbase" (void\*)

Pointer to an **event\_base** to use in place of the internal progress thread. All PMIx library events are to be assigned to the provided event base. The event base *must* be compatible with the event library used by the PMIx implementation - e.g., either both the host and PMIx library must use libevent, or both must use libev. Cross-matches are unlikely to work and should be avoided - it is the responsibility of the host to ensure that the PMIx implementation supports (and was built with) the appropriate event library.

## Description

 Initialize the PMIx tool, returning the process identifier assigned to this tool in the provided **pmix\_proc\_t** struct. The *info* array is used to pass user requests pertaining to the initialization and subsequent operations. Passing a **NULL** value for the array pointer is supported if no directives are desired.

If called with the PMIX\_TOOL\_DO\_NOT\_CONNECT attribute, the PMIx tool library will fully initialize but not attempt to connect to a PMIx server. The tool can connect to a server at a later point in time, if desired, by calling the PMIx\_tool\_attach\_to\_server function. If provided, the proc structure will be set to a zero-length namespace and a rank of PMIX\_RANK\_UNDEF unless the PMIX\_TOOL\_NSPACE and PMIX\_TOOL\_RANK attributes are included in the info array.

In all other cases, the PMIx tool library will automatically attempt to connect to a PMIx server according to the precedence chain described in Section 17.1. If successful, the function will return PMIX\_SUCCESS and will fill the process structure (if provided) with the assigned namespace and rank of the tool. The server to which the tool connects will be designated its *primary* server. Note that each connection attempt in the above precedence chain will retry (with delay between each retry) a number of times according to the values of the corresponding attributes.

Note that the PMIx tool library is referenced counted, and so multiple calls to PMIx\_tool\_init are allowed. If the tool is not connected to any server when this API is called, then the tool will attempt to connect to a server unless the PMIX\_TOOL\_DO\_NOT\_CONNECT is included in the call to API.

## 17.5.2 PMIx tool finalize

## Summary

Finalize the PMIx tool library.

**Format** 1 2 pmix status t 3 PMIx tool finalize(void); 4 Returns **PMIX\_SUCCESS** or a negative value indicating the error. **Description** 5 6 Finalize the PMIx tool library, closing all existing connections to servers. An error code will be 7 returned if, for some reason, a connection cannot be cleanly terminated — in such cases, the 8 connection is dropped. Upon detecting loss of the connection, the PMIx server shall cleanup all 9 associated records of the tool. 17.5.3 PMIx tool disconnect 10 Summary 11 12 Disconnect the PMIx tool from the specified server connection while leaving the tool library initialized. 13 **Format** 14 *PMIx v4.0* 15 pmix status t PMIx\_tool\_disconnect(const pmix\_proc\_t \*server); 16 IN 17 server pmix\_proc\_t structure (handle) 18 19 Returns **PMIX SUCCESS** or a negative value indicating the error. Description 20 Close the current connection to the specified server, if one has been made, while leaving the PMIx 21 22 library initialized. An error code will be returned if, for some reason, the connection cannot be 23 cleanly terminated - in this case, the connection is dropped. In either case, the library will remain initialized. Upon detecting loss of the connection, the PMIx server shall cleanup all associated 24 records of the tool. 25 26 Note that if the server being disconnected is the current *primary* server, then all operations requiring support from a server will return the PMIX\_ERR\_UNREACH error until the tool either 27 28 designates an existing connection to be the *primary* server or, if no other connections exist, the tool

29

establishes a connection to a PMIx server.

#### 17.5.4 PMIx\_tool\_attach\_to\_server Summary Establish a connection to a PMIx server. 3 Format 5 pmix\_status\_t 6 PMIx\_tool\_attach\_to\_server(pmix\_proc\_t \*proc, 7 pmix\_proc\_t \*server, 8 pmix\_info\_t info[], 9 size t ninfo); **INOUT** proc 10 Pointer to pmix\_proc\_t structure (handle) 11 12 INOUT server 13 Pointer to pmix proc t structure (handle) 14 IN info Array of **pmix\_info\_t** structures (array of handles) 15 IN ninfo 16 17 Number of elements in the *info* array (**size** t) Returns **PMIX\_SUCCESS** or a negative value indicating the error. 18 Required Attributes 19 The following attributes are required to be supported by all PMIx libraries: PMIX TOOL ATTACHMENT FILE "pmix.tool.attach" (char\*) 20 Pathname of file containing connection information to be used for attaching to a specific 21 22 server. 23 PMIX SERVER URI "pmix.srvr.uri" (char\*) URI of the PMIx server to be contacted. 24 PMIX\_TCP\_URI "pmix.tcp.uri" (char\*) 25 The URI of the PMIx server to connect to, or a file name containing it in the form of 26 file: <name of file containing it>. 27 PMIX\_SERVER\_PIDINFO "pmix.srvr.pidinfo" (pid\_t) 28 PID of the target PMIx server for a tool. 29 30 PMIX\_SERVER\_NSPACE "pmix.srv.nspace" (char\*) Name of the namespace to use for this PMIx server. 31 32 PMIX\_CONNECT\_TO\_SYSTEM "pmix.cnct.sys" (bool) 33 The requester requires that a connection be made only to a local, system-level PMIx server. 34 PMIX\_CONNECT\_SYSTEM\_FIRST "pmix.cnct.sys.first" (bool)

Preferentially, look for a system-level PMIx server first.

#### PMIX PRIMARY SERVER "pmix.pri.srvr" (bool)

The server to which the tool is connecting shall be designated the *primary* server once connection has been accomplished.

## **Description**

Establish a connection to a server. This function can be called at any time by a PMIx tool to create a new connection to a server. If a specific server is given and the tool is already attached to it, then the API shall return PMIX\_SUCCESS without taking any further action. In all other cases, the tool will attempt to discover a server using the method described in Section 17.1, ignoring all candidates to which it is already connected. The PMIX\_ERR\_UNREACH error shall be returned if no new connection is made.

The process identifier assigned to this tool is returned in the provided *proc* structure. Passing a value of **NULL** for the *proc* parameter is allowed if the user wishes solely to connect to a PMIx server and does not require return of the identifier at that time.

The process identifier of the server to which the tool attached is returned in the *server* structure. Passing a value of **NULL** for the *proc* parameter is allowed if the user wishes solely to connect to a PMIx server and does not require return of the identifier at that time.

Note that the **PMIX\_PRIMARY\_SERVER** attribute must be included in the *info* array if the server being connected to is to become the primary server, or a call to **PMIx\_tool\_set\_server** must be provided immediately after the call to this function.

## ———— Advice to PMIx library implementers ————

When a tool connects to a server that is under a different namespace manager (e.g., host RM) from the prior server, the namespace in the identifier of the tool must remain unique in the new universe. If the namespace of the tool fails to meet this criteria in the new universe, then the new namespace manager is required to return an error and the connection attempt must fail.

## Advice to users -

Some PMIx implementations may not support connecting to a server that is not under the same namespace manager (e.g., host RM) as the server to which the tool is currently connected.

# 17.5.5 PMIx\_tool\_get\_servers

## Summary

Get an array containing the **pmix\_proc\_t** process identifiers of all servers to which the tool is currently connected.

```
Format
 1
2
               pmix status t
 3
               PMIx tool get servers(pmix proc t *servers[], size t *nservers);
               OUT servers
4
                    Address where the pointer to an array of pmix proc t structures shall be returned (handle)
 5
6
               INOUT nservers
                    Address where the number of elements in servers shall be returned (handle)
 7
               Returns PMIX_SUCCESS or a negative value indicating the error.
8
               Description
9
10
               Return an array containing the pmix proc t process identifiers of all servers to which the tool is
               currently connected. The process identifier of the current primary server shall be the first entry in
11
               the array, with the remaining entries in order of attachment from earliest to most recent.
12
    17.5.6
               PMIx_tool_set_server
14
               Summary
15
               Designate a server as the tool's primary server.
               Format
   PMIx v4.0
17
               pmix_status_t
18
               PMIx_tool_set_server(const pmix_proc_t *server,
19
                                          pmix_info_t info[], size_t ninfo);
20
               IN
                    server
21
                    pmix_proc_t structure (handle)
22
               IN
                   info
23
                    Array of pmix_info_t structures (array of handles)
24
               IN
                    ninfo
25
                    Number of elements in the info array (size t)
26
               Returns PMIX SUCCESS or a negative value indicating the error.
```

```
Required Attributes
 1
               The following attributes are required to be supported by all PMIx libraries:
 2
               PMIX WAIT FOR CONNECTION "pmix.wait.conn" (bool)
 3
                     Wait until the specified process has connected to the requesting tool or server, or the
 4
                     operation times out (if the PMIX TIMEOUT directive is included in the request).
 5
               PMIX TIMEOUT "pmix.timeout" (int)
                     Time in seconds before the specified operation should time out (zero indicating infinite) and
6
 7
                     return the PMIX ERR TIMEOUT error. Care should be taken to avoid race conditions
8
                     caused by multiple layers (client, server, and host) simultaneously timing the operation.
               Description
9
10
               Designate the specified server to be the tool's primary server for all subsequent API calls.
    17.5.7
               PMIx_IOF_pull
11
12
               Summary
13
               Register to receive output forwarded from a set of remote processes.
               Format
  PMIx v30
15
               pmix status t
16
               PMIx_IOF_pull(const pmix_proc_t procs[], size_t nprocs,
17
                                  const pmix_info_t directives[], size_t ndirs,
                                 pmix_iof_channel_t channel,
18
19
                                 pmix iof cbfunc t cbfunc,
20
                                 pmix_hdlr_reg_cbfunc_t regcbfunc,
                                 void *regcbdata);
21
               IN
22
                    procs
                    Array of proc structures identifying desired source processes (array of handles)
23
24
               IN
                    nprocs
25
                    Number of elements in the procs array (integer)
                    directives
26
27
                    Array of pmix info t structures (array of handles)
28
               IN
                    ndirs
                    Number of elements in the directives array (integer)
29
                    channel
30
                    Bitmask of IO channels included in the request (pmix_iof_channel_t)
31
32
               IN
                    cbfunc
33
                    Callback function for delivering relevant output (pmix iof cbfunc t function reference)
```

1 2 3 4 5	<ul> <li>IN regcbfunc         Function to be called when registration is completed (pmix_hdlr_reg_cbfunc_t function reference)     </li> <li>IN regcbdata         Data to be passed to the regcbfunc callback function (memory reference)     </li> </ul>
6 7	Returns <b>PMIX_SUCCESS</b> or a negative value indicating the error. In the event the function returns an error, the <i>regcbfunc</i> will <i>not</i> be called.
	Required Attributes
8	The following attributes are required for PMIx libraries that support IO forwarding:
9 0 1	PMIX_IOF_CACHE_SIZE "pmix.iof.csize" (uint32_t)  The requested size of the PMIx server cache in bytes for each specified channel. By default, the server is allowed (but not required) to drop all bytes received beyond the max size.
2 3 4	PMIX_IOF_DROP_OLDEST "pmix.iof.old" (bool)  In an overflow situation, the PMIx server is to drop the oldest bytes to make room in the cache.
5 6 7	PMIX_IOF_DROP_NEWEST "pmix.iof.new" (bool)  In an overflow situation, the PMIx server is to drop any new bytes received until room becomes available in the cache (default).
	▼Optional Attributes
8	The following attributes are optional for PMIx libraries that support IO forwarding:
9 20 21 22 23	PMIX_IOF_BUFFERING_SIZE "pmix.iof.bsize" (uint32_t)  Requests that IO on the specified channel(s) be aggregated in the PMIx tool library until the specified number of bytes is collected to avoid being called every time a block of IO arrives. The PMIx tool library will execute the callback and reset the collection counter whenever the specified number of bytes becomes available. Any remaining buffered data will be <i>flushed</i> to the callback upon a call to deregister the respective channel.
25 26 27 28	PMIX_IOF_BUFFERING_TIME "pmix.iof.btime" (uint32_t)  Max time in seconds to buffer IO before delivering it. Used in conjunction with buffering size, this prevents IO from being held indefinitely while waiting for another payload to arrive.
29 30 31	PMIX_IOF_TAG_OUTPUT "pmix.iof.tag" (bool)  Requests that output be prefixed with the nspace,rank of the source and a string identifying the channel (stdout, stderr, etc.).
32	

```
PMIX_IOF_XML_OUTPUT "pmix.iof.xml" (bool)
 1
                     Requests that output be formatted in XML.
 2
               Description
 3
               Register to receive output forwarded from a set of remote processes.
                                                  Advice to users
 5
               Providing a NULL function pointer for the cbfunc parameter will cause output for the indicated
 6
               channels to be written to their corresponding stdout/stderr file descriptors. Use of
               PMIX RANK WILDCARD to specify all processes in a given namespace is supported but should be
 7
               used carefully due to bandwidth and memory footprint considerations.
 8
    17.5.8
                PMIx IOF deregister
               Summary
10
               Deregister from output forwarded from a set of remote processes.
11
               Format
<sup>12</sup> PMIx v3.0
13
               pmix status t
14
               PMIx IOF deregister(size t iofhdlr,
15
                                           const pmix_info_t directives[], size_t ndirs,
16
                                          pmix_op_cbfunc_t cbfunc, void *cbdata);
17
               IN
                    iofhdlr
18
                    Registration number returned from the pmix hdlr reg cbfunc t callback from the
                    call to PMIx IOF pull (size t)
19
               IN
20
                     directives
                    Array of pmix_info_t structures (array of handles)
21
22
               IN
                    ndirs
                    Number of elements in the directives array (integer)
23
24
                    Callback function to be called when deregistration has been completed. (function reference)
25
26
                    cbdata
27
                    Data to be passed to the cbfunc callback function (memory reference)
28
               A successful return indicates that the request is being processed by the host environment and the
29
               result will be returned in the provided cbfunc. Note that the library must not invoke the callback
               function prior to returning from the API. In all other cases, the cbfunc will not be called.
30
31
               Returns PMIX SUCCESS or one of the following error codes when the condition described occurs:
```

PMIX\_OPERATION\_SUCCEEDED, indicating that the request was immediately processed 1 2 successfully - the *cbfunc* will *not* be called. 3 If none of the above return codes are appropriate, then an implementation must return either a 4 general PMIx error code or an implementation defined error code as described in Section 3.1.1. 5 Description Deregister from output forwarded from a set of remote processes. 6 Advice to PMIx library implementers -7 Any currently buffered IO should be flushed upon receipt of a deregistration request. All received IO after receipt of the request shall be discarded. 8 17.5.9 PMIx\_IOF\_push Summary 10 Push data collected locally (typically from **stdin** or a file) to **stdin** of the target recipients. 11 Format PMIx v3.0 13 pmix\_status\_t 14 PMIx\_IOF\_push(const pmix\_proc\_t targets[], size\_t ntargets, pmix\_byte\_object\_t \*bo, 15 const pmix\_info\_t directives[], size\_t ndirs, 16 17 pmix\_op\_cbfunc\_t cbfunc, void \*cbdata); IN targets 18 Array of proc structures identifying desired target processes (array of handles) 19 IN ntargets 20 21 Number of elements in the *targets* array (integer) IN 22 23 Pointer to pmix byte object t containing the payload to be delivered (handle) directives 24 25 Array of **pmix** info t structures (array of handles) IN ndirs 26 27 Number of elements in the *directives* array (integer) 28 IN directives Array of **pmix\_info\_t** structures (array of handles) 29 IN 30 cbfunc 31 Callback function to be called when operation has been completed. (pmix op cbfunc t 32 function reference)

#### IN cbdata 1 2 Data to be passed to the *cbfunc* callback function (memory reference) 3 A successful return indicates that the request is being processed by the host environment and the 4 result will be returned in the provided cbfunc. Note that the library must not invoke the callback function prior to returning from the API. In all other cases, the *cbfunc* will *not* be called. 5 Returns PMIX SUCCESS or one of the following error codes when the condition described occurs: 6 7 PMIX OPERATION SUCCEEDED, indicating that the request was immediately processed successfully - the *cbfunc* will *not* be called. 8 If none of the above return codes are appropriate, then an implementation must return either a 9 general PMIx error code or an implementation defined error code as described in Section 3.1.1. 10 Required Attributes The following attributes are required for PMIx libraries that support IO forwarding: 11 12 PMIX IOF CACHE SIZE "pmix.iof.csize" (uint32 t) The requested size of the PMIx server cache in bytes for each specified channel. By default, 13 the server is allowed (but not required) to drop all bytes received beyond the max size. 14 PMIX IOF DROP OLDEST "pmix.iof.old" (bool) 15 In an overflow situation, the PMIx server is to drop the oldest bytes to make room in the 16 17 cache. PMIX\_IOF\_DROP\_NEWEST "pmix.iof.new" (bool) 18 In an overflow situation, the PMIx server is to drop any new bytes received until room 19 becomes available in the cache (default). 20 Optional Attributes -----The following attributes are optional for PMIx libraries that support IO forwarding: 21 22 PMIX\_IOF\_BUFFERING\_SIZE "pmix.iof.bsize" (uint32\_t) 23 Requests that IO on the specified channel(s) be aggregated in the PMIx tool library until the specified number of bytes is collected to avoid being called every time a block of IO arrives. 24 The PMIx tool library will execute the callback and reset the collection counter whenever the 25 26 specified number of bytes becomes available. Any remaining buffered data will be flushed to the callback upon a call to deregister the respective channel. 27 28 PMIX\_IOF\_BUFFERING\_TIME "pmix.iof.btime" (uint32\_t) Max time in seconds to buffer IO before delivering it. Used in conjunction with buffering 29 size, this prevents IO from being held indefinitely while waiting for another payload to 30 31 arrive. 32 PMIX IOF PUSH STDIN "pmix.iof.stdin" (bool)

5

1

6 7

9 10 11

8

12

14 15 16

13

Requests that the PMIx library collect the **stdin** of the requester and forward it to the processes specified in the PMIx\_IOF\_push call. All collected data is sent to the same targets until **stdin** is closed, or a subsequent call to **PMIx IOF push** is made that includes the PMIX IOF COMPLETE attribute indicating that forwarding of stdin is to be terminated.

## Description

Called either to:

- push data collected by the caller themselves (typically from stdin or a file) to stdin of the target recipients;
- request that the PMIx library automatically collect and push the **stdin** of the caller to the target recipients; or
- indicate that automatic collection and transmittal of **stdin** is to stop

## Advice to users

Execution of the cbfunc callback function serves as notice that the PMIx library no longer requires the caller to maintain the bo data object - it does not indicate delivery of the payload to the targets. Use of PMIX\_RANK\_WILDCARD to specify all processes in a given namespace is supported but should be used carefully due to bandwidth and memory footprint considerations.

### **CHAPTER 18**

# **Storage Support Definitions**

# 1 Provisional 2

3

4

5

6

7

8

9

10

11

12 13

16

17

23

Distributed and parallel computing systems are increasingly embracing storage hierarchies to meet the diverse data management needs of applications and other systems software in a cost-effective manner. These hierarchies provide access to a number of distinct storage layers, with each potentially composed of different storage hardware (e.g., HDD, SSD, tape, PMEM), deployed at different locations (e.g., on-node, on-switch, on-site, WAN), and designed using different storage paradigms (e.g., file-based, object-based). Each of these systems offers unique performance and usage characteristics that storage system users should carefully consider to ensure the most efficient use of storage resources.

PMIx enables users to better understand storage hierarchies by defining attributes that formalize storage system characteristics, state, and other parameters. These attributes can be queried by applications, I/O libraries and middleware, and workflow systems to discover available storage resources and to inform on which resources are most suitable for different I/O workload requirements.

# 14 18.1 Storage support constants

15	<b>Provisional</b>
10	

The pmix\_storage\_medium\_t is a uint64\_t type that defines a set of bit-mask flags for specifying different types of storage mediums. These can be bitwise OR'd together to accommodate storage systems that mix storage medium types.

18 *Provisional* 

PMIX\_STORAGE\_MEDIUM\_UNKNOWN The storage medium type is unknown.

19 *Provisional* 

PMIX\_STORAGE\_MEDIUM\_TAPE The storage system uses tape media.

20 Provisional

The storage system uses HDDs with traditional SAS, SATA

2122 *Provisional* 

PMIX\_STORAGE\_MEDIUM\_SSD interfaces.

PMIX STORAGE MEDIUM HDD

interfaces.

The storage system uses SSDs with traditional SAS, SATA

24 *Provisional* 

PMIX\_STORAGE\_MEDIUM\_NVME
PMIX\_STORAGE\_MEDIUM\_PMEM

The storage system uses SSDs with NVMe interface.

25 *Provisional* 

The storage system uses persistent memory.

26 *Provisional* 

**PMIX\_STORAGE\_MEDIUM\_RAM** The storage system is volatile (e.g., tmpfs).

		Advice to PMIx library implementers —		
1 2 3 4		PMIx implementations should maintain the same ordering for bit-mask values for <code>pmix_storage_medium_t</code> struct as provided in this standard, since these constants are ordered to provide semantic information that may be of use to PMIx users. Namely, <code>pmix_storage_medium_t</code> constants are ordered in terms of increasing medium bandwidth.		
5 6 7		It is further recommended that implementations should try to allocate empty bits in the mask so that they can be extended to account for new constant definitions corresponding to new storage mediums.		
8 9 10 11	Provisional	The <code>pmix_storage_accessibility_t</code> is a <code>uint64_t</code> type that defines a set of bit-mask flags for specifying different levels of storage accessibility (i.e,. from where a storage system may be accessed). These can be bitwise OR'd together to accommodate storage systems that are accessibile in multiple ways.		
12	Provisional	PMIX_STORAGE_ACCESSIBILITY_NODE  The storage system resources are accessible		
13 14	Provisional	within the same node.  PMIX_STORAGE_ACCESSIBILITY_SESSION The storage system resources are accessible		
15		within the same session.		
16	<b>Provisional</b>	PMIX_STORAGE_ACCESSIBILITY_JOB The storage system resources are accessible		
17		within the same job.		
	<b>Provisional</b>	PMIX_STORAGE_ACCESSIBILITY_RACK The storage system resources are accessible		
19	D : 1	within the same rack.		
20 21	<u>Provisional</u>	PMIX_STORAGE_ACCESSIBILITY_CLUSTER The storage system resources are accessible within the same cluster.		
22	<b>Provisional</b>	PMIX_STORAGE_ACCESSIBILITY_REMOTE The storage system resources are remote.		
	Provisional Provisional			
23		The pmix_storage_persistence_t type specifies different levels of persistence for a		
24		particular storage system.		
25	<b>Provisional</b>	PMIX_STORAGE_PERSISTENCE_TEMPORARY Data on the storage system is persisted only		
26		temporarily (i.e, it does not survive across sessions or node reboots).		
27	<b>Provisional</b>	PMIX_STORAGE_PERSISTENCE_NODE Data on the storage system is persisted on the node.		
28	<b>Provisional</b>	PMIX_STORAGE_PERSISTENCE_SESSION Data on the storage system is persisted for the		
29	Danisis and	duration of the session.  PMIX STORAGE PERSISTENCE JOB  Data on the storage system is persisted for the		
30 31	<u>Provisional</u>	PMIX_STORAGE_PERSISTENCE_JOB Data on the storage system is persisted for the duration of the job.		
	<b>Provisional</b>	PMIX_STORAGE_PERSISTENCE_SCRATCH Data on the storage system is persisted		
33	- Cristonat	according to scratch storage policies (short-term storage, typically persisted for days to weeks).		
34	<b>Provisional</b>	PMIX_STORAGE_PERSISTENCE_PROJECT Data on the storage system is persisted		
35		according to project storage policies (long-term storage, typically persisted for the duration of		
36		a project).		

1	PMIX_STORAGE_PERSISTENCE_	_ARCHIVE Data on the storage system is persisted		
2	according to archive storage policies (long-term storage, typically persisted indefinitely).			
3	The pmix_storage_access_ty	<b>'pe_t</b> type specifies different storage system access types.		
4 Provisional	PMIX_STORAGE_ACCESS_RD	Provide information on storage system read operations.		
5  Provisional	PMIX_STORAGE_ACCESS_WR	Provide information on storage system write operations.		
6 <i>Provisional</i>	PMIX_STORAGE_ACCESS_RDWR	Provide information on storage system read and write		
7	operations.			

# **8 18.2 Storage support attributes**

9	The following attributes may be returned in response to queries (e.g., PMIx_Get or
10	PMIx_Query_info) made by processes or tools.
11 Dunnisianal	<pre>PMIX_STORAGE_ID "pmix.strg.id" (char*)</pre>
11 <i>Provisional</i> 12	An identifier for the storage system (e.g., lustre-fs1, daos-oss1, home-fs)
12 13 <i>Provisional</i>	PMIX_STORAGE_PATH "pmix.strg.path" (char*)
13 <i>Frovisionai</i> 14	Mount point path for the storage system (valid only for file-based storage systems)
14 15 <i>Provisional</i>	PMIX_STORAGE_TYPE "pmix.strg.type" (char*)
16	Type of storage system (i.e., "lustre", "gpfs", "daos", "ext4")
17 <i>Provisional</i>	PMIX_STORAGE_VERSION "pmix.strg.ver" (char*)
18	Version string for the storage system
19 <i>Provisional</i>	PMIX_STORAGE_MEDIUM "pmix.strg.medium" (pmix_storage_medium_t)
20	Types of storage mediums utilized by the storage system (e.g., SSDs, HDDs, tape)
21	PMIX STORAGE ACCESSIBILITY
22 <i>Provisional</i>	"pmix.strg.access" (pmix_storage_accessibility_t)
23	Accessibility level of the storage system (e.g., within same node, within same session)
24	PMIX_STORAGE_PERSISTENCE
25 <i>Provisional</i>	<pre>"pmix.strg.persist" (pmix_storage_persistence_t)</pre>
26	Persistence level of the storage system (e.g., sratch storage or achive storage)
27 <i>Provisional</i>	<pre>PMIX_QUERY_STORAGE_LIST "pmix.strg.list" (char*)</pre>
28	Comma-delimited list of storage identifiers (i.e., PMIX_STORAGE_ID types) for available
29	storage systems
30 <i>Provisional</i>	PMIX_STORAGE_CAPACITY_LIMIT "pmix.strg.caplim" (double)
31	Overall limit on capacity (in bytes) for the storage system
32 <i>Provisional</i>	<pre>PMIX_STORAGE_CAPACITY_USED "pmix.strg.capuse" (double)</pre>
33	Overall used capacity (in bytes) for the storage system
34 <i>Provisional</i>	<pre>PMIX_STORAGE_OBJECT_LIMIT "pmix.strg.objlim" (uint64_t)</pre>
35	Overall limit on number of objects (e.g., inodes) for the storage system
36 <i>Provisional</i>	PMIX_STORAGE_OBJECTS_USED "pmix.strg.objuse" (uint64_t)
37	Overall used number of objects (e.g., inodes) for the storage system

PMIX\_STORAGE\_MINIMAL\_XFER\_SIZE "pmix.strg.minxfer" (double)

38 *Provisional* 

1		Minimal transfer size (in bytes) for the storage system - this is the storage system's atomic
2		unit of transfer (e.g., block size)
3	<b>Provisional</b>	PMIX_STORAGE_SUGGESTED_XFER_SIZE "pmix.strg.sxfer" (double)
4		Suggested transfer size (in bytes) for the storage system
5	<b>Provisional</b>	<pre>PMIX_STORAGE_BW_MAX "pmix.strg.bwmax" (double)</pre>
6		Maximum bandwidth (in bytes/sec) for storage system - provided as the theoretical
7		maximum or the maximum observed bandwidth value
8	<b>Provisional</b>	<pre>PMIX_STORAGE_BW_CUR "pmix.strg.bwcur" (double)</pre>
9		Observed bandwidth (in bytes/sec) for storage system - provided as a recently observed
10		bandwidth value, with the exact measurement interval depending on the storage system
11		and/or PMIx library implementation
12	<b>Provisional</b>	<pre>PMIX_STORAGE_IOPS_MAX "pmix.strg.iopsmax" (double)</pre>
13		Maximum IOPS (in I/O operations per second) for storage system - provided as the
14		theoretical maximum or the maximum observed IOPS value
15	<b>Provisional</b>	PMIX_STORAGE_IOPS_CUR "pmix.strg.iopscur" (double)
16		
		Observed IOPS (in I/O operations per second) for storage system - provided as a recently
17		
17 18		Observed IOPS (in I/O operations per second) for storage system - provided as a recently
		Observed IOPS (in I/O operations per second) for storage system - provided as a recently observed IOPS value, with the exact measurement interval depending on the storage system
18 19	<b>Provisional</b>	Observed IOPS (in I/O operations per second) for storage system - provided as a recently observed IOPS value, with the exact measurement interval depending on the storage system and/or PMIx library implementation
18 19	<u>Provisional</u>	Observed IOPS (in I/O operations per second) for storage system - provided as a recently observed IOPS value, with the exact measurement interval depending on the storage system and/or PMIx library implementation  PMIX_STORAGE_ACCESS_TYPE
18 19 20	Provisional	Observed IOPS (in I/O operations per second) for storage system - provided as a recently observed IOPS value, with the exact measurement interval depending on the storage system and/or PMIx library implementation  PMIX_STORAGE_ACCESS_TYPE  "pmix.strg.atype" (pmix_storage_access_type_t)

### **APPENDIX A**

# **Python Bindings**

While the PMIx Standard is defined in terms of C-based APIs, there is no intent to limit the use of PMIx to that specific language. Support for other languages is captured in the Standard by describing their equivalent syntax for the PMIx APIs and native forms for the PMIx datatypes. This Appendix specifically deals with Python interfaces, beginning with a review of the PMIx datatypes. Support is restricted to Python 3 and above - i.e., the Python bindings do not support Python 2.

Note: the PMIx APIs have been loosely collected into three Python classes based on their PMIx "class" (i.e., client, server, and tool). All processes have access to a basic set of the APIs, and therefore those have been included in the "client" class. Servers can utilize any of those functions plus a set focused on operations not commonly executed by an application process. Finally, tools can also act as servers but have their own initialization function.

# A.1 Design Considerations

Several issues arose during design of the Python bindings:

### 3 A.1.1 Error Codes vs Python Exceptions

The C programming language reports errors through the return of the corresponding integer status codes. PMIx has defined a range of negative values for this purpose. However, Python has the option of raising *exceptions* that effectively operate as interrupts that can be trapped if the program appropriately tests for them. The PMIx Python bindings opted to follow the C-based standard and return PMIx status codes in lieu of raising exceptions as this method was considered more consistent for those working in both domains.

### 20 A.1.2 Representation of Structured Data

PMIx utilizes a number of C-language structures to efficiently bundle related information. For example, the PMIx process identifier is represented as a struct containing a character array for the namespace and a 32-bit unsigned integer for the process rank. There are several options for translating such objects to Python – e.g., the PMIx process identifier could be represented as a two-element tuple (nspace, rank) or as a dictionary 'nspace': name, 'rank': 0. Exploration found no discernible benefit to either representation, nor was any clearly identifiable rationale developed that would lead a user to expect one versus the other for a given PMIx data type. Consistency in the translation (i.e., exclusively using tuple or dictionary) appeared to be the most important criterion. Hence, the decision was made to express all complex datatypes as Python dictionaries.

# A.2 Datatype Definitions

PMIx defines a number of datatypes comprised of fixed-size character arrays, restricted range integers (e.g., uint32\_t), and structures. Each datatype is represented by a named unsigned 16-bit integer (uint16\_t) constant. Users are advised to use the named PMIx constants for indicating datatypes instead of integer values to ensure compatibility with future PMIx versions.

With only a few exceptions, the C-based PMIx datatypes defined in Chapter 3 on page 12 directly translate to Python. However, Python lacks the size-specific value definitions of C (e.g., uint8\_t) and thus some care must be taken to protect against overflow/underflow situations when moving between the languages. Python bindings that accept values including PMIx datatypes shall therefore have the datatype and associated value checked for compatibility with their PMIx-defined equivalents, returning an error if:

- datatypes not defined by PMIx are encountered
- provided values fall outside the range of the C-equivalent definition e.g., if a value identified as **PMIX\_UINT8** lies outside the **uint8\_t**range

Note that explicit labeling of PMIx data type, even when Python itself doesn't care, is often required for the Python bindings to know how to properly interpret and label the provided value when passing it to the PMIx library.

Table A.1 lists the correspondence between data types in the two languages.

Table A.1.: C-to-Python Datatype Correspondence

	· · · · · · · · · · · · · · · · · · ·	Datatype Correspondence	
C-Definition	PMIx Name	Python Definition	Notes
bool	PMIX_BOOL	boolean	
byte	PMIX_BYTE	A single element byte	
		array (i.e., a byte array	
		of length one)	
char*	PMIX_STRING	string	
size_t	PMIX_SIZE	integer	
pid_t	PMIX_PID	integer	value shall be limited to the uint32_t
			range
<pre>int, int8_t, int16_t,</pre>	PMIX_INT, PMIX_INT8,	integer	value shall be limited to its corresponding
int32_t, int64_t	PMIX_INT16,		range
	PMIX_INT32, PMIX_INT64		
uint, uint8_t,	PMIX_UINT, PMIX_UINT8,	integer	value shall be limited to its corresponding
uint16_t, uint32_t,	PMIX_UINT16,		range
uint64_t	PMIX_UINT32,		
	PMIX_UINT64		
float, double	PMIX_FLOAT,	float	value shall be limited to its corresponding
	PMIX_DOUBLE		range
struct timeval	PMIX_TIMEVAL	{'sec': sec, 'usec':	each field is an integer value
	4	microsec}	
time_t	PMIX_TIME	integer	limited to positive values
pmix_data_type_t	PMIX_DATA_TYPE	integer	value shall be limited to the uint16_t
			range
pmix_status_t	PMIX_STATUS	integer	V .
pmix_key_t	N/A	string	The string's length shall be limited to one
			less than the size of the pmix_key_t
			array (to reserve space for the terminating
			NULL)
pmix_nspace_t	N/A	string	The string's length shall be limited to one
			less than the size of the pmix_nspace_t
			array (to reserve space for the terminating
			NULL)

Table A.1.: C-to-Python Datatype Correspondence

C-Definition	PMIx Name	Python Definition	Notes
pmix_rank_t	PMIX_PROC_RANK	integer	value shall be limited to the uint32_t
			range excepting the reserved values near
			UINT32_MAX
pmix_proc_t	PMIX_PROC	{'nspace': nspace,	nspace is a Python string and rank is an
	47 200	'rank': rank}	integer value. The <i>nspace</i> string's length
			shall be limited to one less than the size of
			the pmix_nspace_t array (to reserve
			space for the terminating <b>NULL</b> ), and the
			rank value shall conform to the constraints
			associated with pmix_rank_t
pmix_byte_object_t	PMIX_BYTE_OBJECT	{'bytes': bytes, 'size':	bytes is a Python byte array and size is the
	, ,	size}	integer number of bytes in that array.
pmix_persistence_t	PMIX_PERSISTENCE	integer	value shall be limited to the uint8_t
			range
pmix_scope_t	PMIX_SCOPE	integer	value shall be limited to the uint8_t
			range
<pre>pmix_data_range_t</pre>	PMIX_RANGE	integer	value shall be limited to the uint8_t
			range
pmix_proc_state_t	PMIX_PROC_STATE	integer	value shall be limited to the uint8_t
			range
pmix_proc_info_t	PMIX_PROC_INFO	{'proc': {'nspace':	proc is a Python <b>proc</b> dictionary;
		nspace, 'rank':	hostname and executable are Python
		rank}, 'hostname':	strings; and pid, exitcode, and state are
		hostname, 'executable':	Python integers
		executable, 'pid': pid,	
		'exitcode': exitcode,	
		'state': state}	

Table A.1.: C-to-Python Datatype Correspondence

C-Definition	PMIx Name	Python Definition	Notes
		3	
pmix_data_array_t	PMIX_DATA_ARRAY	{'type': type, 'array':	type is the PMIx type of object in the array
		array}	and array is a Python list containing the
			individual array elements. Note that array
			can consist of any PMIx types, including
			(for example) a Python <b>info</b> object that
			itself contains an <b>array</b> value
<pre>pmix_info_directives_t</pre>	PMIX_INFO_DIRECTIVES	list	list of integer values (defined in Section
			3.2.10)
pmix_alloc_directive_t	PMIX_ALLOC_DIRECTIVE	integer	value shall be limited to the uint8_t
			range
pmix_iof_channel_t	PMIX_IOF_CHANNEL	list	list of integer values (defined in Section
	, , ,		17.3.3)
pmix_envar_t	PMIX_ENVAR	{'envar': envar,	envar and value are Python strings, and
		'value': value,	separator a single-character Python string
		'separator': separator}	
pmix_value_t	PMIX_VALUE	{'value': value,	type is the PMIx datatype of value, and
		'val_type': type}	value is the associated value expressed
			in the appropriate Python form for the
			specified datatype
pmix_info_t	PMIX_INFO	{'key': key, 'flags':	key is a Python string key, flags is an
		flags, value': value,	info directives value, type is
		'val_type': type}	the PMIx datatype of value, and value
			is the associated value expressed in the
			appropriate Python form for the specified
			datatype
pmix_pdata_t	PMIX_PDATA	{'proc': {'nspace':	proc is a Python proc dictionary;
		nspace, 'rank': rank},	key is a Python string <b>key</b> ; type is the
		'key': key, 'value':	PMIx datatype of <i>value</i> ; and <i>value</i> is
		value, 'val_type': type}	the associated value expressed in the
		, = 31 31 7	appropriate Python form for the specified
			datatype
		l .	

Table A.1.: C-to-Python Datatype Correspondence			
C-Definition	PMIx Name	Python Definition	Notes
pmix_app_t	PMIX_APP	{'cmd': cmd, 'argv': [argv], 'env': [env], 'maxprocs': maxprocs, 'info': [info]}	cmd is a Python string; argv and env are Python lists containing Python strings; maxprocs is an integer; and info is a Python list of info values
pmix_query_t	PMIX_QUERY	{'keys': [keys], 'qualifiers': [info]}	keys is a Python list of Python strings, and qualifiers is a Python list of info values
pmix_regattr_t	PMIX_REGATTR	{'name': name, 'key': key, 'type': type, 'info': [info], 'description': [desc]}	name and string are Python strings; type is the PMIx datatype for the attribute's value; info is a Python list of info values; and description is a list of Python strings describing the attribute
pmix_job_state_t	PMIX_JOB_STATE	integer	value shall be limited to the uint8_t range
pmix_link_state_t	PMIX_LINK_STATE	integer	value shall be limited to the uint8_t range
pmix_cpuset_t	PMIX_PROC_CPUSET	{'source': source, 'cpus': bitmap}	source is a string name of the library that created the cpuset; and cpus is a list of string ranges identifying the PUs to which the process is bound (e.g., [1, 3-5, 7])
pmix_locality_t	PMIX_LOCTYPE	list	list of integer values (defined in Section 11.4.2.3) describing the relative locality of the specified local process
pmix_fabric_t	N/A	{'name': name, 'index': idx, 'info': [info]}	name is the string name assigned to the fabric; <i>index</i> is the integer ID assigned to the fabric; <i>info</i> is a list of <b>info</b> describing the fabric
pmix_endpoint_t	PMIX_ENDPOINT	{'uuid': uuid, 'osname': osname, endpt': endpt}	uuid is the string system-unique identifier assigned to the device; osname is the operating system name assigned to the device; endpt is a byteobject containing the endpoint information

Table A.1.: C-to-Python Datatype Correspondence

Table 14.1 C to 1 julion Butter per Correspondence			
C-Definition	PMIx Name	Python Definition	Notes
pmix_device_distance_t	PMIX_DEVICE_DIST	{'uuid': uuid,	<i>uuid</i> is the string system-unique identifier
		'osname': osname,	assigned to the device; osname is the
		mindist': mindist,	operating system name assigned to the
		'maxdist': maxdist}	device; and <i>mindist</i> and <i>maxdist</i> are
			Python integers
pmix_coord_t	PMIX_COORD	{'view': view, 'coord':	view is the pmix_coord_view_t of the
		[coords]}	coordinate; and <i>coord</i> is a list of integer
			coordinates, one for each dimension of the
			fabric
pmix_geometry_t	PMIX_GEOMETRY	{'fabric': idx, 'uuid':	fabric is the Python integer index of the
		uuid, 'osname':	fabric; <i>uuid</i> is the string system-unique
	, , ,	osname, coordinates':	identifier assigned to the device; osname is
		[coords]}	the operating system name assigned to the
			device; and <i>coordinates</i> is a list of <b>coord</b>
			containing the coordinates for the device
	1		across all views
pmix_device_type_t	PMIX_DEVTYPE	list	list of integer values (defined in Section
			11.4.8)
pmix_bind_envelope_t	N/A	integer	one of the values defined in Section
			11.4.4.1

## A.2.1 Example

2

3

5

6 7 8

9 10

11

12 13

14

15

16

17 18

19

20

21 22

23 24

25 26

27

28

29

30

Converting a C-based program to its Python equivalent requires translation of the relevant datatypes as well as use of the appropriate API form. An example small program may help illustrate the changes. Consider the following C-based program snippet:

```
#include <pmix.h>
pmix info t info[2];
PMIX_INFO_LOAD(&info[0], PMIX_PROGRAMMING_MODEL, "TEST", PMIX_STRING)
PMIX_INFO_LOAD (&info[1], PMIX_MODEL_LIBRARY_NAME, "PMIX", PMIX_STRING)
rc = PMIx_Init(&myproc, info, 2);
PMIX_INFO_DESTRUCT(&info[0]);
                                   // free the copied string
                                   // free the copied string
PMIX_INFO_DESTRUCT(&info[1]);
                                     C
Moving to the Python version requires that the pmix info t be translated to the Python info
equivalent, and that the returned information be captured in the return parameters as opposed to a
pointer parameter in the function call, as shown below:
import pmix
myclient = PMIxClient()
info = [{'kev':PMIX PROGRAMMING MODEL,
```

Note the use of the **PMIX\_STRING** identifier to ensure the Python bindings interpret the provided string value as a PMIx "string" and not an array of bytes.

Python

'value': 'TEST', 'val\_type': PMIX\_STRING},

'value': 'PMIX', 'val\_type': PMIX\_STRING}]

{ 'key': PMIX\_MODEL\_LIBRARY\_NAME,

(rc, myproc) = myclient.init(info)

# 1 A.3 Callback Function Definitions

# 2 A.3.1 IOF Delivery Function

3 4	Summary Callback function for delivering forwarded IO to a process
5 <i>PMIx v4.0</i>	Format Python
6 7	<pre>def iofcbfunc(iofhdlr:integer, channel:bitarray,</pre>
8 9 10 11 12 13 14 15 16 17	<ul> <li>IN iofhdlr         Registration number of the handler being invoked (integer)</li> <li>IN channel         Python channel 16-bit bitarray identifying the channel the data arrived on (bitarray)</li> <li>IN source         Python proc identifying the namespace/rank of the process that generated the data (dict)</li> <li>IN payload         Python byteobject containing the data (dict)</li> <li>IN info         List of Python info provided by the source containing metadata about the payload. This could include PMIX_IOF_COMPLETE (list)</li> </ul>
19 20	Returns: nothing  See pmix_iof_cbfunc_t for details
21 <b>A.3.2</b>	Event Handler
22 23	Summary Callback function for event handlers
24 <i>PMIx v4.0</i>	Format

		Python	
1		ef evhandler(evhdlr:integer, status	
2		source:dict, info:list Python	•
3		N iofhdlr	CK
4		Registration number of the handler being invoked	d (integer)
5		V status	a (mieger)
6		Status associated with the operation (integer)	
7		N source	
8		Python proc identifying the namespace/rank of	the process that generated the event (dict)
9		N info	
0		List of Python <b>info</b> provided by the source con	taining metadata about the event (list)
11		N results	
12		List of Python <b>info</b> containing the aggregated r	esults of all prior evhandlers (list)
13		deturns:	
14		$\it rc$ - Status returned by the event handler's operation	(integer)
15 16		results - List of Python <b>info</b> containing results from (list)	m this event handler's operation on the event
17		ee pmix_notification_fn_t for details	
8	A.3.3	erver Module Functions	
19		he following definitions represent functions that may	
20		me of initialization for servicing of client requests. M	Iodule functions that are not provided default
21		returning "not supported" to the caller.	
22	A.3.3.1	Client Connected	
23		Summary	
24		Notify the host server that a client connected to this se	rver.

25 PMIx v4.0 Format

	Python —
1	def clientconnected2(proc:dict is not None, info:list)  Python
2 3 4 5	<ul> <li>IN proc         Python proc identifying the namespace/rank of the process that connected (dict)     </li> <li>IN info         list of Python info containing information about the process (list)     </li> </ul>
6	Returns:
7	• rc - PMIX_SUCCESS or a PMIx error code indicating the connection should be rejected (integer)
8	See pmix_server_client_connected2_fn_t for details
9 <b>A.3.3.2</b> 10 11	Client Finalized Summary Notify the host environment that a client called PMIx_Finalize.
12 <i>PMIx v4.0</i>	Format Python
13	<pre>def clientfinalized(proc:dict is not None):</pre> <pre>Python</pre>
14 15	IN proc Python proc identifying the namespace/rank of the process that finalized (dict)
16	Returns: nothing
17	See pmix_server_client_finalized_fn_t for details
18 <b>A.3.3.3</b>	Client Aborted
19 20	Summary Notify the host environment that a local client called PMIx_Abort.

1		Format Python —			
2		def clientaborted(args:dict is not None)  Python			
3 4		IN args Python dictionary containing:			
5		• 'caller': Python proc identifying the namespace/rank of the process calling abort (dict)			
6		• 'status': PMIx status to be returned on exit (integer)			
7		• 'msg': Optional string message to be printed (string)			
8 9		• 'targets': Optional list of Python <b>proc</b> identifying the namespace/rank of the processes to be aborted (list)			
10		Returns:			
11		• rc - PMIX_SUCCESS or a PMIx error code indicating the operation failed (integer)			
12		See pmix_server_abort_fn_t for details			
13	A.3.3.4	Fence			
14 15		Summary At least one client called either PMIx_Fence or PMIx_Fence_nb			
16	PMIx v4.0	Format Python			
17		def fence(args:dict is not None)  Python			
18 19		IN args Python dictionary containing:			
20 21		• 'procs': List of Python <b>proc</b> identifying the namespace/rank of the participating processes (list)			
22 23		• 'directives': Optional list of Python <b>info</b> containing directives controlling the operation (list)			
24		• 'data': Optional Python bytearray of data to be circulated during fence operation (bytearray)			
25		Returns:			
26		• rc - PMIX_SUCCESS or a PMIx error code indicating the operation failed (integer)			
27		• data - Python bytearray containing the aggregated data from all participants (bytearray)			
28		See pmix_server_fencenb_fn_t for details			

#### 2 Summary 3 Used by the PMIx server to request its local host contact the PMIx server on the remote node that 4 hosts the specified proc to obtain and return a direct modex blob for that proc. <sup>5</sup> *PMIx v4.0* **Format** Python 6 def dmodex(args:dict is not None) Python IN 7 args Python dictionary containing: 8 9 • 'proc': Python proc of process whose data is being requested (dict) 10 • 'directives': Optional list of Python **info** containing directives controlling the operation (list) 11 12 Returns: • rc - PMIX\_SUCCESS or a PMIx error code indicating the operation failed (integer) 13 • data - Python bytearray containing the data for the specified process (bytearray) 14 See pmix server dmodex reg fn t for details 15 A.3.3.6 **Publish** 16 Summary 17 18 Publish data per the PMIx API specification. **Format** <sup>19</sup> *PMIx v4.0* Python 20 def publish (args:dict is not None) Python 21 IN args 22 Python dictionary containing: 23 • 'proc': Python **proc** dictionary of process publishing the data (dict) • 'directives': List of Python **info** containing data and directives (list) 24 Returns: 25 26 • rc - PMIX\_SUCCESS or a PMIx error code indicating the operation failed (integer) 27 See pmix\_server\_publish\_fn\_t for details

A.3.3.5 Direct Modex

1

1	A.3.3.7	Lookup				
2		Summary Lookup published data.				
4	PMIx v4.0	Format Python				
5		def lookup(args:dict is not None)  Python				
6 7		IN args Python dictionary containing:				
8		• 'proc': Python <b>proc</b> of process seeking the data (dict)				
9		• 'keys': List of Python strings (list)				
10		• 'directives': Optional list of Python info containing directives (list)				
11		Returns:				
12		• rc - PMIX_SUCCESS or a PMIx error code indicating the operation failed (integer)				
13		• pdata - List of pdata containing the returned results (list)				
14		See pmix_server_lookup_fn_t for details				
15	A.3.3.8	Unpublish				
16 17		Summary Delete data from the data store.				
18	PMIx v4.0	Format Python				
19		def unpublish(args:dict is not None)  Python				
20 21		IN args Python dictionary containing:				
22		• 'proc': Python <b>proc</b> of process unpublishing data (dict)				
23		• 'keys': List of Python strings (list)				
24		• 'directives': Optional list of Python info containing directives (list)				
25		Returns:				
26		• rc - PMIX_SUCCESS or a PMIx error code indicating the operation failed (integer)				
27		See pmix_server_unpublish_fn_t for details				

#### **A.3.3.9** Spawn 2 Summary 3 Spawn a set of applications/processes as per the PMIx Spawn API. **Format** <sup>4</sup> *PMIx v4.0* Python def spawn(args:dict is not None) 5 **Python** IN args 6 7 Python dictionary containing: 8 • 'proc': Python proc of process making the request (dict) • 'jobinfo': Optional list of Python info job-level directives and information (list) 9 • 'apps': List of Python app describing applications to be spawned (list) 10 Returns: 11 • rc - PMIX\_SUCCESS or a PMIx error code indicating the operation failed (integer) 12 13 • nspace - Python string containing namespace of the spawned job (str) See pmix server spawn fn t for details 14 A.3.3.10 Connect 15 16 Summarv Record the specified processes as *connected*. 17 <sup>18</sup> *PMIx v4.0* Format Python 19 def connect (args:dict is not None) **Python** 20 IN args 21 Python dictionary containing: 22 • 'procs': List of Python **proc** identifying the namespace/rank of the participating processes 23 24 'directives': Optional list of Python **info** containing directives controlling the operation 25 26 Returns: 27 • rc - PMIX\_SUCCESS or a PMIx error code indicating the operation failed (integer) See pmix\_server\_connect\_fn\_t for details 28

468

1	A.3.3.11	Disconnect					
2 3		<b>Summary</b> Disconnect a previously connected set of processes.					
4	PMIx v4.0	Format Python					
5		def disconnect(args:dict is not None)  Python					
6 7		IN args Python dictionary containing:					
8 9		• 'procs': List of Python <b>proc</b> identifying the namespace/rank of the participating processes (list)					
10 11		• 'directives': Optional list of Python <b>info</b> containing directives controlling the operation (list)					
12		Returns:					
13		• <i>rc</i> - <b>PMIX_SUCCESS</b> or a PMIx error code indicating the operation failed (integer)					
14		See pmix_server_disconnect_fn_t for details					
15	A.3.3.12	Register Events					
16		Summary					
17		Register to receive notifications for the specified events.					
18	PMIx v4.0	Format Python					
19		<pre>def register_events(args:dict is not None)</pre>					
20 21		IN args					
		Python dictionary containing:					
22		<ul><li>Yodes': List of Python integers (list)</li></ul>					
22 23 24	4						
23		<ul> <li>'codes': List of Python integers (list)</li> <li>'directives': Optional list of Python info containing directives controlling the operation</li> </ul>					
23 24		<ul> <li>'codes': List of Python integers (list)</li> <li>'directives': Optional list of Python info containing directives controlling the operation (list)</li> </ul>					

#### A.3.3.13 Deregister Events 1 2 Summary 3 Deregister to receive notifications for the specified events. **Format** <sup>4</sup> *PMIx v4.0* **Python** def deregister\_events(args:dict is not None) 5 **Python** IN 6 aras 7 Python dictionary containing: 8 • 'codes': List of Python integers (list) Returns: 9 • rc - PMIX\_SUCCESS or a PMIx error code indicating the operation failed (integer) 10 See pmix\_server\_deregister\_events\_fn\_t for details 11 A.3.3.14 Notify Event 12 13 Summarv 14 Notify the specified range of processes of an event. **Format** 15 *PMIx v4.0* **Python** 16 def notify event (args:dict is not None) **Python** 17 IN args Python dictionary containing: 18 19 • 'code': Python integer pmix\_status\_t (integer) • 'source': Python **proc** of process that generated the event (dict) 20 21 • 'range': Python **range** in which the event is to be reported (integer) • 'directives': Optional list of Python info directives (list) 22 23 Returns: • rc - PMIX\_SUCCESS or a PMIx error code indicating the operation failed (integer) 24 See pmix\_server\_notify\_event\_fn\_t for details 25 A.3.3.15 Query 26 27 Summary 28 Query information from the resource manager.

1		Format Python
2		def query(args:dict is not None)  Python
3		IN args Python dictionary containing:
·		
5		• 'source': Python <b>proc</b> of requesting process (dict)
6 7		• 'queries': List of Python query directives (list)  Returns:
8		• rc - PMIX_SUCCESS or a PMIx error code indicating the operation failed (integer)
9		• <i>info</i> - List of Python <b>info</b> containing the returned results (list)
10		See pmix_server_query_fn_t for details
11	A.3.3.16	Tool Connected
12 13		Summary Register that a tool has connected to the server.
14	PMIx v4.0	Format Python
15		def tool_connected(args:dict is not None)  Python
16 17		IN args Python dictionary containing:
18		• 'directives': Optional list of Python info on the connecting tool (list)
19		Returns:
20		• rc - PMIX_SUCCESS or a PMIx error code indicating the operation failed (integer)
21		• proc - Python proc containing the assigned namespace:rank for the tool (dict)
22		See pmix_server_tool_connection_fn_t for details
23	A.3.3.17	Log
24 25		Summary Log data on behalf of a client.

1	Format Python —
2	def log(args:dict is not None)
	Python —
3 4	IN args Python dictionary containing:
5	• 'source': Python <b>proc</b> of requesting process (dict)
6	• 'data': Optional list of Python <b>info</b> containing data to be logged (list)
7	• 'directives': Optional list of Python <b>info</b> containing directives (list)
8	Returns:
9	• rc - PMIX_SUCCESS or a PMIx error code indicating the operation failed (integer)
10	See pmix_server_log_fn_t for details.
1 <b>A.3.3.</b>	18 Allocate Resources
12 13	Summary Request allocation operations on behalf of a client.
14 PMIx v4.0	Format Python
15	def allocate(args:dict is not None)  Python
16 17	IN args Python dictionary containing:
18	• 'source': Python <b>proc</b> of requesting process (dict)
19	• 'action': Python allocdir specifying requested action (integer)
20	• 'directives': Optional list of Python <b>info</b> containing directives (list)
21	Returns:
22	• rc - PMIX_SUCCESS or a PMIx error code indicating the operation failed (integer)
23	• refarginfo - List of Python info containing results of requested operation (list)
24	See pmix_server_alloc_fn_t for details.
25 <b>A.3.3.</b>	19 Job Control
26 27	Summary Execute a job control action on behalf of a client.

1		Format Python
2		<pre>def job_control(args:dict is not None)</pre>
3 4		IN args Python dictionary containing:
5		• 'source': Python proc of requesting process (dict)
6		• 'targets': List of Python proc specifying target processes (list)
7		• 'directives': Optional list of Python info containing directives (list)
8		Returns:
9		• rc - PMIX_SUCCESS or a PMIx error code indicating the operation failed (integer)
10		See pmix_server_job_control_fn_t for details.
11	A.3.3.20	Monitor
12 13		Summary Request that a client be monitored for activity.
14	PMIx v4.0	Format Python
15		def monitor(args:dict is not None)  Python
16 17		IN args Python dictionary containing:
18		• 'source': Python <b>proc</b> of requesting process (dict)
19		• 'monitor': Python info attribute indicating the type of monitor being requested (dict)
20 21		• 'error': Status code to be used when generating an event notification (integer) alerting that the monitor has been triggered.
22		• 'directives': Optional list of Python info containing directives (list)
23		Returns:
24		• rc - PMIX_SUCCESS or a PMIx error code indicating the operation failed (integer)
25		See pmix_server_monitor_fn_t for details.
26	A.3.3.21	Get Credential
27 28		Summary Request a credential from the host environment.

1	Format Python —	_
2	def get_credential(args:dict is not None) Python	
3 4	IN args Python dictionary containing:	,
5	• 'source': Python proc of requesting process (dict)	
6	• 'directives': Optional list of Python info containing directives (list)	
7	Returns:	
8	• rc - PMIX_SUCCESS or a PMIx error code indicating the operation failed (integer)	
9	• cred - Python byteobject containing returned credential (dict)	
10	• info - List of Python info containing any additional info about the credential (list)	
11	See pmix_server_get_cred_fn_t for details.	
2 <b>A.3.3.22</b>	2 Validate Credential	
13 14	Summary Request validation of a credential	
15 <i>PMIx v4.0</i>	Format Python	_
16	def validate_credential(args:dict is not None)  Python	
17 18	IN args Python dictionary containing:	
19	• 'source': Python <b>proc</b> of requesting process (dict)	
20	• 'credential': Python byteobject containing credential (dict)	
21	• 'directives': Optional list of Python info containing directives (list)	
22	Returns:	
23	• rc - PMIX_SUCCESS or a PMIx error code indicating the operation failed (integer)	
24	• info - List of Python info containing any additional info from the credential (list)	
25	See pmix_server_validate_cred_fn_t for details.	
26 <b>A.3.3.2</b> 3	3 IO Forward	
27 28	<b>Summary</b> Request the specified IO channels be forwarded from the given array of processes.	

1		Format Python
2		<pre>def iof_pull(args:dict is not None)</pre>
3 4		IN args Python dictionary containing:
5		• 'sources': List of Python <b>proc</b> of processes whose IO is being requested (list)
6		• 'channels': Bitmask of Python <b>channel</b> identifying IO channels to be forwarded (integer)
7		• 'directives': Optional list of Python info containing directives (list)
8		Returns:
9		$\bullet$ $\mathit{rc}$ - PMIX_SUCCESS or a PMIx error code indicating the operation failed (integer)
10		See pmix_server_iof_fn_t for details.
11	A.3.3.24	IO Push
12 13		<b>Summary</b> Pass standard input data to the host environment for transmission to specified recipients.
14	PMIx v4.0	Format Python
15		<pre>def iof_push(args:dict is not None)</pre>
16 17		IN args Python dictionary containing:
18		• 'source': Python <b>proc</b> of process whose input is being forwarded (dict)
19		• 'payload': Python byteobject containing input bytes (dict)
20		• 'targets': List of <b>proc</b> of processes that are to receive the payload (list)
21		• 'directives': Optional list of Python info containing directives (list)
22		Returns:
23		• rc - PMIX_SUCCESS or a PMIx error code indicating the operation failed (integer)
24		See pmix_server_stdin_fn_t for details.
25	A.3.3.25	Group Operations
26 27		<b>Summary</b> Request group operations (construct, destruct, etc.) on behalf of a set of processes.

1	Format Python —
2	def group(args:dict is not None)  Python
3 4	IN args Python dictionary containing:
5	• 'op': Operation host is to perform on the specified group (integer)
6	• 'group': String identifier of target group (str)
7	• 'procs': List of Python proc of participating processes (dict)
8	• 'directives': Optional list of Python <b>info</b> containing directives (list)
9	Returns:
10	• <i>rc</i> - <b>PMIX_SUCCESS</b> or a PMIx error code indicating the operation failed (integer)
11	• refarginfo - List of Python info containing results of requested operation (list)
12	See pmix_server_grp_fn_t for details.
з <b>А.З.З.26</b>	6 Fabric Operations
14 15	<b>Summary</b> Request fabric-related operations (e.g., information on a fabric) on behalf of a tool or other process.
16 <i>PMIx v4.0</i>	Format Python
17	def fabric(args:dict is not None)  Python
18 19	IN args Python dictionary containing:
20	• 'source': Python <b>proc</b> of requesting process (dict)
21	• 'index': Identifier of the fabric being operated upon (integer)
22	• 'op': Operation host is to perform on the specified fabric (integer)
23	• 'directives': Optional list of Python info containing directives (list)
24	Returns:
25	• rc - PMIX_SUCCESS or a PMIx error code indicating the operation failed (integer)
26	• refarginfo - List of Python info containing results of requested operation (list)
27	See pmix_server_fabric_fn_t for details.

### A.4 PMIxClient

The client Python class is by far the richest in terms of APIs as it houses all the APIs that an application might utilize. Due to the datatype translation requirements of the C-Python interface, only the blocking form of each API is supported – providing a Python callback function directly to the C interface underlying the bindings was not a supportable option.

### 6 A.4.1 Client.init

### 7 Summary

8

11

12

14

15

16

Initialize the PMIx client library after obtaining a new PMIxClient object.

9 <i>PMIx v4.0</i>	Format	Python	
1 W11x V4.0		•	•
10	rc, proc = myclient.init(info		
		Python	A

#### IN info

List of Python **info** dictionaries (list)

#### 13 Returns:

- rc PMIX\_SUCCESS or a negative value corresponding to a PMIx error constant (integer)
- proc a Python proc dictionary (dict)
  - See PMIx Init for description of all relevant attributes and behaviors.

### 17 A.4.2 Client.initialized

18 <i>PMIx v4.0</i>	Format	Python ————	
FINIX V4.0		T ython	
19	<pre>rc = myclient.initialized()</pre>		
		Python ————————————————————————————————————	

- 20 Returns:
- rc a value of 1 (true) will be returned if the PMIx library has been initialized, and 0 (false) otherwise (integer)
- 23 See PMIx\_Initialized for description of all relevant attributes and behaviors.

### A.4.3 Client.get version

Summary

**Format** 2 **Python** vers = myclient.get\_version() 3 **Python** Returns: 4 5 • vers - Python string containing the version of the PMIx library (e.g., "3.1.4") (integer) 6 See **PMIx\_Get\_version** for description of all relevant attributes and behaviors. Client.finalize Δ.4.4 Summary 8 Finalize the PMIx client library. 9 <sup>10</sup> *PMIx v4.0* **Format Python** rc = myclient.finalize(info:list) 11 **Python** IN info 12 List of Python **info** dictionaries (list) 13 Returns: 14 • rc - PMIX\_SUCCESS or a negative value corresponding to a PMIx error constant (integer) 15 See PMIx\_Finalize for description of all relevant attributes and behaviors. 16 A.4.5 Client.abort

18

19

Request that the provided list of processes be aborted.

```
Format
1
                                                       Python
2
               rc = myclient.abort(status:integer, msg:str, targets:list)
                                                       Python
               IN
3
                    status
 4
                    PMIx status to be returned on exit (integer)
               IN
 5
6
                    String message to be printed (string)
 7
               IN
                    targets
                    List of Python proc dictionaries (list)
8
               Returns:
9
10
               • rc - PMIX_SUCCESS or a negative value corresponding to a PMIx error constant (integer)
11
               See PMIx_Abort for description of all relevant attributes and behaviors.
    A.4.6
              Client.store internal
               Summary
13
14
               Store some data locally for retrieval by other areas of the process
               Format
                                                       Python
   PMIx v4.0
16
               rc = myclient.store_internal(proc:dict, key:str, value:dict)
                                                       Python
               IN
                    proc
17
                    Python proc dictionary of the process being referenced (dict)
18
19
               IN
                    key
                    String key of the data (string)
20
               IN
                    value
21
                    Python value dictionary (dict)
22
               Returns:
23
               • rc - PMIX_SUCCESS or a negative value corresponding to a PMIx error constant (integer)
24
25
               See PMIx Store internal for details.
    A.4.7
              Client.put
               Summary
27
               Push a key/value pair into the client's namespace.
28
```

**Format** 1 Python 2 rc = myclient.put(scope:integer, key:str, value:dict) **Python** IN 3 scope Scope of the data being posted (integer) 4 5 IN 6 String key of the data (string) 7 IN value Python **value** dictionary (dict) 8 Returns: 9 10 • rc - PMIX\_SUCCESS or a negative value corresponding to a PMIx error constant (integer) 11 See PMIx\_Put for description of all relevant attributes and behaviors. Client.commit A.4.8 Summary 13 14 Push all previously **PMIxClient.put** values to the local PMIx server. **Format** <sup>15</sup> *PMIx v4.0* Python 16 rc = myclient.commit() **Pvthon** Returns: 17 • rc - PMIX\_SUCCESS or a negative value corresponding to a PMIx error constant (integer) 18 See **PMIx\_Commit** for description of all relevant attributes and behaviors. 19 Client.fence A.4.9 Summary 21 22 Execute a blocking barrier across the processes identified in the specified list.

```
Format
 1
                                                       Python
 2
               rc = myclient.fence(peers:list, directives:list)
                                                       Python
               IN
 3
                    peers
                    List of Python proc dictionaries (list)
 4
               IN
                    directives
 5
 6
                    List of Python info dictionaries (list)
 7
               Returns:
 8
               • rc - PMIX_SUCCESS or a negative value corresponding to a PMIx error constant (integer)
 9
               See PMIx_Fence for description of all relevant attributes and behaviors.
    A.4.10
                Client.get
11
               Summary
12
               Retrieve a key/value pair.
               Format
   PMIx v4.0
                                                       Python
               rc, val = myclient.get(proc:dict, key:str, directives:list)
14
                                                       Python
15
               IN
                    proc
                    Python proc whose data is being requested (dict)
16
               IN
17
                    Python string key of the data to be returned (str)
18
19
               IN
                    directives
20
                    List of Python info dictionaries (list)
21
               Returns:
22
               • rc - PMIX_SUCCESS or a negative value corresponding to a PMIx error constant (integer)
               • val - Python value containing the returned data (dict)
23
24
               See PMIx Get for description of all relevant attributes and behaviors.
    A.4.11
                Client.publish
               Summary
26
27
               Publish data for later access via PMIx_Lookup.
```

**Format** 1 Python 2 rc = myclient.publish(directives:list) Python IN directives 3 List of Python **info** dictionaries containing data to be published and directives (list) 5 Returns: • rc - PMIX\_SUCCESS or a negative value corresponding to a PMIx error constant (integer) 6 7 See PMIx\_Publish for description of all relevant attributes and behaviors. A.4.12 Client.lookup Summary 9 Lookup information published by this or another process with PMIx\_Publish. 10 **Format** <sup>11</sup> *PMIx v4.0* Python 12 rc,info = myclient.lookup(pdata:list, directives:list) Python 13 IN pdata List of Python **pdata** dictionaries identifying data to be retrieved (list) 14 directives 15 IN List of Python **info** dictionaries (list) 16 Returns: 17 18 • rc - PMIX\_SUCCESS or a negative value corresponding to a PMIx error constant (integer) 19 • info - Python list of **info** containing the returned data (list) See PMIx Lookup for description of all relevant attributes and behaviors. 20 A.4.13 Client.unpublish Summary 22 23 Delete data published by this process with **PMIx\_Publish**.

```
Format
1
                                                      Python
2
               rc = myclient.unpublish(keys:list, directives:list)
                                                      Python
               IN
3
                    kevs
                   List of Python string keys identifying data to be deleted (list)
 4
               IN
                    directives
 5
6
                    List of Python info dictionaries (list)
 7
               Returns:
8
               • rc - PMIX_SUCCESS or a negative value corresponding to a PMIx error constant (integer)
9
               See PMIx_Unpublish for description of all relevant attributes and behaviors.
    A.4.14
                Client.spawn
11
               Summary
12
               Spawn a new job.
               Format
   PMIx v4.0
                                                      Python
               rc,nspace = myclient.spawn(jobinfo:list, apps:list)
14
                                                      Python
15
               IN
                    jobinfo
                    List of Python info dictionaries (list)
16
               IN
17
                    List of Python app dictionaries (list)
18
               Returns:
19
20
               • rc - PMIX_SUCCESS or a negative value corresponding to a PMIx error constant (integer)
21
               • nspace - Python nspace of the new job (dict)
22
               See PMIx Spawn for description of all relevant attributes and behaviors.
    A.4.15
               Client.connect
24
               Summary
25
               Connect namespaces.
```

```
Format
 1
                                                      Python
2
               rc = myclient.connect(peers:list, directives:list)
                                                      Python
               IN
3
                    peers
                   List of Python proc dictionaries (list)
 4
               IN
                    directives
 5
6
                   List of Python info dictionaries (list)
 7
               Returns:
               • rc - PMIX_SUCCESS or a negative value corresponding to a PMIx error constant (integer)
9
               See PMIx_Connect for description of all relevant attributes and behaviors.
               Client.disconnect
    A.4.16
11
               Summary
12
               Disconnect namespaces.
13 PMIx v4.0
               Format
                                                      Python
14
               rc = myclient.disconnect(peers:list, directives:list)
                                                      Python
15
               IN
                    peers
                   List of Python proc dictionaries (list)
16
               IN
                    directives
17
                   List of Python info dictionaries (list)
18
               Returns:
19
20
               • rc - PMIX_SUCCESS or a negative value corresponding to a PMIx error constant (integer)
21
               See PMIx_Disconnect for description of all relevant attributes and behaviors.
    A.4.17 Client.resolve peers
               Summary
23
24
               Return list of processes within the specified nspace on the given node.
```

1	Format Python
2	<pre>rc,procs = myclient.resolve_peers(node:str, nspace:str)</pre>
3 4 5 6	IN node Name of node whose processes are being requested (str)  IN nspace Python nspace whose processes are to be returned (str)
7	Returns:
8	• rc - PMIX_SUCCESS or a negative value corresponding to a PMIx error constant (integer)
9	• procs - List of Python proc dictionaries (list)
10	See PMIx_Resolve_peers for description of all relevant attributes and behaviors.
11 <b>A.4.18</b>	Client.resolve_nodes
12 13	<b>Summary</b> Return list of nodes hosting processes within the specified <b>nspace</b> .
14 <i>PMIx v4.0</i>	Format Python
15	rc, nodes = myclient.resolve_nodes(nspace:str)  Python
16 17	IN nspace Python nspace (str)
18	Returns:
19	• rc - PMIX_SUCCESS or a negative value corresponding to a PMIx error constant (integer)
20	• nodes - List of Python string node names (list)
21	See PMIx_Resolve_nodes for description of all relevant attributes and behaviors.
22 <b>A.4.19</b>	Client.query
23 24	<b>Summary</b> Query information about the system in general.

```
Format
 1
                                                       Python
2
               rc,info = myclient.query(queries:list)
                                                       Python
               IN
                    queries
 3
                    List of Python query dictionaries (list)
               Returns:
 5
               • rc - PMIX_SUCCESS or a negative value corresponding to a PMIx error constant (integer)
 6
 7
               • info - List of Python info containing results of the query (list)
8
               See PMIx_Query_info for description of all relevant attributes and behaviors.
    A.4.20
              Client.log
10
               Summary
11
               Log data to a central data service/store.
               Format
12 PMIx v4.0
                                                       Python
               rc = myclient.log(data:list, directives:list)
13
                                                       Python
14
                    data
                    List of Python info (list)
15
16
               IN
                    directives
                    Optional list of Python info (list)
17
18
               Returns:
19
               • rc - PMIX SUCCESS or a negative value corresponding to a PMIx error constant (integer)
               See PMIx_Log for description of all relevant attributes and behaviors.
20
    A.4.21
                Client.allocation request
               Summary
22
23
               Request an allocation operation from the host resource manager.
```

```
Format
 1
                                                       Python
               rc, info = myclient.allocation_request(request:integer, directives:list)
2
                                                       Python
               IN
 3
                    request
 4
                    Python allocdir specifying requested operation (integer)
               IN
                    directives
 5
6
                    List of Python info describing request (list)
 7
               Returns:
8
               • rc - PMIX_SUCCESS or a negative value corresponding to a PMIx error constant (integer)
9
               • info - List of Python info containing results of the request (list)
               See PMIx_Allocation_request for description of all relevant attributes and behaviors.
10
    A.4.22 Client.job ctrl
               Summary
12
               Request a job control action.
13
               Format
                                                       Python
   PMIx v4.0
15
               rc, info = myclient.job_ctrl(targets:list, directives:list)
                                                       Python
16
               IN
                    targets
                    List of Python proc specifying targets of requested operation (integer)
17
               IN
                    directives
18
                    List of Python info describing operation to be performed (list)
19
20
               Returns:
21
               • rc - PMIX_SUCCESS or a negative value corresponding to a PMIx error constant (integer)
22
               • info - List of Python info containing results of the request (list)
23
               See PMIx Job control for description of all relevant attributes and behaviors.
                Client.monitor
               Summary
25
26
               Request that something be monitored.
```

1		Format Python —————
2		rc,info = myclient.monitor(monitor:dict, error_code:integer, directives:list  Python
3		IN monitor
4 5		Python info specifying specifying the type of monitor being requested (dict)  IN error_code
6		Status code to be used when generating an event notification alerting that the monitor has
7		been triggered (integer)
8		IN directives
9		List of Python info describing request (list)
0		Returns:
1		• rc - PMIX_SUCCESS or a negative value corresponding to a PMIx error constant (integer)
2		• info - List of Python info containing results of the request (list)
3		See PMIx_Process_monitor for description of all relevant attributes and behaviors.
4 5 6	A.4.24	Client.get_credential  Summary Request a credential from the PMIx server/SMS.
7	PMIx v4.0	Format Python
8		rc,cred = myclient.get_credential(directives:list)  Python
9		IN directives Optional list of Python info describing request (list)
21		Returns:
22		• rc - PMIX_SUCCESS or a negative value corresponding to a PMIx error constant (integer)
23		• cred - Python byteobject containing returned credential (dict)
24		See PMIx_Get_credential for description of all relevant attributes and behaviors.
25	A.4.25	Client.validate_credential
26		Summary
27		Request validation of a credential by the PMIx server/SMS.

1		Format Python
2		<pre>rc,info = myclient.validate_credential(cred:dict, directives:list)</pre>
3 4 5 6		<pre>IN     cred           Python byteobject containing credential (dict) IN     directives           Optional list of Python info describing request (list)</pre>
7		Returns:
8		• rc - PMIX_SUCCESS or a negative value corresponding to a PMIx error constant (integer)
9		• <i>info</i> - List of Python <b>info</b> containing additional results of the request (list)
10		See PMIx_Validate_credential for description of all relevant attributes and behaviors.
11	A.4.26	Client.group_construct
12 13 14		<b>Summary</b> Construct a new group composed of the specified processes and identified with the provided group identifier.
15	PMIx v4.0	Format Python
16 17		<pre>rc,info = myclient.construct_group(grp:string,</pre>
18		IN grp
19 20		Python string identifier for the group (str)  IN members
21 22 23		List of Python proc dictionaries identifying group members (list)  IN directives Optional list of Python info describing request (list)
24		Returns:
25		• rc - PMIX_SUCCESS or a negative value corresponding to a PMIx error constant (integer)
26		• info - List of Python info containing results of the request (list)
27		See PMIx_Group_construct for description of all relevant attributes and behaviors.
28	A.4.27	Client.group_invite
29 30		<b>Summary</b> Explicitly invite specified processes to join a group.

```
Format
 1
                                                         Python
 2
               rc, info = myclient.group invite(grp:string,
 3
                                                members: list, directives: list)
                                                         Python
               IN
 4
                     grp
                    Python string identifier for the group (str)
 5
 6
               IN
 7
                    List of Python proc dictionaries identifying processes to be invited (list)
 8
               IN
                     directives
 9
                    Optional list of Python info describing request (list)
               Returns:
10
               • rc - PMIX_SUCCESS or a negative value corresponding to a PMIx error constant (integer)
11
12
               • info - List of Python info containing results of the request (list)
               See PMIx Group invite for description of all relevant attributes and behaviors.
13
    A.4.28 Client.group join
               Summary
15
16
               Respond to an invitation to join a group that is being asynchronously constructed.
               Format
<sup>17</sup> PMIx v4.0
                                                         Python
               rc,info = myclient.group_join(grp:string,
18
19
                                                leader:dict, opt:integer,
                                                directives:list)
20
                                                         Python
21
               IN
                     grp
                    Python string identifier for the group (str)
22
23
               IN
                     leader
24
                    Python proc dictionary identifying process leading the group (dict)
               IN
25
                     opt
                     One of the pmix_group_opt_t values indicating decline/accept (integer)
26
                     directives
27
28
                    Optional list of Python info describing request (list)
               Returns:
29
30
               • rc - PMIX SUCCESS or a negative value corresponding to a PMIx error constant (integer)
31
               • info - List of Python info containing results of the request (list)
32
               See PMIx Group join for description of all relevant attributes and behaviors.
```

490

#### A.4.29 Client.group leave Summary 3 Leave a PMIx Group. **Format** PMIx v4.0 **Python** 5 rc = myclient.group\_leave(grp:string, directives:list) Python 6 IN 7 Python string identifier for the group (str) IN directives 8 9 Optional list of Python **info** describing request (list) 10 Returns: • rc - PMIX\_SUCCESS or a negative value corresponding to a PMIx error constant (integer) 11 12 See PMIx Group leave for description of all relevant attributes and behaviors. Client.group destruct A.4.30 Summary 14 Destruct a PMIx Group. 15 **Format** PMIx v4.0 rc = myclient.group\_destruct(grp:string, directives:list) 17 **Python** IN 18 grp 19 Python string identifier for the group (str) 20 IN directives Optional list of Python info describing request (list) 21

23 • rc - **P** 

Returns:

22

24

27

- rc PMIX\_SUCCESS or a negative value corresponding to a PMIx error constant (integer)
- See PMIx Group\_destruct for description of all relevant attributes and behaviors.

## 5 A.4.31 Client.register\_event\_handler

### 26 Summary

Register an event handler to report events.

1	Format Python —
2 3	<pre>rc,id = myclient.register_event_handler(codes:list,</pre>
4 5 6 7 8 9	<ul> <li>IN codes List of Python integer status codes that should be reported to this handler (llist) </li> <li>IN directives Optional list of Python info describing request (list) </li> <li>IN cbfunc Python evhandler to be called when event is received (func) </li> </ul>
10	Returns:
11	• rc - PMIX_SUCCESS or a negative value corresponding to a PMIx error constant (integer)
12	• <i>id</i> - PMIx reference identifier for handler (integer)
13	See PMIx_Register_event_handler for description of all relevant attributes and behaviors.
14 <b>A.4.32</b>	Client.deregister_event_handler
15	Summary
16	Deregister an event handler.
16	Deregister an event handler.
16 17 <i>PMIx v4.0</i>	Deregister an event handler.  Format  Python  myclient.deregister_event_handler(id:integer)
16 17 <sub>PMIx v4.0</sub> 18	Deregister an event handler.  Format  Python  myclient.deregister_event_handler(id:integer)  Python  IN id
16 17 <i>PMIx v4.0</i> 18 19 20 21 22	Deregister an event handler.  Format  Python  myclient.deregister_event_handler(id:integer)  Python  IN id  PMIx reference identifier for handler (integer)  Returns: None  See PMIx_Deregister_event_handler for description of all relevant attributes and
16 17 <i>PMIx v4.0</i> 18 19 20 21	Deregister an event handler.  Format  Python  myclient.deregister_event_handler(id:integer)  Python  IN id  PMIx reference identifier for handler (integer)  Returns: None
16 17 <i>PMIx v4.0</i> 18 19 20 21 22	Deregister an event handler.  Format  Python  myclient.deregister_event_handler(id:integer)  Python  IN id  PMIx reference identifier for handler (integer)  Returns: None  See PMIx_Deregister_event_handler for description of all relevant attributes and behaviors.

1	Format Python —
2 3	<pre>rc = myclient.notify_event(status:integer, source:dict,</pre>
	A Python
4 5	IN status PMIx status code indicating the event being reported (integer)
6 7	N source Python proc of the process that generated the event (dict)
8	IN range
9 10	Python range in which the event is to be reported (integer)  IN directives
11	Optional list of Python info dictionaries describing the event (list)
12	Returns:
13	• rc - PMIX_SUCCESS or a negative value corresponding to a PMIx error constant (integer)
14	See <b>PMIx_Notify_event</b> for description of all relevant attributes and behaviors.
15 <b>A.4.34</b>	Client.fabric_register
16 17	Summary Register for access to fabric-related information, including communication cost matrix.
18 <i>PMIx v4.0</i>	Format Python
19	<pre>rc,idx,fabricinfo = myclient.fabric_register(directives:list)</pre>
20 21	IN directives Optional list of Python info containing directives (list)
22	Returns:
23	• rc - PMIX_SUCCESS or a negative value corresponding to a PMIx error constant (integer)
24	• <i>idx</i> - Index of the registered fabric (integer)
25	• fabricinfo - List of Python info containing fabric info (list)
26	See PMIx_Fabric_register for details.
27 <b>A.4.35</b>	Client.fabric_update
28 29	<b>Summary</b> Update fabric-related information, including communication cost matrix.

```
Format
 1
                                                       Python
 2
               rc,fabricinfo = myclient.fabric_update(idx:integer)
                                                       Python
                    idx
               IN
 3
                    Index of the registered fabric (list)
 4
               Returns:
 5
               • rc - PMIX_SUCCESS or a negative value corresponding to a PMIx error constant (integer)
 6
 7
               • fabricinfo - List of Python info containing updated fabric info (list)
 8
               See PMIx_Fabric_update for details.
    A.4.36
                Client.fabric deregister
               Summary
10
               Deregister fabric.
11
               Format
  PMIr v40
                                                       Python
13
               rc = myclient.fabric_deregister(idx:integer)
                                                       Python
               IN
14
                    idx
                    Index of the registered fabric (list)
15
16
               Returns:
               • rc - PMIX SUCCESS or a negative value corresponding to a PMIx error constant (integer)
17
18
               See PMIx_Fabric_deregister for details.
                Client.load topology
    A.4.37
               Summary
20
               Load the local hardware topology into the PMIx library.
21
22 <sub>PMIx v4.0</sub>
               Format
                                                       Python
23
               rc = myclient.load_topology()
                                                       Python
               Returns:
24
25
               • rc - PMIX_SUCCESS or a negative value corresponding to a PMIx error constant (integer)
26
               See PMIx Load topology for details - note that the topology loaded into the PMIx library may
27
               be utilized by PMIx and other libraries, but is not directly accessible by Python.
```

### A.4.38 Client.get relative locality Summary 3 Get the relative locality of two local processes. **Format** PMIx v4.0 **Python** rc,locality = myclient.get\_relative\_locality(loc1:str, loc2:str) 5 Python 6 IN loc1 7 Locality string of a process (str) IN loc2 8 Locality string of a process (str) 9 10 Returns: • rc - PMIX\_SUCCESS or a negative value corresponding to a PMIx error constant (integer) 11 12 • locality - locality list containing the relative locality of the two processes (list) 13 See PMIx\_Get\_relative\_locality for details. Client.get cpuset A.4.39 15 Summary 16 Get the PU binding bitmap of the current process. **Format** PMIx v4.0 **Python** 18 rc,cpuset = myclient.get cpuset(ref:integer) **Python** 19 IN ref **bindeny** binding envelope to be used (integer) 20 21 Returns: • rc - PMIX\_SUCCESS or a negative value corresponding to a PMIx error constant (integer) 22 23 • *cpuset* - **cpuset** containing the source and bitmap of the cpuset (dict) 24 See PMIx Get cpuset for details. A.4.40 Client.parse\_cpuset\_string

Summary

Parse the PU binding bitmap from its string representation.

26 27

### APPENDIX A. PYTHON BINDINGS

1		Format Python
2		<pre>rc,cpuset = myclient.parse_cpuset_string(cpuset:string)</pre>
3 4		IN cpuset String returned by PMIxServer.generate_cpuset_string(string)
5		Returns:
6		• rc - PMIX_SUCCESS or a negative value corresponding to a PMIx error constant (integer)
7		• cpuset - cpuset containing the source and bitmap of the cpuset (dict)
8		See PMIx_Parse_cpuset_string for details.
9 10 11	A.4.41	Client.compute_distances Summary Compute distances from specified process location to local devices.
12 <sub>/</sub>	PMIx v4.0	Format Python
13		rc, distances = myclient.compute_distances(cpuset:dict, info:list)  Python
14 15 16 17		<ul> <li>IN cpuset         cpuset describing the location of the process (dict)</li> <li>IN info         List of info dictionaries describing the devices whose distance is to be computed (list)</li> </ul>
18		Returns:
19		• rc - PMIX_SUCCESS or a negative value corresponding to a PMIx error constant (integer)
20 21		• <i>distances</i> - List of <b>devdist</b> structures containing the distances from the caller to the specified devices (list)
22 23		See PMIx_Compute_distances for details. Note that distances can only be computed against the local topology.
24	A.4.42	Client.error_string
25 26		Summary Pretty-print string representation of pmix_status_t.

```
Format
 1
                                                     Python
 2
              rep = myclient.error_string(status:integer)
                                                     Python
 3
              IN
                    status
                   PMIx status code (integer)
 4
              Returns:
 5
              • rep - String representation of the provided status code (str)
 6
 7
              See PMIx_Error_string for further details.
    A.4.43
               Client.proc_state_string
 9
              Summary
10
              Pretty-print string representation of pmix_proc_state_t.
              Format
   PMIx v4.0
                                                     Python
              rep = myclient.proc_state_string(state:integer)
12
                                                     Python
13
              IN
                    state
                   PMIx process state code (integer)
14
              Returns:
15
              • rep - String representation of the provided process state (str)
16
17
              See PMIx_Proc_state_string for further details.
    A.4.44
               Client.scope string
              Summary
19
20
              Pretty-print string representation of pmix_scope_t.
              Format
   PMIx v4.0
                                                     Python
22
              rep = myclient.scope_string(scope:integer)
                                                     Python
              IN
23
                   scope
                   PMIx scope value (integer)
24
              Returns:
25
26
              • rep - String representation of the provided scope (str)
27
              See PMIx_Scope_string for further details
```

## A.4.45 Client.persistence string

```
Summary
 3
              Pretty-print string representation of pmix_persistence_t.
              Format
<sup>4</sup> PMIx v4.0
                                                    Python
5
              rep = myclient.persistence_string(persistence:integer)
                                                    Python
6
              IN
                   persistence
 7
                   PMIx persistence value (integer)
              Returns:
              • rep - String representation of the provided persistence (str)
9
              See PMIx Persistence string for further details.
10
    A.4.46
               Client.data range string
12
              Summary
              Pretty-print string representation of pmix_data_range_t
13
              Format
14 PMIx v4.0
                                                    Python
15
              rep = myclient.data_range_string(range:integer)
                                                    Python
              IN
16
                   range
17
                   PMIx data range value (integer)
              Returns:
18
              • rep - String representation of the provided data range (str)
19
              See PMIx_Data_range_string for further details.
20
    A.4.47 Client.info directives string
22
              Summary
23
              Pretty-print string representation of pmix info directives t.
```

```
Format
 1
                                                    Python
              rep = myclient.info_directives_string(directives:bitarray)
2
                                                    Python
 3
              IN
                   directives
                   PMIx info directives value (bitarray)
 4
 5
              Returns:
              • rep - String representation of the provided info directives (str)
 6
 7
              See PMIx_Info_directives_string for further details.
    A.4.48
               Client.data_type_string
9
              Summary
10
              Pretty-print string representation of pmix_data_type_t.
   PMIx v4.0
                                                    Python
12
              rep = myclient.data_type_string(dtype:integer)
                                                    Python
13
              IN
                   dtype
                   PMIx datatype value (integer)
14
15
              Returns:
              • rep - String representation of the provided datatype (str)
16
17
              See PMIx_Data_type_string for further details.
    A.4.49
               Client.alloc directive string
              Summary
19
20
              Pretty-print string representation of pmix_alloc_directive_t.
              Format
   PMIx v4.0
                                                    Python
22
              rep = myclient.alloc_directive_string(adir:integer)
                                                    Python
              IN
                  adir
23
                   PMIx allocation directive value (integer)
24
              Returns:
25
26
              • rep - String representation of the provided allocation directive (str)
27
              See PMIx Alloc directive string for further details.
```

## A.4.50 Client.iof channel string

```
Summary
 3
              Pretty-print string representation of pmix_iof_channel_t.
              Format
<sup>4</sup> PMIx v4.0
                                                     Python
5
              rep = myclient.iof_channel_string(channel:bitarray)
                                                     Python
6
              IN
                    channel
 7
                   PMIx IOF channel value (bitarray)
8
              Returns:
              • rep - String representation of the provided IOF channel (str)
9
              See PMIx IOF channel string for further details.
10
    A.4.51
               Client.job state string
12
              Summary
              Pretty-print string representation of pmix_job_state_t
13
              Format
14 PMIx v4.0
                                                     Python
15
              rep = myclient.job_state_string(state:integer)
                                                     Python
16
              IN
                    state
17
                   PMIx job state value (integer)
              Returns:
18
              • rep - String representation of the provided job state (str)
19
              See PMIx_Job_state_string for further details.
20
    A.4.52
              Client.get attribute string
22
              Summary
23
              Pretty-print string representation of a PMIx attribute.
```

```
Format
 1
                                                    Python
2
              rep = myclient.get_attribute_string(attribute:str)
                                                     Pvthon
 3
              IN
                   attribute
                   PMIx attribute name (string)
 4
 5
              Returns:
              • rep - String representation of the provided attribute (str)
 6
 7
              See PMIx_Get_attribute_string for further details.
    A.4.53
               Client.get_attribute_name
9
              Summary
              Pretty-print name of a PMIx attribute corresponding to the provided string.
10
              Format
   PMIx v4.0
                                                     Python
12
              rep = myclient.get_attribute_name(attribute:str)
                                                     Python
13
              IN
                   attributestring
14
                   Attribute string (string)
15
              Returns:
              • rep - Attribute name corresponding to the provided string (str)
16
17
              See PMIx_Get_attribute_name for further details.
    A.4.54
               Client.link state string
              Summary
19
20
              Pretty-print string representation of pmix_link_state_t.
              Format
   PMIx v4.0
                                                    Python
22
              rep = myclient.link_state_string(state:integer)
                                                     Python
              IN
23
                   state
                   PMIx link state value (integer)
24
              Returns:
25
26
              • rep - String representation of the provided link state (str)
27
              See PMIx_Link_state_string for further details.
```

## A.4.55 Client.device\_type\_string

Summary 3 Pretty-print string representation of pmix\_device\_type\_t. **Format** <sup>4</sup> *PMIx v4.0* **Python** 5 rep = myclient.device\_type\_string(type:bitarray) **Python** 6 IN type 7 PMIx device type value (bitarray) 8 Returns: • rep - String representation of the provided device type (str) 9 See PMIx Device type string for further details. 10 A.4.56 **Client.progress** 12 Summary Progress the PMIx library. 13 Format 14 *PMIx v4.0* **Python** 15 myclient.progress() **Python** 16 See PMIx\_Progress for further details. **A.5 PMIxServer** 18 The server Python class inherits the Python "client" class as its parent. Thus, it includes all client functions in addition to the ones defined in this section. 19 Server.init A.5.1 Summary 21 22 Initialize the PMIx server library after obtaining a new PMIxServer object.

1		Format Python
2		rc = myserver.init(directives:list, map:dict)
		Python —
3 4 5		IN directives List of Python info dictionaries (list) IN map
6 7		Python dictionary key-function pairs that map <b>server module</b> callback functions to provided implementations (see <b>pmix_server_module_t</b> ) (dict)
8		Returns:
9		• rc - PMIX_SUCCESS or a negative value corresponding to a PMIx error constant (integer)
10		See PMIx_server_init for description of all relevant attributes and behaviors.
11	A.5.2	Server.finalize
12 13		Summary Finalize the PMIx server library.
14	PMIx v4.0	Format Python
15		rc = myserver.finalize()  Python
16		Returns:
17		• rc - PMIX_SUCCESS or a negative value corresponding to a PMIx error constant (integer)
18		See PMIx_server_finalize for details.
19	A.5.3	Server.generate_regex
20 21		<b>Summary</b> Generate a regular expression representation of the input strings.

**Format** 1 **Python** rc,regex = myserver.generate\_regex(input:list) 2 Python IN input 3 4 List of Python strings (e.g., node names) (list) 5 Returns: • rc - PMIX\_SUCCESS or a negative value corresponding to a PMIx error constant (integer) 6 7 • regex - Python bytearray containing regular expression representation of the input list (bytearray) 8 9 See **PMIx generate regex** for details. A.5.4 Server.generate ppn Summary 11 12 Generate a regular expression representation of the input strings. **Format** 13 *PMIx v4.0* Python 14 rc,regex = myserver.generate\_ppn(input:list) Python IN 15 input 16 List of Python strings, each string consisting of a comma-delimited list of ranks on each node, with the strings being in the same order as the node names provided to "generate regex" (list) 17 18 Returns: 19 • rc - PMIX\_SUCCESS or a negative value corresponding to a PMIx error constant (integer) 20 • regex - Python bytearray containing regular expression representation of the input list 21 (bytearray) See PMIx\_generate\_ppn for details. 22 Server.generate\_locality\_string A.5.5 23 Summary 24 25 Generate a PMIx locality string from a given cpuset.

1	Format Python
2	rc, locality = myserver.generate_locality_string(cpuset:dict)
	Python —
3 4	IN cset cpuset containing the bitmap of assigned PUs (dict)
5	Returns:
6	• rc - PMIX_SUCCESS or a negative value corresponding to a PMIx error constant (integer)
7	• <i>locality</i> - String representation of the PMIx locality corresponding to the input bitmap (string)
8	See PMIx_server_generate_locality_string for details.
9 <b>A.5.6</b>	Server.generate_cpuset_string
10 11	<b>Summary</b> Generate a PMIx string representation of the provided cpuset.
12 <i>PMIx v4.0</i>	Format Python
12 <i>PMIx v4.0</i>	rc,cpustr = myserver.generate_cpuset_string(cpuset:dict)
PMIX V4.0	Python
13 14	rc,cpustr = myserver.generate_cpuset_string(cpuset:dict)  Python  IN cset
13 14 15	rc,cpustr = myserver.generate_cpuset_string(cpuset:dict) Python  IN cset cpuset containing the bitmap of assigned PUs (dict)
13 14 15 16	rc,cpustr = myserver.generate_cpuset_string(cpuset:dict) Python  IN cset cpuset containing the bitmap of assigned PUs (dict)  Returns:
13 14 15 16 17	rc, cpustr = myserver.generate_cpuset_string(cpuset:dict)  Python  IN cset cpuset containing the bitmap of assigned PUs (dict)  Returns:  • rc - PMIX_SUCCESS or a negative value corresponding to a PMIx error constant (integer)
13 14 15 16 17 18 19	rc, cpustr = myserver.generate_cpuset_string(cpuset:dict)  Python  IN cset cpuset containing the bitmap of assigned PUs (dict)  Returns:  • rc - PMIX_SUCCESS or a negative value corresponding to a PMIx error constant (integer)  • cpustr - String representation of the input bitmap (string)
13 14 15 16 17 18 19	rc, cpustr = myserver.generate_cpuset_string(cpuset:dict)  Python  IN cset cpuset containing the bitmap of assigned PUs (dict)  Returns:  • rc - PMIX_SUCCESS or a negative value corresponding to a PMIx error constant (integer)  • cpustr - String representation of the input bitmap (string)  See PMIx_server_generate_cpuset_string for details.

1	Format Python	
2	rc = myserver.register_nspace(nspace:str,	
3	nlocalprocs:integ	ger,
4	directives:list)	
	Python —	
5	IN nspace	
6	Python string containing the namespace (str)	
7	IN nlocalprocs	
8 9	Number of local processes (integer)  IN directives	
10	List of Python info dictionaries (list)	
11	Returns:	
12	• rc - PMIX_SUCCESS or a negative value corresponding to a PMIx	error constant (integer)
13	See PMIx_server_register_nspace for description of all rele	vant attributes and behaviors.
14 <b>A.5.8</b>	Server.deregister_nspace	
15	Summary	
15 16	Summary Deregister a namespace.	
16	Deregister a namespace.	
16 17 <i>PMIx v4.0</i>	Deregister a namespace.  Format  Python	
16	Deregister a namespace.  Format  Python  myserver.deregister_nspace(nspace:str)	
16 17 <i>PMIx v4.0</i>	Deregister a namespace.  Format  Python  myserver.deregister_nspace(nspace:str)  Python	•
16 17 <sub>PMIx v4.0</sub> 18	Python  myserver.deregister_nspace(nspace:str) Python  IN nspace	
16 17 <i>PMIx v4.0</i> 18	Deregister a namespace.  Format  Python  myserver.deregister_nspace(nspace:str)  Python	
16 17 <sub>PMIx v4.0</sub> 18	Python  myserver.deregister_nspace(nspace:str) Python  IN nspace	
16 17 <i>PMIx v4.0</i> 18 19 20	Deregister a namespace.  Format  Python  myserver.deregister_nspace(nspace:str)  Python  IN nspace  Python string containing the namespace (str)	
16 17 <i>PMIx v4.0</i> 18 19 20 21	Python  myserver.deregister_nspace(nspace:str) Python  IN nspace Python string containing the namespace (str)  Returns: None	
16 17 <i>PMIx v4.0</i> 18 19 20 21	Python  myserver.deregister_nspace(nspace:str)  Python  IN nspace Python string containing the namespace (str)  Returns: None  See PMIx_server_deregister_nspace for details.	
16 17 <i>PMIx v4.0</i> 18 19 20 21	Python  myserver.deregister_nspace(nspace:str)  Python  IN nspace Python string containing the namespace (str)  Returns: None  See PMIx_server_deregister_nspace for details.	
16 17 <sub>PMIx v4.0</sub> 18 19 20 21 22 23 <b>A.5.9</b>	Python  myserver.deregister_nspace(nspace:str)  Python  IN nspace Python string containing the namespace (str)  Returns: None See PMIx_server_deregister_nspace for details.  Server.register_resources	ry

1		Format Python
2		myserver.register_resources(directives:list)
		Python —
3 4		IN directives List of Python info dictionaries (list)
5		Returns: None
6		See PMIx_server_register_resources for details.
7	A.5.10	Server.deregister_resources
8 9 10	<b>D</b> III 40	Summary Remove non-namespace related information from the local PMIx library  Format
	PMIx v4.0	Python
11		myserver.deregister_resources(directives:list)  Python
12 13		IN directives List of Python info dictionaries (list)
14		Returns: None
15		See PMIx_server_deregister_resources for details.
16	A.5.11	Server.register_client
17 18		Summary Register a client process with the PMIx server library.
19	PMIx v4.0	Format Python
20		<pre>rc = myserver.register_client(proc:dict, uid:integer, gid:integer)</pre>
21 22 23 24 25 26		<ul> <li>IN proc</li> <li>Python proc dictionary identifying the client process (dict)</li> <li>IN uid</li> <li>Linux uid value for user executing client process (integer)</li> <li>IN gid</li> <li>Linux gid value for user executing client process (integer)</li> </ul>
27		Returns:
28		• rc - PMIX_SUCCESS or a negative value corresponding to a PMIx error constant (integer)
29		See PMIx_server_register_client for details.

# 1 A.5.12 Server.deregister\_client

2 3	Summary Deregister a client process and purge all data relating to it.
<sup>4</sup> <i>PMIx v4.0</i>	Format Python
5	<pre>myserver.deregister_client(proc:dict)</pre>
6 7	IN proc Python proc dictionary identifying the client process (dict)
8	Returns: None
9	See PMIx_server_deregister_client for details.
10 <b>A.5.13</b>	Server.setup_fork
11 12	<b>Summary</b> Setup the environment of a child process that is to be forked by the host.
13 <sub>PMIx v4.0</sub>	Format Python
14	rc = myserver.setup_fork(proc:dict, envin:dict)  Python
15 16 17 18	<ul> <li>IN proc</li> <li>Python proc dictionary identifying the client process (dict)</li> <li>INOUT envin</li> <li>Python dictionary containing the environment to be passed to the client (dict)</li> </ul>
19	Returns:
20	• rc - PMIX_SUCCESS or a negative value corresponding to a PMIx error constant (integer)
21	See PMIx_server_setup_fork for details.
22 <b>A.5.14</b>	Server.dmodex_request
23 24	<b>Summary</b> Function by which the host server can request modex data from the local PMIx server.

1		Format Python
2		rc,data = myserver.dmodex_request(proc:dict)
		Python —
3 4		IN proc Python proc dictionary identifying the process whose data is requested (dict)
5		Returns:
6		• rc - PMIX_SUCCESS or a negative value corresponding to a PMIx error constant (integer)
7		• data - Python byteobject containing the returned data (dict)
8		See PMIx_server_dmodex_request for details.
9	A.5.15	Server.setup_application
10 11 12		<b>Summary</b> Function by which the resource manager can request application-specific setup data prior to launch of a <i>job</i> .
13	PMIx v4.0	Format Python
14		rc,info = myserver.setup_application(nspace:str, directives:list)  Python
15		IN nspace
16 17 18		Namespace whose setup information is being requested (str)  IN directives  Python list of info directives
19		Returns:
20		• rc - PMIX_SUCCESS or a negative value corresponding to a PMIx error constant (integer)
21		• <i>info</i> - Python list of <b>info</b> dictionaries containing the returned data (list)
22		See PMIx_server_setup_application for details.
23	A.5.16	Server.register_attributes
24 25		Summary Register host environment attribute support for a function.

1	Python —
2	rc = myserver.register_attributes(function:str, attrs:list)  Python
3 4 5 6	IN function Name of the function (str) IN attrs Python list of regattr describing the supported attributes
7	Returns:
8	• rc - PMIX_SUCCESS or a negative value corresponding to a PMIx error constant (integer)
9	See PMIx_Register_attributes for details.
o <b>A.5.17</b>	Server.setup_local_support
1 2 3	<b>Summary</b> Function by which the local PMIx server can perform any application-specific operations prior to spawning local clients of a given application.
<sup>4</sup> <i>PMIx v4.0</i>	Format Python
5	rc = myserver.setup_local_support(nspace:str, info:list)  Python
6 7 8 9	<ul> <li>IN nspace         Namespace whose setup information is being requested (str)     </li> <li>IN info         Python list of info containing the setup data (list)     </li> </ul>
20	Returns:
<u>?</u> 1	• rc - PMIX_SUCCESS or a negative value corresponding to a PMIx error constant (integer)
22	See PMIx_server_setup_local_support for details.
з <b>А.5.18</b>	Server.iof_deliver
24 25 26	<b>Summary</b> Function by which the host environment can pass forwarded IO to the PMIx server library for distribution to its clients.

1		Format Python —
2		rc = myserver.iof_deliver(source:dict, channel:integer,
3		data:dict, directives:list)
		Python
4		IN source
5 6		Python proc dictionary identifying the process who generated the data (dict)  IN channel
7		Python channel bitmask identifying IO channel of the provided data (integer)
8		IN data
9 10		Python byteobject containing the data (dict)  IN directives
11		Python list of <b>info</b> containing directives (list)
12		Returns:
13		• rc - PMIX_SUCCESS or a negative value corresponding to a PMIx error constant (integer)
14		See PMIx_server_IOF_deliver for details.
15	A.5.19	Server.collect_inventory
16		Summary
17		Collect inventory of resources on a node.
18	PMIx v4.0	Format Python
19		<pre>rc,info = myserver.collect_inventory(directives:list)</pre>
		Python —
20		IN directives
21		Optional Python list of <b>info</b> containing directives (list)
22		Returns:
23		• rc - PMIX_SUCCESS or a negative value corresponding to a PMIx error constant (integer)
24		• <i>info</i> - Python list of <b>info</b> containing the returned data (list)
25		See PMIx_server_collect_inventory for details.
26	A.5.20	Server.deliver_inventory
27		Summary
28		Pass collected inventory to the PMIx server library for storage.

```
Format
 1
                                                     Python
2
              rc = myserver.deliver_inventory(info:list, directives:list)
                                                     Python
              IN
                   info
3
                   - Python list of info dictionaries containing the inventory data (list)
 4
              IN
                   directives
 5
6
                   Python list of info dictionaries containing directives (list)
 7
              Returns:
              • rc - PMIX_SUCCESS or a negative value corresponding to a PMIx error constant (integer)
 8
9
              See PMIx_server_deliver_inventory for details.
    A.5.21
               Server.define_process_set
11
              Summary
12
              Add members to a PMIx process set.
13 PMIx v4.0
              Format
                                                     Python
14
              rc = myserver.define_process_set(members:list, name:str)
                                                     Python
15
              IN
                   members
                   - List of Python proc dictionaries identifying the processes to be added to the process set
16
                   (list)
17
              IN
                   name
18
19
                   - Name of the process set (str)
20
              Returns:
              • rc - PMIX_SUCCESS or a negative value corresponding to a PMIx error constant (integer)
21
22
              See PMIx_server_define_process_set for details.
    A.5.22
              Server.delete process set
              Summary
24
25
              Delete a PMIx process set.
```

```
Format
 1
                                                    Python
              rc = myserver.delete_process_set(name:str)
2
                                                    Python
 3
              IN
                   name
                   - Name of the process set (str)
 4
 5
              Returns:
              • rc - PMIX_SUCCESS or a negative value corresponding to a PMIx error constant (integer)
 6
 7
              See PMIx_server_delete_process_set for details.
    A.5.23
               Server.register_resources
9
              Summary
10
              Register non-namespace related information with the local PMIx server library.
   PMIx v4.0
                                                    Python
12
              rc = myserver.register resources(info:list)
                                                    Python
13
              IN
                   info
                   - List of Python info dictionaries list)
14
              Returns:
15
              • rc - PMIX_SUCCESS or a negative value corresponding to a PMIx error constant (integer)
16
17
              See PMIx_server_register_resources for details.
    A.5.24
               Server.deregister_resources
              Summary
19
20
              Deregister non-namespace related information with the local PMIx server library.
              Format
   PMIx v4.0
                                                    Python
22
              rc = myserver.deregister_resources(info:list)
                                                    Python
              IN
23
                   info
                   - List of Python info dictionaries list)
24
25
              Returns:
26
              • rc - PMIX SUCCESS or a negative value corresponding to a PMIx error constant (integer)
27
              See PMIx server deregister resources for details.
```

## A.6 PMIxTool

The tool Python class inherits the Python "server" class as its parent. Thus, it includes all client and server functions in addition to the ones defined in this section.

### 4 A.6.1 Tool.init

5 **Summary** 

Initialize the PMIx tool library after obtaining a new PMIxTool object.

7 PMIx v4.0 Format

8

10

12 13

14

17

19

21

22

25

rc,proc = mytool.init(info:list)

Python

Python

9 IN info

List of Python **info** directives (list)

11 Returns:

• rc - PMIX\_SUCCESS or a negative value corresponding to a PMIx error constant (integer)

• proc - a Python proc (dict)

See PMIx\_tool\_init for description of all relevant attributes and behaviors.

### 15 A.6.2 Tool.finalize

16 **Summary** 

Finalize the PMIx tool library, closing the connection to the server.

18 *PMIx v4.0* 

Format

rc = mytool.finalize()

Python

**Python** 

20 Returns:

• rc - PMIX\_SUCCESS or a negative value corresponding to a PMIx error constant (integer)

See PMIx\_tool\_finalize for description of all relevant attributes and behaviors.

## 23 A.6.3 Tool.disconnect

24 Summary

Disconnect the PMIx tool from the specified server connection while leaving the tool library

26 initialized.

**Format** 1 **Python** rc = mytool.disconnect(server:dict) 2 Python IN server 3 Process identifier of server from which the tool is to be disconnected (proc) 5 Returns: • rc - PMIX\_SUCCESS or a negative value corresponding to a PMIx error constant (integer) 7 See PMIx\_tool\_disconnect for details. A.6.4 Tool.attach\_to\_server Summary 9 Establish a connection to a PMIx server. 10 **Format** PMIx v4.0 **Python** 12 rc,proc,server = mytool.connect\_to\_server(info:list) Python IN info 13 14 List of Python **info** dictionaries (list) 15 Returns: • rc - PMIX\_SUCCESS or a negative value corresponding to a PMIx error constant (integer) 16 17 • proc - a Python proc containing the tool's identifier (dict) • server - a Python proc containing the identifier of the server to which the tool attached (dict) 18 19 See PMIx\_tool\_attach\_to\_server for details. A.6.5 **Tool.get servers** 21 Summary Get a list containing the proc process identifiers of all servers to which the tool is currently 22 23 connected.

**Format** 1 **Python** 2 rc, servers = mytool.get servers() **Python** Returns: 3 • rc - PMIX\_SUCCESS or a negative value corresponding to a PMIx error constant (integer) 5 • servers - a list of Python proc containing the identifiers of the servers to which the tool is 6 currently attached (dict) 7 See **PMIx\_tool\_get\_servers** for details. A.6.6 Tool.set server Summary 9 10 Designate a server as the tool's *primary* server. **Format** <sup>11</sup> *PMIx v4.0* **Python** rc = mytool.set\_server(proc:dict, info:list) 12 Python 13 IN proc Python **proc** containing the identifier of the servers to which the tool is to attach (list) 14 info 15 IN List of Python **info** dictionaries (list) 16 Returns: 17 18 • rc - PMIX\_SUCCESS or a negative value corresponding to a PMIx error constant (integer) 19 See PMIx tool set server for details. Tool.iof pull A.6.7 Summary 21 22 Register to receive output forwarded from a remote process.

1		Format Python —
2 3		<pre>rc,id = mytool.iof_pull(sources:list, channel:integer,</pre>
		Python
4 5 6 7 8 9 10		<ul> <li>IN sources         <ul> <li>List of Python proc dictionaries of processes whose IO is being requested (list)</li> </ul> </li> <li>IN channel         <ul> <li>Python channel bitmask identifying IO channels to be forwarded (integer)</li> </ul> </li> <li>IN directives         <ul> <li>List of Python info dictionaries describing request (list)</li> </ul> </li> <li>IN cbfunc         <ul> <li>Python iofcbfunc to receive IO payloads (func)</li> </ul> </li> </ul>
12		Returns:
13		• rc - PMIX_SUCCESS or a negative value corresponding to a PMIx error constant (integer)
14		• <i>id</i> - PMIx reference identifier for request (integer)
15		See PMIx_IOF_pull for description of all relevant attributes and behaviors.
16	A.6.8	Tool.iof_deregister
17 18		Summary Deregister from output forwarded from a remote process.
19	PMIx v4.0	Format Python
20		<pre>rc = mytool.iof_deregister(id:integer, directives:list)</pre>
21 22 23 24		IN id PMIx reference identifier returned by pull request (list)  IN directives List of Python info dictionaries describing request (list)
25		Returns:
26		• rc - PMIX_SUCCESS or a negative value corresponding to a PMIx error constant (integer)
27		See PMIx_IOF_deregister for description of all relevant attributes and behaviors.
28	A.6.9	Tool.iof_push
29 30		<b>Summary</b> Push data collected locally (typically from stdin) to stdin of target recipients.

```
Format
 1
                                                    Python
              rc = mytool.iof push(targets:list, data:dict, directives:list)
 2
                                                    Python
              IN
                   sources
 3
 4
                   List of Python proc of target processes (list)
              IN
 5
                   data
6
                   Python byteobject containing data to be delivered (dict)
 7
              IN
                   directives
                   Optional list of Python info describing request (list)
8
              Returns:
9
              • rc - PMIX_SUCCESS or a negative value corresponding to a PMIx error constant (integer)
10
11
              See PMIx_IOF_push for description of all relevant attributes and behaviors.
   A.7 Example Usage
              The following examples are provided to illustrate the use of the Python bindings.
13
   A.7.1 Python Client
              The following example contains a client program that illustrates a fairly common usage pattern.
15
16
              The program instantiates and initializes the PMIxClient class, posts some data that is to be shared
17
              across all processes in the job, executes a "fence" that circulates the data, and then retrieves a value
              posted by one of its peers. Note that the example has been formatted to fit the document layout.
18
                                                    Python
              from pmix import *
19
20
              def main():
21
22
                   # Instantiate a client object
                   myclient = PMIxClient()
23
24
                   print("Testing PMIx ", myclient.get_version())
25
                    # Initialize the PMIx client library, declaring the programming model
26
                   # as "TEST" and the library name as "PMIX", just for the example
27
                    info = ['key':PMIX PROGRAMMING MODEL,
28
                               'value': 'TEST', 'val type': PMIX STRING,
29
                              'key':PMIX_MODEL_LIBRARY_NAME,
```

'value':'PMIX', 'val type':PMIX STRING]

30

31 32

rc,myname = myclient.init(info)

```
if PMIX SUCCESS != rc:
1
2
                    print("FAILED TO INIT WITH ERROR", myclient.error string(rc))
3
                    exit(1)
4
5
                # try posting a value
6
                rc = myclient.put(PMIX_GLOBAL, "mykey",
7
                                   'value':1, 'val_type':PMIX_INT32)
8
                if PMIX SUCCESS != rc:
9
                    print("PMIx Put FAILED WITH ERROR", myclient.error string(rc))
10
                    # cleanly finalize
11
                    myclient.finalize()
12
                    exit(1)
13
                # commit it
14
15
                rc = myclient.commit()
                if PMIX_SUCCESS != rc:
16
17
                    print("PMIx_Commit FAILED WITH ERROR",
18
                           myclient.error_string(rc))
19
                    # cleanly finalize
20
                    myclient.finalize()
21
                    exit(1)
22
23
                # execute fence across all processes in my job
24
                procs = []
25
                info = []
26
                rc = myclient.fence(procs, info)
                if PMIX_SUCCESS != rc:
27
                    print("PMIx_Fence FAILED WITH ERROR", myclient.error_string(rc))
28
29
                    # cleanly finalize
30
                    myclient.finalize()
                    exit(1)
31
32
33
                # Get a value from a peer
                if 0 != myname['rank']:
34
                    info = []
35
36
                    rc, get_val = myclient.get('nspace':"testnspace", 'rank': 0,
37
                                                 "mykey", info)
                    if PMIX SUCCESS != rc:
38
39
                         print ("PMIx Commit FAILED WITH ERROR",
40
                               myclient.error_string(rc))
41
                         # cleanly finalize
42
                         myclient.finalize()
43
                         exit(1)
```

```
1
                    print("Get value returned: ", get_val)
2
3
                # test a fence that should return not supported because
4
                # we pass a required attribute that the server is known
5
                # not to support
6
                procs = []
7
                info = ['key': 'ARBIT', 'flags': PMIX INFO REQD,
8
                          'value':10, 'val type':PMIX INT]
9
                rc = myclient.fence(procs, info)
                if PMIX SUCCESS == rc:
10
                    print("PMIx_Fence SUCCEEDED BUT SHOULD HAVE FAILED")
11
12
                    # cleanly finalize
13
                    myclient.finalize()
14
                    exit(1)
15
                # Publish something
16
                info = ['key': 'ARBITRARY', 'value':10, 'val_type':PMIX_INT]
17
18
                rc = myclient.publish(info)
                if PMIX SUCCESS != rc:
19
20
                    print ("PMIx Publish FAILED WITH ERROR",
21
                           myclient.error_string(rc))
22
                    # cleanly finalize
                    myclient.finalize()
23
24
                    exit(1)
25
26
                # finalize
27
                info = []
28
                myclient.finalize(info)
29
                print("Client finalize complete")
30
            # Python main program entry point
31
32
            if __name__ == '__main__':
33
                main()
                                            Python
```

# A.7.2 Python Server

The following example contains a minimum-level server host program that instantiates and initializes the PMIxServer class. The program illustrates passing several server module functions to the bindings and includes code to setup and spawn a simple client application, waiting until the spawned client terminates before finalizing and exiting itself. Note that the example has been formatted to fit the document layout.

35 36

37

38

39

### Python

```
1
            from pmix import *
2
            import signal, time
3
            import os
            import select
4
5
            import subprocess
6
7
            def clientconnected(proc:tuple is not None):
8
                print("CLIENT CONNECTED", proc)
9
                return PMIX OPERATION SUCCEEDED
10
            def clientfinalized(proc:tuple is not None):
11
                print("CLIENT FINALIZED", proc)
12
13
                return PMIX OPERATION SUCCEEDED
14
15
            def clientfence(procs:list, directives:list, data:bytearray):
16
                # check directives
                if directives is not None:
17
18
                    for d in directives:
19
                         # these are each an info dict
                         if "pmix" not in d['key']:
20
21
                             # we do not support such directives - see if
22
                             # it is required
23
                             try:
24
                                 if d['flags'] & PMIX_INFO_REQD:
                                     # return an error
25
26
                                     return PMIX ERR NOT SUPPORTED
27
                             except:
28
                                 #it can be ignored
29
                                 pass
30
                return PMIX_OPERATION_SUCCEEDED
31
            def main():
32
33
                try:
34
                    myserver = PMIxServer()
35
                except:
                    print ("FAILED TO CREATE SERVER")
36
37
                    exit(1)
38
                print("Testing server version ", myserver.get_version())
39
40
                args = ['key':PMIX_SERVER_SCHEDULER,
                          'value':'T', 'val_type':PMIX_BOOL]
41
42
                map = 'clientconnected': clientconnected,
```

```
'clientfinalized': clientfinalized,
1
2
                        'fencenb': clientfence
                my result = myserver.init(args, map)
3
4
5
                # get our environment as a base
6
                env = os.environ.copy()
7
8
                # register an nspace for the client app
9
                (rc, regex) = myserver.generate regex("test000, test001, test002")
10
                (rc, ppn) = myserver.generate_ppn("0")
11
                kvals = ['key':PMIX_NODE_MAP,
                           'value':regex, 'val_type':PMIX STRING.
12
13
                          'key':PMIX PROC MAP,
                           'value':ppn, 'val_type':PMIX_STRING,
14
15
                          'key':PMIX_UNIV_SIZE,
                           'value':1, 'val_type':PMIX_UINT32,
16
                          'key':PMIX_JOB_SIZE,
17
18
                           'value':1, 'val type':PMIX UINT32]
19
                rc = foo.register nspace("testnspace", 1, kvals)
20
                print("RegNspace ", rc)
21
22
                # register a client
23
                uid = os.getuid()
24
                qid = os.getgid()
25
                rc = myserver.register_client('nspace':"testnspace", 'rank':0,
26
                                               uid, gid)
                print("RegClient ", rc)
27
28
                # setup the fork
29
                rc = myserver.setup_fork('nspace':"testnspace", 'rank':0, env)
30
                print("SetupFrk", rc)
31
32
                # setup the client argv
                args = ["./client.py"]
33
                # open a subprocess with stdout and stderr
34
35
                # as distinct pipes so we can capture their
                # output as the process runs
36
37
                p = subprocess.Popen(args, env=env,
38
                    stdout=subprocess.PIPE, stderr=subprocess.PIPE)
39
                # define storage to catch the output
                stdout = []
40
41
                stderr = []
42
                # loop until the pipes close
43
                while True:
```

```
1
                     reads = [p.stdout.fileno(), p.stderr.fileno()]
2
                     ret = select.select(reads, [], [])
3
4
                     stdout done = True
5
                     stderr done = True
6
7
                     for fd in ret[0]:
8
                         # if the data
9
                         if fd == p.stdout.fileno():
10
                             read = p.stdout.readline()
                             if read:
11
                                 read = read.decode('utf-8').rstrip()
12
                                 print('stdout: ' + read)
13
                                 stdout_done = False
14
15
                         elif fd == p.stderr.fileno():
16
                             read = p.stderr.readline()
17
                             if read:
18
                                 read = read.decode('utf-8').rstrip()
19
                                 print('stderr: ' + read)
20
                                 stderr_done = False
21
22
                     if stdout done and stderr done:
23
                         break
24
                print("FINALIZING")
25
                myserver.finalize()
26
27
28
            if __name__ == '__main__
29
                main()
```

**Python** 

#### APPENDIX B

2

4

5

6 7

8

9

10

11 12

13 14

15

16

18 19

20 21

22

23

24 25

26

# **Revision History**

## B.1 Version 1.0: June 12, 2015

The PMIx version 1.0 *ad hoc* standard was defined in a set of header files as part of the v1.0.0 release of the OpenPMIx library prior to the creation of the formal PMIx 2.0 standard. Below are a summary listing of the interfaces defined in the 1.0 headers.

- Client APIs
- PMIx\_Init, PMIx\_Initialized, PMIx\_Abort, PMIx\_Finalize
  - PMIx\_Put, PMIx Commit.
  - PMIx\_Fence, PMIx\_Fence\_nb
  - PMIx Get, PMIx Get nb
  - PMIx\_Publish, PMIx\_Publish\_nb
  - PMIx Lookup, PMIx Lookup nb
  - PMIx\_Unpublish, PMIx\_Unpublish\_nb
    - PMIx\_Spawn, PMIx\_Spawn\_nb
  - PMIx Connect, PMIx Connect nb
    - PMIx Disconnect, PMIx Disconnect nb
  - PMIx\_Resolve\_nodes, PMIx\_Resolve\_peers
- Server APIs
  - PMIx\_server\_init, PMIx\_server\_finalize
  - PMIx generate regex, PMIx generate ppn
  - PMIx server register nspace, PMIx server deregister nspace
  - PMIx\_server\_register\_client, PMIx\_server\_deregister\_client
  - PMIx\_server\_setup\_fork, PMIx\_server\_dmodex\_request
  - Common APIs
    - PMIx Get version, PMIx Store internal, PMIx Error string
    - PMIx Register errhandler, PMIx Deregister errhandler, PMIx Notify error
  - The **PMIx\_Init** API was subsequently modified in the v1.1.0 release of that library.

### 1 B.2 Version 2.0: Sept. 2018

The following APIs were introduced in v2.0 of the PMIx Standard: 2 3 Client APIs - PMIx\_Query\_info\_nb, PMIx\_Log\_nb 4 5 - PMIx Allocation request nb. PMIx Job control nb. PMIx Process monitor nb, PMIx Heartbeat 6 Server APIs 7 8 - PMIx server setup application, PMIx server setup local support Tool APIs 9 10 - PMIx tool init, PMIx tool finalize Common APIs 11 12 - PMIx\_Register\_event\_handler, PMIx\_Deregister\_event\_handler 13 - PMIx\_Notify\_event 14 - PMIx Proc state string, PMIx Scope string - PMIx\_Persistence\_string, PMIx\_Data\_range\_string 15 16 - PMIx\_Info\_directives\_string, PMIx\_Data\_type\_string 17 - PMIx Alloc directive string 18 - PMIx Data pack, PMIx Data unpack, PMIx Data copy 19 - PMIx\_Data\_print, PMIx\_Data\_copy\_payload

### 20 B.2.1 Removed/Modified APIs

The PMIx\_Init API was modified in v2.0 of the standard from its ad hoc v1.0 signature to include passing of a pmix\_info\_t array for flexibility and "future-proofing" of the API. In addition, the PMIx\_Notify\_error, PMIx\_Register\_errhandler, and PMIx\_Deregister\_errhandler APIs were replaced. This pre-dated official adoption of PMIx as a Standard.

## 26 B.2.2 Deprecated constants

The following constants were deprecated in v2.0:

28 PMIX\_MODEX
29 PMIX\_INFO\_ARRAY

### B.2.3 Deprecated attributes

```
2
              The following attributes were deprecated in v2.0:
 3
              PMIX_ERROR_NAME "pmix.errname" (pmix_status_t)
                    Specific error to be notified
 4
              PMIX_ERROR_GROUP_COMM "pmix.errgroup.comm" (bool)
 5
6
                    Set true to get comm errors notification
7
              PMIX ERROR_GROUP_ABORT "pmix.errgroup.abort" (bool)
8
                    Set true to get abort errors notification
9
              PMIX_ERROR_GROUP_MIGRATE "pmix.errgroup.migrate" (bool)
10
                    Set true to get migrate errors notification
              PMIX_ERROR_GROUP_RESOURCE "pmix.errgroup.resource" (bool)
11
                    Set true to get resource errors notification
12
              PMIX ERROR GROUP SPAWN "pmix.errgroup.spawn" (bool)
13
                    Set true to get spawn errors notification
14
15
              PMIX ERROR GROUP NODE "pmix.errgroup.node" (bool)
                    Set true to get node status notification
16
              PMIX ERROR GROUP LOCAL "pmix.errgroup.local" (bool)
17
                    Set true to get local errors notification
18
              PMIX ERROR GROUP GENERAL "pmix.errgroup.gen" (bool)
19
20
                    Set true to get notified of generic errors
21
              PMIX ERROR HANDLER ID "pmix.errhandler.id" (int)
22
                    Errhandler reference id of notification being reported
```

### B.3 Version 2.1: Dec. 2018

The v2.1 update includes clarifications and corrections from the v2.0 document, plus addition of examples:

- Clarify description of **PMIx** Connect and **PMIx** Disconnect APIs.
- Explain that values for the PMIX COLLECTIVE ALGO are environment-dependent
- Identify the namespace/rank values required for retrieving attribute-associated information using the PMIx Get API
- Provide definitions for session, job, application, and other terms used throughout the document
- Clarify definitions of PMIX UNIV SIZE versus PMIX JOB SIZE
- Clarify server module function return values
- Provide examples of the use of **PMIx Get** for retrieval of information
- Clarify the use of PMIx\_Get versus PMIx\_Query\_info\_nb
- Clarify return values for non-blocking APIs and emphasize that callback functions must not be invoked prior to return from the API
- Provide detailed example for construction of the PMIx\_server\_register\_nspace input information array

24 25

26

27

28 29

30

31

32

33

34

35

36 37

- Define information levels (e.g., *session* vs *job*) and associated attributes for both storing and
   retrieving values
  - Clarify roles of PMIx server library and host environment for collective operations
  - Clarify definition of **PMIX\_UNIV\_SIZE**

### B.4 Version 2.2: Jan 2019

6 The v2.2 update includes the following clarifications and corrections from the v2.1 document:

- Direct modex upcall function (pmix\_server\_dmodex\_req\_fn\_t) cannot complete
  atomically as the API cannot return the requested information except via the provided callback
  function
- Add missing **pmix\_data\_array\_t** definition and support macros
- Add a rule divider between implementer and host environment required attributes for clarity
- Add PMIX\_QUERY\_QUALIFIERS\_CREATE macro to simplify creation of pmix\_query\_t qualifiers
- Add PMIX\_APP\_INFO\_CREATE macro to simplify creation of pmix\_app\_t directives
- Add flag and PMIX\_INFO\_IS\_END macro for marking and detecting the end of a pmix\_info\_t array
- Clarify the allowed hierarchical nesting of the PMIX\_SESSION\_INFO\_ARRAY,
   PMIX JOB INFO ARRAY, and associated attributes

### 9 B.5 Version 3.0: Dec. 2018

- The following APIs were introduced in v3.0 of the PMIx Standard:
- Client APIs

3

4

7

8

9 10

11 12

13

14

15 16

17

18

20

22

23

24

26

- PMIx\_Log, PMIx\_Job\_control
  - PMIx\_Allocation\_request, PMIx\_Process\_monitor
  - PMIx\_Get\_credential, PMIx\_Validate\_credential
- Server APIs
  - PMIx server IOF deliver
  - PMIx server\_collect\_inventory, PMIx\_server\_deliver\_inventory
- Tool APIs
- 29 PMIx\_IOF\_pull, PMIx\_IOF\_push, PMIx\_IOF\_deregister
- 30 PMIx\_tool\_connect\_to\_server
- Common APIs
- 32 PMIx\_IOF\_channel\_string

1 The document added a chapter on security credentials, a new section for IO forwarding to the 2 Process Management chapter, and a few blocking forms of previously-existing non-blocking APIs. Attributes supporting the new APIs were introduced, as well as additional attributes for a few 3 existing functions. 4 **Removed constants** B.5.1 6 The following constants were removed in v3.0: 7 PMIX MODEX 8 PMIX INFO ARRAY B.5.2 **Deprecated attributes** 10 The following attributes were deprecated in v3.0: 11 PMIX COLLECTIVE ALGO REQD "pmix.calreqd" (bool) 12 If **true**, indicates that the requested choice of algorithm is mandatory. B.5.3 Removed attributes 13 14 The following attributes were removed in v3.0: 15 PMIX\_ERROR\_NAME "pmix.errname" (pmix\_status\_t) 16 Specific error to be notified PMIX ERROR GROUP COMM "pmix.errgroup.comm" (bool) 17 18 Set true to get comm errors notification PMIX\_ERROR\_GROUP\_ABORT "pmix.errgroup.abort" (bool) 19 20 Set true to get abort errors notification 21 PMIX\_ERROR\_GROUP\_MIGRATE "pmix.errgroup.migrate" (bool) 22 Set true to get migrate errors notification PMIX\_ERROR\_GROUP\_RESOURCE "pmix.errgroup.resource" (bool) 23 Set true to get resource errors notification 24 PMIX\_ERROR\_GROUP\_SPAWN "pmix.errgroup.spawn" (bool) 25 26 Set true to get spawn errors notification PMIX\_ERROR\_GROUP\_NODE "pmix.errgroup.node" (bool) 27 Set true to get node status notification 28 PMIX\_ERROR\_GROUP\_LOCAL "pmix.errgroup.local" (bool) 29 30 Set true to get local errors notification PMIX ERROR GROUP GENERAL "pmix.errgroup.gen" (bool) 31

Set true to get notified of generic errors

PMIX ERROR HANDLER ID "pmix.errhandler.id" (int)

Errhandler reference id of notification being reported

32

33

### B.6 Version 3.1: Jan. 2019

3

4

5 6

7

8

9 10

11

12

13

14 15

16

17 18

19

20 21

22

23

24 25

26 27

28

29 30

32

33

34

35

36

- 2 The v3.1 update includes clarifications and corrections from the v3.0 document:
  - Direct modex upcall function (pmix\_server\_dmodex\_req\_fn\_t) cannot complete
    atomically as the API cannot return the requested information except via the provided callback
    function
  - Fix typo in name of **PMIX\_FWD\_STDDIAG** attribute
  - Correctly identify the information retrieval and storage attributes as "new" to v3 of the standard
  - Add missing pmix\_data\_array\_t definition and support macros
  - Add a rule divider between implementer and host environment required attributes for clarity
  - Add PMIX\_QUERY\_QUALIFIERS\_CREATE macro to simplify creation of pmix\_query\_t qualifiers
  - Add PMIX\_APP\_INFO\_CREATE macro to simplify creation of pmix\_app\_t directives
  - Add new attributes to specify the level of information being requested where ambiguity may exist (see 6.1)
  - Add new attributes to assemble information by its level for storage where ambiguity may exist (see 16.2.3.1)
  - Add flag and PMIX\_INFO\_IS\_END macro for marking and detecting the end of a pmix\_info\_t array
  - Clarify that PMIX\_NUM\_SLOTS is duplicative of (a) PMIX\_UNIV\_SIZE when used at the session level and (b) PMIX\_MAX\_PROCS when used at the job and application levels, but leave it in for backward compatibility.
  - Clarify difference between PMIX\_JOB\_SIZE and PMIX\_MAX\_PROCS
  - Clarify that PMIx\_server\_setup\_application must be called per-job instead of per-application as the name implies. Unfortunately, this is a historical artifact. Note that both PMIX\_NODE\_MAP and PMIX\_PROC\_MAP must be included as input in the *info* array provided to that function. Further descriptive explanation of the "instant on" procedure will be provided in the next version of the PMIx Standard.
  - Clarify how the PMIx server expects data passed to the host by
     pmix\_server\_fencenb\_fn\_t should be aggregated across nodes, and provide a code
     snippet example

### B.7 Version 3.2: Oct. 2020

- The v3.2 update includes clarifications and corrections from the v3.1 document:
- Correct an error in the PMIx\_Allocation\_request function signature, and clarify the allocation ID attributes
- Rename the **PMIX\_ALLOC\_ID** attribute to **PMIX\_ALLOC\_REQ\_ID** to clarify that this is a string the user provides as a means to identify their request to query status

- Add a new PMIX\_ALLOC\_ID attribute that contains the identifier (provided by the host environment) for the resulting allocation which can later be used to reference the allocated resources in, for example, a call to PMIx\_Spawn
  - Update the PMIx\_generate\_regex and PMIx\_generate\_ppn descriptions to clarify
    that the output from these generator functions may not be a NULL-terminated string, but instead
    could be a byte array of arbitrary binary content.
  - Add a new **PMIX\_REGEX** constant that represents a regular expression data type.

### **B.7.1** Deprecated constants

1

3

4

5

6

7

9

The following constants were deprecated in v3.2:

```
10
              PMIX_ERR_DATA_VALUE_NOT_FOUND
                                                     Data value not found
              PMIX_ERR_HANDSHAKE_FAILED
                                                Connection handshake failed
11
              PMIX ERR IN ERRNO
                                      Error defined in errno
12
              PMIX ERR_INVALID_ARG
13
                                          Invalid argument
                                           Invalid arguments
14
              PMIX ERR INVALID ARGS
15
              PMIX_ERR_INVALID_KEY
                                          Invalid key
16
              PMIX ERR INVALID KEY LENGTH
                                                   Invalid key length
17
              PMIX_ERR_INVALID_KEYVALP
                                               Invalid key/value pair
                                              Invalid argument length
18
              PMIX_ERR_INVALID_LENGTH
19
              PMIX ERR INVALID NAMESPACE
                                                 Invalid namespace
                                                Invalid number of arguments
20
              PMIX ERR INVALID NUM ARGS
                                                   Invalid number parsed
21
              PMIX ERR INVALID NUM PARSED
                                           Invalid size
22
              PMIX_ERR_INVALID_SIZE
23
              PMIX ERR_INVALID_VAL
                                          Invalid value
24
              PMIX ERR INVALID VAL LENGTH
                                                   Invalid value length
                                               Not implemented
25
              PMIX_ERR_NOT_IMPLEMENTED
              PMIX_ERR_PACK_MISMATCH
                                             Pack mismatch
26
27
              PMIX ERR PROC ENTRY NOT FOUND
                                                     Process not found
28
              PMIX ERR PROC REQUESTED ABORT
                                                     Process is already requested to abort
              PMIX ERR READY FOR HANDSHAKE
29
                                                    Ready for handshake
30
              PMIX ERR SERVER FAILED REQUEST
                                                      Failed to connect to the server
                                                Server is not available
              PMIX ERR SERVER NOT AVAIL
31
32
              PMIX ERR SILENT
                                    Silent error
              PMIX_GDS_ACTION_COMPLETE
33
                                               The Global Data Storage (GDS) action has completed
34
              PMIX NOTIFY ALLOC COMPLETE
                                                  Notify that a requested allocation operation is complete
35
                    the result of the request will be included in the info array
```

### B.7.2 Deprecated attributes

```
2
              The following attributes were deprecated in v3.2:
 3
              PMIX_ARCH "pmix.arch" (uint32_t)
                    Architecture flag.
 4
 5
              PMIX_COLLECTIVE_ALGO "pmix.calgo" (char*)
6
                    Comma-delimited list of algorithms to use for the collective operation. PMIx does not
7
                    impose any requirements on a host environment's collective algorithms. Thus, the
8
                    acceptable values for this attribute will be environment-dependent - users are encouraged to
9
                    check their host environment for supported values.
              PMIX_DSTPATH "pmix.dstpath" (char*)
10
11
                    Path to shared memory data storage (dstore) files. Deprecated from Standard as being
                    implementation specific.
12
              PMIX_HWLOC_HOLE_KIND "pmix.hwlocholek" (char*)
13
                    Kind of VM "hole" HWLOC should use for shared memory
14
              PMIX_HWLOC_SHARE_TOPO "pmix.hwlocsh" (bool)
15
16
                    Share the HWLOC topology via shared memory
              PMIX_HWLOC_SHMEM_ADDR "pmix.hwlocaddr" (size_t)
17
                    Address of the HWLOC shared memory segment.
18
              PMIX_HWLOC_SHMEM_FILE "pmix.hwlocfile" (char*)
19
                    Path to the HWLOC shared memory file.
20
21
              PMIX_HWLOC_SHMEM_SIZE "pmix.hwlocsize" (size_t)
                    Size of the HWLOC shared memory segment.
22
              PMIX HWLOC XML V1 "pmix.hwlocxml1" (char*)
23
                    XML representation of local topology using HWLOC's v1.x format.
24
              PMIX HWLOC XML V2 "pmix.hwlocxml2" (char*)
25
26
                    XML representation of local topology using HWLOC's v2.x format.
              PMIX_LOCAL_TOPO "pmix.ltopo" (char*)
27
                    XML representation of local node topology.
28
29
              PMIX MAPPER "pmix.mapper" (char*)
30
                    Mapping mechanism to use for placing spawned processes - when accessed using
                    PMIx_Get, use the PMIX_RANK_WILDCARD value for the rank to discover the mapping
31
                    mechanism used for the provided namespace.
32
33
              PMIX MAP BLOB "pmix.mblob" (pmix byte object t)
                    Packed blob of process location.
34
              PMIX NON PMI "pmix.nonpmi" (bool)
35
                    Spawned processes will not call PMIx Init.
36
              PMIX_PROC_BLOB "pmix.pblob" (pmix_byte_object_t)
37
                    Packed blob of process data.
38
              PMIX_PROC_URI "pmix.puri" (char*)
39
                    URI containing contact information for the specified process.
40
              PMIX TOPOLOGY FILE "pmix.topo.file" (char*)
41
42
                    Full path to file containing XML topology description
```

1	<pre>PMIX_TOPOLOGY_SIGNATURE "pmix.toposig" (char*)</pre>
2	Topology signature string.
3	<pre>PMIX_TOPOLOGY_XML "pmix.topo.xml" (char*)</pre>
4	XML-based description of topology

### 5 B.8 Version 4.0: Dec. 2020

 NOTE: The PMIx Standard document has undergone significant reorganization in an effort to become more user-friendly. Highlights include:

- Moving all added, deprecated, and removed items to this revision log section to make them more visible
- Co-locating constants and attribute definitions with the primary API that uses them citations and hyperlinks are retained elsewhere
- Splitting the Key-Value Management chapter into separate chapters on the use of reserved keys, non-reserved keys, and non-process-related key-value data exchange
- Creating a new chapter on synchronization and data access methods
- Removing references to specific implementations of PMIx and to implementation-specific features and/or behaviors

In addition to the reorganization, the following changes were introduced in v4.0 of the PMIx Standard:

- Clarified that the PMIx\_Fence\_nb operation can immediately return
   PMIX\_OPERATION\_SUCCEEDED in lieu of passing the request to a PMIx server if only the calling process is involved in the operation
- Added the **PMIx\_Register\_attributes** API by which a host environment can register the attributes it supports for each server-to-host operation
- Added the ability to query supported attributes from the PMIx tool, client and server libraries, as well as the host environment via the new pmix\_regattr\_t structure. Both human-readable and machine-parsable output is supported. New attributes to support this operation include:
  - PMIX\_CLIENT\_ATTRIBUTES, PMIX\_SERVER\_ATTRIBUTES,
     PMIX\_TOOL\_ATTRIBUTES, and PMIX\_HOST\_ATTRIBUTES to identify which library supports the attribute; and
  - PMIX\_MAX\_VALUE, PMIX\_MIN\_VALUE, and PMIX\_ENUM\_VALUE to provide machine-parsable description of accepted values
- Add PMIX\_APP\_WILDCARD to reference all applications within a given job
- Fix signature of blocking APIs PMIx\_Allocation\_request, PMIx\_Job\_control, PMIx\_Process\_monitor, PMIx\_Get\_credential, and PMIx\_Validate\_credential to allow return of results
- Update description to provide an option for blocking behavior of the
   PMIx\_Register\_event\_handler, PMIx\_Deregister\_event\_handler,
   PMIx\_Notify\_event, PMIx\_IOF\_pull, PMIx\_IOF\_deregister, and
   PMIx IOF push APIs. The need for blocking forms of these functions was not initially

anticipated but has emerged over time. For these functions, the return value is sufficient to provide the caller with information otherwise returned via callback. Thus, use of a **NULL** value as the callback function parameter was deemed a minimal disruption method for providing the desired capability

- Added a chapter on fabric support that includes new APIs, datatypes, and attributes
- Added a chapter on process sets and groups that includes new APIs and attributes
- Added APIs and a new datatypes to support generation and parsing of PMIx locality and cpuset strings
- Added a new chapter on tools that provides deeper explanation on their operation and collecting
  all tool-relevant definitions into one location. Also introduced two new APIs and removed
  restriction that limited tools to being connected to only one server at a time.
- Extended behavior of **PMIx\_server\_init** to scalably expose the topology description to the local clients. This includes creating any required shared memory backing stores and/or XML representations, plus ensuring that all necessary key-value pairs for clients to access the description are included in the job-level information provided to each client.
- Added a new API by which the host can manually progress the PMIx library in lieu of the library's own progress thread. s

The above changes included introduction of the following APIs and data types:

• Client APIs

1

3

5

6

7 8

9

10 11

12

13

14

15

16

17

18 19

20 21

22 23

24

25

26 27

28 29

30

31

32

33

34

35

36

37

38

- PMIx\_Group\_construct, PMIx\_Group\_construct\_nb
- PMIx\_Group\_destruct, PMIx\_Group\_destruct\_nb
- PMIx\_Group\_invite, PMIx\_Group\_invite\_nb
- PMIx Group join, PMIx Group join nb
- PMIx Group leave, PMIx Group leave nb
- PMIx\_Get\_relative\_locality, PMIx\_Load\_topology
- PMIx\_Parse\_cpuset\_string, PMIx\_Get\_cpuset
- PMIx Link state string, PMIx Job state string
- PMIx\_Device\_type\_string
  - PMIx\_Fabric\_register, PMIx\_Fabric\_register\_nb
  - PMIx\_Fabric\_update, PMIx\_Fabric\_update\_nb
  - PMIx Fabric deregister, PMIx Fabric deregister nb
  - PMIx\_Compute\_distances, PMIx\_Compute\_distances\_nb
  - PMIx Get attribute string, PMIx Get attribute name
  - PMIx\_Progress
- Server APIs
  - PMIx\_server\_generate\_locality\_string
  - PMIx\_Register\_attributes
  - PMIx\_server\_define\_process\_set, PMIx\_server\_delete\_process\_set
  - pmix\_server\_grp\_fn\_t, pmix\_server\_fabric\_fn\_t
  - pmix server client connected2 fn t

```
1
              - PMIx_server_generate_cpuset_string
2
              - PMIx server register resources, PMIx server deregister resources

    Tool APIs

 3
              - PMIx tool disconnect
 4
5
              - PMIx_tool_set_server
6
              - PMIx_tool_attach_to_server
 7
              - PMIx tool get servers
8
            • Data types
9
              - pmix regattr t
              - pmix_cpuset_t
10
11
              - pmix_topology_t
12
              - pmix_locality_t
              - pmix bind envelope t
13
              - pmix_group_opt_t
14
15
              - pmix_group_operation_t
16
              - pmix_fabric_t
17
              - pmix device distance t
18
              - pmix_coord_t
19
              - pmix coord view t
20
              - pmix geometry t
21
              - pmix_link_state_t
              - pmix_job_state_t
22
              - pmix_device_type_t
23
24

    Callback functions

              - pmix_device_dist_cbfunc_t
25
   B.8.1 Added Constants
            General error constants
27
28
            PMIX ERR EXISTS OUTSIDE SCOPE
```

29

30

31

PMIX\_ERR\_PARAM\_VALUE\_NOT\_SUPPORTED

PMIX ERR EMPTY

1	Data type constants
2	PMIX_COORD
3	PMIX_REGATTR
4	PMIX_REGEX
5	PMIX_JOB_STATE
6	PMIX_LINK_STATE
7	PMIX_PROC_CPUSET
8	PMIX_GEOMETRY
9	PMIX_DEVICE_DIST
10	PMIX_ENDPOINT
11	PMIX_TOPO
12	PMIX_DEVTYPE
13	PMIX_LOCTYPE
14	PMIX_DATA_TYPE_MAX
15	PMIX_COMPRESSED_BYTE_OBJECT
16	
17	Info directives
18	PMIX_INFO_REQD_PROCESSED
19	
20	Server constants
21	PMIX ERR REPEAT ATTR REGISTRATION
22	
23	Job-Mgmt constants
24	PMIX_ERR_CONFLICTING_CLEANUP_DIRECTIVES
25	
26	Publish constants
27	PMIX_ERR_DUPLICATE_KEY
28	
29	Tool constants
30	PMIX_LAUNCHER_READY
31	PMIX ERR IOF FAILURE
32	PMIX ERR_IOF_COMPLETE
33	PMIX_EVENT_JOB_START
34	PMIX_LAUNCH_COMPLETE
35	PMIX EVENT JOB END
36	PMIX EVENT SESSION START
37	PMIX_EVENT_SESSION_END
38	PMIX_ERR_PROC_TERM_WO_SYNC
39	PMIX_ERR_PROC_IERM_WO_SINC  PMIX ERR JOB CANCELED
40	PMIX_ERR_JOB_ABORTED
	<u></u>

1	PMIX_ERR_JOB_KILLED_BY_CMD
2	PMIX_ERR_JOB_ABORTED_BY_SIG
3	PMIX_ERR_JOB_TERM_WO_SYNC
4	PMIX_ERR_JOB_SENSOR_BOUND_EXCEEDED
5	PMIX_ERR_JOB_NON_ZERO_TERM
6	PMIX_ERR_JOB_ABORTED_BY_SYS_EVENT
7	PMIX_DEBUG_WAITING_FOR_NOTIFY
8	PMIX_DEBUGGER_RELEASE
9	
10	Fabric constants
11	PMIX FABRIC UPDATE PENDING
12	PMIX_FABRIC_UPDATED
13	PMIX_FABRIC_UPDATE_ENDPOINTS
14	PMIX_COORD_VIEW_UNDEF
15	PMIX_COORD_LOGICAL_VIEW
16	PMIX_COORD_PHYSICAL_VIEW
17	PMIX_COORD_FHISICAL_VIEW PMIX_LINK_STATE_UNKNOWN
18	PMIX_LINK_STATE_ONKNOWN PMIX_LINK_DOWN
19	PMIX LINK UP
20	PMIX_FABRIC_REQUEST_INFO
21	PMIX_FABRIC_UPDATE_INFO
22	11111_11111110_01111111111111
23	Sets-Groups constants
24	PMIX PROCESS SET DEFINE
25	PMIX_PROCESS_SET_DELETE
26	PMIX_GROUP_INVITED
27	PMIX_GROUP_LEFT
28	PMIX_GROUP_MEMBER_FAILED
29	PMIX_GROUP_INVITE_ACCEPTED
30	PMIX_GROUP_INVITE_DECLINED
31	PMIX_GROUP_INVITE_FAILED
32	PMIX_GROUP_MEMBERSHIP_UPDATE
33	PMIX_GROUP_CONSTRUCT_ABORT
34	PMIX_GROUP_CONSTRUCT_COMPLETE
35	PMIX_GROUP_LEADER_FAILED
36	PMIX_GROUP_LEADER_SELECTED
37	PMIX_GROUP_CONTEXT_ID_ASSIGNED
38	
39	Process-Mgmt constants
40	PMIX_ERR_JOB_ALLOC_FAILED
41	PMIX_ERR_JOB_APP_NOT_EXECUTABLE

```
1
              PMIX_ERR_JOB_NO_EXE_SPECIFIED
 2
              PMIX ERR JOB FAILED TO MAP
 3
              PMIX ERR JOB FAILED TO LAUNCH
 4
              PMIX LOCALITY UNKNOWN
 5
              PMIX LOCALITY NONLOCAL
6
              PMIX LOCALITY SHARE HWTHREAD
7
              PMIX LOCALITY SHARE CORE
8
              PMIX LOCALITY SHARE L1CACHE
              PMIX_LOCALITY_SHARE L2CACHE
9
10
              PMIX_LOCALITY_SHARE_L3CACHE
11
              PMIX_LOCALITY_SHARE_PACKAGE
12
              PMIX_LOCALITY_SHARE_NUMA
13
              PMIX LOCALITY SHARE NODE
14
              Events
15
16
              PMIX EVENT SYS BASE
17
              PMIX EVENT NODE DOWN
18
              PMIX EVENT NODE OFFLINE
              PMIX EVENT SYS OTHER
19
20
    B.8.2 Added Attributes
22
              Sync-Access attributes
23
              PMIX COLLECT GENERATED JOB INFO "pmix.collect.gen" (bool)
24
                    Collect all job-level information (i.e., reserved keys) that was locally generated by PMIx
                    servers. Some job-level information (e.g., distance between processes and fabric devices) is
25
                    best determined on a distributed basis as it primarily pertains to local processes. Should
26
27
                    remote processes need to access the information, it can either be obtained collectively using
28
                    the PMIx Fence operation with this directive, or can be retrieved one peer at a time using
                    PMIx Get without first having performed the job-wide collection.
29
30
              PMIX ALL CLONES PARTICIPATE "pmix.clone.part" (bool)
31
                    All clones of the calling process must participate in the collective operation.
```

The user *must not* release any returned data pointers.

PMIX GET STATIC VALUES "pmix.get.static" (bool)

PMIX\_GET\_POINTER\_VALUES "pmix.get.pntrs" (bool)

Request that the data be returned in the provided storage location. The caller is responsible for destructing the **pmix\_value\_t** using the **PMIX\_VALUE\_DESTRUCT** macro when

Request that any pointers in the returned value point directly to values in the key-value store.

done.

32

33

34 35

36

37 38

39

PMIX\_GET\_REFRESH\_CACHE "pmix.get.refresh" (bool)

1 2 3 4 5 6 7	When retrieving data for a remote process, refresh the existing local data cache for the process in case new values have been put and committed by the process since the last refresh Local process information is assumed to be automatically updated upon posting by the process. A NULL key will cause all values associated with the process to be refreshed otherwise, only the indicated key will be updated. A process rank of PMIX_RANK_WILDCARD can be used to update job-related information in dynamic environments. The user is responsible for subsequently updating refreshed values they may have cached in their own local memory.
9 0 1 2 3 4 5	PMIX_QUERY_RESULTS "pmix.qry.res" (pmix_data_array_t)  Contains an array of query results for a given pmix_query_t passed to the  PMIx_Query_info APIs. If qualifiers were included in the query, then the first element of the array shall be the PMIX_QUERY_QUALIFIERS attribute containing those qualifiers Each of the remaining elements of the array is a pmix_info_t containing the query key and the corresponding value returned by the query. This attribute is solely for reporting purposes and cannot be used in PMIx_Get or other query operations.
6 7 8 9	<pre>PMIX_QUERY_QUALIFIERS "pmix.qry.quals" (pmix_data_array_t) Contains an array of qualifiers that were included in the query that produced the provided results. This attribute is solely for reporting purposes and cannot be used in PMIx_Get or other query operations.</pre>
20 21	<pre>PMIX_QUERY_SUPPORTED_KEYS "pmix.qry.keys" (char*) Returns comma-delimited list of keys supported by the query function. NO QUALIFIERS.</pre>
22 23 24	PMIX_QUERY_SUPPORTED_QUALIFIERS "pmix.qry.quals" (char*)  Return comma-delimited list of qualifiers supported by a query on the provided key, instead of actually performing the query on the key. NO QUALIFIERS.
25 26 27 28 29	PMIX_QUERY_NAMESPACE_INFO "pmix.qry.nsinfo" (pmix_data_array_t*)  Return an array of active namespace information - each element will itself contain an array including the namespace plus the command line of the application executing within it.  OPTIONAL QUALIFIERS: PMIX_NSPACE of specific namespace whose info is being requested.
30 31 32 33	PMIX_QUERY_ATTRIBUTE_SUPPORT "pmix.qry.attrs" (bool)  Query list of supported attributes for specified APIs. REQUIRED QUALIFIERS: one or more of PMIX_CLIENT_FUNCTIONS, PMIX_SERVER_FUNCTIONS, PMIX_TOOL_FUNCTIONS, and PMIX_HOST_FUNCTIONS.
34 35 36 37	PMIX_QUERY_AVAIL_SERVERS "pmix.qry.asrvrs" (pmix_data_array_t*)  Return an array of pmix_info_t, each element itself containing a  PMIX_SERVER_INFO_ARRAY entry holding all available data for a server on this node to which the caller might be able to connect.

PMIX\_SERVER\_INFO\_ARRAY "pmix.srv.arr" (pmix\_data\_array\_t)

1 2	Array of <b>pmix_info_t</b> about a given server, starting with its <b>PMIX_NSPACE</b> and including at least one of the rendezvous-required pieces of information.
3 4	PMIX_CLIENT_FUNCTIONS "pmix.client.fns" (bool)  Request a list of functions supported by the PMIx client library.
5 6	PMIX_CLIENT_ATTRIBUTES "pmix.client.attrs" (bool) Request attributes supported by the PMIx client library.
7 8	PMIX_SERVER_FUNCTIONS "pmix.srvr.fns" (bool) Request a list of functions supported by the PMIx server library.
9 0	PMIX_SERVER_ATTRIBUTES "pmix.srvr.attrs" (bool) Request attributes supported by the PMIx server library.
1 2	PMIX_HOST_FUNCTIONS "pmix.srvr.fns" (bool)  Request a list of functions supported by the host environment.
3 4	<pre>PMIX_HOST_ATTRIBUTES "pmix.host.attrs" (bool) Request attributes supported by the host environment.</pre>
5 6	<pre>PMIX_TOOL_FUNCTIONS "pmix.tool.fns" (bool) Request a list of functions supported by the PMIx tool library.</pre>
7 8	<pre>PMIX_TOOL_ATTRIBUTES "pmix.setup.env" (bool) Request attributes supported by the PMIx tool library functions.</pre>
9	Server attributes
20 21	PMIX_TOPOLOGY2 "pmix.topo2" (pmix_topology_t)  Provide a pointer to an implementation-specific description of the local node topology.
22 23 24	<pre>PMIX_SERVER_SHARE_TOPOLOGY "pmix.srvr.share" (bool) The PMIx server is to share its copy of the local node topology (whether given to it or self-discovered) with any clients.</pre>
25 26 27	<pre>PMIX_SERVER_SESSION_SUPPORT "pmix.srvr.sess" (bool) The host RM wants to declare itself as being the local session server for PMIx connection requests.</pre>
28 29 80	<pre>PMIX_SERVER_START_TIME "pmix.srvr.strtime" (char*)     Time when the server started - i.e., when the server created it's rendezvous file (given in ctime string format).</pre>
31 32 33	PMIX_SERVER_SCHEDULER "pmix.srv.sched" (bool)  Server is supporting system scheduler and desires access to appropriate WLM-supporting features. Indicates that the library is to be initialized for scheduler support.
84	<pre>PMIX_JOB_INFO_ARRAY "pmix.job.arr" (pmix_data_array_t)</pre>

 Provide an array of <code>pmix\_info\_t</code> containing job-realm information. The <code>PMIX\_SESSION\_ID</code> attribute of the <code>session</code> containing the <code>job</code> is required to be included in the array whenever the PMIx server library may host multiple sessions (e.g., when executing with a host RM daemon). As information is registered one job (aka namespace) at a time via the <code>PMIx\_server\_register\_nspace</code> API, there is no requirement that the array

the **PMIx\_server\_register\_nspace** API, there is no requirement that the array contain either the **PMIX\_NSPACE** or **PMIX\_JOBID** attributes when used in that context (though either or both of them may be included). At least one of the job identifiers must be provided in all other contexts where the job being referenced is ambiguous.

#### PMIX\_APP\_INFO\_ARRAY "pmix.app.arr" (pmix\_data\_array\_t)

Provide an array of **pmix\_info\_t** containing application-realm information. The **PMIX\_NSPACE** or **PMIX\_JOBID** attributes of the *job* containing the application, plus its **PMIX\_APPNUM** attribute, must to be included in the array when the array is *not* included as part of a call to **PMIx\_server\_register\_nspace** - i.e., when the job containing the application is ambiguous. The job identification is otherwise optional.

#### PMIX\_PROC\_INFO\_ARRAY "pmix.pdata" (pmix\_data\_array\_t)

Provide an array of pmix\_info\_t containing process-realm information. The PMIX\_RANK and PMIX\_NSPACE attributes, or the PMIX\_PROCID attribute, are required to be included in the array when the array is not included as part of a call to PMIX\_server\_register\_nspace - i.e., when the job containing the process is ambiguous. All three may be included if desired. When the array is included in some broader structure that identifies the job, then only the PMIX\_RANK or the PMIX\_PROCID attribute must be included (the others are optional).

### PMIX\_NODE\_INFO\_ARRAY "pmix.node.arr" (pmix\_data\_array\_t)

Provide an array of **pmix\_info\_t** containing node-realm information. At a minimum, either the **PMIX\_NODEID** or **PMIX\_HOSTNAME** attribute is required to be included in the array, though both may be included.

#### PMIX MAX VALUE "pmix.descr.maxval" (varies)

Used in **pmix\_regattr\_t** to describe the maximum valid value for the associated attribute.

#### PMIX MIN VALUE "pmix.descr.minval" (varies)

Used in **pmix\_regattr\_t** to describe the minimum valid value for the associated attribute.

#### PMIX\_ENUM\_VALUE "pmix.descr.enum" (char\*)

Used in <code>pmix\_regattr\_t</code> to describe accepted values for the associated attribute. Numerical values shall be presented in a form convertible to the attribute's declared data type. Named values (i.e., values defined by constant names via a typical C-language enum declaration) must be provided as their numerical equivalent.

#### PMIX\_HOMOGENEOUS\_SYSTEM "pmix.homo" (bool)

The nodes comprising the session are homogeneous - i.e., they each contain the same number of identical packages, fabric interfaces, GPUs, and other devices.

1 2 3 4	PMIX_REQUIRED_KEY "pmix.req.key" (char*)  Identifies a key that must be included in the requested information. If the specified key is not already available, then the PMIx servers are required to delay response to the dmodex request until either the key becomes available or the request times out.
5 6 7 8	Job-Mgmt attributes  PMIX_ALLOC_ID "pmix.alloc.id" (char*)  A string identifier (provided by the host environment) for the resulting allocation which can later be used to reference the allocated resources in, for example, a call to PMIx_Spawn.
9 10 11	<pre>PMIX_ALLOC_QUEUE "pmix.alloc.queue" (char*) Name of the WLM queue to which the allocation request is to be directed, or the queue being referenced in a query.</pre>
12 13 14 15	Publish attributes  PMIX_ACCESS_PERMISSIONS "pmix.aperms" (pmix_data_array_t)  Define access permissions for the published data. The value shall contain an array of pmix_info_t structs containing the specified permissions.
16 17	PMIX_ACCESS_USERIDS "pmix.auids" (pmix_data_array_t) Array of effective UIDs that are allowed to access the published data.
18 19	<pre>PMIX_ACCESS_GRPIDS "pmix.agids" (pmix_data_array_t) Array of effective GIDs that are allowed to access the published data.</pre>
20 21 22 23	Reserved keys  PMIX_NUM_ALLOCATED_NODES "pmix.num.anodes" (uint32_t)  Number of nodes in the specified realm regardless of whether or not they currently host processes. Defaults to the <i>job</i> realm.
24 25 26	<pre>PMIX_NUM_NODES "pmix.num.nodes" (uint32_t)     Number of nodes currently hosting processes in the specified realm. Defaults to the job realm.</pre>
27 28 29	PMIX_CMD_LINE "pmix.cmd.line" (char*)  Command line used to execute the specified job (e.g., "mpirun -n 2 -map-by foo ./myapp: -n 4 ./myapp2").
30 31 32	PMIX_APP_ARGV "pmix.app.argv" (char*)  Consolidated argv passed to the spawn command for the given application (e.g., "./myapp arg1 arg2 arg3").
33 34 35 36 37 38	PMIX_PACKAGE_RANK "pmix.pkgrank" (uint16_t)  Rank of the specified process on the <i>package</i> where this process resides - refers to the numerical location (starting from zero) of the process on its package when counting only those processes from the same job that share the package, ordered by their overall rank within that job. Note that processes that are not bound to PUs within a single specific package cannot have a package rank.

1 2 3	<pre>PMIX_REINCARNATION "pmix.reinc" (uint32_t) Number of times this process has been re-instantiated - i.e, a value of zero indicates that the process has never been restarted. 5</pre>
4 5	PMIX_HOSTNAME_ALIASES "pmix.alias" (char*)  Comma-delimited list of names by which the target node is known.
6 7	PMIX_HOSTNAME_KEEP_FQDN "pmix.fqdn" (bool) FQDNs are being retained by the PMIx library.
8 9	PMIX_CPUSET_BITMAP "pmix.bitmap" (pmix_cpuset_t*)  Bitmap applied to the process upon launch.
10 11	PMIX_EXTERNAL_PROGRESS "pmix.evext" (bool)  The host shall progress the PMIx library via calls to PMIx_Progress
12 13 14	<pre>PMIX_NODE_MAP_RAW "pmix.nmap.raw" (char*)     Comma-delimited list of nodes containing procs within the specified realm. Defaults to the      job realm.</pre>
15 16 17	PMIX_PROC_MAP_RAW "pmix.pmap.raw" (char*)  Semi-colon delimited list of strings, each string containing a comma-delimited list of ranks on the corresponding node within the specified realm. Defaults to the <i>job</i> realm.
18 19 20 21	Tool attributes  PMIX_TOOL_CONNECT_OPTIONAL "pmix.tool.conopt" (bool)  The tool shall connect to a server if available, but otherwise continue to operate unconnected.
22 23 24	<pre>PMIX_TOOL_ATTACHMENT_FILE "pmix.tool.attach" (char*) Pathname of file containing connection information to be used for attaching to a specific server.</pre>
25 26 27	<pre>PMIX_LAUNCHER_RENDEZVOUS_FILE "pmix.tool.lncrnd" (char*) Pathname of file where the launcher is to store its connection information so that the spawning tool can connect to it.</pre>
28 29 30	<pre>PMIX_PRIMARY_SERVER "pmix.pri.srvr" (bool) The server to which the tool is connecting shall be designated the primary server once connection has been accomplished.</pre>
31 32 33 34	PMIX_NOHUP "pmix.nohup" (bool)  Any processes started on behalf of the calling tool (or the specified namespace, if such specification is included in the list of attributes) should continue after the tool disconnects from its server.
35	<pre>PMIX_LAUNCHER_DAEMON "pmix.lnch.dmn" (char*)</pre>

Path to executable that is to be used as the backend daemon for the launcher. This replaces the launcher's own daemon with the specified executable. Note that the user is therefore responsible for ensuring compatibility of the specified executable and the host launcher.

#### PMIX\_FORKEXEC\_AGENT "pmix.frkex.agnt" (char\*)

Path to executable that the launcher's backend daemons are to fork/exec in place of the actual application processes. The fork/exec agent shall connect back (as a PMIx tool) to the launcher's daemon to receive its spawn instructions, and is responsible for starting the actual application process it replaced. See Section 17.4.3 for details.

### PMIX\_EXEC\_AGENT "pmix.exec.agnt" (char\*)

Path to executable that the launcher's backend daemons are to fork/exec in place of the actual application processes. The launcher's daemon shall pass the full command line of the application on the command line of the exec agent, which shall not connect back to the launcher's daemon. The exec agent is responsible for exec'ing the specified application process in its own place. See Section 17.4.3 for details.

#### PMIX\_IOF\_PUSH\_STDIN "pmix.iof.stdin" (bool)

Requests that the PMIx library collect the **stdin** of the requester and forward it to the processes specified in the **PMIx\_IOF\_push** call. All collected data is sent to the same targets until **stdin** is closed, or a subsequent call to **PMIx\_IOF\_push** is made that includes the **PMIX\_IOF\_COMPLETE** attribute indicating that forwarding of **stdin** is to be terminated.

#### PMIX\_IOF\_COPY "pmix.iof.cpy" (bool)

Requests that the host environment deliver a copy of the specified output stream(s) to the tool, letting the stream(s) continue to also be delivered to the default location. This allows the tool to tap into the output stream(s) without redirecting it from its current final destination.

#### PMIX\_IOF\_REDIRECT "pmix.iof.redir" (bool)

Requests that the host environment intercept the specified output stream(s) and deliver it to the requesting tool instead of its current final destination. This might be used, for example, during a debugging procedure to avoid injection of debugger-related output into the application's results file. The original output stream(s) destination is restored upon termination of the tool.

### PMIX\_DEBUG\_TARGET "pmix.dbg.tgt" (pmix\_proc\_t\*)

Identifier of process(es) to be debugged - a rank of **PMIX\_RANK\_WILDCARD** indicates that all processes in the specified namespace are to be included.

#### PMIX\_DEBUG\_DAEMONS\_PER\_PROC "pmix.dbg.dpproc" (uint16\_t)

Number of debugger daemons to be spawned per application process. The launcher is to pass the identifier of the namespace to be debugged by including the **PMIX\_DEBUG\_TARGET** attribute in the daemon's job-level information. The debugger daemons spawned on a given node are responsible for self-determining their specific target process(es) - e.g., by referencing their own **PMIX\_LOCAL\_RANK** in the daemon debugger job versus the corresponding **PMIX\_LOCAL\_RANK** of the target processes on the node.

1 PMIX\_DEBUG\_DAEMONS\_PER\_NODE "pmix.dbg.dpnd" (uint16\_t) 2 Number of debugger daemons to be spawned on each node where the target job is executing. The launcher is to pass the identifier of the namespace to be debugged by including the 3 4 PMIX DEBUG TARGET attribute in the daemon's job-level information. The debugger 5 daemons spawned on a given node are responsible for self-determining their specific target 6 process(es) - e.g., by referencing their own PMIX LOCAL RANK in the daemon debugger 7 job versus the corresponding **PMIX LOCAL RANK** of the target processes on the node. 8 PMIX WAIT FOR CONNECTION "pmix.wait.conn" (bool) Wait until the specified process has connected to the requesting tool or server, or the 9 operation times out (if the **PMIX TIMEOUT** directive is included in the request). 10 PMIX LAUNCH DIRECTIVES "pmix.lnch.dirs" (pmix data array t\*) 11 12 Array of pmix info t containing directives for the launcher - a convenience attribute for retrieving all directives with a single call to PMIx Get. 13 Fabric attributes 14 PMIX\_SERVER\_SCHEDULER "pmix.srv.sched" (bool) 15 16 Server is supporting system scheduler and desires access to appropriate WLM-supporting 17 features. Indicates that the library is to be initialized for scheduler support. 18 PMIX FABRIC COST MATRIX "pmix.fab.cm" (pointer) 19 Pointer to a two-dimensional square array of point-to-point relative communication costs expressed as **uint16** t values. 20 21 PMIX FABRIC GROUPS "pmix.fab.grps" (string) 22 A string delineating the group membership of nodes in the overall system, where each fabric group consists of the group number followed by a colon and a comma-delimited list of nodes 23 in that group, with the groups delimited by semi-colons (e.g., 24 25 0:node000, node002, node004, node006; 1:node001, node003, 26 node005, node007) PMIX\_FABRIC\_VENDOR "pmix.fab.vndr" (string) 27 Name of the vendor (e.g., Amazon, Mellanox, HPE, Intel) for the specified fabric. 28 PMIX FABRIC IDENTIFIER "pmix.fab.id" (string) 29 An identifier for the specified fabric (e.g., MgmtEthernet, Slingshot-11, OmniPath-1). 30 31 PMIX\_FABRIC\_INDEX "pmix.fab.idx" (size\_t) 32 The index of the fabric as returned in **pmix fabric t**. 33 PMIX FABRIC NUM DEVICES "pmix.fab.nverts" (size t) 34 Total number of fabric devices in the overall system - corresponds to the number of rows or columns in the cost matrix. 35 36 PMIX FABRIC COORDINATES "pmix.fab.coords" (pmix data array t)

Array of <code>pmix\_geometry\_t</code> fabric coordinates for devices on the specified node. The array will contain the coordinates of all devices on the node, including values for all supported coordinate views. The information for devices on the local node shall be provided if the node is not specified in the request.

#### PMIX FABRIC DIMS "pmix.fab.dims" (uint32 t)

Number of dimensions in the specified fabric plane/view. If no plane is specified in a request, then the dimensions of all planes in the overall system will be returned as a **pmix\_data\_array\_t** containing an array of **uint32\_t** values. Default is to provide dimensions in *logical* view.

#### PMIX\_FABRIC\_ENDPT "pmix.fab.endpt" (pmix\_data\_array\_t)

Fabric endpoints for a specified process. As multiple endpoints may be assigned to a given process (e.g., in the case where multiple devices are associated with a package to which the process is bound), the returned values will be provided in a pmix\_data\_array\_t of pmix\_endpoint\_t elements.

#### PMIX\_FABRIC\_SHAPE "pmix.fab.shape" (pmix\_data\_array\_t\*)

The size of each dimension in the specified fabric plane/view, returned in a <code>pmix\_data\_array\_t</code> containing an array of <code>uint32\_t</code> values. The size is defined as the number of elements present in that dimension - e.g., the number of devices in one dimension of a physical view of a fabric plane. If no plane is specified, then the shape of each plane in the overall system will be returned in a <code>pmix\_data\_array\_t</code> array where each element is itself a two-element array containing the <code>PMIX\_FABRIC\_PLANE</code> followed by that plane's fabric shape. Default is to provide the shape in <code>logical</code> view.

#### PMIX\_FABRIC\_SHAPE\_STRING "pmix.fab.shapestr" (string)

Network shape expressed as a string (e.g., "10x12x2"). If no plane is specified, then the shape of each plane in the overall system will be returned in a pmix\_data\_array\_t array where each element is itself a two-element array containing the PMIX\_FABRIC\_PLANE followed by that plane's fabric shape string. Default is to provide the shape in *logical* view.

#### PMIX\_SWITCH\_PEERS "pmix.speers" (pmix\_data\_array\_t)

Peer ranks that share the same switch as the process specified in the call to PMIx\_Get.

Returns a pmix\_data\_array\_t array of pmix\_info\_t results, each element containing the PMIX\_SWITCH\_PEERS key with a three-element pmix\_data\_array\_t array of pmix\_info\_t containing the PMIX\_DEVICE\_ID of the local fabric device, the PMIX\_FABRIC\_SWITCH identifying the switch to which it is connected, and a comma-delimited string of peer ranks sharing the switch to which that device is connected.

#### PMIX FABRIC PLANE "pmix.fab.plane" (string)

ID string of a fabric plane (e.g., CIDR for Ethernet). When used as a modifier in a request for information, specifies the plane whose information is to be returned. When used directly as a key in a request, returns a **pmix\_data\_array\_t** of string identifiers for all fabric planes in the overall system.

PMIX\_FABRIC\_SWITCH "pmix.fab.switch" (string)

1 2 3 4	ID string of a fabric switch. When used as a modifier in a request for information, specifies the switch whose information is to be returned. When used directly as a key in a request, returns a <pre>pmix_data_array_t</pre> of string identifiers for all fabric switches in the overall system.
5 6 7 8	PMIX_FABRIC_DEVICE "pmix.fabdev" (pmix_data_array_t)  An array of pmix_info_t describing a particular fabric device using one or more of the attributes defined below. The first element in the array shall be the PMIX_DEVICE_ID of the device.
9 0	PMIX_FABRIC_DEVICE_INDEX "pmix.fabdev.idx" (uint32_t) Index of the device within an associated communication cost matrix.
1 2 3	<pre>PMIX_FABRIC_DEVICE_NAME "pmix.fabdev.nm" (string) The operating system name associated with the device. This may be a logical fabric interface name (e.g. "eth0" or "eno1") or an absolute filename.</pre>
4 5	<pre>PMIX_FABRIC_DEVICE_VENDOR "pmix.fabdev.vndr" (string)</pre>
6 7	PMIX_FABRIC_DEVICE_BUS_TYPE "pmix.fabdev.btyp" (string) The type of bus to which the device is attached (e.g., "PCI", "GEN-Z").
8 9	<pre>PMIX_FABRIC_DEVICE_VENDORID "pmix.fabdev.vendid" (string) This is a vendor-provided identifier for the device or product.</pre>
20 21	<pre>PMIX_FABRIC_DEVICE_DRIVER "pmix.fabdev.driver" (string) The name of the driver associated with the device.</pre>
22 23	<pre>PMIX_FABRIC_DEVICE_FIRMWARE "pmix.fabdev.fmwr" (string) The device's firmware version.</pre>
24 25 26	<pre>PMIX_FABRIC_DEVICE_ADDRESS "pmix.fabdev.addr" (string) The primary link-level address associated with the device, such as a MAC address. If multiple addresses are available, only one will be reported.</pre>
27 28 29	PMIX_FABRIC_DEVICE_COORDINATES "pmix.fab.coord" (pmix_geometry_t) The pmix_geometry_t fabric coordinates for the device, including values for all supported coordinate views.
30 31	PMIX_FABRIC_DEVICE_MTU "pmix.fabdev.mtu" (size_t) The maximum transfer unit of link level frames or packets, in bytes.
32	<pre>PMIX_FABRIC_DEVICE_SPEED "pmix.fabdev.speed" (size_t) The active link data rate, given in bits per second.</pre>
94 95 96 97	PMIX_FABRIC_DEVICE_STATE "pmix.fabdev.state" (pmix_link_state_t)  The last available physical port state for the specified device. Possible values are  PMIX_LINK_STATE_UNKNOWN, PMIX_LINK_DOWN, and PMIX_LINK_UP, to indicate if the port state is unknown or not applicable (unknown), inactive (down), or active (up).

1 2 3	<pre>PMIX_FABRIC_DEVICE_TYPE "pmix.fabdev.type" (string)     Specifies the type of fabric interface currently active on the device, such as Ethernet or InfiniBand.</pre>
4 5 6 7 8 9	PMIX_FABRIC_DEVICE_PCI_DEVID "pmix.fabdev.pcidevid" (string)  A node-level unique identifier for a PCI device. Provided only if the device is located on a PCI bus. The identifier is constructed as a four-part tuple delimited by colons comprised of the PCI 16-bit domain, 8-bit bus, 8-bit device, and 8-bit function IDs, each expressed in zero-extended hexadecimal form. Thus, an example identifier might be "abc1:0f:23:01". The combination of node identifier (PMIX_HOSTNAME or PMIX_NODEID) and PMIX_FABRIC_DEVICE_PCI_DEVID shall be unique within the overall system.
11	Device attributes
12	<pre>PMIX_DEVICE_DISTANCES "pmix.dev.dist" (pmix_data_array_t)</pre>
13 14	Return an array of <b>pmix_device_distance_t</b> containing the minimum and maximum distances of the given process location to all devices of the specified type on the local node.
15	PMIX_DEVICE_TYPE "pmix.dev.type" (pmix_device_type_t)
16	Bitmask specifying the type(s) of device(s) whose information is being requested. Only used
17	as a directive/qualifier.
18	<pre>PMIX_DEVICE_ID "pmix.dev.id" (string)</pre>
19	System-wide UUID or node-local OS name of a particular device.
20	Sets-Groups attributes
21	<pre>PMIX_QUERY_NUM_PSETS "pmix.qry.psetnum" (size_t)</pre>
22	Return the number of process sets defined in the specified range (defaults to
23	PMIX_RANGE_SESSION).
24	<pre>PMIX_QUERY_PSET_NAMES "pmix.qry.psets" (pmix_data_array_t*)</pre>
25	Return a pmix_data_array_t containing an array of strings of the process set names
26	defined in the specified range (defaults to <b>PMIX_RANGE_SESSION</b> ).
27	<pre>PMIX_QUERY_PSET_MEMBERSHIP "pmix.qry.pmems" (pmix_data_array_t*)</pre>
28	Return an array of <pre>pmix_proc_t</pre> containing the members of the specified process set.
29	<pre>PMIX_PSET_NAME "pmix.pset.nm" (char*)</pre>
30	The name of the newly defined process set.
31	<pre>PMIX_PSET_MEMBERS "pmix.pset.mems" (pmix_data_array_t*)</pre>
32	An array of pmix_proc_t containing the members of the newly defined process set.
33	<pre>PMIX_PSET_NAMES "pmix.pset.nms" (pmix_data_array_t*)</pre>
34	Returns an array of <b>char</b> * string names of the process sets in which the given process is a
35	member.
36	<pre>PMIX_QUERY_NUM_GROUPS "pmix.qry.pgrpnum" (size_t)</pre>
37	Return the number of process groups defined in the specified range (defaults to session).
38	OPTIONAL QUALIFERS: PMIX_RANGE.

#### PMIX\_QUERY\_GROUP\_NAMES "pmix.qry.pqrp" (pmix\_data\_array\_t\*) 1 2 Return a pmix data array t containing an array of string names of the process groups defined in the specified range (defaults to session). OPTIONAL QUALIFERS: 3 4 PMIX RANGE. 5 PMIX QUERY GROUP MEMBERSHIP 6 "pmix.gry.pgrpmems" (pmix data array t\*) Return a pmix\_data\_array\_t of pmix\_proc\_t containing the members of the 7 specified process group. REQUIRED QUALIFIERS: PMIX GROUP ID. 8 9 PMIX\_GROUP\_ID "pmix.grp.id" (char\*) User-provided group identifier - as the group identifier may be used in PMIx operations, the 10 user is required to ensure that the provided ID is unique within the scope of the host 11 12 environment (e.g., by including some user-specific or application-specific prefix or suffix to 13 the string). 14 PMIX GROUP LEADER "pmix.grp.ldr" (bool) This process is the leader of the group. 15 16 PMIX GROUP OPTIONAL "pmix.grp.opt" (bool) Participation is optional - do not return an error if any of the specified processes terminate 17 without having joined. The default is false. 18 19 PMIX GROUP NOTIFY TERMINATION "pmix.grp.notterm" (bool) 20 Notify remaining members when another member terminates without first leaving the group. 21 22 PMIX GROUP FT COLLECTIVE "pmix.grp.ftcoll" (bool) Adjust internal tracking on-the-fly for terminated processes during a PMIx group collective 23 24 operation. 25 PMIX GROUP ASSIGN CONTEXT ID "pmix.grp.actxid" (bool) Requests that the RM assign a new context identifier to the newly created group. The 26 27 identifier is an unsigned, size t value that the RM guarantees to be unique across the range 28 specified in the request. Thus, the value serves as a means of identifying the group within that range. If no range is specified, then the request defaults to PMIX RANGE SESSION. 29 30 PMIX GROUP LOCAL ONLY "pmix.grp.lcl" (bool) 31 Group operation only involves local processes. PMIx implementations are required to 32 automatically scan an array of group members for local vs remote processes - if only local processes are detected, the implementation need not execute a global collective for the 33 34 operation unless a context ID has been requested from the host environment. This can result 35 in significant time savings. This attribute can be used to optimize the operation by indicating whether or not only local processes are represented, thus allowing the implementation to 36 bypass the scan. 37 38 PMIX\_GROUP\_CONTEXT\_ID "pmix.grp.ctxid" (size\_t) Context identifier assigned to the group by the host RM. 39

1 2 3	<pre>PMIX_GROUP_ENDPT_DATA "pmix.grp.endpt" (pmix_byte_object_t)</pre> Data collected during group construction to ensure communication between group members is supported upon completion of the operation.
4 5 6	<pre>PMIX_GROUP_NAMES "pmix.pgrp.nm" (pmix_data_array_t*) Returns an array of char* string names of the process groups in which the given process is a member.</pre>
7 8 9 10 11	Process Mgmt attributes  PMIX_OUTPUT_TO_DIRECTORY "pmix.outdir" (char*)  Direct output into files of form " <directory>/<jobid>/rank.<rank>/  stdout[err]" - can be assigned to the entire job (by including attribute in the job_info array) or on a per-application basis in the info array for each pmix_app_t.</rank></jobid></directory>
12 13	PMIX_TIMEOUT_STACKTRACES "pmix.tim.stack" (bool) Include process stacktraces in timeout report from a job.
14 15	PMIX_TIMEOUT_REPORT_STATE "pmix.tim.state" (bool)  Report process states in timeout report from a job.
16 17 18 19 20 21 22 23 24	PMIX_NOTIFY_JOB_EVENTS "pmix.note.jev" (bool)  Requests that the launcher generate the PMIX_EVENT_JOB_START,  PMIX_LAUNCH_COMPLETE, and PMIX_EVENT_JOB_END events. Each event is to include at least the namespace of the corresponding job and a PMIX_EVENT_TIMESTAMP indicating the time the event occurred. Note that the requester must register for these individual events, or capture and process them by registering a default event handler instead of individual handlers and then process the events based on the returned status code. Another common method is to register one event handler for all job-related events, with a separate handler for non-job events - see PMIx_Register_event_handler for details.
25 26 27	<pre>PMIX_NOTIFY_PROC_TERMINATION "pmix.noteproc" (bool) Requests that the launcher generate the PMIX_EVENT_PROC_TERMINATED event whenever a process either normally or abnormally terminates.</pre>
28 29 30	<pre>PMIX_NOTIFY_PROC_ABNORMAL_TERMINATION "pmix.noteabproc" (bool) Requests that the launcher generate the PMIX_EVENT_PROC_TERMINATED event only when a process abnormally terminates.</pre>
31 32 33	PMIX_LOG_PROC_TERMINATION "pmix.logproc" (bool)  Requests that the launcher log the PMIX_EVENT_PROC_TERMINATED event whenever a process either normally or abnormally terminates.
34 35 36	<pre>PMIX_LOG_PROC_ABNORMAL_TERMINATION "pmix.logabproc" (bool) Requests that the launcher log the PMIX_EVENT_PROC_TERMINATED event only when a process abnormally terminates.</pre>
37	<pre>PMIX_LOG_JOB_EVENTS "pmix.log.jev" (bool)</pre>

```
Requests that the launcher log the PMIX_EVENT_JOB_START,
 1
 2
                   PMIX LAUNCH COMPLETE, and PMIX EVENT JOB END events using PMIx Log,
                   subject to the logging attributes of Section 12.4.3.
 3
 4
              PMIX LOG COMPLETION "pmix.logcomp" (bool)
 5
                   Requests that the launcher log the PMIX EVENT JOB END event for normal or abnormal
 6
                   termination of the spawned job using PMIx Log, subject to the logging attributes of
 7
                   Section 12.4.3. The event shall include the returned status code
8
                   (PMIX JOB TERM STATUS) for the corresponding job; the identity (PMIX PROCID)
9
                   and exit status (PMIX_EXIT_CODE) of the first failed process, if applicable; and a
                   PMIX EVENT TIMESTAMP indicating the time the termination occurred.
10
              PMIX FIRST ENVAR "pmix.envar.first" (pmix envar t*)
11
12
                   Ensure the given value appears first in the specified envar using the separator character,
13
                   creating the envar if it doesn't already exist
              Event attributes
14
              PMIX_EVENT_TIMESTAMP "pmix.evtstamp" (time_t)
15
16
                   System time when the associated event occurred.
    B.8.3 Added Environmental Variables
17
              Tool environmental variables
18
19
              PMIX LAUNCHER RNDZ URI
20
              PMIX LAUNCHER RNDZ FILE
21
              PMIX KEEPALIVE PIPE
22
   B.8.4 Added Macros
24
              PMIX_CHECK_RESERVED_KEY PMIX_INFO_WAS_PROCESSED PMIX_INFO_PROCESSED
25
              PMIX_INFO_LIST_START PMIX_INFO_LIST_ADD PMIX_INFO_LIST_XFER
26
              PMIX_INFO_LIST_CONVERT PMIX_INFO_LIST_RELEASE
    B.8.5
             Deprecated APIs
27
              pmix evhdlr reg_cbfunc_t Renamed to pmix hdlr_reg_cbfunc_t
28
29
              The pmix_server_client_connected_fn_t server module entry point has been
30
              deprecated in favor of pmix server client connected2 fn t
31
              PMIx tool connect to server Replaced by PMIx tool attach to server to
32
              allow return of the process identifier of the server to which the tool has attached.
```

### B.8.6 Deprecated constants

```
2
             The following constants were deprecated in v4.0:
             PMIX ERR DEBUGGER RELEASE
 3
                                              Renamed to PMIX DEBUGGER RELEASE
             PMIX_ERR_JOB_TERMINATED
                                           Renamed to PMIX_EVENT_JOB_END
 4
 5
             PMIX EXISTS
                             Renamed to PMIX ERR EXISTS
 6
             PMIX_ERR_PROC_ABORTED
                                         Consolidated with PMIX_EVENT_PROC_TERMINATED
 7
             PMIX_ERR_PROC_ABORTING
                                          Consolidated with PMIX EVENT PROC TERMINATED
8
             PMIX ERR LOST CONNECTION TO SERVER
                                                        Consolidated into
9
                 PMIX_ERR_LOST_CONNECTION
10
             PMIX ERR LOST PEER CONNECTION
                                                  Consolidated into
                 PMIX ERR LOST CONNECTION
11
12
             PMIX ERR LOST CONNECTION TO CLIENT
                                                        Consolidated into
13
                 PMIX_ERR_LOST_CONNECTION
                                                 Renamed to PMIX ERR JOB TERM WO SYNC
14
             PMIX ERR INVALID TERMINATION
15
             PMIX PROC TERMINATED
                                        Renamed to PMIX EVENT PROC TERMINATED
             PMIX_ERR_NODE_DOWN
                                     Renamed to PMIX_EVENT_NODE_DOWN
16
                                         Renamed to PMIX_EVENT_NODE_OFFLINE
17
             PMIX_ERR_NODE_OFFLINE
18
             PMIX_ERR_SYS_OTHER
                                     Renamed to PMIX_EVENT_SYS_OTHER
                                          Connection has been requested by a PMIx-based tool -
19
             PMIX CONNECT REQUESTED
20
                 deprecated as not required.
                                           A tool or client has connected to the PMIx server -
21
             PMIX PROC HAS CONNECTED
22
                 deprecated in favor of the new pmix_server_client_connected2_fn_t server
23
                 module API
```

### 24 B.8.7 Removed constants

PMIX ERR HANDSHAKE FAILED

25

26

27

The following constants were removed from the PMIx Standard in v4.0 as they are internal to a particular PMIx implementation.

Connection handshake failed

```
28
              PMIX_ERR_READY_FOR_HANDSHAKE
                                                   Ready for handshake
29
              PMIX ERR IN ERRNO
                                      Error defined in errno
              PMIX ERR INVALID VAL LENGTH
30
                                                  Invalid value length
                                             Invalid argument length
31
              PMIX ERR INVALID LENGTH
32
              PMIX_ERR_INVALID_NUM_ARGS
                                                Invalid number of arguments
33
              PMIX_ERR_INVALID_ARGS
                                           Invalid arguments
              PMIX_ERR_INVALID_NUM_PARSED
                                                  Invalid number parsed
34
              PMIX_ERR_INVALID_KEYVALP
                                              Invalid key/value pair
35
36
              PMIX ERR INVALID SIZE
                                           Invalid size
              PMIX ERR PROC REQUESTED ABORT
37
                                                    Process is already requested to abort
              PMIX ERR SERVER FAILED REQUEST
                                                      Failed to connect to the server
38
              PMIX ERR PROC ENTRY NOT FOUND
                                                     Process not found
39
```

```
1
                                          Invalid argument
              PMIX_ERR_INVALID_ARG
2
              PMIX ERR INVALID KEY
                                          Invalid key
 3
              PMIX_ERR_INVALID_KEY_LENGTH
                                                  Invalid key length
 4
                                          Invalid value
              PMIX_ERR_INVALID_VAL
 5
              PMIX ERR INVALID NAMESPACE
                                                 Invalid namespace
6
              PMIX ERR SERVER NOT AVAIL
                                                Server is not available
 7
              PMIX ERR SILENT
                                    Silent error
8
              PMIX_ERR_PACK_MISMATCH
                                            Pack mismatch
9
              PMIX_ERR_DATA_VALUE_NOT FOUND
                                                     Data value not found
10
              PMIX ERR NOT IMPLEMENTED
                                               Not implemented
              PMIX_GDS_ACTION_COMPLETE
                                               The GDS action has completed
11
12
              PMIX NOTIFY ALLOC COMPLETE
                                                 Notify that a requested allocation operation is complete
                  - the result of the request will be included in the info array
13
```

### 4 B.8.8 Deprecated attributes

```
The following attributes were deprecated in v4.0:
15
16
            PMIX_TOPOLOGY "pmix.topo" (hwloc_topology_t)
17
                 Renamed to PMIX TOPOLOGY2.
18
            PMIX_DEBUG_JOB "pmix.dbg.job" (char*)
                 Renamed to PMIX DEBUG TARGET)
19
20
            PMIX RECONNECT SERVER "pmix.tool.recon" (bool)
21
                 Renamed to the PMIx tool connect to server API
22
            PMIX ALLOC NETWORK "pmix.alloc.net" (array)
                 Renamed to PMIX ALLOC FABRIC
23
            PMIX ALLOC NETWORK ID "pmix.alloc.netid" (char*)
24
25
                 Renamed to PMIX ALLOC FABRIC ID
            PMIX_ALLOC_NETWORK_QOS "pmix.alloc.netqos" (char*)
26
27
                 Renamed to PMIX ALLOC FABRIC QOS
            PMIX ALLOC NETWORK TYPE "pmix.alloc.nettype" (char*)
28
                 Renamed to PMIX ALLOC FABRIC TYPE
29
30
            PMIX ALLOC NETWORK PLANE "pmix.alloc.netplane" (char*)
                 Renamed to PMIX_ALLOC_FABRIC_PLANE
31
            PMIX_ALLOC_NETWORK_ENDPTS "pmix.alloc.endpts" (size_t)
32
33
                 Renamed to PMIX_ALLOC_FABRIC_ENDPTS
34
            PMIX ALLOC NETWORK ENDPTS NODE "pmix.alloc.endpts.nd" (size t)
35
                 Renamed to PMIX_ALLOC_FABRIC_ENDPTS_NODE
            PMIX ALLOC NETWORK_SEC_KEY "pmix.alloc.nsec" (pmix_byte_object_t)
36
                 Renamed to PMIX_ALLOC_FABRIC_SEC_KEY
37
            PMIX_PROC_DATA "pmix.pdata" (pmix_data_array_t)
38
39
                 Renamed to PMIX PROC INFO ARRAY
            PMIX_LOCALITY "pmix.loc" (pmix_locality_t)
40
```

1 Relative locality of the specified process to the requester, expressed as a bitmask as per the 2 description in the pmix locality t section. This value is unique to the requesting 3 process and thus cannot be communicated by the server as part of the job-level information. 4 Its use has been replaced by the **PMIx Get relative locality** function. Removed attributes B.8.9 5 The following attributes were removed from the PMIx Standard in v4.0 as they are internal to a 6 particular PMIx implementation. Users are referred to the PMIx Load topology API for 7 8 obtaining the local topology description. 9 PMIX\_LOCAL\_TOPO "pmix.ltopo" (char\*) 10 XML representation of local node topology. PMIX TOPOLOGY XML "pmix.topo.xml" (char\*) 11 12 XML-based description of topology PMIX\_TOPOLOGY\_FILE "pmix.topo.file" (char\*) 13 Full path to file containing XML topology description 14 15 PMIX TOPOLOGY SIGNATURE "pmix.toposig" (char\*) Topology signature string. 16 PMIX HWLOC\_SHMEM\_ADDR "pmix.hwlocaddr" (size\_t) 17 Address of the HWLOC shared memory segment. 18 PMIX\_HWLOC\_SHMEM\_SIZE "pmix.hwlocsize" (size\_t) 19 20 Size of the HWLOC shared memory segment. PMIX\_HWLOC\_SHMEM\_FILE "pmix.hwlocfile" (char\*) 21 Path to the HWLOC shared memory file. 22 PMIX\_HWLOC\_XML\_V1 "pmix.hwlocxml1" (char\*) 23 XML representation of local topology using HWLOC's v1.x format. 24 25 PMIX HWLOC XML V2 "pmix.hwlocxml2" (char\*) XML representation of local topology using HWLOC's v2.x format. 26 PMIX HWLOC SHARE TOPO "pmix.hwlocsh" (bool) 27 28 Share the HWLOC topology via shared memory 29 PMIX HWLOC HOLE KIND "pmix.hwlocholek" (char\*) Kind of VM "hole" HWLOC should use for shared memory 30 PMIX DSTPATH "pmix.dstpath" (char\*) 31 Path to shared memory data storage (dstore) files. Deprecated from Standard as being 32 33 implementation specific. PMIX\_COLLECTIVE\_ALGO "pmix.calgo" (char\*) 34 Comma-delimited list of algorithms to use for the collective operation. PMIx does not 35 impose any requirements on a host environment's collective algorithms. Thus, the 36 acceptable values for this attribute will be environment-dependent - users are encouraged to 37

PMIX\_COLLECTIVE\_ALGO\_REQD "pmix.calreqd" (bool)

If true, indicates that the requested choice of algorithm is mandatory.

PMIX PROC BLOB "pmix.pblob" (pmix byte object t)

check their host environment for supported values.

38

39

40

```
Packed blob of process data.
 1
 2
              PMIX MAP BLOB "pmix.mblob" (pmix byte object t)
 3
                    Packed blob of process location.
 4
              PMIX_MAPPER "pmix.mapper" (char*)
 5
                    Mapping mechanism to use for placing spawned processes - when accessed using
6
                    PMIx_Get, use the PMIX_RANK_WILDCARD value for the rank to discover the mapping
 7
                    mechanism used for the provided namespace.
              PMIX_NON_PMI "pmix.nonpmi" (bool)
8
9
                    Spawned processes will not call PMIx_Init.
              PMIX_PROC_URI "pmix.puri" (char*)
10
                    URI containing contact information for the specified process.
11
12
              PMIX_ARCH "pmix.arch" (uint32_t)
13
                    Architecture flag.
```

### B.9 Version 4.1: TBD

- The v4.1 update includes clarifications and corrections from the v4.0 document:
- Provisional Items:

17

20

21

22

Storage Chapter 18 on page 450

### 8 B.9.1 Added Data Structures (Provisional)

- - pmix\_storage\_accessibility\_t
  - pmix storage persistence t
    - pmix storage access type t

### B.9.2 Added Constants (Provisional)

#### Storage constants 24 25 PMIX\_STORAGE\_MEDIUM\_UNKNOWN PMIX\_STORAGE\_MEDIUM\_TAPE 26 27 PMIX STORAGE MEDIUM HDD 28 PMIX STORAGE MEDIUM SSD 29 PMIX STORAGE MEDIUM NVME PMIX\_STORAGE\_MEDIUM\_PMEM 30 31 PMIX STORAGE MEDIUM RAM 32 PMIX STORAGE ACCESSIBILITY NODE 33 PMIX STORAGE ACCESSIBILITY SESSION 34 PMIX STORAGE ACCESSIBILITY JOB PMIX STORAGE ACCESSIBILITY RACK 35

```
1
             PMIX_STORAGE_ACCESSIBILITY_CLUSTER
2
             PMIX STORAGE ACCESSIBILITY REMOTE
             PMIX STORAGE PERSISTENCE_TEMPORARY
 3
4
             PMIX STORAGE PERSISTENCE NODE
5
             PMIX STORAGE PERSISTENCE SESSION
6
             PMIX STORAGE PERSISTENCE JOB
7
             PMIX STORAGE PERSISTENCE SCRATCH
8
             PMIX STORAGE PERSISTENCE PROJECT
9
             PMIX STORAGE PERSISTENCE ARCHIVE
10
             PMIX STORAGE ACCESS RD
11
             PMIX_STORAGE_ACCESS_WR
             PMIX_STORAGE_ACCESS_RDWR
12
    B.9.3 Added Attributes (Provisional)
13
             Storage attributes
14
15
             PMIX_STORAGE_ID "pmix.strg.id" (char*)
                   An identifier for the storage system (e.g., lustre-fs1, daos-oss1, home-fs)
16
17
             PMIX_STORAGE_PATH "pmix.strg.path" (char*)
18
                   Mount point path for the storage system (valid only for file-based storage systems)
19
             PMIX STORAGE_TYPE "pmix.strg.type" (char*)
                   Type of storage system (i.e., "lustre", "gpfs", "daos", "ext4")
20
21
             PMIX_STORAGE_VERSION "pmix.strg.ver" (char*)
22
                   Version string for the storage system
             PMIX STORAGE MEDIUM "pmix.strg.medium" (pmix_storage_medium_t)
23
                   Types of storage mediums utilized by the storage system (e.g., SSDs, HDDs, tape)
24
25
             PMIX STORAGE ACCESSIBILITY
              "pmix.strg.access" (pmix_storage_accessibility_t)
26
27
                   Accessibility level of the storage system (e.g., within same node, within same session)
28
             PMIX STORAGE PERSISTENCE
29
              "pmix.strq.persist" (pmix storage persistence t)
                   Persistence level of the storage system (e.g., sratch storage or achive storage)
30
             PMIX_QUERY_STORAGE_LIST "pmix.strg.list" (char*)
31
                   Comma-delimited list of storage identifiers (i.e., PMIX STORAGE ID types) for available
32
33
                   storage systems
             PMIX_STORAGE_CAPACITY_LIMIT "pmix.strg.caplim" (double)
34
35
                   Overall limit on capacity (in bytes) for the storage system
36
             PMIX STORAGE CAPACITY USED "pmix.strq.capuse" (double)
```

Overall used capacity (in bytes) for the storage system

1 2	PMIX_STORAGE_OBJECT_LIMIT "pmix.strg.objlim" (uint64_t)  Overall limit on number of objects (e.g., inodes) for the storage system
3 4	PMIX_STORAGE_OBJECTS_USED "pmix.strg.objuse" (uint64_t)  Overall used number of objects (e.g., inodes) for the storage system
5 6 7	<pre>PMIX_STORAGE_MINIMAL_XFER_SIZE "pmix.strg.minxfer" (double)  Minimal transfer size (in bytes) for the storage system - this is the storage system's atomic unit of transfer (e.g., block size)</pre>
8 9	<pre>PMIX_STORAGE_SUGGESTED_XFER_SIZE "pmix.strg.sxfer" (double) Suggested transfer size (in bytes) for the storage system</pre>
0 1 2	PMIX_STORAGE_BW_MAX "pmix.strg.bwmax" (double)  Maximum bandwidth (in bytes/sec) for storage system - provided as the theoretical maximum or the maximum observed bandwidth value
3 4 5 6	PMIX_STORAGE_BW_CUR "pmix.strg.bwcur" (double)  Observed bandwidth (in bytes/sec) for storage system - provided as a recently observed bandwidth value, with the exact measurement interval depending on the storage system and/or PMIx library implementation
7 8 9	PMIX_STORAGE_IOPS_MAX "pmix.strg.iopsmax" (double)  Maximum IOPS (in I/O operations per second) for storage system - provided as the theoretical maximum or the maximum observed IOPS value
20 21 22 23	PMIX_STORAGE_IOPS_CUR "pmix.strg.iopscur" (double)  Observed IOPS (in I/O operations per second) for storage system - provided as a recently observed IOPS value, with the exact measurement interval depending on the storage system and/or PMIx library implementation
24 25	<pre>PMIX_STORAGE_ACCESS_TYPE "pmix.strg.atype" (pmix_storage_access_type_t)</pre>
26 27	Qualifier describing the type of storage access to return information for (e.g., for qualifying PMIX_STORAGE_BW_CUR, PMIX_STORAGE_IOPS_CUR, or
28	PMIX_STORAGE_SUGGESTED_XFER_SIZE attributes)

### **APPENDIX C**

• IBM, Inc.

• Allinea (ARM)

23

24

# Acknowledgements

1 2 3 4		This document represents the work of many people who have contributed to the PMIx community. Without the hard work and dedication of these people this document would not have been possible. The sections below list some of the active participants and organizations in the various PMIx standard iterations.
5	<b>C.1</b>	Version 4.0
6		The following list includes some of the active participants in the PMIx v4 standardization process.
7		Ralph H. Castain and Danielle Sikich
8		Joshua Hursey and David Solt
9		Dirk Schubert
10		John DelSignore
11		Aurelien Bouteiller
12		Michael A Raymond
13		Howard Pritchard and Nathan Hjelm
14		Brice Goglin
15		Kathryn Mohror and Stephen Herbein
16		Thomas Naughton and Swaroop Pophale
17		William E. Allcock and Paul Rich
18		Michael Karo
19	•	Artem Polyakov
20 21		The following institutions supported this effort through time and travel support for the people listed above.
22		Intel Corporation

- Perforce 1 • University of Tennessee, Knoxville 2 3 • The Exascale Computing Project, an initiative of the US Department of Energy • National Science Foundation HPE Co. 5 • Los Alamos National Laboratory 6 INRIA • Lawrence Livermore National Laboratory 8 9 • Oak Ridge National Laboratory • Argonne National Laboratory 10 Altair 11 12 • NVIDIA C.2 Version 3.0 The following list includes some of the active participants in the PMIx v3 standardization process. 14 • Ralph H. Castain, Andrew Friedley, Brandon Yates 15 • Joshua Hursey and David Solt 16 • Aurelien Bouteiller and George Bosilca 17 18 • Dirk Schubert • Kevin Harms 19 Artem Polyakov 20 The following institutions supported this effort through time and travel support for the people listed 21
- Intel Corporation

above.

- IBM, Inc.
- University of Tennessee, Knoxville
- The Exascale Computing Project, an initiative of the US Department of Energy
- National Science Foundation
- Argonne National Laboratory

22

24

25

- Allinea (ARM)
- NVIDIA

#### C.3 Version 2.0

- 4 The following list includes some of the active participants in the PMIx v2 standardization process.
- Ralph H. Castain, Annapurna Dasari, Christopher A. Holguin, Andrew Friedley, Michael Klemm
   and Terry Wilmarth
  - Joshua Hursey, David Solt, Alexander Eichenberger, Geoff Paulsen, and Sameh Sharkawi
  - Aurelien Bouteiller and George Bosilca
  - Artem Polyakov, Igor Ivanov and Boris Karasev
- Gilles Gouaillardet
  - Michael A Raymond and Jim Stoffel
- Dirk Schubert
- Moe Jette

7

8

11

14

18

22

23

26 27

- Takahiro Kawashima and Shinji Sumimoto
- Howard Pritchard
- David Beer
- Brice Goglin
  - Geoffroy Vallee, Swen Boehm, Thomas Naughton and David Bernholdt
- Adam Moody and Martin Schulz
- Ryan Grant and Stephen Olivier
- Michael Karo
  - The following institutions supported this effort through time and travel support for the people listed above.
- Intel Corporation
- IBM, Inc.
  - University of Tennessee, Knoxville
  - The Exascale Computing Project, an initiative of the US Department of Energy
- National Science Foundation
- Mellanox, Inc.

- Research Organization for Information Science and Technology 1 • HPE Co. 2 3 • Allinea (ARM) • SchedMD, Inc. • Fujitsu Limited 5 • Los Alamos National Laboratory 6 • Adaptive Solutions, Inc. • INRIA 8 9 • Oak Ridge National Laboratory • Lawrence Livermore National Laboratory 10 • Sandia National Laboratory 11 12 Altair C.4 Version 1.0 The following list includes some of the active participants in the PMIx v1 standardization process. 14 • Ralph H. Castain, Annapurna Dasari and Christopher A. Holguin 15 16 • Joshua Hursey and David Solt • Aurelien Bouteiller and George Bosilca 17 18 • Artem Polyakov, Elena Shipunova, Igor Ivanov, and Joshua Ladd • Gilles Gouaillardet 19 • Gary Brown 20 21 • Moe Jette 22 The following institutions supported this effort through time and travel support for the people listed 23 above. Intel Corporation 24
- University of Tennessee, Knoxville 26

• IBM, Inc.

- Mellanox, Inc.
- Research Organization for Information Science and Technology

25

27

- Adaptive Solutions, Inc.
- SchedMD, Inc.



# **Bibliography**

- [1] Ralph H. Castain, David Solt, Joshua Hursey, and Aurelien Bouteiller. PMIx: Process management for exascale environments. In *Proceedings of the 24th European MPI Users' Group Meeting*, EuroMPI '17, pages 14:1–14:10, New York, NY, USA, 2017. ACM.
- [2] Balaji P. et al. PMI: A scalable parallel process-management interface for extreme-scale systems. In *Recent Advances in the Message Passing Interface*, EuroMPI '10, pages 31–41, Berlin, Heidelberg, 2010. Springer.

### Index

General terms and other items not induced in the other indices.

```
application, 6, 94, 106, 302, 304, 308, 526, 529
attribute, 8
client, <u>7</u>, <u>58</u>
clients, 7
clone, 7
clones, <u>7</u>, 67, 70, 178, 181, 182, 184, 207, 210, 537
data realm, 97, 267, 268
data realms, 97
device, 8
devices, 8
Direct Modex, 255, 318
fabric, 7
fabric device, 8
fabric devices, 8
fabric plane, 8, 163, 168, 199, 202, 203, 272, 321
fabric planes, 8
fabrics, 7
host environment, 7
instant on, 8, 111, 254
job, 6, 7, 94, 99–103, 106, 292–296, 298, 302–304, 306, 308, 319, 321, 322, 509, 526, 527, 529,
          540-542
key, 8
namespace, 6
node, 7, 94, 106, 163, 168, 199, 202, 203, 302, 321
package, 7, 104, 300, 541
peer, 7, 105, 298
peers, 7
process, 7, 94, 106, 163, 168, 199, 202, 203, 302, 321
```

```
processing unit, 7
rank, <u>7</u>, <u>308</u>
realm, 97
realms, 97
resource manager, 7
RM, <u>7</u>
scheduler, <u>7</u>, <u>270</u>
session, <u>6</u>, 94, 99, 106, 107, 292, 293, 302, 303, 526, 527, 529, 540
thread, 7
threads, 7
workflow, 7
workflows, 7, 390
```

### Index of APIs

```
PMIx Abort, 24, 157, 158, 343, 345, 464, 479, 524
    PMIxClient.abort (Python), 478
PMIx Alloc directive string, 55, 499, 525
    PMIxClient.alloc directive string (Python), 499
PMIx Allocation request, 95, 196, 196, 202, 487, 527, 529, 532
    PMIxClient.allocation request (Python), 486
PMIx Allocation request nb, 199, 202, 204, 525
PMIx_Commit, 67, 69, 70, 112, 114, 114, 115, 318, 319, 346, 350, 480, 524
    PMIxClient.commit (Python), 480
PMIx_Compute_distances, 190, 191, 496, 533
    PMIxClient.compute_distances (Python), 496
PMIx_Compute_distances_nb, 191, 533
PMIx_Connect, 177, 179, 181, 182, 184, 228–230, 433, 434, 484, 524, 526
    PMIxClient.connect (Python), 483
PMIx Connect nb, 179, 179, 524
pmix_connection_cbfunc_t, 371, 371
pmix_credential_cbfunc_t, 278, 388, 389
PMIx_Data_copy, 154, 525
PMIx Data copy payload, 155, 525
PMIx Data pack, 150, 151, 290, 525
PMIx Data print, 154, 525
PMIx Data range string, 55, 498, 525
    PMIxClient.data range string (Python), 498
PMIx Data type string, 55, 499, 525
    PMIxClient.data type string (Python), 499
PMIx Data unpack, 152, 525
PMIx_Deregister_event_handler, 142, 492, 525, 532
    PMIxClient.deregister_event_handler (Python), 492
pmix_device_dist_cbfunc_t, 192, 192, 534
PMIx_Device_type_string, 57, 502, 533
    PMIxClient.device_type_string (Python), 502
PMIx_Disconnect, 181, 182–184, 230, 433, 434, 484, 524, 526
    PMIxClient.disconnect (Python), 484
PMIx Disconnect nb, 183, 184, 230, 524
pmix dmodex response fn t, 318, 319
PMIx_Error_string, 54, 497, 524
    PMIxClient.error_string (Python), 496
pmix event notification cbfunc fn t, 141, 147, 147
```

```
PMIx_Fabric_deregister, 274, 275, 494, 533
    PMIxClient.fabric deregister (Python), 494
PMIx Fabric deregister nb, 275, 533
PMIx Fabric register, 263, 271, 273, 493, 533
    PMIxClient.fabric register (Python), 493
PMIx Fabric register nb, 272, 533
PMIx Fabric update, 272, 273, 274, 494, 533
    PMIxClient.fabric update (Python), 493
PMIx Fabric update nb, 274, 533
PMIx_Fence, 4, 66, 67, 68, 70, 111, 179, 182, 227, 236, 240, 255, 288, 318, 345, 347, 465, 481,
         524, 537
    PMIxClient.fence (Python), 480
PMIx Fence nb, 52, 68, 345, 347, 465, 524, 532
PMIx_Finalize, 24, 62, 64, 64, 176, 342, 343, 433, 434, 464, 478, 524
    PMIxClient.finalize (Python), 478
PMIx_generate_ppn, 291, 504, 524, 530
    PMIxServer.generate_ppn (Python), 504
PMIx_generate_regex, 289, 291, 303, 504, 524, 530
    PMIxServer.generate regex (Python), 503
PMIx Get, 3, 8, 27, 62, 67, 70, 71, 72, 73, 75–77, 80, 81, 84–86, 89, 94, 95, 97–100, 102–104,
         106, 107, 111, 115, 160–162, 166, 167, 170–172, 186, 188, 189, 202, 211, 217, 224, 226,
         228, 232, 236, 255, 257, 267, 268, 270, 295, 299, 303, 333, 359, 361, 409, 418–420, 434,
         452, 481, 524, 526, 531, 537, 538, 544, 545, 554
    PMIxClient.get (Python), 481
PMIx Get attribute name, 56, 501, 533
    PMIxClient.get attribute name (Python), 501
PMIx_Get_attribute_string, 56, 501, 533
    PMIxClient.get attribute string (Python), 500
PMIx_Get_cpuset, 189, 495, 533
    PMIxClient.get_cpuset (Python), 495
PMIx_Get_credential, 277, 279, 389, 488, 527, 532
    PMIxClient.get_credential (Python), 488
PMIx Get credential nb, 278
PMIx_Get_nb, 52, 73, 524
PMIx_Get_relative_locality, 186, 188, 299, 334, 495, 533, 553
    PMIxClient.get relative locality (Python), 495
PMIx Get version, 10, 59, 478, 524
    PMIxClient.get version (Python), 478
PMIx Group construct, 227, 228, 233, 235, 236, 239, 489, 533
    PMIxClient.group construct (Python), 489
PMIx Group construct nb, 236, 239, 533
PMIx Group destruct, 230, 239, 240, 242, 252, 491, 533
    PMIxClient.group destruct (Python), 491
```

```
PMIx_Group_destruct_nb, 240, 242, 533
PMIx Group invite, 229, 242, 244, 245, 247, 490, 533
    PMIxClient.group invite (Python), 489
PMIx Group invite nb, 245, 533
PMIx Group join, 229, 244, 247, 247–249, 251, 490, 533
    PMIxClient.group_join (Python), 490
PMIx Group join nb, 247, 249, 251, 533
PMIx Group leave, 230, 251, 252, 253, 491, 533
    PMIxClient.group leave (Python), 491
PMIx_Group_leave_nb, 252, 533
pmix_hdlr_reg_cbfunc_t, 53, 136, 445, 446, 550
pmix_info_cbfunc_t, 51, 53, 53, 84, 191, 200, 208, 210, 215, 216, 237, 245, 250, 331, 372, 380,
         382, 383, 385, 386, 399, 402
PMIx_Info_directives_string, 55, 499, 525
    PMIxClient.info_directives_string (Python), 498
PMIx_Init, 7, 58, 59, 62, 81, 86, 103, 341, 413, 417, 427, 428, 435, 477, 525, 531, 554
    PMIxClient.init (Python), 477
PMIx_Initialized, <u>58</u>, 477, 524
    PMIxClient.initialized (Python), 477
pmix iof cbfunc t, 396, 444, 462
    iofebfune (Python), 462
PMIx IOF channel string, 56, 500, 527
    PMIxClient.iof channel string (Python), 500
PMIx IOF deregister, 446, 517, 527, 532
    PMIxTool.iof_deregister (Python), 517
PMIx_IOF_pull, 360, 376, 411, 412, 416, 419, 420, 422, 444, 446, 517, 527, 532
    PMIxTool.iof_pull (Python), 516
PMIx_IOF_push, 360, 376, 411, 416, 419, 422–424, 426, 447, 449, 518, 527, 532, 543
    PMIxTool.iof_push (Python), 517
PMIx_Job_control, 196, 205, 206, 209–211, 384, 429, 487, 527, 532
    PMIxClient.job_ctrl (Python), 487
PMIx_Job_control_nb, 77, 204, 207, 301, 525
PMIx_Job_state_string, 56, 500, 533
    PMIxClient.job_state_string (Python), 500
PMIx_Link_state_string, 56, 501, 533
    PMIxClient.link_state_string (Python), 501
PMIx Load topology, 185, 494, 533, 553
    PMIxClient.load topology (Python), 494
PMIx Log, 173, 218, 220, 224, 413, 432, 486, 527, 550
    PMIxClient.log (Python), 486
PMIx Log nb, 221, 224, 525
PMIx Lookup, 117, 122, 123, 125, 481, 482, 524
    PMIxClient.lookup (Python), 482
```

```
pmix_lookup_cbfunc_t, 128, 128, 353
PMIx Lookup nb, 123, 128, 129, 524
pmix modex cbfunc t, 51, 345, 348, 348, 349
pmix notification fn t, 136, 141, 141, 463
    evhandler (Python), 462
PMIx Notify event, 143, 370, 493, 525, 532
    PMIxClient.notify event (Python), 492
pmix op cbfunc t, 52, 52, 119, 131, 143, 144, 147, 180, 183, 221, 241, 252, 273–275, 292,
         312–316, 323, 329, 330, 332, 340–342, 344, 351, 355, 362, 364, 366, 368, 369, 378, 394,
         397, 447
PMIx_Parse_cpuset_string, 188, 334, 496, 533
    PMIxClient.parse_cpuset_string (Python), 495
PMIx Persistence string, 55, 498, 525
    PMIxClient.persistence_string (Python), 498
PMIx_Proc_state_string, 54, 497, 525
    PMIxClient.proc_state_string (Python), 497
PMIx_Process_monitor, 196, 212, 216, 488, 527, 532
    PMIxClient.monitor (Python), 487
PMIx Process monitor nb, 214, 217, 525
PMIx_Progress, 61, 64, 287, 289, 439, 502, 533, 542
    PMIxClient.progress (Python), 502
PMIx_Publish, 117, 119-122, 352, 482, 524
    PMIxClient.publish (Python), 481
PMIx Publish nb, 119, 122, 524
PMIx Put, 27, 66–70, 94, 97, 112, 112–115, 177, 236, 244, 318, 319, 346, 350, 480, 524
    PMIxClient.put (Python), 479
PMIx_Query_info, 8, 79, 84, 88, 89, 91, 94, 226, 228, 267, 268, 403, 407, 427, 428, 452, 486, 538
    PMIxClient.query (Python), 485
PMIx_Query_info_nb, 77, 84, 84, 95, 176, 303, 324, 525, 526
PMIx_Register_attributes, 324, 510, 532, 533
    PMIxServer.register_attributes (Python), 509
PMIx_Register_event_handler, 77, 135, 172, 413, 433, 492, 525, 532, 549
    PMIxClient.register_event_handler (Python), 491
pmix_release_cbfunc_t, 51, 51
PMIx_Resolve_nodes, 78, 485, 524
    PMIxClient.resolve nodes (Python), 485
PMIx Resolve peers, 78, 105, 298, 485, 524
    PMIxClient.resolve peers (Python), 484
PMIx Scope string, 54, 497, 525
    PMIxClient.scope string (Python), 497
pmix server abort fn t, 343, 465
    clientaborted (Python), 464
pmix server alloc fn t, 379, 472
```

```
allocate (Python), 472
pmix server client connected 2 fn t, 52, 276, 315, 316, 339, 340, 340–342, 464, 533, 550, 551
    clientconnected2 (Python), 463
pmix server client finalized fn t, 342, 343, 464
    clientfinalized (Python), 464
PMIx_server_collect_inventory, 331, 333, 511, 527
    PMIxServer.collect inventory (Python), 511
pmix server connect fn t, 177, 362, 363, 365, 468
    connect (Python), 468
PMIx_server_define_process_set, 226, 336, 512, 533
    PMIxServer.define_process_set (Python), 512
PMIx_server_delete_process_set, 226, 337, 513, 533
    PMIxServer.delete_process_set (Python), 512
PMIx_server_deliver_inventory, 332, 512, 527
    PMIxServer.deliver_inventory (Python), 511
PMIx_server_deregister_client, 316, 508, 524
    PMIxServer.deregister_client (Python), 508
pmix_server_deregister_events_fn_t, 367, 470
    deregister_events (Python), 470
PMIx_server_deregister_nspace, <u>312</u>, 316, 506, 524
    PMIxServer.deregister_nspace (Python), 506
PMIx server deregister resources, 313, 507, 513, 534
    PMIxServer.deregister resources (Python), 507, 513
pmix server disconnect fn t, 363, 365, 469
    disconnect (Python), 469
pmix_server_dmodex_req_fn_t, 106, 115, 116, 348, 348, 466, 527, 529
    dmodex (Python), 466
PMIx_server_dmodex_request, 317, 318, 319, 509, 524
    PMIxServer.dmodex_request (Python), 508
pmix_server_fabric_fn_t, 263, 270, 401, 476, 533
    fabric (Python), 476
pmix_server_fencenb_fn_t, 345, 347, 348, 465, 529
    fence (Python), 465
PMIx_server_finalize, 288, 503, 524
    PMIxServer.finalize (Python), 503
PMIx_server_generate_cpuset_string, 189, 334, 505, 534
    PMIxServer.generate cpuset string (Python), 505
PMIx server generate locality string, 185, 186, 333, 505, 533
    PMIxServer.generate locality string (Python), 504
pmix_server_get_cred_fn_t, <u>388</u>, 392, 474
    get_credential (Python), 473
pmix server grp fn t, 398, 476, 533
    group (Python), 475
```

```
PMIx_server_init, 58, 284, 288, 324, 338, 404, 405, 409, 503, 524, 533
    PMIxServer.init (Python), 502
PMIx server IOF deliver, 330, 421, 511, 527
    PMIxServer.iof deliver (Python), 510
pmix server iof fn t, 393, 475
    iof_pull (Python), 474
pmix server job control fn t, 382, 473
    job control (Python), 472
pmix server listener fn t, 370
pmix_server_log_fn_t, 377, 472
    log (Python), 471
pmix_server_lookup_fn_t, 352, 467
    lookup (Python), 467
pmix_server_module_t, 285, 287, 324, 325, 338, 338, 339, 503
pmix_server_monitor_fn_t, 385, 473
    monitor (Python), 473
pmix_server_notify_event_fn_t, 142, 146, 369, 370, 470
    notify_event (Python), 470
pmix_server_publish_fn_t, 350, 466
    publish (Python), 466
pmix_server_query_fn_t, 372, 471
    query (Python), 470
PMIx server register client, 276, 314, 316, 341, 343, 507, 524
    PMIxServer.register client (Python), 507
pmix_server_register_events_fn_t, 365, 469
    register events (Python), 469
PMIx_server_register_nspace, 10, 52, 290, 291, 292, 293, 302, 303, 306, 313, 330, 334, 506, 524,
         526, 540
    PMIxServer.register_nspace (Python), 505
PMIx_server_register_resources, 294, 297, 298, 312, 507, 513, 534
    PMIxServer.register_resources (Python), 506, 513
PMIx_server_setup_application, 319, 323, 329, 333, 509, 525, 529
    PMIxServer.setup_application (Python), 509
PMIx_server_setup_fork, 317, 508, 524
    PMIxServer.setup_fork (Python), 508
PMIx_server_setup_local_support, 328, 510, 525
    PMIxServer.setup local support (Python), 510
pmix_server_spawn_fn_t, 176, 357, 414, 468
    spawn (Python), 468
pmix_server_stdin_fn_t, 397, 475
    iof push (Python), 475
pmix server tool connection fn t, 276, 374, 404, 471
    tool connected (Python), 471
```

```
pmix_server_unpublish_fn_t, 355, 467
    unpublish (Python), 467
pmix server validate cred fn t, 390, 474
    validate credential (Python), 474
pmix setup application cbfunc t, 320, 323
PMIx Spawn, 101, 103, 104, 158, 159, 164, 169, 170, 173, 199, 202, 299, 301, 317, 357, 358, 360,
         361, 381, 409, 411, 414, 415, 418–420, 426–431, 434, 435, 468, 483, 524, 530, 541
    PMIxClient.spawn (Python), 483
pmix spawn cbfunc t, 164, 176, 176, 357
PMIx_Spawn_nb, 164, 173, 176, 524
PMIx_Store_internal, 112, 113, 479, 524
    PMIxClient.store_internal (Python), 479
PMIx tool attach to server, 406, 409, 418, 439, 441, 515, 534, 550
    PMIxTool.attach_to_server (Python), 515
PMIx_tool_connect_to_server, 527, 552
pmix_tool_connection_cbfunc_t, 375, 376, 377
PMIx_tool_disconnect, 440, 515, 534
    PMIxTool.disconnect (Python), 514
PMIx tool finalize, 439, 514, 525
    PMIxTool.finalize (Python), 514
PMIx_tool_get_servers, <u>442</u>, 516, 534
    PMIxTool.get servers (Python), 515
PMIx tool init, 58, 403, 406, 408–410, 417–419, 421, 436, 439, 514, 525
    PMIxTool.init (Python), 514
PMIx tool set server, 405, 418, 419, 442, 443, 516, 534
    PMIxTool.set server (Python), 516
PMIx_Unpublish, 130, 131, 132, 483, 524
    PMIxClient.unpublish (Python), 482
PMIx_Unpublish_nb, 131, 524
PMIx_Validate_credential, 280, 489, 527, 532
    PMIxClient.validate_credential (Python), 488
PMIx_Validate_credential_nb, 281
pmix_validation_cbfunc_t, 282, 391, 392
pmix_value_cbfunc_t, 52, 52
pmix_evhdlr_reg_cbfunc_t
    (Deprecated), 550
pmix_server_client_connected_fn_t
    (Deprecated), 339, 550
PMIx_tool_connect_to_server
    (Deprecated), 550
```

### **Index of Support Macros**

```
PMIX APP CONSTRUCT, 174
PMIX APP CREATE, 175
PMIX APP DESTRUCT, 174
PMIX APP FREE, 175
PMIX APP INFO CREATE, 175, 527, 529
PMIX APP RELEASE, 175
PMIX ARGV APPEND, 45
PMIX ARGV APPEND UNIQUE, 46
PMIX ARGV COPY, 48
PMIX_ARGV_COUNT, 48
PMIX_ARGV_FREE, 46
PMIX_ARGV_JOIN, 47
PMIX_ARGV_PREPEND, 45
PMIX_ARGV_SPLIT, 47
PMIX_BYTE_OBJECT_CONSTRUCT, 42
PMIX_BYTE_OBJECT_CREATE, 42
PMIX BYTE OBJECT DESTRUCT, 42
PMIX_BYTE_OBJECT_FREE, 43
PMIX BYTE OBJECT LOAD, 43
PMIX CHECK KEY, 17
PMIX CHECK NSPACE, 18
PMIX CHECK PROCID, 22
PMIX CHECK RANK, 20
PMIX CHECK RESERVED KEY, 17, 550
PMIX COORD CONSTRUCT, 260
PMIX COORD CREATE, 260
PMIX_COORD_DESTRUCT, 260
PMIX_COORD_FREE, 260
PMIX_CPUSET_CONSTRUCT, 335
PMIX CPUSET CREATE, 335
PMIX_CPUSET_DESTRUCT, 335
PMIX_CPUSET_FREE, 336
PMIX_DATA_ARRAY_CONSTRUCT, 44
PMIX DATA ARRAY CREATE, 44
PMIX DATA ARRAY DESTRUCT, 44
PMIX DATA ARRAY FREE, 44
PMIX DATA BUFFER CONSTRUCT, 149, 151, 153
PMIX DATA BUFFER CREATE, 149, 151, 153
```

```
PMIX_DATA_BUFFER_DESTRUCT, 149
PMIX DATA BUFFER LOAD, 150
PMIX DATA BUFFER RELEASE, 149
PMIX DATA BUFFER UNLOAD, 150, 290
PMIX DEVICE DIST CONSTRUCT, 194
PMIX_DEVICE_DIST_CREATE, 194
PMIX DEVICE DIST DESTRUCT, 194
PMIX DEVICE DIST FREE, 195
PMIX ENDPOINT CONSTRUCT, 258
PMIX_ENDPOINT_CREATE, 258
PMIX_ENDPOINT_DESTRUCT, 258
PMIX_ENDPOINT_FREE, 259
PMIX ENVAR CONSTRUCT, 40
PMIX_ENVAR_CREATE, 41
PMIX_ENVAR_DESTRUCT, 13, 40
PMIX_ENVAR_FREE, 41
PMIX_ENVAR_LOAD, 41
PMIX FABRIC CONSTRUCT, 267
PMIX GEOMETRY CONSTRUCT, 261
PMIX GEOMETRY CREATE, 262
PMIX GEOMETRY DESTRUCT, 262
PMIX GEOMETRY FREE, 262
PMIx Heartbeat, 216, 525
PMIX INFO CONSTRUCT, 32
PMIX INFO CREATE, 32, 37, 39
PMIX INFO DESTRUCT, 32
PMIX_INFO_FREE, 33
PMIX INFO IS END, 39, 527, 529
PMIX_INFO_IS_OPTIONAL, 39
PMIX_INFO_IS_REQUIRED, 37, 38, 38
PMIX_INFO_LIST_ADD, 35, 550
PMIX_INFO_LIST_CONVERT, 36, 550
PMIX INFO LIST RELEASE, 36, 550
PMIX_INFO_LIST_START, 35, 35, 36, 550
PMIX_INFO_LIST_XFER, 36, 550
PMIX_INFO_LOAD, 33
PMIX INFO OPTIONAL, 38
PMIX INFO PROCESSED, 39, 550
PMIX INFO REQUIRED, 37, 38
PMIX_INFO_TRUE, 34
PMIX INFO WAS PROCESSED, 39, 550
PMIX INFO XFER, 34, 303
PMIX LOAD KEY, 17
```

```
PMIX_LOAD_NSPACE, 19
PMIX LOAD PROCID, 22, 22
PMIX MULTICLUSTER NSPACE CONSTRUCT, 23
PMIX MULTICLUSTER NSPACE PARSE, 23
PMIX PDATA CONSTRUCT, 126
PMIX_PDATA_CREATE, 126
PMIX PDATA DESTRUCT, 126
PMIX PDATA FREE, 127
PMIX PDATA LOAD, 127
PMIX_PDATA_RELEASE, 126
PMIX_PDATA_XFER, 128
PMIX_PROC_CONSTRUCT, 20
PMIX PROC CREATE, 21
PMIX_PROC_DESTRUCT, 21
PMIX_PROC_FREE, 21, 78
PMIX_PROC_INFO_CONSTRUCT, 25
PMIX_PROC_INFO_CREATE, 26
PMIX PROC INFO DESTRUCT, 25
PMIX PROC INFO FREE, 26
PMIX PROC INFO RELEASE, 26
PMIX PROC LOAD, 22
PMIX PROC RELEASE, 21
PMIX QUERY CONSTRUCT, 92
PMIX QUERY CREATE, 93
PMIX QUERY DESTRUCT, 92
PMIX QUERY FREE, 93
PMIX_QUERY_QUALIFIERS_CREATE, 93, 527, 529
PMIX OUERY RELEASE, 93
PMIX_REGATTR_CONSTRUCT, 326
PMIX REGATTR CREATE, 327
PMIX_REGATTR_DESTRUCT, 327
PMIX_REGATTR_FREE, 327
PMIX_REGATTR_LOAD, 328
PMIX REGATTR XFER, 328
PMIX_SETENV, 48
PMIX SYSTEM EVENT, 139
PMIX TOPOLOGY CONSTRUCT, 187
PMIX TOPOLOGY CREATE, 187
PMIX TOPOLOGY DESTRUCT, 187
PMIX_TOPOLOGY_FREE, 187
PMIX VALUE CONSTRUCT, 28
PMIX VALUE CREATE, 29
PMIX VALUE DESTRUCT, 28, 72, 76, 537
```

PMIX\_VALUE\_FREE, 29 PMIX\_VALUE\_GET\_NUMBER, 31 PMIX\_VALUE\_LOAD, 29 PMIX\_VALUE\_RELEASE, 29 PMIX\_VALUE\_UNLOAD, 30 PMIX\_VALUE\_XFER, 31

### **Index of Data Structures**

```
pmix alloc directive t, 50, 55, 197, 200, 204, 204, 380, 458, 499
pmix app t, 45, 46, 49, 159, 161, 164–166, 171, 173, 173–175, 357, 358, 360, 411, 413–415, 417,
         418, 427, 430, 435, 459, 527, 529, 549
pmix bind envelope t, 189, 189, 460, 534
pmix byte object t, 42, 42, 43, 50, 277, 278, 280, 282, 330, 390, 391, 397, 447, 457
pmix coord t, 50, 259, 259–261, 460, 534
pmix coord view t, 262, 460, 534
pmix cpuset t, 50, 190, 191, 333, 334, 335, 335, 336, 459, 534
pmix data array t, 27, 36, 43, 43, 44, 50, 82, 83, 87, 89, 90, 95, 105, 198, 201, 203, 228, 231, 265,
         267–271, 293, 294, 296–298, 306, 308, 309, 321, 373, 382, 402, 428, 436, 458, 527, 529,
         545-548
pmix_data_buffer_t, 148, 148–152, 155, 156
pmix_data_range_t, 50, 55, 121, 121, 144, 369, 457, 498
pmix_data_type_t, 30, 31, 33, 35, 44, 49, 49, 50, 55, 127, 151, 153–155, 328, 456, 499
pmix_device_distance_t, 50, 190, 192, 193, 193–195, 300, 460, 534, 547
pmix_device_type_t, 51, 57, 192, 192, 193, 270, 460, 502, 534
pmix endpoint t, 51, 257, 257–259, 270, 459, 545
pmix_envar_t, 13, 40, 40, 41, 50, 458
pmix fabric operation t, 263, 263, 401
pmix fabric t, 257, 263, 264, 264, 267, 268, 271–275, 402, 459, 534, 544
pmix geometry t, 50, 256, 261, 261, 262, 269, 460, 534, 545, 546
pmix_group_operation_t, 399, 401, 401, 534
pmix group opt t, 247, 250, 251, 251, 490, 534
pmix info directives t, 37, 37, 50, 55, 458, 498
pmix info t, 4, 5, 8, 17, 32, 32–39, 50, 53, 59, 62, 64, 79, 83, 89, 91–93, 95, 118, 120–123, 141,
         144, 147, 175, 190, 191, 197, 198, 200, 201, 203–205, 207, 210, 211, 213, 216, 220, 223,
         225, 233, 235, 237, 239, 241–243, 245, 247, 250–252, 264, 265, 268–270, 277, 278, 280,
         282, 285, 287, 292–294, 296, 297, 302, 303, 306, 308, 309, 320, 321, 326, 328, 330–332,
         337, 340, 360, 369, 375, 376, 379, 381, 382, 385, 386, 393, 394, 396, 402, 411, 413–415,
         417, 420, 427, 435, 437, 441, 443, 444, 446, 447, 458, 461, 525, 527, 529, 538–541,
         544-546
pmix_iof_channel_t, 50, 56, 330, 394, 396, 424, 424, 444, 458, 500
pmix_job_state_t, 26, 26, 50, 56, 459, 500, 534
pmix key t, 8, 16, 16, 71, 112, 328, 456
pmix link state t, 50, 56, 257, 263, 263, 266, 269, 459, 501, 534, 546
pmix locality t, 51, 186, 188, 188, 459, 534, 552, 553
pmix_nspace_t, 18, 18, 19, 22, 23, 176, 456, 457
pmix pdata t, 122, 123, 125, 125–129, 458
```

```
pmix_persistence_t, 50, 55, 121, 121, 457, 498
pmix proc info t, 24, 24–26, 50, 81, 82, 86, 87, 89, 90, 373, 428, 436, 457
pmix proc state t, 23, 23, 50, 54, 457, 497
pmix proc t, 19, 20, 20–22, 50, 62, 66, 68, 69, 73, 90, 105, 127, 137, 138, 140, 141, 144, 145, 151,
          152, 157, 158, 228, 231–233, 237, 242, 245, 248, 298, 315–318, 328, 330, 336, 340–342,
         344, 345, 349, 351, 353, 355, 357, 362, 364, 369, 372, 377, 378, 380, 383, 386, 388, 391,
         394, 396, 397, 399–401, 437, 439–443, 457, 547, 548
pmix query t, 50, 81, 86, 89, 91, 91–94, 372, 374, 459, 527, 529, 538
pmix rank t, 19, 19, 20, 22, 50, 457
pmix_regattr_t, 50, 95, 324, 325, 325–328, 459, 532, 534, 540
pmix_scope_t, 50, 54, 113, 113, 457, 497
pmix_status_t, 14, 14, 30, 31, 35, 36, 45, 46, 48, 50, 53, 54, 136, 139, 141, 144, 147, 192, 319, 323,
          366, 368, 369, 377, 390, 393, 456, 470, 496
pmix_storage_access_type_t, 452, 452, 554
pmix_storage_accessibility_t, 451, 451, 554
pmix_storage_medium_t, 450, 450, 451, 554
pmix_storage_persistence_t, 451, 451, 554
pmix_topology_t, 51, 185, 186, 186, 187, 190, 191, 534
pmix_value_t, 8, 27, 27–31, 50, 52, 72, 73, 76, 112, 458, 537
```

### **Index of Constants**

```
PMIX ALLOC DIRECTIVE, 50
PMIX ALLOC EXTEND, 204
PMIX ALLOC EXTERNAL, 204
PMIX ALLOC NEW, 204
PMIX ALLOC REAQUIRE, 204
PMIX ALLOC RELEASE, 204
PMIX APP, 50
PMIX APP WILDCARD, 13
PMIX BOOL, 49
PMIX BUFFER, 50
PMIX_BYTE, 49
PMIX_BYTE_OBJECT, 50
PMIX_COMMAND, 50
PMIX_COMPRESSED_BYTE_OBJECT, 50
PMIX_COMPRESSED_STRING, 50
PMIX_COORD, 50
PMIX COORD LOGICAL VIEW, 263
PMIX_COORD_PHYSICAL_VIEW, 263
PMIX COORD VIEW UNDEF, 263
PMIX CPUBIND PROCESS, 189
PMIX CPUBIND THREAD, 189
PMIX DATA ARRAY, 50
PMIX DATA RANGE, 50
PMIX DATA TYPE, 50
PMIX DATA TYPE MAX, 51
PMIX DEBUG WAITING FOR NOTIFY, 434
PMIX_DEBUGGER_RELEASE, 434
PMIX_DEVICE_DIST, 50
PMIX DEVTYPE, 51
PMIX DEVTYPE BLOCK, 193
PMIX_DEVTYPE_COPROC, 193
PMIX_DEVTYPE_DMA, 193
PMIX_DEVTYPE_GPU, 193
PMIX DEVTYPE NETWORK, 193
PMIX DEVTYPE OPENFABRICS, 193
PMIX DEVTYPE UNKNOWN, 193
PMIX DOUBLE, 49
PMIX ENDPOINT, 51
```

```
PMIX_ENVAR, 50
PMIX ERR BAD PARAM, 15
PMIX ERR COMM FAILURE, 15
PMIX ERR CONFLICTING CLEANUP DIRECTIVES, 210
PMIX ERR DUPLICATE KEY, 120
PMIX_ERR_EMPTY, 15
PMIX ERR EVENT REGISTRATION, 138
PMIX ERR EXISTS, 14
PMIX ERR EXISTS OUTSIDE SCOPE, 14
PMIX_ERR_INIT, 15
PMIX_ERR_INVALID_CRED, 14
PMIX_ERR_INVALID_OPERATION, 15
PMIX ERR IOF COMPLETE, 425
PMIX_ERR_IOF_FAILURE, 425
PMIX ERR JOB ABORTED, 433
PMIX_ERR_JOB_ABORTED_BY_SIG, 433
PMIX_ERR_JOB_ABORTED_BY_SYS_EVENT, 434
PMIX ERR JOB ALLOC FAILED, 169
PMIX ERR JOB APP NOT EXECUTABLE, 169
PMIX ERR JOB CANCELED, 433
PMIX ERR JOB FAILED TO LAUNCH, 169
PMIX ERR JOB FAILED TO MAP, 169
PMIX ERR JOB KILLED BY CMD, 433
PMIX ERR JOB NO EXE SPECIFIED, 169
PMIX ERR JOB NON ZERO TERM, 434
PMIX ERR JOB SENSOR BOUND EXCEEDED, 434
PMIX_ERR_JOB_TERM_WO_SYNC, 434
PMIX ERR LOST CONNECTION, 15
PMIX_ERR_NO_PERMISSIONS, 15
PMIX ERR NOMEM, 15
PMIX_ERR_NOT_FOUND, 15
PMIX_ERR_NOT_SUPPORTED, 15
PMIX_ERR_OUT_OF_RESOURCE, 15
PMIX ERR PACK FAILURE, 15
PMIX_ERR_PARAM_VALUE_NOT_SUPPORTED, 15
PMIX_ERR_PARTIAL_SUCCESS, 16
PMIX ERR PROC CHECKPOINT, 210
PMIX ERR PROC MIGRATE, 210
PMIX ERR PROC RESTART, 210
PMIX_ERR_PROC_TERM_WO_SYNC, 433
PMIX ERR REPEAT ATTR REGISTRATION, 325
PMIX ERR RESOURCE BUSY, 15
PMIX ERR TIMEOUT, 15
```

```
PMIX_ERR_TYPE_MISMATCH, 14
PMIX ERR UNKNOWN DATA TYPE, 14
PMIX ERR UNPACK FAILURE, 15
PMIX ERR UNPACK INADEQUATE SPACE, 14
PMIX ERR UNPACK READ PAST END OF BUFFER, 15
PMIX ERR UNREACH, 15
PMIX ERR WOULD BLOCK, 14
PMIX ERROR, 14
PMIX EVENT ACTION COMPLETE, 147
PMIX_EVENT_ACTION_DEFERRED, 147
PMIX_EVENT_JOB_END, 433
PMIX_EVENT_JOB_START, 433
PMIX EVENT NO ACTION TAKEN, 147
PMIX_EVENT_NODE_DOWN, 139
PMIX_EVENT_NODE_OFFLINE, 139
PMIX_EVENT_PARTIAL_ACTION_TAKEN, 147
PMIX_EVENT_PROC_TERMINATED, 433
PMIX EVENT SESSION END, 433
PMIX_EVENT_SESSION_START, 433
PMIX EVENT SYS BASE, 139
PMIX_EVENT_SYS_OTHER, 139
PMIX EXTERNAL ERR BASE, 16
PMIX FABRIC REQUEST INFO, 263
PMIX FABRIC UPDATE ENDPOINTS, 257
PMIX FABRIC UPDATE INFO, 263
PMIX FABRIC UPDATE PENDING, 257
PMIX_FABRIC_UPDATED, 257
PMIX FLOAT, 49
PMIX_FWD_ALL_CHANNELS, 424
PMIX FWD NO CHANNELS, 424
PMIX_FWD_STDDIAG_CHANNEL, 424
PMIX_FWD_STDERR_CHANNEL, 424
PMIX FWD STDIN CHANNEL, 424
PMIX FWD STDOUT CHANNEL, 424
PMIX GEOMETRY, 50
PMIX GLOBAL, 113
PMIX GROUP ACCEPT, 251
PMIX GROUP CONSTRUCT, 401
PMIX GROUP CONSTRUCT ABORT, 231
PMIX_GROUP_CONSTRUCT_COMPLETE, 231
PMIX GROUP CONTEXT ID ASSIGNED, 231
PMIX GROUP DECLINE, 251
PMIX GROUP DESTRUCT, 401
```

```
PMIX_GROUP_INVITE_ACCEPTED, 231
PMIX GROUP INVITE DECLINED, 231
PMIX GROUP INVITE FAILED, 231
PMIX GROUP INVITED, 230
PMIX GROUP LEADER FAILED, 231
PMIX_GROUP_LEADER_SELECTED, 231
PMIX GROUP LEFT, 230
PMIX GROUP MEMBER FAILED, 230
PMIX GROUP MEMBERSHIP UPDATE, 231
PMIX_INFO, 50
PMIX_INFO_ARRAY_END, 37
PMIX_INFO_DIR_RESERVED, 37
PMIX INFO DIRECTIVES, 50
PMIX_INFO_REQD, 37
PMIX_INFO_REQD_PROCESSED, 37
PMIX_INT, 49
PMIX_INT16, 49
PMIX INT32, 49
PMIX INT64, 49
PMIX INT8, 49
PMIX INTERNAL, 113
PMIX IOF CHANNEL, 50
PMIX JCTRL CHECKPOINT, 210
PMIX JCTRL CHECKPOINT COMPLETE, 210
PMIX JCTRL PREEMPT ALERT, 210
PMIX JOB STATE, 50
PMIX_JOB_STATE_AWAITING_ALLOC, 27
PMIX JOB STATE CONNECTED, 27
PMIX_JOB_STATE_LAUNCH_UNDERWAY, 27
PMIX_JOB_STATE_RUNNING, 27
PMIX_JOB_STATE_SUSPENDED, 27
PMIX_JOB_STATE_TERMINATED, 27
PMIX_JOB_STATE_TERMINATED_WITH_ERROR, 27
PMIX_JOB_STATE_UNDEF, 27
PMIX_JOB_STATE_UNTERMINATED, 27
PMIX KVAL, 50
PMIX LAUNCH COMPLETE, 433
PMIX LAUNCHER READY, 420
PMIX LINK DOWN, 263
PMIX_LINK_STATE, 50
PMIX LINK STATE UNKNOWN, 263
PMIX LINK UP, 263
PMIX LOCAL, 113
```

```
PMIX_LOCALITY_NONLOCAL, 188
PMIX LOCALITY SHARE CORE, 188
PMIX LOCALITY SHARE HWTHREAD, 188
PMIX LOCALITY SHARE L1CACHE, 188
PMIX LOCALITY SHARE L2CACHE, 188
PMIX_LOCALITY_SHARE_L3CACHE, 188
PMIX LOCALITY SHARE NODE, 188
PMIX LOCALITY SHARE NUMA, 188
PMIX LOCALITY SHARE PACKAGE, 188
PMIX_LOCALITY_UNKNOWN, 188
PMIX_LOCTYPE, 51
PMIX_MAX_KEYLEN, 13
PMIX MAX NSLEN, 13
PMIX_MODEL_DECLARED, 62
PMIX_MODEL_RESOURCES, 62
PMIX_MONITOR_FILE_ALERT, 217
PMIX_MONITOR_HEARTBEAT_ALERT, 217
PMIX OPENMP PARALLEL ENTERED, 62
PMIX OPENMP PARALLEL EXITED, 62
PMIX OPERATION IN PROGRESS, 15
PMIX_OPERATION_SUCCEEDED, 15
PMIX PDATA, 50
PMIX PERSIST, 50
PMIX PERSIST APP, 121
PMIX PERSIST FIRST READ, 121
PMIX PERSIST INDEF, 121
PMIX_PERSIST_INVALID, 121
PMIX PERSIST PROC, 121
PMIX_PERSIST_SESSION, 121
PMIX PID, 49
PMIX_POINTER, 50
PMIX_PROC, 50
PMIX PROC CPUSET, 50
PMIX PROC INFO, 50
PMIX PROC RANK, 50
PMIX_PROC_STATE, 50
PMIX PROC STATE ABORTED, 24
PMIX PROC STATE ABORTED BY SIG, 24
PMIX PROC STATE CALLED ABORT, 24
PMIX_PROC_STATE_CANNOT_RESTART, 24
PMIX PROC STATE COMM FAILED, 24
PMIX PROC STATE CONNECTED, 24
PMIX PROC STATE ERROR, 24
```

```
PMIX_PROC_STATE_FAILED_TO_LAUNCH, 24
PMIX PROC STATE FAILED TO START, 24
PMIX PROC STATE HEARTBEAT FAILED, 24
PMIX PROC STATE KILLED BY CMD, 24
PMIX PROC STATE LAUNCH UNDERWAY, 24
PMIX_PROC_STATE_MIGRATING, 24
PMIX PROC STATE PREPPED, 24
PMIX PROC STATE RESTART, 24
PMIX PROC STATE RUNNING, 24
PMIX_PROC_STATE_SENSOR_BOUND_EXCEEDED, 24
PMIX_PROC_STATE_TERM_NON_ZERO, 24
PMIX_PROC_STATE_TERM_WO_SYNC, 24
PMIX PROC STATE TERMINATE, 24
PMIX_PROC_STATE_TERMINATED, 24
PMIX_PROC_STATE_UNDEF, 24
PMIX_PROC_STATE_UNTERMINATED, 24
PMIX_PROCESS_SET_DEFINE, 227
PMIX_PROCESS_SET_DELETE, 227
PMIX QUERY, 50
PMIX QUERY PARTIAL SUCCESS, 88
PMIX_RANGE_CUSTOM, 121
PMIX RANGE GLOBAL, 121
PMIX RANGE INVALID, 121
PMIX RANGE LOCAL, 121
PMIX RANGE NAMESPACE, 121
PMIX RANGE PROC LOCAL, 121
PMIX_RANGE_RM, 121
PMIX RANGE SESSION, 121
PMIX_RANGE_UNDEF, 121
PMIX RANK INVALID, 19
PMIX_RANK_LOCAL_NODE, 19
PMIX_RANK_LOCAL_PEERS, 19
PMIX RANK UNDEF, 19
PMIX_RANK_VALID, 19
PMIX_RANK_WILDCARD, 19
PMIX REGATTR, 50
PMIX REGEX, 50
PMIX REMOTE, 113
PMIX SCOPE, 50
PMIX SCOPE UNDEF, 113
PMIX SIZE, 49
PMIX STATUS, 50
PMIX STORAGE ACCESS RD, 452
```

```
PMIX_STORAGE_ACCESS_RDWR, 452
PMIX STORAGE ACCESS WR, 452
PMIX STORAGE ACCESSIBILITY CLUSTER, 451
PMIX STORAGE ACCESSIBILITY JOB, 451
PMIX STORAGE ACCESSIBILITY NODE, 451
PMIX_STORAGE_ACCESSIBILITY_RACK, 451
PMIX STORAGE ACCESSIBILITY REMOTE, 451
PMIX STORAGE ACCESSIBILITY SESSION, 451
PMIX STORAGE MEDIUM HDD, 450
PMIX_STORAGE_MEDIUM_NVME, 450
PMIX_STORAGE_MEDIUM_PMEM, 450
PMIX_STORAGE_MEDIUM_RAM, 450
PMIX STORAGE MEDIUM SSD, 450
PMIX_STORAGE_MEDIUM_TAPE, 450
PMIX STORAGE MEDIUM UNKNOWN, 450
PMIX_STORAGE_PERSISTENCE_ARCHIVE, 452
PMIX_STORAGE_PERSISTENCE_JOB, 451
PMIX STORAGE PERSISTENCE NODE, 451
PMIX STORAGE PERSISTENCE PROJECT, 451
PMIX STORAGE PERSISTENCE SCRATCH, 451
PMIX STORAGE PERSISTENCE SESSION, 451
PMIX STORAGE PERSISTENCE TEMPORARY, 451
PMIX STRING, 49
PMIX SUCCESS, 14
PMIX TIME, 50
PMIX TIMEVAL, 50
PMIX_TOPO, 51
PMIX UINT, 49
PMIX_UINT16, 49
PMIX UINT32, 49
PMIX_UINT64, 49
PMIX_UINT8, 49
PMIX UNDEF, 49
PMIX_VALUE, 50
PMIX_CONNECT_REQUESTED
   Deprecated, 551
PMIX_ERR_DATA_VALUE_NOT_FOUND
   Deprecated, 530
   Removed, 552
PMIX ERR DEBUGGER RELEASE
   Deprecated, 551
PMIX_ERR_HANDSHAKE_FAILED
   Deprecated, 530
```

D
Removed, <u>551</u> PMIX_ERR_IN_ERRNO
Deprecated, 530
Removed, 551
PMIX_ERR_INVALID_ARG
Deprecated, 530
Removed, <u>552</u>
PMIX_ERR_INVALID_ARGS
Deprecated, 530
Removed, 551
PMIX_ERR_INVALID_KEY
Deprecated, 530
Removed, 552
PMIX_ERR_INVALID_KEY_LENGTH
Deprecated, <u>530</u>
Removed, <u>552</u>
PMIX_ERR_INVALID_KEYVALP
Deprecated, <u>530</u>
<b>Removed</b> , <u>551</u>
PMIX_ERR_INVALID_LENGTH
Deprecated, <u>530</u>
<b>Removed</b> , <u>551</u>
PMIX_ERR_INVALID_NAMESPACE
Deprecated, <u>530</u>
<b>Removed</b> , <u>552</u>
PMIX_ERR_INVALID_NUM_ARGS
Deprecated, <u>530</u>
Removed, <u>551</u>
PMIX_ERR_INVALID_NUM_PARSED
Deprecated, <u>530</u>
Removed, 551
PMIX_ERR_INVALID_SIZE
Deprecated, <u>530</u> Removed, <u>551</u>
PMIX_ERR_INVALID_TERMINATION
Deprecated, 551
PMIX_ERR_INVALID_VAL
Deprecated, 530
Removed, <u>552</u>
PMIX_ERR_INVALID_VAL_LENGTH
Deprecated, 530
Removed, 551
PMIX FRR IOR TERMINATED

```
Deprecated, 551
PMIX ERR LOST CONNECTION TO CLIENT
   Deprecated, 551
PMIX ERR LOST CONNECTION TO SERVER
   Deprecated, 551
PMIX_ERR_LOST_PEER_CONNECTION
   Deprecated, 551
PMIX ERR NODE DOWN
   Deprecated, 551
PMIX_ERR_NODE_OFFLINE
   Deprecated, 551
PMIX_ERR_NOT_IMPLEMENTED
   Deprecated, 530
   Removed, 552
PMIX_ERR_PACK_MISMATCH
   Deprecated, 530
   Removed, 552
PMIX_ERR_PROC_ABORTED
   Deprecated, 551
PMIX_ERR_PROC_ABORTING
   Deprecated, 551
PMIX ERR PROC ENTRY NOT FOUND
   Deprecated, 530
   Removed, 551
PMIX_ERR_PROC_REQUESTED_ABORT
   Deprecated, 530
   Removed, 551
PMIX_ERR_READY_FOR_HANDSHAKE
   Deprecated, 530
   Removed, 551
PMIX_ERR_SERVER_FAILED_REQUEST
   Deprecated, 530
   Removed, 551
PMIX_ERR_SERVER_NOT_AVAIL
   Deprecated, 530
   Removed, 552
PMIX ERR SILENT
   Deprecated, 530
   Removed, 552
PMIX_ERR_SYS_OTHER
   Deprecated, 551
PMIX EXISTS
   Deprecated, 551
```

PMIX\_GDS\_ACTION\_COMPLETE Deprecated, 530 **Removed**, <u>552</u> PMIX\_INFO\_ARRAY Deprecated, <u>525</u> PMIX\_MODEX Deprecated, <u>525</u> PMIX\_NOTIFY\_ALLOC\_COMPLETE Deprecated, <u>530</u> **Removed**, <u>552</u> PMIX\_PROC\_HAS\_CONNECTED Deprecated, <u>551</u> PMIX\_PROC\_TERMINATED Deprecated, <u>551</u>

## **Index of Environmental Variables**

PMIX\_KEEPALIVE\_PIPE, <u>409</u>, 418, 419, 550 PMIX\_LAUNCHER\_RNDZ\_FILE, 405, <u>409</u>, 550 PMIX\_LAUNCHER\_RNDZ\_URI, <u>409</u>, 418, 419, 550

### **Index of Attributes**

```
PMIX ACCESS GRPIDS, 121, 541
PMIX ACCESS PERMISSIONS, 118, 120, 120, 541
PMIX ACCESS USERIDS, 121, 541
PMIX ADD ENVAR, 162, 167, 173
PMIX ADD HOST, 160, 165, 170, 359
PMIX ADD HOSTFILE, 160, 165, 170, 359
PMIX ALL CLONES PARTICIPATE, 67, 70, 70, 178, 181, 182, 184, 537
PMIX ALLOC BANDWIDTH, 163, 168, 198, 201, 203, 203, 321, 382
PMIX ALLOC CPU LIST, 162, 168, 198, 201, 203, 381
PMIX_ALLOC_FABRIC, 198, 201, 203, 320, 381, 552
PMIX_ALLOC_FABRIC_ENDPTS, 163, 168, 198, 199, 201, 202, 203, 203, 320, 321, 381, 552
PMIX ALLOC_FABRIC_ENDPTS_NODE, 163, 168, 199, 202, 203, 321, 552
PMIX_ALLOC_FABRIC_ID, 198, 201, 203, 203, 320, 381, 552
PMIX_ALLOC_FABRIC_PLANE, 163, 168, 198, 201, 202, 203, 203, 321, 382, 552
PMIX ALLOC FABRIC OOS, 163, 168, 198, 201, 202, 203, 203, 321, 382, 552
PMIX_ALLOC_FABRIC_SEC_KEY, 198, 199, 201, 202, 203, 203, 321, 382, 552
PMIX_ALLOC_FABRIC_TYPE, 163, 168, 198, 201, 202, 203, 203, 320, 321, 381, 382, 552
PMIX_ALLOC_ID, 199, 202, 381, 529, 530, 541
PMIX ALLOC MEM SIZE, 162, 168, 198, 201, 203, 381
PMIX ALLOC NODE LIST, 162, 168, 198, 201, 202, 381
PMIX ALLOC NUM CPU LIST, 162, 168, 198, 201, 203, 381
PMIX ALLOC NUM CPUS, 162, 168, 197, 201, 202, 381
PMIX ALLOC NUM NODES, 162, 168, 197, 200, 202, 381
PMIX ALLOC QUEUE, 82, 87, 89, 162, 168, 202, 373, 541
PMIX ALLOC REQ ID, 197, 200, 202, 529
PMIX ALLOC TIME, 162, 168, 197, 201, 203, 381
PMIX_ALLOCATED_NODELIST, 99, 294
PMIX_ANL_MAP, 100, 101, 295
PMIX APP ARGV, 102, 296, 541
PMIX APP INFO, 72, 75, 80, 85, 97, 102, 105, 296, 297
PMIX_APP_INFO_ARRAY, 293, 296, 302, 302, 308, 540
PMIX_APP_MAP_REGEX, 103, 296
PMIX_APP_MAP_TYPE, 103, 296
PMIX APP RANK, 103, 299
PMIX APP SIZE, 102, 296, 307
PMIX APPEND ENVAR, 162, 167, 173
PMIX APPLDR, 102, 296, 308
PMIX APPNUM, 72, 75, 80, 85, 98, 102, 103, 105, 293, 296–298, 302, 308, 540
```

```
PMIX_ATTR_UNDEF, 5
PMIX AVAIL PHYS MEMORY, 91, 105, 298
PMIX BINDTO, 160, 166, 170, 295, 359
PMIX CLEANUP EMPTY, 206, 209, 212
PMIX CLEANUP IGNORE, 206, 209, 212
PMIX_CLEANUP_LEAVE_TOPDIR, 206, 209, 212
PMIX CLEANUP RECURSIVE, 206, 209, 212
PMIX CLIENT ATTRIBUTES, 81, 86, 91, 95, 427, 532, 539
PMIX CLIENT AVG MEMORY, 83, 88, 91
PMIX_CLIENT_FUNCTIONS, 81, 86, 90, 91, 95, 538, 539
PMIX_CLUSTER_ID, 98, 294
PMIX_CMD_LINE, 101, 541
PMIX COLLECT DATA, 67, 69, 70, 111, 346
PMIX_COLLECT_GENERATED_JOB_INFO, 67, 69, 70, 70, 255, 346, 537
PMIX COLLECTIVE ALGO, 526
PMIX_CONNECT_MAX_RETRIES, 409, 438
PMIX_CONNECT_RETRY_DELAY, 410, 438
PMIX CONNECT SYSTEM FIRST, 407, 409, 437, 441
PMIX_CONNECT_TO_SYSTEM, 407, 409, 437, 441
PMIX COSPAWN APP, 163, 168, 435
PMIX CPU LIST, 161, 167, 171, 361
PMIX CPUS PER PROC, 161, 167, 171, 361
PMIX CPUSET, 104, 189, 300, 334
PMIX CPUSET BITMAP, 104, 300, 542
PMIX CRED TYPE, 279, 389
PMIX CREDENTIAL, 104, 375
PMIX_CRYPTO_KEY, 279, 296
PMIX DAEMON MEMORY, 83, 88, 91
PMIX_DATA_SCOPE, 72, 75, 77
PMIX DEBUG DAEMONS PER NODE, 360, 429, 430, 435, 436, 544
PMIX_DEBUG_DAEMONS_PER_PROC, 360, 429, 430, 435, 436, 543
PMIX_DEBUG_STOP_IN_INIT, 413, 417, 419, 427, 430, 435
PMIX DEBUG STOP ON EXEC, 413, 419, 426, 428, 434
PMIX_DEBUG_TARGET, 360, 428–430, 435, 435, 436, 543, 544, 552
PMIX_DEBUG_WAIT_FOR_NOTIFY, 414, 427, 434, 435
PMIX DEBUGGER DAEMONS, 360, 429, 430, 435
PMIX DEVICE DISTANCES, 195, 270, 300, 547
PMIX DEVICE ID, 195, 255, 256, 266, 269, 270, 314, 545–547
PMIX DEVICE TYPE, 195, 547
PMIX DISPLAY MAP, 160, 166, 170, 359
PMIX EMBED BARRIER, 64, 64
PMIX ENUM VALUE, 326, 326, 532, 540
PMIX EVENT ACTION TIMEOUT, 140, 145
```

```
PMIX_EVENT_AFFECTED_PROC, 138, 140, 145, 433
PMIX EVENT AFFECTED PROCS, 138, 140, 145, 433
PMIX EVENT BASE, 61, 287, 439
PMIX EVENT CUSTOM RANGE, 137, 140, 145
PMIX EVENT DO NOT CACHE, 140, 145
PMIX_EVENT_HDLR_AFTER, 137, 139
PMIX EVENT HDLR APPEND, 137, 140
PMIX EVENT HDLR BEFORE, 137, 139
PMIX EVENT HDLR FIRST, 137, 139
PMIX_EVENT_HDLR_FIRST_IN_CATEGORY, 137, 139
PMIX_EVENT_HDLR_LAST, 137, 139
PMIX_EVENT_HDLR_LAST_IN_CATEGORY, 137, 139
PMIX EVENT HDLR NAME, 137, 139
PMIX_EVENT_HDLR_PREPEND, 137, 139
PMIX_EVENT_NON_DEFAULT, 140, 145
PMIX_EVENT_PROXY, 140, 145
PMIX_EVENT_RETURN_OBJECT, 137, 140
PMIX EVENT SILENT TERMINATION, 163, 169, 173
PMIX EVENT TERMINATE JOB, 140, 145
PMIX EVENT TERMINATE NODE, 140, 145
PMIX EVENT TERMINATE PROC, 140, 145
PMIX EVENT TERMINATE SESSION, 140, 145
PMIX EVENT TEXT MESSAGE, 140, 145
PMIX EVENT TIMESTAMP, 140, 172, 173, 413, 414, 432, 433, 549, 550
PMIX_EXEC_AGENT, 417, 420, 431, 543
PMIX EXIT CODE, 103, 172, 173, 413, 414, 432, 550
PMIX_EXTERNAL_PROGRESS, 60, 287, 289, 439, 542
PMIX FABRIC COORDINATES, 268, 544
PMIX_FABRIC_COST_MATRIX, 265, 267, 544
PMIX FABRIC DEVICE, 255, 265, 268, 269, 546
PMIX_FABRIC_DEVICE_ADDRESS, 256, 266, 269, 546
PMIX_FABRIC_DEVICE_BUS_TYPE, 256, 266, 269, 546
PMIX FABRIC DEVICE COORDINATES, 256, 269, 546
PMIX FABRIC DEVICE DRIVER, 256, 266, 269, 546
PMIX_FABRIC_DEVICE_FIRMWARE, 256, 266, 269, 546
PMIX_FABRIC_DEVICE_INDEX, 256, 269, 402, 546
PMIX FABRIC DEVICE MTU, 257, 266, 269, 546
PMIX FABRIC DEVICE NAME, 255, 256, 265, 269, 314, 546
PMIX FABRIC DEVICE PCI DEVID, 256, 266, 269, 270, 547
PMIX_FABRIC_DEVICE_SPEED, 257, 266, 269, 546
PMIX FABRIC DEVICE STATE, 257, 266, 269, 546
PMIX FABRIC DEVICE TYPE, 257, 266, 269, 547
PMIX FABRIC DEVICE VENDOR, 256, 266, 269, 546
```

```
PMIX_FABRIC_DEVICE_VENDORID, 256, 269, 546
PMIX FABRIC DEVICES, 255, 268
PMIX FABRIC DIMS, 265, 268, 545
PMIX FABRIC ENDPT, 270, 545
PMIX FABRIC GROUPS, 265, 267, 544
PMIX FABRIC IDENTIFIER, 264, 268, 271, 402, 544
PMIX FABRIC INDEX, 263, 268, 268, 544
PMIX FABRIC NUM DEVICES, 264, 268, 544
PMIX FABRIC PLANE, 265, 267, 268, 271, 272, 402, 545
PMIX_FABRIC_SHAPE, 265, 268, 545
PMIX_FABRIC_SHAPE_STRING, 265, 268, 545
PMIX_FABRIC_SWITCH, 267, 270, 545
PMIX FABRIC VENDOR, 264, 268, 271, 402, 544
PMIX_FIRST_ENVAR, 162, 167, 173, 550
PMIX_FORKEXEC_AGENT, 417, 419, 420, 431, 543
PMIX_FWD_STDDIAG, 412, 416, 420, 529
PMIX_FWD_STDERR, 360, 376, 411, 416, 420, 421
PMIX FWD STDIN, 359, 376, 411, 415, 419, 421
PMIX FWD STDOUT, 360, 376, 411, 416, 419, 419, 421
PMIX GET POINTER VALUES, 72, 73, 75, 76, 537
PMIX_GET_REFRESH_CACHE, 72, 75, 76, 115, 537
PMIX GET STATIC VALUES, 71–73, 76, 76, 537
PMIX GLOBAL RANK, 103, 299
PMIX GROUP ASSIGN CONTEXT ID, 232, 234, 238, 243, 246, 400, 401, 548
PMIX GROUP CONTEXT ID, 232, 400, 548
PMIX GROUP ENDPT DATA, 232, 400, 549
PMIX_GROUP_FT_COLLECTIVE, 232, 234, 238, 243, 246, 548
PMIX GROUP ID, 231, 231, 400, 548
PMIX_GROUP_LEADER, 232, 234, 235, 238, 244, 249, 548
PMIX GROUP LOCAL ONLY, 232, 234, 238, 400, 548
PMIX_GROUP_MEMBERSHIP, 232, 235, 400
PMIX_GROUP_NAMES, 232, 549
PMIX GROUP NOTIFY TERMINATION, 232, 234, 235, 238, 240, 243, 246, 548
PMIX_GROUP_OPTIONAL, 232, 234, 235, 238, 243, 246, 400, 548
PMIX_GRPID, 81, 86, 118, 119, 122, 125, 130, 132, 197, 200, 205, 208, 213, 215, 219, 222, 277,
        279, 281, 282, 351, 352, 354, 356, 358, 367, 373, 375, 377, 378, 381, 384, 387, 389, 392,
        393, 395, 398
PMIX HOMOGENEOUS SYSTEM, 287, 289, 540
PMIX HOST, 159, 165, 170, 358
PMIX HOST ATTRIBUTES, 81, 86, 91, 95, 428, 532, 539
PMIX HOST FUNCTIONS, 81, 86, 90, 91, 95, 538, 539
PMIX HOSTFILE, 160, 165, 170, 358
PMIX HOSTNAME, 72, 75, 80, 82, 83, 85, 87, 88, 90, 91, 98, 105, 105, 255, 256, 266, 270, 293,
```

```
297–300, 302, 314, 373, 428, 436, 540, 547
PMIX HOSTNAME ALIASES, 105, 297, 542
PMIX HOSTNAME KEEP FQDN, 99, 295, 542
PMIX IMMEDIATE, 72, 74, 76, 106, 115
PMIX INDEX ARGV, 161, 166, 171, 360
PMIX IOF BUFFERING SIZE, 395, 412, 416, 425, 445, 448
PMIX IOF BUFFERING TIME, 395, 412, 416, 425, 445, 448
PMIX IOF CACHE SIZE, 395, 412, 416, 425, 445, 448
PMIX IOF COMPLETE, 396, 424, 425, 426, 449, 462, 543
PMIX_IOF_COPY, 422, 426, 543
PMIX_IOF_DROP_NEWEST, 395, 412, 416, 425, 445, 448
PMIX_IOF_DROP_OLDEST, 395, 412, 416, 425, 445, 448
PMIX IOF PUSH STDIN, 423, 425, 448, 543
PMIX_IOF_REDIRECT, 422, 426, 543
PMIX_IOF_TAG_OUTPUT, 412, 416, 422, 425, 445
PMIX_IOF_TIMESTAMP_OUTPUT, 412, 417, 423, 425, 445
PMIX_IOF_XML_OUTPUT, 412, 417, 423, 425, 446
PMIX JOB CONTINUOUS, 161, 167, 172, 361
PMIX JOB CTRL CANCEL, 206, 209, 211, 384
PMIX JOB CTRL CHECKPOINT, 206, 209, 211, 384
PMIX JOB CTRL CHECKPOINT EVENT, 206, 209, 211, 385
PMIX JOB CTRL CHECKPOINT METHOD, 207, 210, 211, 385
PMIX JOB CTRL CHECKPOINT SIGNAL, 206, 209, 211, 385
PMIX JOB CTRL CHECKPOINT TIMEOUT, 207, 209, 211, 385
PMIX JOB CTRL ID, 205, 206, 208, 209, 211, 211, 384
PMIX JOB CTRL KILL, 206, 208, 211, 384
PMIX_JOB_CTRL_PAUSE, 205, 208, 211, 384
PMIX JOB CTRL PREEMPTIBLE, 207, 210, 211, 385
PMIX_JOB_CTRL_PROVISION, 207, 210, 211, 385
PMIX JOB CTRL_PROVISION_IMAGE, 207, 210, 211, 385
PMIX_JOB_CTRL_RESTART, 206, 209, 211, 384
PMIX_JOB_CTRL_RESUME, 205, 208, 211, 384
PMIX_JOB_CTRL_SIGNAL, 206, 209, 211, 384
PMIX JOB CTRL TERMINATE, 206, 209, 211, 384
PMIX_JOB_INFO, 72, 75, 80, 85, 97, 100
PMIX_JOB_INFO_ARRAY, 292, 294, 302, 302, 303, 306, 527, 539
PMIX JOB NUM APPS, 101, 295, 306
PMIX JOB RECOVERABLE, 161, 167, 172, 361
PMIX JOB SIZE, 101, 294, 306, 307, 526, 529
PMIX JOB TERM STATUS, 172, 173, 413, 414, 432, 433, 434, 550
PMIX JOBID, 100, 292–294, 302, 306, 433, 540
PMIX LAUNCH DIRECTIVES, 419, 420, 544
PMIX LAUNCHER, 404, 409, 410
```

```
PMIX_LAUNCHER_DAEMON, 417, 420, 542
PMIX LAUNCHER RENDEZVOUS FILE, 405, 410, 542
PMIX LOCAL CPUSETS, 105, 298, 310
PMIX LOCAL PEERS, 105, 105, 298, 309
PMIX LOCAL PROCS, 105, 298
PMIX LOCAL RANK, 104, 299, 429-431, 436, 543, 544
PMIX LOCAL SIZE, 105, 297
PMIX LOCALITY STRING, 186, 188, 299, 334
PMIX LOCALLDR, 105, 297
PMIX_LOG_COMPLETION, 173, 413, 432, 550
PMIX_LOG_EMAIL, 220, 223, 225, 379
PMIX_LOG_EMAIL_ADDR, 220, 223, 225, 379
PMIX LOG EMAIL MSG, 220, 223, 225, 379
PMIX_LOG_EMAIL_SENDER_ADDR, 220, 223, 225
PMIX_LOG_EMAIL_SERVER, 220, 223, 225
PMIX_LOG_EMAIL_SRVR_PORT, 220, 223, 225
PMIX_LOG_EMAIL_SUBJECT, 220, 223, 225, 379
PMIX LOG GENERATE TIMESTAMP, 219, 222, 224
PMIX LOG GLOBAL DATASTORE, 220, 223, 225
PMIX LOG GLOBAL SYSLOG, 219, 222, 224
PMIX_LOG_JOB_EVENTS, 172, 413, 432, 549
PMIX LOG JOB RECORD, 220, 223, 225
PMIX LOG LOCAL SYSLOG, 219, 222, 224
PMIX LOG MSG, 224, 379
PMIX LOG ONCE, 219, 222, 224
PMIX LOG PROC ABNORMAL TERMINATION, 172, 549
PMIX_LOG_PROC_TERMINATION, 172, 549
PMIX LOG SOURCE, 219, 222, 224
PMIX_LOG_STDERR, 219, 222, 224, 378
PMIX LOG STDOUT, 219, 222, 224, 378
PMIX_LOG_SYSLOG, 219, 222, 224, 378
PMIX_LOG_SYSLOG_PRI, 219, 222, 224
PMIX LOG TAG OUTPUT, 220, 223, 224
PMIX LOG TIMESTAMP, 219, 222, 224
PMIX LOG TIMESTAMP OUTPUT, 220, 223, 224
PMIX LOG XML OUTPUT, 220, 223, 224
PMIX MAPBY, 160, 166, 170, 170, 295, 359
PMIX MAX PROCS, 99, 99–102, 293–296, 298, 325, 529
PMIX MAX RESTARTS, 161, 167, 172, 361
PMIX MAX VALUE, 326, 326, 532, 540
PMIX MERGE STDERR STDOUT, 161, 166, 171, 360
PMIX MIN VALUE, 326, 326, 532, 540
PMIX MODEL AFFINITY_POLICY, 61, 63
```

```
PMIX_MODEL_CPU_TYPE, 61, 63
PMIX MODEL LIBRARY NAME, 61, 63, 297, 322
PMIX MODEL LIBRARY VERSION, 61, 63, 297, 322
PMIX MODEL NUM CPUS, 61, 63
PMIX MODEL NUM THREADS, 61, 63
PMIX MODEL PHASE NAME, 63, 140
PMIX MODEL PHASE TYPE, 63, 140
PMIX MONITOR APP CONTROL, 213, 216, 217, 387
PMIX MONITOR CANCEL, 213, 216, 217, 387
PMIX_MONITOR_FILE, 213, 214, 216, 217, 387
PMIX_MONITOR_FILE_ACCESS, 213, 216, 218, 387
PMIX_MONITOR_FILE_CHECK_TIME, 214, 216, 218, 388
PMIX MONITOR FILE DROPS, 214, 216, 218, 388
PMIX_MONITOR_FILE_MODIFY, 214, 216, 218, 387
PMIX MONITOR FILE SIZE, 213, 216, 217, 387
PMIX_MONITOR_HEARTBEAT, 213, 216, 217, 387
PMIX_MONITOR_HEARTBEAT_DROPS, 213, 216, 217, 387
PMIX_MONITOR_HEARTBEAT_TIME, 213, 216, 217, 387
PMIX MONITOR ID, 213, 215, 217, 387
PMIX NO OVERSUBSCRIBE, 161, 167, 171, 361
PMIX NO PROCS ON HEAD, 161, 167, 171, 361
PMIX NODE INFO, 72, 75, 80, 85, 98, 105, 298
PMIX NODE INFO ARRAY, 293, 297, 302, 303, 307, 309, 313, 314, 540
PMIX NODE LIST, 99, 101, 103
PMIX NODE MAP, 99, 101, 102, 295, 306–308, 321, 322, 529
PMIX NODE MAP RAW, 100, 542
PMIX_NODE_RANK, 104, 299, 430
PMIX NODE SIZE, 105, 297
PMIX_NODEID, 72, 75, 80, 83, 85, 88, 91, 98, 105, 105, 256, 266, 270, 293, 297–299, 302, 314,
       540, 547
PMIX_NOHUP, 412, 417, 420, 542
PMIX_NOTIFY_COMPLETION, 172, 413, 432
PMIX NOTIFY JOB EVENTS, 172, 412, 432, 549
PMIX NOTIFY PROC ABNORMAL TERMINATION, 172, 549
PMIX_NOTIFY_PROC_TERMINATION, 172, 549
PMIX NPROC OFFSET, 100, 295
PMIX NSDIR, 101, 104, 298, 300
PMIX NSPACE, 81–83, 86–91, 100, 292–294, 302, 307, 373, 374, 428, 433, 436, 538–540
PMIX NUM ALLOCATED NODES, 99, 541
PMIX NUM NODES, 97, 99, 101, 102, 306, 307, 541
PMIX NUM SLOTS, 99, 100, 102
PMIX OPTIONAL, 71, 74, 76, 115
PMIX OUTPUT TO DIRECTORY, 171, 549
```

```
PMIX_OUTPUT_TO_FILE, 161, 166, 171, 360
PMIX PACKAGE RANK, 104, 300, 541
PMIX PARENT ID, 103, 358, 418
PMIX PERSISTENCE, 118, 120, 120, 351, 457
PMIX PERSONALITY, 160, 165, 170, 359
PMIX PPR, 160, 166, 170, 359
PMIX PREFIX, 159, 165, 170, 358
PMIX PRELOAD BIN, 160, 165, 170, 359
PMIX PRELOAD FILES, 160, 165, 170, 359
PMIX_PREPEND_ENVAR, 162, 167, 173
PMIX_PRIMARY_SERVER, 410, 442, 542
PMIX_PROC_INFO, 80, 85, 98
PMIX PROC INFO ARRAY, 293, 298, 302, 308, 540, 552
PMIX_PROC_MAP, 100, 100, 101, 103, 295, 306, 307, 321, 322, 529
PMIX_PROC_MAP_RAW, 100, 542
PMIX_PROC_PID, 83, 88, 104
PMIX_PROC_STATE_STATUS, 83, 88, 434
PMIX PROC TERM STATUS, 433, 434
PMIX PROCDIR, 104, 300
PMIX PROCID, 80–82, 85–87, 90, 103, 172, 173, 293, 302, 374, 413, 414, 432, 540, 550
PMIX_PROGRAMMING_MODEL, 61, <u>63</u>, 297, 322
PMIX PSET MEMBERS, 227, 228, 547
PMIX PSET NAME, 227, 228, 547
PMIX PSET NAMES, 226, 228, 296, 547
PMIX QUERY ALLOC STATUS, 82, 87, 90, 374
PMIX QUERY ATTRIBUTE SUPPORT, 81, 86, 90, 94, 427, 538
PMIX_QUERY_AUTHORIZATIONS, 83, 88, 90
PMIX OUERY AVAIL SERVERS, 90, 407, 538
PMIX_QUERY_DEBUG_SUPPORT, 82, 87, 90, 373
PMIX OUERY GROUP MEMBERSHIP, 231, 548
PMIX_QUERY_GROUP_NAMES, 231, 548
PMIX_QUERY_JOB_STATUS, 82, 87, 89, 373
PMIX OUERY LOCAL ONLY, 90, 374
PMIX_QUERY_LOCAL_PROC_TABLE, 82, 87, 89, 373, 428, 436
PMIX_QUERY_MEMORY_USAGE, 82, 87, 90, 374
PMIX_QUERY_NAMESPACE_INFO, 89, 538
PMIX QUERY NAMESPACES, 82, 87, 89, 373, 428
PMIX QUERY NUM GROUPS, 231, 547
PMIX QUERY NUM PSETS, 90, 228, 547
PMIX_QUERY_PROC_TABLE, 82, 87, 89, 373, 428, 436
PMIX QUERY PSET MEMBERSHIP, 90, 228, 547
PMIX QUERY PSET NAMES, 90, 228, 547
PMIX QUERY QUALIFIERS, 83, 89, 89, 538
```

```
PMIX_QUERY_QUEUE_LIST, 82, 87, 89, 373
PMIX QUERY QUEUE STATUS, 82, 87, 89, 373
PMIX QUERY REFRESH CACHE, 80, 84, 85, 89, 94
PMIX QUERY REPORT AVG, 82, 87, 90, 374
PMIX QUERY REPORT MINMAX, 82, 87, 90, 374
PMIX_QUERY_RESULTS, 83, 89, 538
PMIX QUERY SPAWN SUPPORT, 82, 87, 90, 373
PMIX QUERY STORAGE LIST, 452, 555
PMIX QUERY SUPPORTED KEYS, 89, 538
PMIX_QUERY_SUPPORTED_QUALIFIERS, 89, 538
PMIX_RANGE, 118, 120, 120, 123, 125, 131, 132, 137, 214, 231, 351, 354, 356, 370, 400, 401,
       457, 547, 548
PMIX RANK, 81, 82, 86, 87, 90, 103, 163, 169, 293, 298, 302, 374, 431, 435, 540
PMIX_RANKBY, 160, 166, 170, 295, 359
PMIX_REGISTER_CLEANUP, 206, 209, 211
PMIX_REGISTER_CLEANUP_DIR, 206, 209, 212
PMIX_REGISTER_NODATA, 292, 302
PMIX REINCARNATION, 104, 299, 542
PMIX REPORT BINDINGS, 161, 167, 171, 361
PMIX REQUESTOR IS CLIENT, 358, 362
PMIX REQUESTOR IS TOOL, 358, 362
PMIX REQUIRED KEY, 349, 350, 541
PMIX RM NAME, 99, 294
PMIX RM VERSION, 99, 294
PMIX SEND HEARTBEAT, 214, 216, 217
PMIX SERVER ATTRIBUTES, 81, 86, 91, 95, 532, 539
PMIX_SERVER_ENABLE_MONITORING, 287, 289
PMIX SERVER FUNCTIONS, 81, 86, 90, 91, 95, 538, 539
PMIX_SERVER_GATEWAY, 285, 289
PMIX SERVER HOSTNAME, 294, 409
PMIX_SERVER_INFO_ARRAY, 91, 91, 538
PMIX_SERVER_NSPACE, 285, 289, 294, 407, 437, 441
PMIX SERVER PIDINFO, 407, 409, 437, 441
PMIX_SERVER_RANK, 285, 289, 294
PMIX_SERVER_REMOTE_CONNECTIONS, 286, 288
PMIX_SERVER_SCHEDULER, 267, 270, 285, 289, 539, 544
PMIX SERVER SESSION SUPPORT, 285, 289, 539
PMIX SERVER SHARE TOPOLOGY, 287, 288, 539
PMIX SERVER START TIME, 289, 539
PMIX SERVER SYSTEM SUPPORT, 285, 289, 404
PMIX SERVER TMPDIR, 285, 287, 289, 404–406
PMIX SERVER TOOL SUPPORT, 276, 285, 287, 288
PMIX SERVER URI, 83, 88, 406, 407, 409, 437, 441
```

```
PMIX_SESSION_ID, 98, 98, 100, 107, 292, 293, 302, 306, 433, 540
PMIX SESSION INFO, 72, 75, 80, 85, 97, 99, 107, 293, 295, 322
PMIX SESSION INFO ARRAY, 292, 293, 302, 303, 306, 527
PMIX SET ENVAR, 162, 167, 173
PMIX SET SESSION CWD, 159, 165, 171, 358
PMIX_SETUP_APP_ALL, 320, 323
PMIX_SETUP_APP_ENVARS, 320, 323
PMIX SETUP APP NONENVARS, 320, 323
PMIX SINGLE LISTENER, 60, 286, 288
PMIX_SOCKET_MODE, 60, 286, 288, 438
PMIX_SPAWN_TOOL, 163, 169, 172, 419
PMIX_SPAWNED, 104, 299, 358
PMIX STDIN TGT, 160, 166, 171, 359
PMIX_STORAGE_ACCESS_TYPE, 453, 556
PMIX_STORAGE_ACCESSIBILITY, 452, 555
PMIX_STORAGE_BW_CUR, 453, 453, 556
PMIX_STORAGE_BW_MAX, 453, 556
PMIX STORAGE CAPACITY LIMIT, 452, 555
PMIX STORAGE CAPACITY USED, 452, 555
PMIX_STORAGE_ID, 452, 452, 555
PMIX_STORAGE_IOPS_CUR, <u>453</u>, 453, 556
PMIX STORAGE IOPS MAX, 453, 556
PMIX_STORAGE_MEDIUM, 452, 555
PMIX STORAGE MINIMAL XFER SIZE, 452, 556
PMIX STORAGE OBJECT LIMIT, 452, 556
PMIX STORAGE OBJECTS USED, 452, 556
PMIX_STORAGE_PATH, 452, 555
PMIX STORAGE PERSISTENCE, 452, 555
PMIX_STORAGE_SUGGESTED_XFER_SIZE, 453, 453, 556
PMIX STORAGE TYPE, 452, 555
PMIX_STORAGE_VERSION, 452, 555
PMIX_SWITCH_PEERS, 270, 270, 545
PMIX SYSTEM TMPDIR, 285, 289, 404, 406
PMIX_TAG_OUTPUT, 160, 166, 171, 360
PMIX_TCP_DISABLE_IPV4, 60, 63, 286, 438
PMIX_TCP_DISABLE_IPV6, 60, 63, 286, 438
PMIX TCP IF EXCLUDE, 60, 63, 286, 438
PMIX TCP IF INCLUDE, 60, 63, 286, 438
PMIX TCP IPV4 PORT, 60, 63, 286, 438
PMIX TCP IPV6 PORT, 60, 63, 286, 438
PMIX TCP REPORT URI, 60, 62, 286, 438
PMIX TCP URI, 63, 406, 407, 437, 441
PMIX TDIR RMCLEAN, 99, 296
```

```
PMIX_THREADING_MODEL, 61, 63
PMIX TIME REMAINING, 77, 83, 88, 90, 374
PMIX TIMEOUT, 4, 67, 70, 73, 76, 77, 106, 115, 116, 118, 120, 123, 125, 131, 132, 178, 181,
        182, 184, 230, 234, 236, 239, 240, 242, 243, 247, 248, 250, 278, 279, 281, 283, 346, 350,
        352, 354, 356, 361, 363, 365, 389, 392, 410, 444, 544
PMIX TIMEOUT REPORT STATE, 172, 549
PMIX_TIMEOUT_STACKTRACES, 172, 549
PMIX TIMESTAMP OUTPUT, 161, 166, 171, 360
PMIX TMPDIR, 99, 101, 298
PMIX_TOOL_ATTACHMENT_FILE, 406, 407, 410, 437, 441, 542
PMIX_TOOL_ATTRIBUTES, 81, 86, 91, 95, 532, 539
PMIX_TOOL_CONNECT_OPTIONAL, 410, 542
PMIX TOOL DO NOT CONNECT, 406, 410, 437, 439
PMIX_TOOL_FUNCTIONS, 81, 86, 90, 91, 95, 538, 539
PMIX_TOOL_NSPACE, 375, 405, 408, 437, 439
PMIX_TOOL_RANK, 375, 405, 409, 437, 439
PMIX_TOPOLOGY2, 287, 288, 539, 552
PMIX UNIV SIZE, 8, 98, 293, 306, 526, 527, 529
PMIX UNSET ENVAR, 162, 167, 173
PMIX USERID, 81, 86, 118, 119, 122, 125, 130, 132, 197, 200, 205, 208, 213, 215, 219, 222, 277,
        279, 280, 282, 351–354, 356, 358, 366, 373, 375, 377, 378, 380, 384, 387, 389, 391, 393,
        394, 398
PMIX USOCK DISABLE, 60, 286, 288
PMIX VERSION INFO, 376, 377
PMIX WAIT, 75, 77, 123, 125, 354
PMIX WAIT FOR CONNECTION, 410, 444, 544
PMIX_WDIR, 159, 165, 170, 296, 358
PMIX ALLOC NETWORK
    Deprecated, 552
PMIX ALLOC NETWORK ENDPTS
    Deprecated, 552
PMIX_ALLOC_NETWORK_ENDPTS_NODE
    Deprecated, 552
PMIX_ALLOC_NETWORK_ID
    Deprecated, 552
PMIX_ALLOC_NETWORK_PLANE
    Deprecated, 552
PMIX ALLOC NETWORK OOS
    Deprecated, 552
PMIX ALLOC NETWORK SEC KEY
    Deprecated, 552
PMIX ALLOC NETWORK TYPE
    Deprecated, 552
```

PMIX_ARCH
Deprecated, <u>531</u>
<b>Removed</b> , <u>554</u>
PMIX_COLLECTIVE_ALGO
Deprecated, <u>531</u>
<b>Removed</b> , <u>553</u>
PMIX_COLLECTIVE_ALGO_REQD
Deprecated, <u>528</u>
<b>Removed</b> , <u>553</u>
$PMIX\_DEBUG\_JOB$
Deprecated, <u>552</u>
PMIX_DSTPATH
Deprecated, <u>531</u>
<b>Removed</b> , <u>553</u>
PMIX_ERROR_GROUP_ABORT
Deprecated, <u>526</u>
<b>Removed</b> , <u>528</u>
PMIX_ERROR_GROUP_COMM
Deprecated, <u>526</u>
<b>Removed</b> , <u>528</u>
PMIX_ERROR_GROUP_GENERAL
Deprecated, <u>526</u>
<b>Removed</b> , <u>528</u>
PMIX_ERROR_GROUP_LOCAL
Deprecated, <u>526</u>
Removed, <u>528</u>
PMIX_ERROR_GROUP_MIGRATE
Deprecated, <u>526</u>
<b>Removed</b> , <u>528</u>
PMIX_ERROR_GROUP_NODE
Deprecated, <u>526</u>
<b>Removed</b> , <u><b>528</b></u>
PMIX_ERROR_GROUP_RESOURCE
Deprecated, <u>526</u>
Removed, <u>528</u>
PMIX_ERROR_GROUP_SPAWN
Deprecated, <u>526</u>
Removed, <u>528</u>
PMIX_ERROR_HANDLER_ID
Deprecated, <u>526</u>
Removed, 528
PMIX_ERROR_NAME
Deprecated, <u>526</u>

D 1 500
Removed, <u>528</u>
PMIX_HWLOC_HOLE_KIND
<b>Deprecated</b> , <u>531</u>
Removed, <u>553</u>
PMIX_HWLOC_SHARE_TOPO
Deprecated, <u>531</u>
Removed, <u>553</u>
PMIX_HWLOC_SHMEM_ADDI
Deprecated, <u>531</u>
Removed, <u>553</u>
PMIX_HWLOC_SHMEM_FILE
Deprecated, <u>531</u>
Removed, <u>553</u>
PMIX_HWLOC_SHMEM_SIZE
Deprecated, <u>531</u>
Removed, <u>553</u>
PMIX_HWLOC_XML_V1
Deprecated, <u>531</u>
Removed, <u>553</u>
PMIX_HWLOC_XML_V2
Deprecated, <u>531</u>
<b>Removed</b> , <u>553</u>
PMIX_LOCAL_TOPO
Deprecated, <u>531</u>
<b>Removed</b> , <u>553</u>
PMIX_LOCALITY
Deprecated, <u>552</u>
PMIX_MAP_BLOB
Deprecated, <u>531</u>
<b>Removed</b> , <u><b>554</b></u>
PMIX_MAPPER
Deprecated, <u>531</u>
<b>Removed</b> , <u>554</u>
PMIX_NON_PMI
Deprecated, <u>531</u>
<b>Removed</b> , <u><b>554</b></u>
PMIX_PROC_BLOB
Deprecated, <u>531</u>
<b>Removed</b> , <u><b>553</b></u>
PMIX_PROC_DATA
Deprecated, <u>552</u>
PMIX_PROC_URI
Deprecated, <u>531</u>

Removed, 554

PMIX\_RECONNECT\_SERVER

Deprecated, 552

PMIX\_TOPOLOGY

Deprecated, 552

PMIX\_TOPOLOGY\_FILE

Deprecated, 531

Removed, 553

PMIX\_TOPOLOGY\_SIGNATURE

Deprecated, 532

Removed, 553

PMIX\_TOPOLOGY\_XML

Deprecated, 532

Removed, 553

PMIX\_TOPOLOGY\_XML

Deprecated, 532

Removed, 553