

Process Management Interface for Exascale (PMIx) Standard


Version 4.2rc2

April 2024

This document describes the Process Management Interface for Exascale (PMIx) Standard, version 4.2rc2.

Comments: Please provide comments on the PMIx Standard by filing issues on the document repository https://github.com/pmix/pmix-standard/issues or by sending them to the PMIx Community mailing list at https://groups.google.com/forum/#!forum/pmix. Comments should include the version of the PMIx standard you are commenting about, and the page, section, and line numbers that you are referencing. Please note that messages sent to the mailing list from an unsubscribed e-mail address will be ignored.

Copyright © 2018-2020 PMIx Administrative Steering Committee (ASC). Permission to copy without fee all or part of this material is granted, provided the PMIx ASC copyright notice and the title of this document appear, and notice is given that copying is by permission of PMIx ASC.



Contents

1.	Intro	duction	1
	1.1.	Background	1
	1.2.	PMIx Architecture Overview	1
	1.3.		3
			3
2.	PMIx	Terms and Conventions	6
	2.1.	Notational Conventions	8
	2.2.	Semantics	9
	2.3.	Naming Conventions	0
	2.4.	Procedure Conventions	0
3.	Data	Structures and Types 1	2
	3.1.	Constants	3
		3.1.1. PMIx Return Status Constants	4
		3.1.1.1. User-Defined Error and Event Constants	5
	3.2.	Data Types	6
		3.2.1. Key Structure	6
		3.2.1.1. Key support macros	6
		3.2.2. Namespace Structure	8
		3.2.2.1. Namespace support macros	8
		3.2.3. Rank Structure	9
		3.2.3.1. Rank support macros	20
		3.2.4. Process Structure	20
		3.2.4.1. Process structure support macros	21
		3.2.5. Process State Structure	25
		3.2.6. Process Information Structure	26
		3.2.6.1. Process information structure support macros	26
		3 2 7 Job State Structure	8.

		3.2.8. Value Structure	28
		3.2.8.1. Value structure support	29
		3.2.9. Info Structure	33
		3.2.9.1. Info structure support macros	33
		3.2.9.2. Info structure list macros	36
		3.2.10. Info Type Directives	38
		3.2.10.1. Info Directive support macros	39
		3.2.11. Environmental Variable Structure	41
		3.2.11.1. Environmental variable support macros	41
		3.2.12. Byte Object Type	43
		3.2.12.1. Byte object support macros	43
		3.2.13. Data Array Structure	45
		3.2.13.1. Data array support macros	45
		3.2.14. Argument Array Macros	46
		3.2.15. Set Environment Variable	49
	3.3.	Generalized Data Types Used for Packing/Unpacking	50
	3.4.	General Callback Functions	52
		3.4.1. Release Callback Function	52
		3.4.2. Op Callback Function	52
		3.4.3. Value Callback Function	53
		3.4.4. Info Callback Function	53
		3.4.5. Handler registration callback function	54
	3.5.	PMIx Datatype Value String Representations	54
	0 !!	and the second s	
4.		nt Initialization and Finalization	57
	4.1.	PMIx_Initialized	57
	4.2.	PMIx_Get_version	58
	4.3.	PMIx_Init	58
		4.3.1. Initialization events	61
		4.3.2. Initialization attributes	61
		4.3.2.1. Connection attributes	61
		4.3.2.2. Programming model attributes	61
	4.4.	PMIx_Finalize	62
		4.4.1. Finalize attributes	63

	4.5.	PMIx_Progress	63
5.	Sync	hronization and Data Access Operations	64
	5.1.	PMIx_Fence	64
	5.2.	PMIx_Fence_nb	66
		5.2.1. Fence-related attributes	68
	5.3.	PMIx_Get	69
		5.3.1. PMIx_Get_nb	71
		5.3.2. Retrieval attributes	74
	5.4.	Query	75
		5.4.1. PMIx_Resolve_peers	75
		5.4.2. PMIx_Resolve_nodes	76
		5.4.3. PMIx_Query_info	76
		5.4.4. PMIx_Query_info_nb	81
		5.4.5. Query-specific constants	85
		5.4.6. Query attributes	85
		5.4.7. Query Structure	87
		5.4.7.1. Query structure support macros	88
	5.5.	Using Get vs Query	89
	5.6.	Accessing attribute support information	90
_	D		00
6.		erved Keys	92
	6.1.	Data realms	92
		6.1.1. Session realm attributes	93
		6.1.2. Job realm attributes	94
		6.1.3. Application realm attributes	96
		6.1.4. Process realm attributes	97
		6.1.5. Node realm keys	99
	6.2.	Retrieval rules for reserved keys	100
		6.2.1. Accessing information: examples	101
		6.2.1.1. Session-level information	101
		6.2.1.2. Job-level information	102
		6.2.1.3. Application-level information	102
		6.2.1.4. Process-level information	103

		6.2.1.5. Node-level information	103
7.	Proc	ess-Related Non-Reserved Keys	105
	7.1.	Posting Key/Value Pairs	105
		7.1.1. PMIx_Put	106
		7.1.1.1. Scope of Put Data	107
		7.1.2. PMIx_Store_internal	107
		7.1.3. PMIx_Commit	108
	7.2.	Retrieval rules for non-reserved keys	108
8.	Publ	ish/Lookup Operations	110
	8.1.	PMIx_Publish	110
	8.2.	PMIx_Publish_nb	111
	8.3.	Publish-specific constants	113
	8.4.	Publish-specific attributes	113
	8.5.	Publish-Lookup Datatypes	113
		8.5.1. Range of Published Data	114
		8.5.2. Data Persistence Structure	114
	8.6.	PMIx_Lookup	114
	8.7.	PMIx_Lookup_nb	116
		8.7.1. Lookup Returned Data Structure	118
		8.7.1.1. Lookup data structure support macros	118
		8.7.2. Lookup Callback Function	121
	8.8.	Retrieval rules for published data	122
	8.9.	PMIx_Unpublish	122
	8.10.	PMIx_Unpublish_nb	123
9.	Even	nt Notification	126
	9.1.	Notification and Management	126
		9.1.1. Events versus status constants	128
		9.1.2. PMIx_Register_event_handler	128
		9.1.3. Event registration constants	131
		9.1.4. System events	131
		9.1.5. Event handler registration and notification attributes	131
		9.1.5.1. Fault tolerance event attributes	132

	9	.1.5.2.	Hybrid pro	ogrammi	ng ev	ent at	tribu	tes			 	 		132
	9.1.6.	Notific	ation Functi	on							 	 		133
	9.1.7.	PMIx_	_Deregist	:er_ev	ent_	hand	ile	r.			 	 		134
	9.1.8.	PMIx_	_Notify_e	event							 	 		135
	9.1.9.	Notific	ation Handl	er Comp	letior	Call	back	Fun	ctior	ı.	 	 		138
	9	.1.9.1.	Completio	n Callba	ck Fu	nctio	n Sta	tus (Code	s.	 	 	•	139
10. Data	Packing	g and U	Inpacking										•	140
10.1.	Data Bu	ffer Typ	e								 	 	•	140
10.2.	Support	Macros									 	 	•	140
10.3.	General	Routine	s								 	 	•	142
	10.3.1.	PMIx_	_Data_pac	zk							 	 		142
	10.3.2.	PMIx_	_Data_unp	pack .							 	 		144
	10.3.3.	PMIx_	_Data_cop	ру							 	 	•	145
	10.3.4.	PMIx_	_Data_pri	int							 	 		146
	10.3.5.	PMIx_	_Data_cop	oy_pay	load	l.,					 	 		147
	10.3.6.	PMIx_	_Data_loa	ad							 	 		147
	10.3.7.	PMIx_	_Data_unl	load .							 	 		148
	10.3.8.	PMIx_	_Data_com	npress							 	 		149
	10.3.9.	PMIx_	_Data_ded	compre	ss .						 	 		149
	10.3.10.	PMIx_	_Data_emb	oed							 	 		150
11.Proc	ess Mar	ageme	ent										•	152
11.1.	Abort .										 	 		152
	11.1.1.	PMIx_	_Abort .								 	 		152
11.2.	Process	Creation	ı								 	 		153
	11.2.1.	PMIx_	_Spawn .								 	 		153
	11.2.2.	PMIx_	_Spawn_nb	.							 	 		159
	11.2.3.	Spawn	-specific cor	nstants .							 	 		164
	11.2.4.	Spawn	attributes								 	 		164
	11.2.5.	Applic	ation Structi	ure							 	 		167
	1	1.2.5.1.	App struct	ure supp	ort m	acros					 	 		168
	1	1.2.5.2.	Spawn Cal	llback Fu	ınctio	n					 	 		170

11.3.	Connect	ting and Disconnecting Processes	171
	11.3.1.	PMIx_Connect	171
	11.3.2.	PMIx_Connect_nb	173
	11.3.3.	PMIx_Disconnect	175
	11.3.4.	PMIx_Disconnect_nb	177
11.4.	Process	Locality	178
	11.4.1.	PMIx_Load_topology	178
	11.4.2.	PMIx_Get_relative_locality	179
	1	1.4.2.1. Topology description	180
	1	11.4.2.2. Topology support macros	180
	1	1.4.2.3. Relative locality of two processes	181
	1	11.4.2.4. Locality keys	181
	11.4.3.	PMIx_Parse_cpuset_string	181
	11.4.4.	PMIx_Get_cpuset	182
	1	1.4.4.1. Binding envelope	182
	11.4.5.	PMIx_Compute_distances	183
	11.4.6.	PMIx_Compute_distances_nb	184
	11.4.7.	Device Distance Callback Function	184
	11.4.8.	Device type	185
	11.4.9.	Device Distance Structure	186
	11.4.10.	Device distance support macros	186
	11.4.11.	Device distance attributes	188
12.Job	Manage	ment and Reporting	189
	•	on Requests	189
		PMIx_Allocation_request	189
	12.1.2.	PMIx_Allocation_request_nb	192
	12.1.3.	Job Allocation attributes	194
	12.1.4.	Job Allocation Directives	195
12.2.	Job Con	itrol	196
	12.2.1.	PMIx_Job_control	196
	12.2.2.	PMIx_Job_control_nb	199
	12.2.3.	Job control constants	201
	1224	Joh control avanta	201

	12.2.5.	Job control attributes	202
12.3.	Process	and Job Monitoring	203
	12.3.1.	PMIx_Process_monitor	203
	12.3.2.	PMIx_Process_monitor_nb	205
	12.3.3.	PMIx_Heartbeat	207
	12.3.4.	Monitoring events	207
	12.3.5.	Monitoring attributes	208
12.4.	Logging	ţ	208
	12.4.1.	PMIx_Log	208
	12.4.2.	PMIx_Log_nb	211
	12.4.3.	Log attributes	214
12 Droc	nace Sate	s and Groups	216
		s and Groups Sets	216
13.1.	13.1.1.	Process Set Constants	217
	13.1.1.		217
12.2		Process Set Attributes	
13.2.		Groups	218
	13.2.1.	Relation to the host environment	218
	13.2.2.	Construction procedure	219
	13.2.3.	Destruct procedure	220
	13.2.4.	Process Group Events	220
	13.2.5.	Process Group Attributes	221
	13.2.6.	PMIx_Group_construct	222
	13.2.7.	PMIx_Group_construct_nb	225
	13.2.8.	PMIx_Group_destruct	228
	13.2.9.	PMIx_Group_destruct_nb	229
	13.2.10.	PMIx_Group_invite	230
		PMIx_Group_invite_nb	233
	13.2.12.	PMIx_Group_join	235
	13.2.13.	PMIx_Group_join_nb	237
	1	3.2.13.1. Group accept/decline directives	238
	13.2.14.	PMIx_Group_leave	239
	13 2 15	PMTy Croup leave ph	240

14. Fabr	ic Supp	ort Definitions	242
14.1.	Fabric S	Support Events	245
14.2.	Fabric S	support Datatypes	245
	14.2.1.	Fabric Endpoint Structure	245
	14.2.2.	Fabric endpoint support macros	245
	14.2.3.	Fabric Coordinate Structure	247
	14.2.4.	Fabric coordinate support macros	247
	14.2.5.	Fabric Geometry Structure	248
	14.2.6.	Fabric geometry support macros	249
	14.2.7.	Fabric Coordinate Views	250
	14.2.8.	Fabric Link State	251
	14.2.9.	Fabric Operation Constants	251
	14.2.10.	Fabric registration structure	251
	1	4.2.10.1. Static initializer for the fabric structure	254
	1	4.2.10.2. Initialize the fabric structure	254
14.3.	Fabric S	upport Attributes	254
14.4.	Fabric S	upport Functions	257
	14.4.1.	PMIx_Fabric_register	258
	14.4.2.	PMIx_Fabric_register_nb	259
	14.4.3.	PMIx_Fabric_update	260
	14.4.4.	PMIx_Fabric_update_nb	260
	14.4.5.	PMIx_Fabric_deregister	261
	14.4.6.	PMIx_Fabric_deregister_nb	262
15.Secu	ıritv		263
	•	ng Credentials	263
13.11	15.1.1.		264
	15.1.2.	PMIx_Get_credential_nb	265
	15.1.3.	Credential Attributes	266
15.2		ng Credentials	266
10.2.		PMIx_Validate_credential	266
		PMTy Validate gradential nb	268

16.Serv	er-Spec	ific Interfaces	270
16.1.	Server I	nitialization and Finalization	270
	16.1.1.	PMIx_server_init	270
	16.1.2.	PMIx_server_finalize	273
	16.1.3.	Server Initialization Attributes	274
16.2.	Server S	Support Functions	275
	16.2.1.	PMIx_generate_regex	275
	16.2.2.	PMIx_generate_ppn	276
	16.2.3.	PMIx_server_register_nspace	276
	1	6.2.3.1. Namespace registration attributes	286
	1	6.2.3.2. Assembling the registration information	287
	16.2.4.	PMIx_server_deregister_nspace	294
	16.2.5.	PMIx_server_register_resources	296
	16.2.6.	PMIx_server_deregister_resources	296
	16.2.7.	PMIx_server_register_client	297
	16.2.8.	PMIx_server_deregister_client	299
	16.2.9.	PMIx_server_setup_fork	299
	16.2.10.	PMIx_server_dmodex_request	300
	1	6.2.10.1. Server Direct Modex Response Callback Function	301
	16.2.11.	PMIx_server_setup_application	302
	1	6.2.11.1. Server Setup Application Callback Function	305
	1	6.2.11.2. Server Setup Application Attributes	306
	16.2.12.	PMIx_Register_attributes	306
	1	6.2.12.1. Attribute registration constants	308
	1	6.2.12.2. Attribute registration structure	308
	1	6.2.12.3. Attribute registration structure descriptive attributes	309
	1	6.2.12.4. Attribute registration structure support macros	309
	16.2.13.	PMIx_server_setup_local_support	311
	16.2.14.	PMIx_server_IOF_deliver	312
	16.2.15.	PMIx_server_collect_inventory	313
	16.2.16.	PMIx_server_deliver_inventory	314
	16.2.17.	PMIx server generate locality string	315

	16.2.18. PMIx_server_generate_cpuset_string	316
	16.2.18.1. Cpuset Structure	316
	16.2.18.2. Cpuset support macros	316
	16.2.19. PMIx_server_define_process_set	318
	16.2.20. PMIx_server_delete_process_set	318
16.3.	Server Function Pointers	319
	16.3.1. pmix_server_module_t Module	319
	16.3.2. pmix_server_client_connected_fn_t	321
	16.3.3. pmix_server_client_connected2_fn_t	321
	16.3.4. pmix_server_client_finalized_fn_t	323
	16.3.5. pmix_server_abort_fn_t	324
	16.3.6. pmix_server_fencenb_fn_t	325
	16.3.6.1. Modex Callback Function	328
	16.3.7. pmix_server_dmodex_req_fn_t	328
	16.3.7.1. Dmodex attributes	330
	16.3.8. pmix_server_publish_fn_t	330
	16.3.9. pmix_server_lookup_fn_t	332
	16.3.10. pmix_server_unpublish_fn_t	334
	16.3.11. pmix_server_spawn_fn_t	336
	16.3.11.1. Server spawn attributes	341
	16.3.12. pmix_server_connect_fn_t	341
	16.3.13. pmix_server_disconnect_fn_t	342
	16.3.14. pmix_server_register_events_fn_t	344
	16.3.15. pmix_server_deregister_events_fn_t	346
	16.3.16. pmix_server_notify_event_fn_t	348
	16.3.17. pmix_server_listener_fn_t	349
	16.3.17.1. PMIx Client Connection Callback Function	350
	16.3.18. pmix_server_query_fn_t	350
	16.3.19. pmix_server_tool_connection_fn_t	353
	16.3.19.1.Tool connection attributes	355
	16.3.19.2. PMIx Tool Connection Callback Function	355
	16.3.20. pmix_server_log_fn_t	355
	16.3.21. pmix_server_alloc_fn_t	357

	16.3.22.	<pre>pmix_server_job_control_fn_t</pre>	360
	16.3.23.	<pre>pmix_server_monitor_fn_t</pre>	362
	16.3.24.	<pre>pmix_server_get_cred_fn_t</pre>	365
	1	6.3.24.1. Credential callback function	366
	16.3.25.	<pre>pmix_server_validate_cred_fn_t</pre>	367
	16.3.26.	Credential validation callback function	369
	16.3.27.	<pre>pmix_server_iof_fn_t</pre>	370
	1	6.3.27.1.IOF delivery function	372
	16.3.28.	<pre>pmix_server_stdin_fn_t</pre>	373
	16.3.29.	pmix_server_grp_fn_t	374
	1	6.3.29.1. Group Operation Constants	376
	16.3.30.	<pre>pmix_server_fabric_fn_t</pre>	376
17 Tools	s and De	ebuggers	379
		ion Mechanisms	379
17.11.	17.1.1.	Rendezvousing with a local server	382
	17.1.2.	Connecting to a remote server	383
	17.1.3.	Attaching to running jobs	383
	17.1.4.	Tool initialization attributes	384
	17.1.5.	Tool initialization environmental variables	384
	17.1.6.	Tool connection attributes	384
17.2.		ng Applications with Tools	385
	17.2.1.	Direct launch	386
	17.2.2.	Indirect launch	390
	1	7.2.2.1. Initiator-based command line parsing	390
		7.2.2.2. Intermediate Launcher (IL)-based command line parsing	394
	17.2.3.	Tool spawn-related attributes	395
	17.2.4.	Tool rendezvous-related events	395
17.3.	IO Forw	varding	396
	17.3.1.	Forwarding stdout/stderr	396
	17.3.2.	Forwarding stdin	398
	17.3.3.	IO Forwarding Channels	400
	17.3.4.	IO Forwarding constants	400
	17.3.5.	IO Forwarding attributes	400

	17.4.	Debugg	er Suppor	t								 		 	 402
		17.4.1.	Co-Loca	ition of De	bugger	Daem	ons					 		 	 404
		17.4.2.	Co-Spav	vn of Debi	ıgger Da	aemor	ns .					 		 	 405
		17.4.3.	Debugge	er Agents								 		 	 406
		17.4.4.	Tracking	g the job li	fecycle .							 		 	 406
		1	17.4.4.1.	Job lifecyo	ele event	ts						 		 	 407
		1	17.4.4.2.	Job lifecyo	ele attrib	outes .						 		 	 408
		17.4.5.	Debugge	er-related o	constant	s						 		 	 408
		17.4.6.	Debugge	er attribute	s							 		 	 409
	17.5.	Tool-Sp	ecific API	[s								 		 	 410
		17.5.1.	PMIx_t	cool_in	it							 		 	 410
		17.5.2.	PMIx_t	cool_fi	nalize	∍						 		 	 413
		17.5.3.	PMIx_t	cool_di	sconne	ect .						 		 	 414
		17.5.4.	PMIx_t	cool_at	tach_t	co_se	erve	er				 		 	 414
		17.5.5.	PMIx_t	ool_ge	t_serv	vers						 		 	 416
		17.5.6.	PMIx_t	cool_se	t_serv	ær.						 		 	 416
		17.5.7.	PMIx_I	OF_pul	1							 		 	 417
		17.5.8.	PMIx_I	OF_der	egiste	er						 		 	 419
		17.5.9.	PMIx_I	OF_pus	h							 		 	 420
	٥.	•													400
18		•	•	initions	•	•									423
				onstants (I											
	18.2.	Storage	support at	ttributes (1	rovision	ıal)			• •	• •	•	 	• •	 	 425
Α.	Pyth	on Bind	lings												427
	A.1.	Design	Considera	tions								 		 	 427
		A.1.1.	Error Co	odes vs Py	thon Ex	ceptio	ns .					 		 	 427
		A.1.2.		ntation of											
	A.2.	Datatyp	•	ons											
		A.2.1.	Example									 		 	 434
	A.3.	Callbac		n Definitio											
		A.3.1.		ivery Fund											
		A 2 2	Erront II.	•											125

	A.3.3.	Server Module Functions	36
		A.3.3.1. Client Connected	36
		A.3.3.2. Client Finalized	36
		A.3.3.3. Client Aborted	36
		A.3.3.4. Fence	37
		A.3.3.5. Direct Modex	37
		A.3.3.6. Publish	38
		A.3.3.7. Lookup	38
		A.3.3.8. Unpublish	39
		A.3.3.9. Spawn	39
		A.3.3.10. Connect	10
		A.3.3.11. Disconnect	10
		A.3.3.12. Register Events	11
		A.3.3.13. Deregister Events	11
		A.3.3.14. Notify Event	12
		A.3.3.15. Query	12
		A.3.3.16. Tool Connected	13
		A.3.3.17. Log	13
		A.3.3.18. Allocate Resources	14
		A.3.3.19. Job Control	14
		A.3.3.20. Monitor	15
		A.3.3.21. Get Credential	15
		A.3.3.22. Validate Credential	16
		A.3.3.23. IO Forward	16
		A.3.3.24. IO Push	17
		A.3.3.25. Group Operations	17
		A.3.3.26. Fabric Operations	18
A.4.	PMIxC	lient	19
	A.4.1.	Client.init	19
	A.4.2.	Client.initialized	19
	A.4.3.	Client.get_version	19
	A.4.4.	Client.finalize	50
	A.4.5.	Client.abort	50

A.4.6.	Client.store_internal	450
A.4.7.	Client.put	451
A.4.8.	Client.commit	451
A.4.9.	Client.fence	452
A.4.10.	Client.get	452
A.4.11.	Client.publish	453
A.4.12.	Client.lookup	453
A.4.13.	Client.unpublish	454
A.4.14.	Client.spawn	454
A.4.15.	Client.connect	455
A.4.16.	Client.disconnect	455
A.4.17.	Client.resolve_peers	456
A.4.18.	Client.resolve_nodes	456
A.4.19.	Client.query	457
A.4.20.	Client.log	457
A.4.21.	Client.allocation_request	458
A.4.22.	Client.job_ctrl	458
A.4.23.	Client.monitor	459
A.4.24.	Client.get_credential	459
A.4.25.	Client.validate_credential	460
A.4.26.	Client.group_construct	460
A.4.27.	Client.group_invite	461
A.4.28.	Client.group_join	461
A.4.29.	Client.group_leave	462
A.4.30.	Client.group_destruct	462
A.4.31.	Client.register_event_handler	463
A.4.32.	Client.deregister_event_handler	463
A.4.33.	Client.notify_event	464
A.4.34.	Client.fabric_register	464
A.4.35.	Client.fabric_update	465
A.4.36.	Client.fabric_deregister	465
A.4.37.	Client.load_topology	466
Δ 4 38	Client get relative locality	466

	A.4.39.	Client.get_cpuset	7
	A.4.40.	Client.parse_cpuset_string	7
	A.4.41.	Client.compute_distances	7
	A.4.42.	Client.error_string	8
	A.4.43.	Client.proc_state_string	8
	A.4.44.	Client.scope_string 46	9
	A.4.45.	Client.persistence_string	9
	A.4.46.	Client.data_range_string	0
	A.4.47.	Client.info_directives_string	0
	A.4.48.	Client.data_type_string	0
	A.4.49.	Client.alloc_directive_string	1
	A.4.50.	Client.iof_channel_string	1
	A.4.51.	Client.job_state_string	2
	A.4.52.	Client.get_attribute_string	2
	A.4.53.	Client.get_attribute_name	2
	A.4.54.	Client.link_state_string	3
	A.4.55.	Client.device_type_string	3
	A.4.56.	Client.progress	4
A.5.	PMIxSe	rver	4
	A.5.1.	Server.init	4
	A.5.2.	Server.finalize	4
	A.5.3.	Server.generate_regex	5
	A.5.4.	Server.generate_ppn	5
	A.5.5.	Server.generate_locality_string	6
	A.5.6.	Server.generate_cpuset_string	6
	A.5.7.	Server.register_nspace	6
	A.5.8.	Server.deregister_nspace	7
	A.5.9.	Server.register_resources	7
	A.5.10.	Server.deregister_resources	8
	A.5.11.	Server.register_client	8
	A.5.12.	Server.deregister_client	8
	A.5.13.	Server.setup_fork	9
	Δ 5 14	Server dmodey request 47	a

		A.5.15.	Server.setup_application	480
		A.5.16.	Server.register_attributes	480
		A.5.17.	Server.setup_local_support	480
		A.5.18.	Server.iof_deliver	481
		A.5.19.	Server.collect_inventory	481
		A.5.20.	Server.deliver_inventory	482
		A.5.21.	Server.define_process_set	482
		A.5.22.	Server.delete_process_set	483
		A.5.23.	Server.register_resources	483
		A.5.24.	Server.deregister_resources	484
	A.6.	PMIxTo	ol	484
		A.6.1.	Tool.init	484
		A.6.2.	Tool.finalize	484
		A.6.3.	Tool.disconnect	485
		A.6.4.	Tool.attach_to_server	485
		A.6.5.	Tool.get_servers	486
		A.6.6.	Tool.set_server	486
		A.6.7.	Tool.iof_pull	486
		A.6.8.	Tool.iof_deregister	487
		A.6.9.	Tool.iof_push	487
	A.7.	Example	e Usage	488
		A.7.1.	Python Client	488
		A.7.2.	Python Server	490
В.	Revis	sion His	etory	494
	B.1.	Version	1.0: June 12, 2015	494
	B.2.	Version	2.0: Sept. 2018	495
		B.2.1.	Removed/Modified Application Programming Interfaces (APIs)	495
		B.2.2.	Deprecated constants	495
		B.2.3.	Deprecated attributes	496
	B.3.	Version	2.1: Dec. 2018	496
	B.4.	Version	2.2: Jan 2019	497
	B.5.	Version	3.0: Dec. 2018	497
		D 5 1	Pamayad agnetants	407

		B.5.2.	Deprecated attributes	498
		B.5.3.	Removed attributes	498
	B.6.	Version	3.1: Jan. 2019	498
	B.7.	Version	3.2: Oct. 2020	499
		B.7.1.	Deprecated constants	499
		B.7.2.	Deprecated attributes	500
	B.8.	Version	4.0: Dec. 2020	501
		B.8.1.	Added Constants	503
		B.8.2.	Added Attributes	506
		B.8.3.	Added Environmental Variables	517
		B.8.4.	Added Macros	518
		B.8.5.	Deprecated APIs	518
		B.8.6.	Deprecated constants	518
		B.8.7.	Removed constants	518
		B.8.8.	Deprecated attributes	519
		B.8.9.	Removed attributes	520
	B.9.	Version	4.1: Oct. 2021	521
		B.9.1.	Added Functions (Provisional)	521
		B.9.2.	Added Data Structures (Provisional)	521
		B.9.3.	Added Macros (Provisional)	521
		B.9.4.	Added Constants (Provisional)	522
		B.9.5.	$Added\ Attributes\ (Provisional)\ .\ .\ .\ .\ .\ .\ .\ .\ .\ .\ .\ .\ .\$	522
	B.10.	Version	4.2: TBD	524
		B.10.1.	Errata	524
		B.10.2.	Deprecated constants	524
		B.10.3.	Deprecated attributes	524
		B.10.4.	Deprecated macros	524
		B.10.5.	Added Functions (Provisional)	525
		B.10.6.	Added Macros (Provisional)	525
		B.10.7.	Added Constants (Provisional)	525
		B.10.8.	Added Attributes (Provisional)	526
_	A oka	owledge	omente	528
U.		Varsion		520

C.2. Version 3.0	529
C.3. Version 2.0	530
C.4. Version 1.0	531
Bibliography	532
ndex	533
ndex of APIs	535
ndex of Support Macros	542
ndex of Data Structures	546
ndex of Constants	548
ndex of Environmental Variables	557
nday of Attributes	558

CHAPTER 1

Introduction

Process Management Interface - Exascale (PMIx) is an application programming interface standard that provides libraries and programming models with portable and well-defined access to commonly needed services in distributed and parallel computing systems. A typical example of such a service is the portable and scalable exchange of network addresses to establish communication channels between the processes of a parallel application or service. As such, PMIx gives distributed system software providers a better understanding of how programming models and libraries can interface with and use system-level services. As a standard, PMIx provides APIs that allow for portable access to these varied system software services and the functionalities they offer. Although these services can be defined and implemented directly by the system software components providing them, the community represented by the ASC feels that the development of a shared standard better serves the community. As a result, PMIx enables programming languages and libraries to focus on their core competencies without having to provide their own system-level services.

1.1 Background

The Process Management Interface (PMI) has been used for quite some time as a means of exchanging wireup information needed for inter-process communication. Two versions (PMI-1 and PMI-2 [2]) have been released as part of the MPICH effort, with PMI-2 demonstrating better scaling properties than its PMI-1 predecessor.

PMI-1 and PMI-2 can be implemented using PMIx though PMIx is not a strict superset of either. Since its introduction, PMIx has expanded on earlier PMI efforts by providing an extended version of the PMI APIs which provide necessary functionality for launching and managing parallel applications and tools at scale.

The increase in adoption has motivated the creation of this document to formally specify the intended behavior of the PMIx APIs.

More information about the PMIx standard and affiliated projects can be found at the PMIx web site: https://pmix.org

1.2 PMIx Architecture Overview

The presentation of the PMIx APIs within this document makes some basic assumptions about how these APIs are used and implemented. These assumptions are generally made only to simplify the presentation and explain PMIx with the expectation that most readers have similar concepts on how

computing systems are organized today. However, ultimately this document should only be assumed to define a set of APIs.

A concept that is fundamental to PMIx is that a PMIx implementation might operate primarily as a *messenger*, and not a *doer* — i.e., a PMIx implementation might rely heavily or fully on other software components to provide functionality [1]. Since a PMIx implementation might only deliver requests and responses to other software components, the API calls include ways to provide arbitrary information to the backend components that actually implement the functionality. Also, because PMIx implementations generally rely heavily on other system software, a PMIx implementation might not be able to guarantee that a feature is available on all platforms the implementation supports. These aspects are discussed in detail in the remainder of this chapter.




Figure 1.1.: PMIx-SMS Interactions

Fig. 1.1 shows a typical PMIx implementation in which the application is built against a PMIx client library that contains the client-side APIs, attribute definitions, and communication support for interacting with the local PMIx server. PMIx clients are processes which are started through the PMIx infrastructure, either by the PMIx implementation directly or through a System Management Software stack (SMS) component, and have registered as clients. A PMIx client is created in such a way that the PMIx client library will be have sufficient information available to authenticate with the PMIx server. The PMIx server will have sufficient knowledge about the process which it created, either directly or through other SMS, to authenticate the process and provide information the process requests such as its identity and the identity of its peers.

As clients invoke PMIx APIs, it is possible that some client requests can be handled at the client level. Other requests might require communication with the local PMIx server, which subsequently might request services from the host SMS (represented here by a Resource Manager (RM) daemon). The interaction between the PMIx server and SMS are achieved using callback functions registered during server initialization. The host SMS can indicate its lack of support for any

operation by simply providing a *NULL* for the associated callback function, or can create a function entry that returns *not supported* when called.

Recognizing the burden this places on SMS vendors, the PMIx community has included interfaces by which the host SMS (containing the local PMIx service instance) can request support from local SMS elements via the PMIx API. Once the SMS has transferred the request to an appropriate location, a PMIx server interface can be used to pass the request between SMS subsystems. For example, a request for network traffic statistics can utilize the PMIx networking abstractions to retrieve the information from the Fabric Manager. This reduces the portability and interoperability issues between the individual subsystems by transferring the burden of defining the interoperable interfaces from the SMS subsystems to the PMIx community, which continues to work with those providers to develop the necessary support.

Fig. 1.1 shows how tools can interact with the PMIx architecture. Tools, whether standalone or embedded in job scripts, are an exception to the normal client registration process. A process can register as a tool, provided the PMIx client library has adequate rendezvous information to connect to the appropriate PMIx server (either hosted on the local machine or on a remote machine). This allows processes which were not created by the PMIx infrastructure to request access to PMIx functionality.

1.3 Portability of Functionality

It is difficult to define a portable API that will provide access to the many and varied features underlying the operations for which PMIx provides access. For example, the options and features provided to request the creation of new processes varied dramatically between different systems existing at the time PMIx was introduced. Many RMs provide rich interfaces to specify the resources assigned to processes. As a result, PMIx is faced with the challenge of attempting to meet the seamingly conflicting goals of creating an API which allows access to these diverse features while being portable across a wide range of existing software environments. In addition, the functionalities required by different clients vary greatly. Producing a PMIx implementation which can provide the needs of all possible clients on all of its target systems could be so burdensome as to discourage PMIx implementations.

To help address this issue, the PMIx APIs are designed to allow resource managers and other system management stack components to decide on support of a particular function and allow client applications to query and adjust to the level of support available. PMIx clients should be written to account for the possibility that a PMIx API might return an error code indicating that the call is not supported. The PMIx community continues to look at ways to assist SMS implementers in their decisions on what functionality to support by highlighting functions and attributes that are critical to basic application execution (e.g., PMIx_Get) for certain classes of applications.

1.3.1 Attributes in PMIx

An area where differences between support on different systems can be challenging is regarding the attributes that provide information to the client process and/or control the behavior of a PMIx API.

Most PMIx API calls can accept additional information or attributes specified in the form of key/value pairs. These attributes provide information to the PMIx implementation that influence the behavior of the API call. In addition to API calls being optional, support for the individual attributes of an API call can vary between systems or implementations.

An application can adapt to the attribute support on a particular system in one of two ways. PMIx provides an API to enable an application to query the attributes supported by a particular API (See 5.6). Through this API, the PMIx implementation can provide detailed information about the attributes supported on a system for each API call queried. Alternatively, the application can mark attributes as required using a flag within the <code>pmix_info_t</code> (See 3.2.9). If the required attribute is not available on the system or the desired value for the attribute is not available, the call will return the error code for *not supported*.

For example, the **PMIX_TIMEOUT** attribute can be used to specify the time (in seconds) before the requested operation should time out. The intent of this attribute is to allow the client to avoid "hanging" in a request that takes longer than the client wishes to wait, or may never return (e.g., a **PMIx_Fence** that a blocked participant never enters).

The application can query the attribute support for **PMIx_Fence** and search whether **PMIX_TIMEOUT** is listed as a supported attribute. The application can also set the required flag in the **pmix_info_t** for that attribute when making the **PMIx_Fence** call. This will return an error if this attribute is not supported. If the required flag is not set, the library and SMS host are allowed to treat the attribute as optional, ignoring it if support is not available.

It is therefore critical that users and application implementers:

- a) consider whether or not a given attribute is required, marking it accordingly; and
- b) check the return status on all PMIx function calls to ensure support was present and that the request was accepted. Note that for non-blocking APIs, a return of **PMIX_SUCCESS** only indicates that the request had no obvious errors and is being processed the eventual callback will return the status of the requested operation itself.

PMIx clients (e.g., tools, parallel programming libraries) may find that they depend only on a small subset of interfaces and attributes to work correctly. PMIx clients are strongly advised to define a document itemizing the PMIx interfaces and associated attributes that are required for correct operation, and are optional but recommended for full functionality. The PMIx standard cannot define this list for all given PMIx clients, but such a list is valuable to RMs desiring to support these clients.

A PMIx implementation may be able to support only a subset of the PMIx API and attributes on a particular system due to either its own limitations or limitations of the SMS with which it interfaces. A PMIx implementation may also provide additional attributes beyond those defined herein in order to allow applications to access the full features of the underlying SMS. PMIx implementations are strongly advised to document the PMIx interfaces and associated attributes they support, with any annotations about behavior limitations. The PMIx standard cannot define this support for implementations, but such documentation is valuable to PMIx clients desiring to support a broad range of systems.

While a PMIx library implementer, or an SMS component server, may choose to support a particular PMIx API, they are not required to support every attribute that might apply to it. This would pose a significant barrier to entry for an implementer as there can be a broad range of applicable attributes to a given API, at least some of which may rarely be used.

Note that an environment that does not include support for a particular attribute/API pair is not "incomplete" or of lower quality than one that does include that support. Vendors must decide where to invest their time based on the needs of their target markets, and it is perfectly reasonable for them to perform cost/benefit decisions when considering what functions and attributes to support.

Attributes in this document are organized according to their primary usage, either grouped with a specific API or included in an appropriate functional chapter. Attributes in the PMIx Standard all start with "PMIX" in their name, and many include a functional description as part of their name (e.g., the use of "PMIX_FABRIC_" at the beginning of fabric-specific attributes). The PMIx Standard also defines an attribute that can be used to indicate that an attribute variable has not yet been set:

PMIX ATTR UNDEF "pmix.undef" (NULL)

A default attribute name signifying that the attribute field of a PMIx structure (e.g., a pmix_info_t) has not yet been defined.

CHAPTER 2

PMIx Terms and Conventions

In this chapter we describe some common terms and conventions used throughout this document. The PMIx Standard has adopted the widespread use of key-value *attributes* to add flexibility to the functionality expressed in the existing APIs. Accordingly, the ASC has chosen to require that the definition of each standard API include the passing of an array of attributes. These provide a means of customizing the behavior of the API as future needs emerge without having to alter or create new variants of it. In addition, attributes provide a mechanism by which researchers can easily explore new approaches to a given operation without having to modify the API itself.

In an effort to maintain long-term backward compatibility, PMIx does not include large numbers of APIs that each focus on a narrow scope of functionality, but instead relies on the definition of fewer generic APIs that include arrays of key-value attributes for "tuning" the function's behavior. Thus, modifications to the PMIx standard primarily consist of the definition of new attributes along with a description of the APIs to which they relate and the expected behavior when used with those APIs.

The following terminology is used throughout this document:

- session refers to a pool of resources with a unique identifier (a.k.a., the session ID) assigned by
 the WorkLoad Manager (WLM) that has been reserved for one or more users. Historically, High
 Performance Computing (HPC) sessions have consisted of a static allocation of resources e.g., a
 block of nodes assigned to a user in response to a specific request and managed as a unified
 collection. However, this is changing in response to the growing use of dynamic programming
 models that require on-the-fly allocation and release of system resources. Accordingly, the term
 session in this document refers to a potentially dynamic entity, perhaps comprised of resources
 accumulated as a result of multiple allocation requests that are managed as a single unit by the
 WLM.
- *job* refers to a set of one or more *applications* executed as a single invocation by the user within a session with a unique identifier (a.k.a, the *job ID*) assigned by the RM or launcher. For example, the command line "*mpiexec -n 1 app1 : -n 2 app2*" generates a single Multiple Program Multiple Data (MPMD) job containing two applications. A user may execute multiple *jobs* within a given session, either sequentially or in parallel.
- namespace refers to a character string value assigned by the RM or launcher (e.g., mpiexec) to a job. All applications executed as part of that job share the same namespace. The namespace assigned to each job must be unique within the scope of the governing RM and often is implemented as a string representation of a numerical job ID. The namespace and job terms will be used interchangeably throughout the document.
- application refers to a single executable (binary, script, etc.) member of a job.

- process refers to an operating system process, also commonly referred to as a heavyweight process. A process is often comprised of multiple lightweight threads, commonly known as simply threads.
 client refers to a process that was registered with the PMIx server prior to being started, and connects to that PMIx server via PMIx. Init using its assigned namespace and rank with formula.
 - connects to that PMIx server via **PMIx_Init** using its assigned namespace and rank with the information required to connect to that server being provided to the process at time of start of execution.
 - *tool* refers to a process that may or may not have been registered with the PMIx server prior to being started and intializes using **PMIx_tool_init**.
 - clone refers to a process that was directly started by a PMIx client (e.g., using fork/exec) and calls
 PMIx_Init, thus connecting to its local PMIx server using the same namespace and rank as its
 parent process.
 - rank refers to the numerical location (starting from zero) of a process within the defined scope. Thus, job rank is the rank of a process within its job and is synonymous with its unqualified rank, while application rank is the rank of that process within its application.
 - *peer* refers to another process within the same *job*.

- workflow refers to an orchestrated execution plan frequently involving multiple jobs carried out under the control of a workflow manager process. An example workflow might first execute a computational job to generate the flow of liquid through a complex cavity, followed by a visualization job that takes the output of the first job as its input to produce an image output.
- *scheduler* refers to the component of the SMS responsible for scheduling of resource allocations. This is also generally referred to as the *system workflow manager* for the purposes of this document, the *WLM* acronym will be used interchangeably to refer to the scheduler.
- resource manager is used in a generic sense to represent the subsystem that will host the PMIx server library. This could be a vendor-supplied resource manager or a third-party agent such as a programming model's runtime library.
- *host environment* is used interchangeably with *resource manager* to refer to the process hosting the PMIx server library.
- *node* refers to a single operating system instance. Note that this may encompass one or more physical objects.
- package refers to a single object that is either soldered or connected to a printed circuit board via a mechanical socket. Packages may contain multiple chips that include (but are not limited to) processing units, memory, and peripheral interfaces.
- processing unit, or PU, is the electronic circuitry within a computer that executes instructions. Depending upon architecture and configuration settings, it may consist of a single hardware thread or multiple hardware threads collectively organized as a core.

- *fabric* is used in a generic sense to refer to the networks within the system regardless of speed or protocol. Any use of the term *network* in the document should be considered interchangeable with *fabric*.
- fabric device (or fabric devices) refers to an operating system fabric interface, which may be physical or virtual. Any use of the term Network Interface Card (NIC) in the document should be considered interchangeable with fabric device.
- fabric plane refers to a collection of fabric devices in a common logical or physical configuration. Fabric planes are often implemented in HPC clusters as separate overlay or physical networks controlled by a dedicated fabric manager.
- attribute refers to a key-value pair comprised of a string key (represented by a pmix_key_t structure) and an associated value containing a PMIx data type (e.g., boolean, integer, or a more complex PMIx structure). Attributes are used both as directives when passed as qualifiers to APIs (e.g., in a pmix_info_t array), and to identify the contents of information (e.g., to specify that the contents of the corresponding pmix_value_t in a pmix_info_t represent the PMIX_UNIV_SIZE).
- key refers to the string component of a defined attribute. The PMIx Standard will often refer to passing of a key to an API (e.g., to the PMIx_Query_info or PMIx_Get APIs) as a means of identifying requested information. In this context, the data type specified in the attribute's definition indicates the data type the caller should expect to receive in return. Note that not all attributes can be used as keys as some have specific uses solely as API qualifiers.
- *instant on* refers to a PMIx concept defined as: "All information required for setup and communication (including the address vector of endpoints for every process) is available to each process at start of execution"

The following sections provide an overview of the conventions used throughout the PMIx Standard document.

2.1 Notational Conventions

Some sections of this document describe programming language specific examples or APIs. Tex	ίt
that applies only to programs for which the base language is C is shown as follows:	

C

C specific text...

int foo = 42;

Some text is for information only, and is not part of the normative specification. These take several forms, described in their examples below:

Note: General text... 1 Rationale Throughout this document, the rationale for the design choices made in the interface specification is 2 3 set off in this section. Some readers may wish to skip these sections, while readers interested in interface design may want to read them carefully. Advice to users 5 Throughout this document, material aimed at users and that illustrates usage is set off in this 6 section. Some readers may wish to skip these sections, while readers interested in programming 7 with the PMIx API may want to read them carefully. ——— Advice to PMIx library implementers ————— 8 Throughout this document, material that is primarily commentary to PMIx library implementers is 9 set off in this section. Some readers may wish to skip these sections, while readers interested in 10 PMIx implementations may want to read them carefully. - Advice to PMIx server hosts -----11 Throughout this document, material that is primarily commentary aimed at host environments (e.g., RMs and RunTime Environments (RTEs)) providing support for the PMIx server library is set off in 12 this section. Some readers may wish to skip these sections, while readers interested in integrating 13 14 PMIx servers into their environment may want to read them carefully. 15 Attributes added in this version of the standard are shown in *magenta* to distinguish them from 16 those defined in prior versions, which are shown in **black**. Deprecated attributes are shown in **green** and may be removed in a future version of the standard. 17 **Semantics** 19 The following terms will be taken to mean: • shall, must and will indicate that the specified behavior is required of all conforming 20 21 implementations 22 • should and may indicate behaviors that a complete implementation would include, but are not 23 required of all conforming implementations

2.3 Naming Conventions

- 2 The PMIx standard has adopted the following conventions:
 - PMIx constants and attributes are prefixed with **PMIX**.
 - Structures and type definitions are prefixed with pmix.
 - Underscores are used to separate words in a function or variable name.
 - Lowercase letters are used in PMIx client APIs except for the PMIx prefix (noted below) and the first letter of the word following it. For example, **PMIx_Get_version**.
 - PMIx server and tool APIs are all lower case letters following the prefix e.g.,
 PMIx_server_register_nspace.
 - The **PMIx** prefix is used to denote functions.
 - The **pmix**_ prefix is used to denote function pointer and type definitions.
- Users should not use the "PMIX", "PMIx", or "pmix" prefixes in their applications or libraries so as to avoid symbol conflicts with current and later versions of the PMIx Standard.

14 2.4 Procedure Conventions

While the current APIs are based on the C programming language, it is not the intent of the PMIx Standard to preclude the use of other languages. Accordingly, the procedure specifications in the PMIx Standard are written in a language-independent syntax with the arguments marked as IN, OUT, or INOUT. The meanings of these are:

- IN: The call may use the input value but does not update the argument from the perspective of the caller at any time during the calls execution,
- OUT: The call may update the argument but does not use its input value
- INOUT: The call may both use and update the argument.

Many PMIx interfaces, particularly nonblocking interfaces, use a **(void*)** callback data object passed to the function that is then passed to the associated callback. On the client side, the callback data object is an opaque, client-provided context that the client can pass to a non-blocking call. When the nonblocking call completes, the callback data object is passed back to the client without modification by the PMIx library, thus allowing the client to associate a context with that callback. This is useful if there are many outstanding nonblocking calls.

A similar model is used for the server module functions (see 16.3.1). In this case, the PMIx library is making an upcall into its host via the PMIx server module callback function and passing a specific callback function pointer and callback data object. The PMIx library expects the host to call the cbfunc with the necessary arguments and pass back the original callback data obect upon completing the operation. This gives the server-side PMIx library the ability to associate a context

with the call back (since multiple operations may be outstanding). The host has no visibility into the contents of the callback data object object, nor is permitted to alter it in any way.

CHAPTER 3

Data Structures and Types

1 2 3 4	This chapter defines PMIx standard data structures (along with macros for convenient use), types, and constants. These apply to all consumers of the PMIx interface. Where necessary for clarification, the description of, for example, an attribute may be copied from this chapter into a section where it is used.
5	A PMIx implementation may define additional attributes beyond those specified in this document. Advice to PMIx library implementers
6 7 8	Structures, types, and macros in the PMIx Standard are defined in terms of the C-programming language. Implementers wishing to support other languages should provide the equivalent definitions in a language-appropriate manner.
9 0 1 2	If a PMIx implementation chooses to define additional attributes they should avoid using the "PMIX" prefix in their name or starting the attribute string with a "pmix" prefix. This helps the end user distinguish between what is defined by the PMIx standard and what is specific to that PMIx implementation, and avoids potential conflicts with attributes defined by the Standard.
	Advice to users
3 4 5	Use of increment/decrement operations on indices inside PMIx macros is discouraged due to unpredictable behavior as the index may be cited more than once in the macro. The PMIx standard only governs the existence and syntax of macros - it does not specify their implementation.
6 7 8 9	Users are also advised to use the macros and APIs for creating, loading, and releasing PMIx structures to avoid potential issues with release of memory. For example, pointing a <code>pmix_envar_t</code> element at a static string variable and then using <code>PMIX_ENVAR_DESTRUCT</code> to clear it would generate an error as the static string had not been allocated.

1 3.1 Constants

2 3 4 5 6	PMIx defines a few values that are used throughout the standard to set the size of fixed arrays or as a means of identifying values with special meaning. The community makes every attempt to minimize the number of such definitions. The constants defined in this section may be used before calling any PMIx library initialization routine. Additional constants associated with specific data structures or types are defined in the section describing that data structure or type.
7	PMIX_MAX_NSLEN Maximum namespace string length as an integer.
	Advice to PMIx library implementers ————————————————————————————————————
8 9 10	PMIX_MAX_NSLEN should have a minimum value of 63 characters. Namespace arrays in PMIx defined structures must reserve a space of size PMIX_MAX_NSLEN+1 to allow room for the NULL terminator
11	PMIX_MAX_KEYLEN Maximum key string length as an integer. Advice to PMIx library implementers
12 13 14	PMIX_MAX_KEYLEN should have a minimum value of 63 characters. Key arrays in PMIx defined structures must reserve a space of size PMIX_MAX_KEYLEN+1 to allow room for the NULL terminator
15	PMIX_APP_WILDCARD A value to indicate that the user wants the data for the given key from

3.1.1 PMIx Return Status Constants

The pmix_status_t structure is an int type for return status. The tables shown in this section define the possible values for pmix_status_t. PMIx errors are required to always be negative, with 0 reserved for pmix_success. Values in the list that were deprecated in later standards are denoted as such. Values added to the list in this version of the standard are shown in magenta.

Advice to PMIx library implementers -

A PMIx implementation must define all of the constants defined in this section, even if they will never return the specific value to the caller.

Advice to users ———

Other than **PMIX_SUCCESS** (which is required to be zero), the actual value of any PMIx error constant is left to the PMIx library implementer. Thus, users are advised to always refer to constant by name, and not a specific implementation's value, for portability between implementations and compatibility across library versions.

The following values are general constants used in a variety of places.

PMIX SUCCESS Success.

PMIX ERROR General Error.

PMIX_ERR_EXISTS Requested operation would overwrite an existing value - typically returned when an operation would overwrite an existing file or directory.

PMIX_ERR_EXISTS_OUTSIDE_SCOPE The requested key exists, but was posted in a *scope* (see Section 7.1.1.1) that does not include the requester

PMIX_ERR_INVALID_CRED Invalid security credentials.

PMIX_ERR_WOULD_BLOCK Operation would block.

PMIX_ERR_UNKNOWN_DATA_TYPE The data type specified in an input to the PMIx library is not recognized by the implementation.

PMIX_ERR_TYPE_MISMATCH The data type found in an object does not match the expected data type as specified in the API call - e.g., a request to unpack a **PMIX_BOOL** value from a buffer that does not contain a value of that type in the current unpack location.

PMIX_ERR_UNPACK_INADEQUATE_SPACE Inadequate space to unpack data - the number of values in the buffer exceeds the specified number to unpack.

PMIX_ERR_UNPACK_READ_PAST_END_OF_BUFFER Unpacking past the end of the provided buffer - the number of values in the buffer is less than the specified number to unpack, or a request was made to unpack a buffer beyond the buffer's end.

PMIX ERR UNPACK FAILURE The unpack operation failed for an unspecified reason.

PMIX ERR PACK FAILURE The pack operation failed for an unspecified reason.

PMIX_ERR_NO_PERMISSIONS The user lacks permissions to execute the specified operation.

PMIX ERR TIMEOUT Either a user-specified or system-internal timeout expired.

1 The specified target server or client process is not reachable - i.e., a PMIX_ERR_UNREACH 2 suitable connection either has not been or can not be made. 3 PMIX ERR BAD PARAM One or more incorrect parameters (e.g., passing an attribute with a 4 value of the wrong type), or multiple parameters containing conflicting directives (e.g., 5 multiple instances of the same attribute with different values, or different attributes specifying 6 conflicting behaviors), were passed to a PMIx API. 7 PMIX ERR EMPTY An array or list was given that has no members in it - i.e., the object is 8 empty. 9 PMIX_ERR_RESOURCE_BUSY Resource busy - typically seen when an attempt to establish a connection to another process (e.g., a PMIx server) cannot be made due to a communication 10 11 failure. Resource exhausted. 12 PMIX_ERR_OUT_OF_RESOURCE Error during initialization. 13 PMIX ERR INIT 14 PMIX_ERR_NOMEM Out of memory. 15 PMIX ERR NOT FOUND The requested information was not found. 16 PMIX ERR NOT SUPPORTED The requested operation is not supported by either the PMIx 17 implementation or the host environment. 18 PMIX ERR PARAM VALUE NOT SUPPORTED The requested operation is supported by the PMIx implementation and (if applicable) the host environment. However, at least one 19 20 supplied parameter was given an unsupported value, and the operation cannot therefore be executed as requested. 21 PMIX ERR COMM FAILURE Communication failure - a message failed to be sent or 22 23 received, but the connection remains intact. 24 PMIX ERR LOST CONNECTION Lost connection between server and client or tool. 25 PMIX ERR INVALID OPERATION The requested operation is supported by the implementation and host environment, but fails to meet a requirement (e.g., requesting to 26 disconnect from processes without first connecting to them, inclusion of conflicting 27 28 directives, or a request to perform an operation that conflicts with an ongoing one). 29 PMIX OPERATION IN PROGRESS A requested operation is already in progress - the 30 duplicate request shall therefore be ignored. PMIX_OPERATION_SUCCEEDED The requested operation was performed atomically - no 31 32 callback function will be executed. 33 PMIX ERR PARTIAL SUCCESS The operation is considered successful but not all elements of the operation were concluded (e.g., some members of a group construct operation chose 34 35 not to participate). **User-Defined Error and Event Constants** 3.1.1.1 36 37 PMIx establishes a boundary for constants defined in the PMIx standard. Negative values larger (i.e., more negative) than this (and any positive values greater than zero) are guaranteed not to 38 conflict with PMIx values. 39 40 PMIX EXTERNAL ERR BASE A starting point for user-level defined error and event 41 constants. Negative values that are more negative than the defined constant are guaranteed not

to conflict with PMIx values. Definitions should always be based on the

1 **PMIX_EXTERNAL_ERR_BASE** constant and not a specific value as the value of the constant 2 may change.

3.2 Data Types

This section defines various data types used by the PMIx APIs. The version of the standard in which a particular data type was introduced is shown in the margin.

3.2.1 Key Structure

7 The pmix_key_t structure is a statically defined character array of length
8 PMIX_MAX_KEYLEN+1, thus supporting keys of maximum length PMIX_MAX_KEYLEN while
9 preserving space for a mandatory NULL terminator.

PMIx v2.0

5

10

17

18

19

21

typedef char pmix_key_t[PMIX_MAX_KEYLEN+1];

C

11 Characters in the key must be standard alphanumeric values supported by common utilities such as *strcmp*.

Advice to users


References to keys in PMIx v1 were defined simply as an array of characters of size

PMIX_MAX_KEYLEN+1. The pmix_key_t type definition was introduced in version 2 of the standard. The two definitions are code-compatible and thus do not represent a break in backward compatibility.

Passing a **pmix_key_t** value to the standard *sizeof* utility can result in compiler warnings of incorrect returned value. Users are advised to avoid using *sizeof(pmix_key_t)* and instead rely on the **PMIX_MAX_KEYLEN** constant.

0 3.2.1.1 Key support macros

The following macros are provided for convenience when working with PMIx keys.



3.2.2 Namespace Structure

The pmix_nspace_t structure is a statically defined character array of length 2 3 PMIX_MAX_NSLEN+1, thus supporting namespaces of maximum length PMIX_MAX_NSLEN 4 while preserving space for a mandatory **NULL** terminator. 5 typedef char pmix_nspace_t[PMIX_MAX_NSLEN+1]; 6 Characters in the namespace must be standard alphanumeric values supported by common utilities 7 such as *strcmp*. Advice to users 8 References to namespace values in PMIx v1 were defined simply as an array of characters of size 9 **PMIX MAX NSLEN+1.** The **pmix nspace t** type definition was introduced in version 2 of the standard. The two definitions are code-compatible and thus do not represent a break in backward 10 11 compatibility. 12 Passing a pmix_nspace_t value to the standard size of utility can result in compiler warnings of 13 incorrect returned value. Users are advised to avoid using *sizeof(pmix_nspace_t)* and instead rely on the PMIX MAX NSLEN constant. 14 3.2.2.1 Namespace support macros 15 16 The following macros are provided for convenience when working with PMIx namespace 17 structures. Check namespace macro 18 Compare the string in a **pmix_nspace_t** to a given value. 19 *PMIx v3.0* 20 PMIX CHECK NSPACE (a, b) IN 21 22 Pointer to the structure whose value is to be checked (pointer to pmix nspace t) 23 IN 24 String value to be compared against (**char***)

Returns **true** if the namespace matches the given value

1		Check invalid namespace macro
2		Check if the provided pmix_nspace_t is invalid.
3		PMIX_NSPACE_INVALID(a)
		<u> </u>
4		IN a
5		Pointer to the structure whose value is to be checked (pointer to pmix_nspace_t)
6 7		Returns true if the namespace is invalid (i.e., starts with a NULL resulting in a zero-length string value)
8		Load namespace macro
9		Load a namespace into a pmix_nspace_t.
	PMIx v4.0	C
10		PMIX_LOAD_NSPACE(a, b)
		C
11		IN a
12		Pointer to the target structure (pointer to <pre>pmix_nspace_t)</pre>
13 14		IN b
15		String value to be loaded - if NULL is given, then the target structure will be initialized to zero's (char*)
16		No return value.
		To letalli value.
17	3.2.3	Rank Structure
18		The pmix_rank_t structure is a uint32_t type for rank values.
	PMIx v1.0	C
19		<pre>typedef uint32_t pmix_rank_t;</pre>
		C
20		The following constants can be used to set a variable of the type pmix_rank_t . All definitions
21		were introduced in version 1 of the standard unless otherwise marked. Valid rank values start at
22		zero.
23		PMIX_RANK_UNDEF A value to request job-level data where the information itself is not
24		associated with any specific rank, or when passing a pmix_proc_t identifier to an
25 26		operation that only references the namespace field of that structure.
26 27		PMIX_RANK_WILDCARD A value to indicate that the user wants the data for the given key from every rank that posted that key.
28		PMIX_RANK_LOCAL_NODE Special rank value used to define groups of ranks. This constant
29		defines the group of all ranks on a local node.

```
1
                                              Special rank value used to define groups of ranks. This
               PMIX_RANK_LOCAL_PEERS
2
                    constant defines the group of all ranks on a local node within the same namespace as the
 3
                    current process.
 4
               PMIX RANK INVALID
                                         An invalid rank value.
 5
               PMIX_RANK_VALID
                                      Define an upper boundary for valid rank values.
    3.2.3.1
6
              Rank support macros
 7
               The following macros are provided for convenience when working with PMIx ranks.
               Check rank macro
8
9
               Check two ranks for equality, taking into account wildcard values
  PMIx v4.0
10
               PMIX CHECK RANK(a, b)
               IN
11
12
                    Rank to be checked (pmix_rank_t)
13
               IN
14
                    Rank to be checked (pmix_rank_t)
               Returns true if the ranks are equal, or at least one of the ranks is PMIX_RANK_WILDCARD
15
16
               Check rank is valid macro
               Check if the given rank is a valid value
17
  PMIx v4.1
               PMIX RANK IS VALID(a)
18
               IN
19
20
                    Rank to be checked (pmix_rank_t)
21
               Returns true if the given rank is valid (i.e., less than PMIX_RANK_VALID)
   3.2.4
             Process Structure
               The pmix_proc_t structure is used to identify a single process in the PMIx universe. It contains
23
24
               a reference to the namespace and the pmix_rank_t within that namespace.
  PMIx v1.0
25
               typedef struct pmix_proc {
26
                    pmix_nspace_t nspace;
27
                    pmix_rank_t rank;
               } pmix proc t;
28
```

3.2.4.1 **Process structure support macros** 2 The following macros are provided to support the **pmix_proc_t** structure. 3 Static initializer for the proc structure 4 (Provisional) 5 Provide a static initializer for the **pmix proc t** fields. PMIx v4.2 6 PMIX PROC STATIC INIT Initialize the proc structure 7 8 Initialize the **pmix_proc_t** fields. PMIx v1.0 9 PMIX PROC CONSTRUCT (m) IN m 10 Pointer to the structure to be initialized (pointer to **pmix_proc_t**) 11 12 Destruct the proc structure Destruct the **pmix_proc_t** fields. 13 14 PMIX PROC DESTRUCT (m) 15 IN 16 Pointer to the structure to be destructed (pointer to pmix proc t) 17 There is nothing to release here as the fields in pmix_proc_t are either a statically-declared array (the 18 namespace) or a single value (the rank). However, the macro is provided for symmetry in the code and for 19 future-proofing should some allocated field be included some day. 20 Create a proc array Allocate and initialize an array of **pmix proc** t structures. 21 PMIx v1.0 22 PMIX PROC CREATE (m, n) 23 INOUT m Address where the pointer to the array of **pmix_proc_t** structures shall be stored (handle) 24 25 IN 26 Number of structures to be allocated (size_t)

1 2	Free a proc structure Release a pmix_proc_t structure. C
3	PMIX_PROC_RELEASE (m)
4 5	IN m Pointer to a pmix_proc_t structure (handle)
6 7 <i>PMIx v1.0</i>	Free a proc array Release an array of pmix_proc_t structures. C
8	PMIX_PROC_FREE (m, n)
9 10 11 12	IN m Pointer to the array of pmix_proc_t structures (handle) IN n Number of structures in the array (size_t)
13 14 <i>PMIx v2.0</i>	Load a proc structure Load values into a pmix_proc_t. C
15	PMIX_PROC_LOAD(m, n, r)
16 17 18 19 20 21	<pre>IN m Pointer to the structure to be loaded (pointer to pmix_proc_t) IN n Namespace to be loaded (pmix_nspace_t) IN r Rank to be assigned (pmix_rank_t)</pre>
22	No return value. Deprecated in favor of PMIX_LOAD_PROCID
23 24 <i>PMIx v3.0</i>	Compare identifiers Compare two pmix_proc_t identifiers.



```
Transfer a procID structure
 1
 2
                Transfer contents of one pmix_proc_t value to another pmix_proc_t.
                PMIX_PROCID_XFER(d, s)
 3
 4
                IN
                      d
 5
                      Pointer to the target structure (pointer to pmix proc t)
 6
                IN
                      Pointer to the source structure (pointer to pmix_proc_t)
                Construct a multi-cluster namespace
 8
                Construct a multi-cluster identifier containing a cluster ID and a namespace.
 9
   PMIx v4.0
                PMIX_MULTICLUSTER_NSPACE_CONSTRUCT(m, n, r)
10
11
                IN
12
                      pmix_nspace_t structure that will contain the multi-cluster identifier (pmix_nspace_t)
                IN
13
14
                      Cluster identifier (char*)
15
                IN
16
                      Namespace to be loaded (pmix_nspace_t)
17
                Combined length of the cluster identifier and namespace must be less than PMIX MAX NSLEN-2.
                Parse a multi-cluster namespace
18
                Parse a multi-cluster identifier into its cluster ID and namespace parts.
19
   PMIx v4.0
20
                PMIX MULTICLUSTER NSPACE PARSE (m, n, r)
21
                IN
22
                      pmix_nspace_t structure containing the multi-cluster identifier (pointer to pmix_nspace_t)
23
                IN
                      Location where the cluster ID is to be stored (pmix_nspace_t)
24
25
                IN
                      Location where the namespace is to be stored (pmix_nspace_t)
26
```

3.2.5 Process State Structure

PMIX_PROC_STATE_FAILED_TO_LAUNCH

2

3

4 5

6

7

8

9

10

11

12

13

14

15 16

17

18 19

20

21

22

23

24

25

26

27

28 29

30

31

32

The pmix_proc_state_t structure is a uint8_t type for process state values. The following constants can be used to set a variable of the type pmix_proc_state_t.

Advice to users -

The fine-grained nature of the following constants may exceed the ability of an RM to provide updated process state values during the process lifetime. This is particularly true of states for short-lived processes.

```
PMIX PROC STATE UNDEF
                              Undefined process state.
PMIX PROC STATE PREPPED
                                 Process is ready to be launched.
PMIX_PROC_STATE_LAUNCH_UNDERWAY
                                           Process launch is underway.
                                 Process is ready for restart.
PMIX_PROC_STATE_RESTART
PMIX_PROC_STATE_TERMINATE
                                   Process is marked for termination.
PMIX PROC STATE RUNNING
                                 Process has been locally fork'ed by the RM.
PMIX_PROC_STATE_CONNECTED
                                   Process has connected to PMIx server.
PMIX PROC STATE UNTERMINATED
                                       Define a "boundary" between the terminated states and
     PMIX PROC STATE CONNECTED so users can easily and quickly determine if a process is still
     running or not. Any value less than this constant means that the process has not terminated.
PMIX PROC STATE TERMINATED
                                     Process has terminated and is no longer running.
                              Define a boundary so users can easily and quickly determine if a process
PMIX PROC STATE ERROR
     abnormally terminated. Any value above this constant means that the process has terminated abnormally.
PMIX PROC STATE KILLED BY CMD
                                         Process was killed by a command.
                                 Process was aborted by a call to PMIx Abort.
PMIX PROC STATE ABORTED
PMIX PROC STATE FAILED TO START
                                           Process failed to start.
PMIX_PROC_STATE_ABORTED_BY_SIG
                                          Process aborted by a signal.
                                       Process exited without calling PMIx_Finalize.
PMIX PROC STATE TERM WO SYNC
PMIX PROC STATE COMM FAILED
                                      Process communication has failed.
PMIX_PROC_STATE_SENSOR_BOUND_EXCEEDED
                                                   Process exceeded a specified sensor limit.
PMIX PROC STATE CALLED ABORT
                                       Process called PMIx Abort.
PMIX_PROC_STATE_HEARTBEAT_FAILED
                                            Frocess failed to send heartbeat within specified time
PMIX PROC STATE MIGRATING
                                   Process failed and is waiting for resources before restarting.
                                          Process failed and cannot be restarted.
PMIX_PROC_STATE_CANNOT_RESTART
PMIX PROC STATE TERM NON ZERO
                                         Process exited with a non-zero status.
```

Unable to launch process.

3.2.6 Process Information Structure

```
2
               The pmix proc info t structure defines a set of information about a specific process including it's name,
 3
               location, and state.
 4
               typedef struct pmix proc info {
 5
                    /** Process structure */
 6
                    pmix_proc_t proc;
 7
                    /** Hostname where process resides */
 8
                    char *hostname;
 9
                    /** Name of the executable */
10
                    char *executable name;
11
                    /** Process ID on the host */
12
                    pid_t pid;
13
                    /** Exit code of the process. Default: 0 */
14
                    int exit_code;
15
                    /** Current state of the process */
16
                    pmix_proc_state_t state;
17
               } pmix proc info t;
     3.2.6.1
                Process information structure support macros
18
19
               The following macros are provided to support the pmix_proc_info_t structure.
               Static initializer for the proc info structure
20
21
               (Provisional)
22
               Provide a static initializer for the pmix proc info t fields.
  PMIx v4.2
23
               PMIX PROC INFO STATIC INIT
               Initialize the process information structure
24
               Initialize the pmix_proc_info_t fields.
25
  PMIx v2.0
               PMIX PROC INFO CONSTRUCT (m)
26
27
               IN
28
                    Pointer to the structure to be initialized (pointer to pmix_proc_info_t)
```



3.2.7 Job State Structure

The pmix_job_state_t structure is a uint8_t type for job state values. The following constants can be used to set a variable of the type pmix_job_state_t.

Advice to users –

The fine-grained nature of the following constants may exceed the ability of an RM to provide updated job state values during the job lifetime. This is particularly true for short-lived jobs.

```
Undefined job state.
PMIX JOB STATE UNDEF
PMIX JOB STATE AWAITING ALLOC
                                          Job is waiting for resources to be allocated to it.
PMIX JOB STATE LAUNCH UNDERWAY
                                            Job launch is underway.
PMIX JOB STATE RUNNING
                                 All processes in the job have been spawned and are executing.
                                    All processes in the job have been suspended.
PMIX_JOB_STATE_SUSPENDED
PMIX JOB STATE CONNECTED
                                    All processes in the job have connected to their PMIx server.
                                        Define a "boundary" between the terminated states and
PMIX_JOB_STATE_UNTERMINATED
     PMIX_JOB_STATE_TERMINATED so users can easily and quickly determine if a job is still running
     or not. Any value less than this constant means that the job has not terminated.
                                     All processes in the job have terminated and are no longer running -
PMIX JOB STATE TERMINATED
     typically will be accompanied by the job exit status in response to a query.
```

PMIX JOB STATE TERMINATED WITH ERROR Define a boundary so users can easily and quickly determine if a job abnormally terminated - typically will be accompanied by a job-related error code in response to a query Any value above this constant means that the job terminated abnormally.

3.2.8 Value Structure

The pmix value t structure is used to represent the value passed to PMIx Put and retrieved by PMIx_Get, as well as many of the other PMIx functions.

A collection of values may be specified under a single key by passing a pmix_value_t containing an array of type pmix data array t, with each array element containing its own object. All members shown below were introduced in version 1 of the standard unless otherwise marked.

PMIx v1.0

1

2

3

4 5

6

7

8

9

10

11

12

13

14

15

16

17

18

19

20 21

22

23

24

```
1
             typedef struct pmix_value {
2
                 pmix data type t type;
 3
                 union {
4
                      bool flag;
5
                      uint8_t byte;
6
                      char *string;
7
                      size_t size;
8
                      pid_t pid;
9
                      int integer;
10
                      int8_t int8;
11
                      int16_t int16;
12
                      int32_t int32;
13
                      int64_t int64;
14
                      unsigned int uint;
15
                      uint8_t uint8;
16
                      uint16 t uint16;
17
                      uint32_t uint32;
18
                      uint64_t uint64;
19
                      float fval:
20
                      double dval;
21
                      struct timeval tv;
22
                                                       // version 2.0
                      time_t time;
23
                                                       // version 2.0
                      pmix_status_t status;
24
                      pmix_rank_t rank;
                                                       // version 2.0
25
                                                        // version 2.0
                      pmix_proc_t *proc;
26
                      pmix_byte_object_t bo;
27
                      pmix_persistence_t persist;
                                                       // version 2.0
28
                                                        // version 2.0
                      pmix_scope_t scope;
29
                                                       // version 2.0
                      pmix_data_range_t range;
30
                      pmix proc state t state;
                                                        // version 2.0
31
                      pmix_proc_info_t *pinfo;
                                                       // version 2.0
32
                      pmix_data_array_t *darray;
                                                        // version 2.0
33
                      void *ptr;
                                                        // version 2.0
                      pmix_alloc_directive_t adir;
34
                                                        // version 2.0
35
                 } data;
36
             } pmix_value_t;
```

3.2.8.1 Value structure support

The following macros and APIs are provided to support the **pmix_value_t** structure.

Static initializer for the value structure

(Provisional)

Provide a static initializer for the **pmix_value_t** fields.

PMIx v4.2

37 38

39 40

	· ·
1	PMIX_VALUE_STATIC_INIT
	S Comments
2	Initialize the value structure
3	Initialize the pmix_value_t fields.
PMIx v1.0	- C
4	DMTV VALUE CONCEDUCE ()
4	PMIX_VALUE_CONSTRUCT (m)
	- C
_	
5	IN m
6	Pointer to the structure to be initialized (pointer to pmix_value_t)
	5
7	Destruct the value structure
8	Destruct the pmix_value_t fields.
PMIx v1.0	C
	· ·
9	PMIX_VALUE_DESTRUCT(m)
	<u> </u>
10	IN m
11	Pointer to the structure to be destructed (pointer to pmix_value_t)
	•
12	Create a value array
13	Allocate and initialize an array of pmix_value_t structures.
PMIx v1.0	
I MIX VI.O	·
14	PMIX_VALUE_CREATE(m, n)
	S Comments
15	INOUT m
16	Address where the pointer to the array of pmix_value_t structures shall be stored (handle)
17	•••
18	Number of structures to be allocated (size_t)
10	Error o volue etructuro
19	Free a value structure
20	Release a pmix_value_t structure.
PMIx v4.0	C —
14	
21	PMIX_VALUE_RELEASE (m)
	C
22	IN m
23	Pointer to a pmix_value_t structure (handle)

```
Free a value array
 1
 2
                Release an array of pmix_value_t structures.
 3
                PMIX VALUE FREE (m, n)
                IN
 5
                     Pointer to the array of pmix_value_t structures (handle)
 6
                IN
 7
                     Number of structures in the array (size_t)
                Load a value structure
 8
                Summary
 9
                Load data into a pmix value t structure.
10
11
                Format
    PMIx v4.2
12
                pmix_status_t
13
                PMIx_Value_load(pmix_value_t *val,
14
                                    const void *data,
15
                                     pmix_data_type_t type);
16
                     val
17
                     The pmix_value_t into which the data is to be loaded (pointer to pmix_value_t)
18
                IN
                     Pointer to the data value to be loaded (handle)
19
20
                IN
21
                     Type of the provided data value (pmix data type t)
22
                Returns PMIX_SUCCESS or a negative value corresponding to a PMIx error constant.
                Description
23
                Copy the provided data into the pmix_value_t. Any data stored in the source value can be modified or
24
                free'd without affecting the copied data once the function has completed.
25
                Unload a value structure
26
27
                Summary
28
                Unload data from a pmix_value_t structure.
```

1	Format C	
2 3 4 5	<pre>pmix_status_t PMIx_Value_unload(pmix_value_t *val,</pre>	
6 7 8 9 10 11	IN val The pmix_value_t from which the data is to be unloaded () INOUT data Pointer to the location where the data value is to be returned (h INOUT sz Pointer to return the size of the unloaded value (handle)	andle)
13 14 15	Returns PMIX_SUCCESS or a negative value corresponding to a PM Description Return a copy of the data in the pmix_value_t. The source value affecting the copied data once the function has completed.	
16 17	Memory will be allocated and the pointer to that data will be in the d pmix_value_t will not be altered. The user is responsible for rele	2
18 19 20	Transfer data between value structures Summary Transfer the data value between two pmix_value_t structures.	
21 <i>PMIx v4.2</i>	Pormat C	
22 23 24	<pre>pmix_status_t PMIx_Value_xfer(pmix_value_t *dest,</pre>	·
25 26 27 28	<pre>IN dest Pointer to the pmix_value_t destination (handle) IN src Pointer to the pmix_value_t source (handle)</pre>	
29	Returns PMIX_SUCCESS or a negative value corresponding to a PM	IIx error constant.
30 31 32	Description Copy the data in the source pmix_value_t into the destination pm modified or free'd without affecting the copied data once the function	

```
Retrieve a numerical value from a value struct
 1
 2
                Retrieve a numerical value from a pmix_value_t structure.
 3
                PMIX VALUE GET NUMBER(s, m, n, t)
                OUT s
 5
                     Status code for the request (pmix_status_t)
 6
 7
                     Pointer to thepmix_value_t structure (handle)
 8
                OUT n
 9
                     Variable to be set to the value (match expected type)
                IN
10
11
                     Type of number expected in m (pmix data type t)
12
                Sets the provided variable equal to the numerical value contained in the given pmix_value_t, returning
13
                success if the data type of the value matches the expected type and PMIX_ERR_BAD_PARAM if it doesn't
                Info Structure
     3.2.9
                The pmix_info_t structure defines a key/value pair with associated directive. All fields were defined in
15
16
                version 1.0 unless otherwise marked.
    PMIx v1.0
17
                typedef struct pmix_info_t {
18
                     pmix_key_t key;
19
                     pmix_info_directives_t flags; // version 2.0
20
                     pmix_value_t value;
21
                } pmix_info_t;
     3.2.9.1
                Info structure support macros
22
23
                The following macros are provided to support the pmix_info_t structure.
                Static initializer for the info structure
24
25
                (Provisional)
26
                Provide a static initializer for the pmix_info_t fields.
    PMIx v4.2
                PMIX INFO STATIC INIT
27
```

1 2	Initialize the info structure Initialize the pmix_info_t fields.
3	PMIX_INFO_CONSTRUCT (m)
4 5	<pre>IN m Pointer to the structure to be initialized (pointer to pmix_info_t)</pre>
6 7 <i>PMIx v1.0</i>	Destruct the info structure Destruct the pmix_info_t fields.
8	PMIX_INFO_DESTRUCT (m)
9 10	<pre>IN m Pointer to the structure to be destructed (pointer to pmix_info_t)</pre>
11 12 <i>PMIx v1.0</i>	Create an info array Allocate and initialize an array of info structures.
13	PMIX_INFO_CREATE(m, n)
14 15 16 17	INOUT m Address where the pointer to the array of pmix_info_t structures shall be stored (handle) IN n Number of structures to be allocated (size_t)
18 19 <i>PMIx v1.0</i>	Free an info array Release an array of pmix_info_t structures.
20	PMIX_INFO_FREE(m, n)
21 22 23 24	<pre>IN m Pointer to the array of pmix_info_t structures (handle) IN n Number of structures in the array (size_t)</pre>
25 26 27	Load key and value data into a info struct Summary Load data into a pmix_info_t structure.

```
Format
 1
 2
                pmix status t
 3
                PMIx_Info_load(pmix_info_t *info,
 4
                                   const char* key,
 5
                                   const void *data,
 6
                                   pmix_data_type_t type);
 7
                     info
 8
                     The pmix_info_t into which the data is to be loaded (handle)
 9
                IN
10
                     Pointer to the key to be loaded (handle)
                IN
11
                     Pointer to the data value to be loaded (handle)
12
                IN
13
                     type
14
                     Type of the provided data value (pmix_data_type_t)
15
                Returns PMIX SUCCESS or a negative value corresponding to a PMIx error constant.
                Description
16
17
                Copy the provided data into the pmix_info_t. Any data stored in the source parameters can be modified or
                free'd without affecting the copied data once the function has completed. Passing NULL as the data
18
19
                parameter with a PMIX_BOOL type will set the associated info to true. This is a shorthand for the
20
                following where NULL replaces an explicit variable true_value:
21
                // A PMIX_BOOL with a NULL data is equivalent to an explicit true data
22
                  bool true value = true;
23
                  PMIX Info load(&info1, PMIX SESSION INFO, &true value, PMIX BOOL);
                  PMIX_Info_load(&info2, PMIX_SESSION_INFO, NULL, PMIX_BOOL);
24
                Copy data between info structures
25
                Summary
26
27
                Copy all data between two pmix info t structures.
28
                Format
    PMIx v4.2
29
                pmix_status_t
30
                PMIx_Info_xfer(pmix_info_t *dest,
31
                                  pmix_info_t *src);
32
                IN
                     dest
33
                     The pmix_info_t into which the data is to be copied (handle)
34
                IN
35
                     The pmix_info_t from which the data is to be copied (handle)
36
                Returns PMIX SUCCESS or a negative value corresponding to a PMIx error constant.
```

1 2 3	Description Copy the data in the source pmix_info_t into the destination. Any data stored in the source structure can be modified or free'd without affecting the copied data once the function has completed.
4 5 <i>PMIx v2.0</i>	Test a boolean info struct A special macro for checking if a boolean pmix_info_t is true.
6	PMIX_INFO_TRUE (m)
7 8	IN m Pointer to a pmix_info_t structure (handle)
9	A pmix_info_t structure is considered to be of type PMIX_BOOL and value true if:
10 11	 the structure reports a type of PMIX_UNDEF, or the structure reports a type of PMIX_BOOL and the data flag is true
12 3.2.9.	2 Info structure list macros
13 14	Constructing an array of <code>pmix_info_t</code> is a fairly common operation. The following macros are provided to simplify this construction.
15 16 17 18	Start a list of pmix_info_t structures Summary Initialize a list of pmix_info_t structures. The actual list is opaque to the caller and is implementation-dependent.
19 _{PMIx v4.2}	Format C
20 21	<pre>void* PMIx_Info_list_start(void);</pre>
22 23 24	Description Note that the returned pointer will be initialized to an opaque structure whose elements are implementation-dependent. The caller must not modify or dereference the object.
25 26 27	Add a pmix_info_t structure to a list Summary Add a pmix_info_t structure containing the specified value to the provided list.

```
Format
 1
 2
                pmix status t
 3
                PMIx_Info_list_add(void *ptr,
 4
                                        const char *key,
 5
                                         const void *value,
 6
                                        pmix data type t type);
 7
 8
                     A void* pointer initialized via PMIx Info list start (handle)
 9
                IN
                     String key to be loaded - must be less than or equal to PMIX_MAX_KEYLEN in length (handle)
10
                IN
11
                     Pointer to the data value to be loaded (handle)
12
                IN
13
                     type
                     Type of the provided data value (pmix_data_type_t)
14
                Returns PMIX SUCCESS or a negative value corresponding to a PMIx error constant.
15
                Description
16
17
                Copy the provided key and data into a pmix_info_t on the list. The key and any data stored in the source
                value can be modified or free'd without affecting the copied data once the function has completed.
18
                Transfer a pmix_info_t structure to a list
19
20
                Summary
                Transfer the information in a pmix_info_t structure to a structure on the provided list.
21
                Format
22
    PMIx v4.2
23
                pmix_status_t
24
                PMIx_Info_list_xfer(void *ptr,
                         const pmix_info_t *src);
25
26
                IN
                     A void* pointer initialized via PMIx_Info_list_start (handle)
27
28
                IN
                     Pointer to the source pmix_info_t (pointer to pmix_info_t)
29
30
                Returns PMIX_SUCCESS or a negative value corresponding to a PMIx error constant.
                Description
31
32
                All data (including key, value, and directives) will be copied into a destination pmix_info_t on the list. The
33
                source pmix_info_t may be free'd without affecting the copied data once the function has completed.
                Convert a pmix info t list to an array
34
                Summary
35
36
                Transfer the information in the provided pmix info t list to a pmix data array t array
```

```
Format
 1
 2
                 pmix status t
 3
                 PMIx_Info_list_convert(void *ptr,
 4
                                              pmix_data_array_t *par);
 5
                 IN
 6
                      A void* pointer initialized via PMIx Info list start (handle)
 7
                 IN
                     par
 8
                      Pointer to an instantiated pmix_data_array_t structure where the pmix_info_t array is to be
 9
                      stored (pointer to pmix_data_array_t
                 Returns PMIX SUCCESS or a negative value corresponding to a PMIx error constant.
10
                 Description
11
12
                 Information collected in the provided list of pmix info t will be transferred to a pmix data array t
                 containing pmix info t structures.
13
                 Release a pmix_info_t list
14
                 Summary
15
16
                 Release the provided pmix_info_t list
17 <sub>PMIx v4.2</sub>
                 Format
18
                 void
                 PMIx_Info_list_release(void *ptr);
19
20
                 IN
                      A void* pointer initialized via PMIx Info_list_start (handle)
21
22
                 Description
23
                 Information contained in the pmix_info_t on the list shall be released in addition to whatever backing
24
                 storage the implementation may have allocated to support construction of the list.
                  Info Type Directives
      3.2.10
25
26 PMIx v2.0
                 The pmix info directives t structure is a uint32 t type that defines the behavior of command
27
                 directives via pmix info t arrays. By default, the values in the pmix info t array passed to a PMIx are
28
                 optional.
                                          Advice to users
29
                 A PMIx implementation or PMIx-enabled RM may ignore any pmix info t value passed to a PMIx API
30
                 that it does not support or does not recognize if it is not explicitly marked as PMIX_INFO_REQD. This is
31
                 because the values specified default to optional, meaning they can be ignored in such circumstances. This may
32
                 lead to unexpected behavior when porting between environments or PMIx implementations if the user is
33
                 relying on the behavior specified by the pmix_info_t value. Users relying on the behavior defined by the
34
                 pmix info t are advised to set the PMIX INFO REQD flag using the PMIX INFO REQUIRED macro.
```

Advice to PMIx library implementers 1 The top 16-bits of the pmix_info_directives_t are reserved for internal use by PMIx library 2 implementers - the PMIx standard will not specify their intent, leaving them for customized use by 3 implementers. Implementers are advised to use the provided PMIX_INFO_IS_REQUIRED macro for testing 4 this flag, and must return PMIX ERR NOT SUPPORTED as soon as possible to the caller if the required 5 behavior is not supported. 6 The following constants were introduced in version 2.0 (unless otherwise marked) and can be used to set a 7 variable of the type **pmix_info_directives_t**. 8 PMIX INFO REQD The behavior defined in the **pmix** info t array is required, and not optional. This 9 is a bit-mask value. 10 PMIX INFO REOD PROCESSED Mark that this required attribute has been processed. A required 11 attribute can be handled at any level - the PMIx client library might take care of it, or it may be resolved 12 by the PMIx server library, or it may pass up to the host environment for handling. If a level does not 13 recognize or support the required attribute, it is required to pass it upwards to give the next level an 14 opportunity to process it. Thus, the host environment (or the server library if the host does not support 15 the given operation) must know if a lower level has handled the requirement so it can return a 16 PMIX ERR NOT SUPPORTED error status if the host itself cannot meet the request. Upon processing 17 the request, the level must therefore mark the attribute with this directive to alert any subsequent levels 18 that the requirement has been met. PMIX INFO ARRAY END 19 Mark that this **pmix** info t struct is at the end of an array created by the 20 PMIX_INFO_CREATE macro. This is a bit-mask value. 21 A bit-mask identifying the bits reserved for internal use by implementers PMIX INFO DIR RESERVED 22 - these currently are set as **0xffff0000**. -Advice to PMIx server hosts-23 Host environments are advised to use the provided PMIX INFO IS REQUIRED macro for testing this flag 24 and must return PMIX ERR NOT SUPPORTED as soon as possible to the caller if the required behavior is 25 not supported. 3.2.10.1 Info Directive support macros 26 27 The following macros are provided to support the setting and testing of **pmix info t** directives. Mark an info structure as required 28 29 Set the PMIX_INFO_REQD flag in a pmix_info_t structure. PMIx v2.0 PMIX_INFO_REQUIRED(info); 30 31 IN info

Pointer to the pmix_info_t (pointer to pmix_info_t)

This macro simplifies the setting of the PMIX INFO REOD flag in pmix info t structures.

32

```
Mark an info structure as optional
 1
 2
                Unsets the PMIX_INFO_REQD flag in a pmix_info_t structure.
   PMIx v2.0
 3
                PMIX_INFO_OPTIONAL(info);
                IN
                     info
 5
                     Pointer to the pmix_info_t (pointer to pmix_info_t)
 6
                This macro simplifies marking a pmix info t structure as optional.
                Test an info structure for required directive
                Test the PMIX_INFO_REQD flag in a pmix_info_t structure, returning true if the flag is set.
   PMIx v2.0
 9
                PMIX_INFO IS_REQUIRED(info);
10
                IN
                     info
11
                     Pointer to the pmix_info_t (pointer to pmix_info_t)
12
                This macro simplifies the testing of the required flag in pmix_info_t structures.
                Test an info structure for optional directive
13
                Test a pmix_info_t structure, returning true if the structure is optional.
14
   PMIx v2.0
15
                PMIX_INFO_IS_OPTIONAL(info);
16
                IN
                     info
17
                     Pointer to the pmix_info_t (pointer to pmix_info_t)
18
                Test the PMIX_INFO_REQD flag in a pmix_info_t structure, returning true if the flag is not set.
                Mark a required attribute as processed
19
                Mark that a required pmix_info_t structure has been processed.
20
   PMIx v4.0
21
                PMIX INFO PROCESSED (info);
22
                     info
23
                     Pointer to the pmix_info_t (pointer to pmix_info_t)
24
                Set the PMIX_INFO_REQD_PROCESSED flag in a pmix_info_t structure indicating that is has been
25
                processed.
```

```
Test if a required attribute has been processed
 1
 2
                Test that a required pmix_info_t structure has been processed.
                PMIX_INFO_WAS_PROCESSED(info);
 3
                IN
                     info
 5
                      Pointer to the pmix info t (pointer to pmix info t)
 6
                Test the PMIX INFO REQD PROCESSED flag in a pmix info t structure.
                Test an info structure for end of array directive
 7
 8
                Test a pmix_info_t structure, returning true if the structure is at the end of an array created by the
 9
                PMIX INFO CREATE macro.
    PMIx v2.2
10
                PMIX_INFO IS END(info);
11
                      info
12
                      Pointer to the pmix_info_t (pointer to pmix_info_t)
13
                This macro simplifies the testing of the end-of-array flag in pmix_info_t structures.
      3.2.11
                  Environmental Variable Structure
14
    PMIx v3.0
15
                Define a structure for specifying environment variable modifications. Standard environment variables (e.g.,
16
                PATH, LD_LIBRARY_PATH, and LD_PRELOAD) take multiple arguments separated by delimiters.
17
                Unfortunately, the delimiters depend upon the variable itself - some use semi-colons, some colons, etc. Thus,
18
                the operation requires not only the name of the variable to be modified and the value to be inserted, but also
19
                the separator to be used when composing the aggregate value.
20
                typedef struct {
21
                      char *envar;
22
                      char *value;
23
                      char separator;
24
                 } pmix_envar_t;
```

3.2.11.1 Environmental variable support macros

25 26

The following macros are provided to support the **pmix_envar_t** structure.

1 2	Static initializer for the envar structure (Provisional)
3	Provide a static initializer for the pmix_envar_t fields.
4	PMIX_ENVAR_STATIC_INIT
5	Initialize the envar structure
6 <i>PMIx v3.0</i>	Initialize the pmix_envar_t fields.
7	PMIX_ENVAR_CONSTRUCT (m)
8 9	IN m Pointer to the structure to be initialized (pointer to pmix_envar_t)
10 11	Destruct the envar structure
<i>PMIx v3.0</i>	Clear the pmix_envar_t fields.
12	PMIX_ENVAR_DESTRUCT (m)
13 14	<pre>IN m Pointer to the structure to be destructed (pointer to pmix_envar_t)</pre>
15 16 <i>PMIx v3.0</i>	Create an envar array Allocate and initialize an array of pmix_envar_t structures.
1 MIX V3.0	PMIX_ENVAR_CREATE(m, n)
18 19 20 21	INOUT m Address where the pointer to the array of pmix_envar_t structures shall be stored (handle) IN n Number of structures to be allocated (size_t)
22 23	Free an envar array Release an array of pmix_envar_t structures.
<i>PMIx v3.0</i>	PMIX_ENVAR_FREE(m, n)
	C
25 26 27	<pre>IN m Pointer to the array of pmix_envar_t structures (handle) IN n</pre>
28	Number of structures in the array (size_t)

```
Load an envar structure
 1
 2
               Load values into a pmix_envar_t.
    PMIx v2.0
 3
               PMIX ENVAR LOAD (m, e, v, s)
               IN
 5
                    Pointer to the structure to be loaded (pointer to pmix_envar_t)
 6
               IN
 7
                    Environmental variable name (char*)
 8
               IN
 9
                     Value of variable (char*)
               IN
10
11
                    Separator character (char)
     3.2.12
                 Byte Object Type
12
               The pmix_byte_object_t structure describes a raw byte sequence.
13
    PMIx v1.0
14
               typedef struct pmix_byte_object {
15
                    char *bytes;
16
                    size_t size;
17
                } pmix_byte_object_t;
     3.2.12.1 Byte object support macros
18
19
               The following macros support the pmix_byte_object_t structure.
               Static initializer for the byte object structure
20
21
               (Provisional)
22
               Provide a static initializer for the pmix_byte_object_t fields.
    PMIx v4.2
23
               PMIX BYTE OBJECT STATIC INIT
               Initialize the byte object structure
24
25
               Initialize the pmix_byte_object_t fields.
    PMIx v2.0
26
               PMIX_BYTE_OBJECT_CONSTRUCT (m)
27
               IN
28
                    Pointer to the structure to be initialized (pointer to pmix_byte_object_t)
```

```
Destruct the byte object structure
 2
                Clear the pmix_byte_object_t fields.
 3
                PMIX BYTE OBJECT DESTRUCT (m)
                IN
 5
                     Pointer to the structure to be destructed (pointer to pmix byte object t)
                Create a byte object structure
                Allocate and intitialize an array of pmix_byte_object_t structures.
   PMIx v2.0
 8
                PMIX BYTE OBJECT CREATE (m, n)
 9
                INOUT m
10
                     Address where the pointer to the array of pmix_byte_object_t structures shall be stored (handle)
11
                IN
12
                     Number of structures to be allocated (size_t)
                Free a byte object array
13
                Release an array of pmix_byte_object_t structures.
14
   PMIx v2.0
15
                PMIX BYTE OBJECT FREE (m, n)
16
                IN
17
                     Pointer to the array of pmix_byte_object_t structures (handle)
18
                IN
19
                     Number of structures in the array (size_t)
                Load a byte object structure
20
                Load values into a pmix_byte_object_t.
21
   PMIx v2.0
22
                PMIX BYTE OBJECT LOAD (b, d, s)
23
                IN
24
                     Pointer to the structure to be loaded (pointer to pmix byte object t)
25
                IN
26
                     Pointer to the data to be loaded (char*)
27
                IN
28
                     Number of bytes in the data array (size_t)
```

3.2.13 Data Array Structure

```
2
                The pmix data array t structure defines an array data structure.
 3
                typedef struct pmix_data_array {
 4
                     pmix_data_type_t type;
 5
                     size_t size;
 6
                     void *array;
 7
                } pmix_data_array_t;
     3.2.13.1 Data array support macros
 8
 9
                The following macros support the pmix_data_array_t structure.
                Static initializer for the data array structure
10
11
                (Provisional)
12
                Provide a static initializer for the pmix_data_array_t fields.
    PMIx v4.2
13
                PMIX DATA ARRAY STATIC INIT
                Initialize a data array structure
14
15
                Initialize the pmix_data_array_t fields, allocating memory for the array of the indicated type.
    PMIx v2.2
16
                PMIX_DATA_ARRAY_CONSTRUCT(m, n, t)
17
                IN
18
                     Pointer to the structure to be initialized (pointer to pmix_data_array_t
                IN
19
20
                     Number of elements in the array (size_t)
21
                IN
22
                     PMIx data type of the array elements (pmix data type t)
23
                Destruct a data array structure
                Destruct the pmix_data_array_t, releasing the memory in the array.
24
    PMIx v2.2
                PMIX DATA ARRAY DESTRUCT (m)
25
                IN
26
27
                     Pointer to the structure to be destructed (pointer to pmix_data_array_t)
```

1	Create a data array structure
2	Allocate memory for the pmix_data_array_t object itself, and then allocate memory for the array of the
3	indicated type.
	· ·
4	PMIX_DATA_ARRAY_CREATE(m, n, t)
	C —
5	INOUT m
6	Variable to be set to the address of the structure (pointer to pmix_data_array_t)
7	IN n
8 9	Number of elements in the array (size_t) IN t
10	PMIx data type of the array elements (pmix_data_type_t)
11	Free a data array structure
12 <i>PMIx v2.2</i>	Release the memory in the array, and then release the pmix_data_array_t object itself.
13	PMIX_DATA_ARRAY_FREE (m)
	C -
14	IN m
15	Pointer to the structure to be released (pointer to <pre>pmix_data_array_t</pre>
16 3.2.1 4	Argument Array Macros
17	The following macros support the construction and release of NULL -terminated argv arrays of strings.
10	
18 19	Argument array extension Append a string to a NULL-terminated, argv-style array of strings.
19	
	C —
20	<pre>PMIX_ARGV_APPEND(r, a, b);</pre>
	C
21	OUT r
22	Status code indicating success or failure of the operation (pmix_status_t)
23	INOUT a
24	Argument list (pointer to NULL-terminated array of strings)
25	IN b
26	Argument to append to the list (string)
27	This function helps the caller build the argv portion of pmix_app_t structure, arrays of keys for querying,
28	or other places where argy-style string arrays are required.
	Advice to users —
_	
29	The provided argument is copied into the destination array - thus, the source string can be free'd without
30	affecting the array once the macro has completed.

1 2	Argument array prepend Prepend a string to a NULL-terminated, argv-style array of strings.
۷	riepend a string to a NOLL-terminated, argy-style array of strings.
3	PMIX_ARGV_PREPEND(r, a, b);
4	OUT r
5	Status code indicating success or failure of the operation (pmix_status_t)
6	INOUT a
7	Argument list (pointer to NULL-terminated array of strings)
8	IN b
9	Argument to append to the list (string)
0	This function helps the caller build the argv portion of pmix_app_t structure, arrays of keys for querying, or other places where argv-style string arrays are required.
	Advice to users
2	The provided argument is copied into the destination array - thus, the source string can be free'd without
3	affecting the array once the macro has completed.
J	anceting the array once the macro has completed.
4 5 6	Argument array extension - unique Append a string to a NULL-terminated, argy-style array of strings, but only if the provided argument doesn't already exist somewhere in the array.
7	PMIX_ARGV_APPEND_UNIQUE(r, a, b);
	C
8	OUT r
9	Status code indicating success or failure of the operation (pmix_status_t)
0	INOUT a
1	Argument list (pointer to NULL-terminated array of strings)
2	IN b
3	Argument to append to the list (string)
4	This function helps the caller build the argv portion of pmix_app_t structure, arrays of keys for querying,
5	or other places where argy-style string arrays are required.
	Advice to users
	Advice to users
6	The provided argument is copied into the destination array - thus, the source string can be free'd without
7	affecting the array once the macro has completed.

1	Argument array release
2	Free an argy-style array and all of the strings that it contains.
	▼ C − ▼
3	PMIX ARGV FREE(a);
Ü	C
4	IN a
5	Argument list (pointer to NULL-terminated array of strings)
6	This function releases the array and all of the strings it contains.
7	Argument array split
8	Split a string into a NULL-terminated argy array.
	C
•	
9	PMIX_ARGV_SPLIT(a, b, c);
0	OUT a
1	Resulting argv-style array (char**)
2	IN b
3	String to be split (char*)
4	IN c
5	Delimiter character (char)
6	Split an input string into a NULL-terminated argv array. Do not include empty strings in the resulting array.
	Advice to users
7	
7 8	All strings are inserted into the argy array by value; the newly-allocated array makes no references to the src_string argument (i.e., it can be freed after calling this function without invalidating the output argy array)
O	sic_suring argument (i.e., it can be freed after carning this function without invalidating the output argy array)
9	Argument array join
0	Join all the elements of an argy array into a single newly-allocated string.
	C
	• • • • • • • • • • • • • • • • • • •
1	PMIX_ARGV_JOIN(a, b, c);
	C
2	OUT a
3	Resulting string (char*)
4	IN b
5	Argv-style array to be joined (char**)
6	IN c
7	Delimiter character (char)
8	Join all the elements of an argy array into a single newly-allocated string.

1		Argument array count
2		Return the length of a NULL-terminated argy array.
		C
_		
3		PMIX_ARGV_COUNT(r, a);
		C
4		OUT r
5		Number of strings in the array (integer)
6		IN a
7		Argy-style array (char**)
0		
8		Count the number of elements in an argv array
9		Argument array copy
10		Copy an argy array, including copying all of its strings.
		C
11		PMIX_ARGV_COPY(a, b);
		C -
12		OUT a
13		New argv-style array (char**)
14		IN b
15		Argv-style array (char**)
16		Copy an argy array, including copying all of its strings.
17	3.2.15	Set Environment Variable
17	5.2.15	Set Livilonnient variable
18		Summary
19		Set an environment variable in a NULL -terminated, env-style array.
		C
20		PMIX_SETENV(r, name, value, env);
		C
21		OUT r
22		Status code indicating success or failure of the operation (pmix_status_t)
23		IN name
24		Argument name (string)
25		<pre>IN value</pre>
26		Argument value (string)
27		INOUT env
28		Environment array to update (pointer to array of strings)

Description

1

3

4 5

7

8

9

10

11

12

Similar to **setenv** from the C API, this allows the caller to set an environment variable in the specified **env** array, which could then be passed to the **pmix_app_t** structure or any other destination.

Advice to users

The provided name and value are copied into the destination environment array - thus, the source strings can be free'd without affecting the array once the macro has completed.

3.3 Generalized Data Types Used for Packing/Unpacking

The pmix_data_type_t structure is a uint16_t type for identifying the data type for packing/unpacking purposes. New data type values introduced in this version of the Standard are shown in magenta.

Advice to PMIx library implementers

The following constants can be used to set a variable of the type <code>pmix_data_type_t</code>. Data types in the PMIx Standard are defined in terms of the C-programming language. Implementers wishing to support other languages should provide the equivalent definitions in a language-appropriate manner. Additionally, a PMIx implementation may choose to add additional types.

```
13
                PMIX_UNDEF
                                Undefined.
14
                PMIX BOOL
                               Boolean (converted to/from native true/false) (bool).
15
                PMIX_BYTE
                               A byte of data (uint8_t).
16
                                 NULL terminated string (char*).
                PMIX STRING
17
                PMIX SIZE
                               Size size t.
18
                PMIX PID
                              Operating Process IDentifier (PID) (pid_t).
19
                PMIX INT
                              Integer (int).
20
                PMIX INT8
                               8-byte integer (int8_t).
21
                PMIX INT16
                                16-byte integer (int16_t).
22
                PMIX_INT32
                                32-byte integer (int32_t).
23
                PMIX INT64
                                64-byte integer (int64_t).
24
                               Unsigned integer (unsigned int).
                PMIX_UINT
25
                PMIX_UINT8
                                Unsigned 8-byte integer (uint8_t).
26
                PMIX UINT16
                                 Unsigned 16-byte integer (uint16_t).
27
                PMIX_UINT32
                                 Unsigned 32-byte integer (uint32_t).
28
                PMIX UINT64
                                 Unsigned 64-byte integer (uint64_t).
29
                PMIX FLOAT
                                Float (float).
30
                PMIX_DOUBLE
                                 Double (double).
31
                PMIX TIMEVAL
                                   Time value (struct timeval).
32
                PMIX TIME
                               Time (time t).
33
                                 Status code pmix status t.
                PMIX STATUS
34
                PMIX VALUE
                                Value (pmix_value_t).
35
                PMIX PROC
                               Process (pmix proc t).
```

```
1
                PMIX_APP
                              Application context.
 2
                PMIX_INFO
                               Info object.
 3
                PMIX_PDATA
                                 Pointer to data.
 4
                PMIX BUFFER
                                  Buffer.
 5
                PMIX BYTE OBJECT
                                         Byte object (pmix_byte_object_t).
 6
                PMIX KVAL
                               Key/value pair.
 7
                                   Persistance (pmix persistence t).
                PMIX PERSIST
 8
                                   Pointer to an object (void*).
                PMIX POINTER
 9
                                 Scope (pmix scope t).
                PMIX SCOPE
10
                PMIX DATA RANGE
                                       Range for data (pmix_data_range_t).
11
                PMIX COMMAND
                                   PMIx command code (used internally).
12
                PMIX_INFO_DIRECTIVES
                                              Directives flag for pmix_info_t (pmix_info_directives_t).
13
                PMIX_DATA_TYPE
                                      Data type code (pmix_data_type_t).
14
                                       Process state (pmix proc state t).
                PMIX PROC STATE
15
                PMIX PROC INFO
                                      Process information (pmix_proc_info_t).
16
                                       Data array (pmix_data_array_t).
                PMIX DATA ARRAY
17
                PMIX_PROC_RANK
                                      Process rank (pmix_rank_t).
18
                PMIX_PROC_NSPACE
                                         Process namespace (pmix_nspace_t). %
19
                PMIX QUERY
                                 Query structure (pmix_query_t).
20
                PMIX_COMPRESSED_STRING
                                                String compressed with zlib (char*).
21
                PMIX COMPRESSED BYTE OBJECT
                                                       Byte object whose bytes have been compressed with zlib
22
                     (pmix_byte_object_t).
23
                PMIX ALLOC DIRECTIVE
                                              Allocation directive (pmix_alloc_directive_t).
24
                PMIX IOF CHANNEL
                                         Input/output forwarding channel (pmix iof channel t).
25
                PMIX ENVAR
                                 Environmental variable structure (pmix_envar_t).
26
                PMIX COORD
                                 Structure containing fabric coordinates (pmix coord t).
27
                                   Structure supporting attribute registrations (pmix_regattr_t).
                PMIX_REGATTR
28
                PMIX REGEX
                                 Regular expressions - can be a valid NULL-terminated string or an arbitrary array of bytes.
29
                                      Job state (pmix job state t).
                PMIX JOB STATE
30
                PMIX LINK STATE
                                       Link state (pmix_link_state_t).
31
                PMIX PROC CPUSET
                                         Structure containing the binding bitmap of a process (pmix cpuset t).
32
                PMIX GEOMETRY
                                    Geometry structure containing the fabric coordinates of a specified
33
                     device.(pmix geometry t).
34
                PMIX_DEVICE_DIST
                                        Structure containing the minimum and maximum relative distance from the caller
35
                     to a given fabric device. (pmix_device_distance_t).
36
                PMIX ENDPOINT
                                     Structure containing an assigned endpoint for a given fabric device.
37
                     (pmix_endpoint_t).
38
                               Structure containing the topology for a given node. (pmix_topology_t).
                PMIX TOPO
39
                                   Bitmask containing the types of devices being referenced. (pmix_device_type_t).
                PMIX DEVTYPE
40
                PMIX LOCTYPE
                                   Bitmask describing the relative location of another process. (pmix_locality_t).
41
                PMIX_DATA_TYPE_MAX
                                           A starting point for implementer-specific data types. Values above this are
42
                     guaranteed not to conflict with PMIx values. Definitions should always be based on the
43
                     PMIX DATA TYPE MAX constant and not a specific value as the value of the constant may change.
```

3.4 **General Callback Functions**

2 PMIx provides blocking and nonblocking versions of most APIs. In the nonblocking versions, a callback is 3 activated upon completion of the the operation. This section describes many of those callbacks.

Release Callback Function 3.4.1

Summary 5 6 The pmix_release_cbfunc_t is used by the pmix_modex_cbfunc_t and 7 pmix info cbfunc t operations to indicate that the callback data may be reclaimed/freed by the caller. $8_{PMIx v1.0}$ _____ C ____ 9 typedef void (*pmix_release_cbfunc_t) (void *cbdata);

11 **INOUT** cbdata

10

12

13

24

25

27

28

Callback data passed to original API call (memory reference)

Description

14 Since the data is "owned" by the host server, provide a callback function to notify the host server that we are done with the data so it can be released. 15

3.4.2 Op Callback Function 16

Summary 17 18 The **pmix** op **cbfunc** t is used by operations that simply return a status. PMIx v1.0 19 typedef void (*pmix_op_cbfunc_t) 20 (pmix status t status, void *cbdata); 21 status 22 Status associated with the operation (handle) 23 IN

Description

26 Used by a wide range of PMIx API's including PMIx Fence nb,

pmix_server_client_connected2_fn_t, PMIx_server_register_nspace. This callback

function is used to return a status to an often nonblocking operation.

Callback data passed to original API call (memory reference)

3.4.3 Value Callback Function

```
2
                Summary
 3
                The pmix_value_cbfunc_t is used by PMIx_Get_nb to return data.
                typedef void (*pmix_value_cbfunc_t)
 4
 5
                      (pmix_status_t status,
 6
                      pmix_value_t *kv, void *cbdata);
 7
                IN
                     status
 8
                     Status associated with the operation (handle)
 9
                IN
10
                     Key/value pair representing the data (pmix value t)
                IN
11
12
                     Callback data passed to original API call (memory reference)
                Description
13
14
                A callback function for calls to PMIx_Get_nb. The status indicates if the requested data was found or not. A
15
                pointer to the pmix value t structure containing the found data is returned. The pointer will be NULL if
16
                the requested data was not found.
     3.4.4
                Info Callback Function
17
                Summarv
18
19
                The pmix_info_cbfunc_t is a general information callback used by various APIs.
    PMIx v2.0
20
                typedef void (*pmix_info_cbfunc_t)
21
                      (pmix_status_t status,
22
                      pmix info t info[], size t ninfo,
23
                      void *cbdata,
24
                      pmix release cbfunc t release fn,
25
                      void *release_cbdata);
26
                IN
27
                     Status associated with the operation (pmix_status_t)
28
                IN
29
                     Array of pmix_info_t returned by the operation (pointer)
30
                IN
                     ninfo
31
                     Number of elements in the info array (size_t)
32
                IN
                     cbdata
33
                     Callback data passed to original API call (memory reference)
34
                IN
                     release fn
35
                     Function to be called when done with the info data (function pointer)
36
                IN
                     release_cbdata
37
                     Callback data to be passed to release_fn (memory reference)
```

Description 1 2 The status indicates if requested data was found or not. An array of pmix info t will contain the key/value 3 3.4.5 Handler registration callback function 5 Summary 6 Callback function for calls to register handlers, e.g., event notification and IOF requests. **Format** 7 *PMIx v3.0* 8 typedef void (*pmix_hdlr_reg_cbfunc_t) 9 (pmix_status_t status, 10 size_t refid, 11 void *cbdata); 12 IN status 13 PMIX_SUCCESS or an appropriate error constant (pmix_status_t) 14 reference identifier assigned to the handler by PMIx, used to deregister the handler (size_t) 15 16 cbdata object provided to the registration call (pointer) 17 Description 18 19 Callback function for calls to register handlers, e.g., event notification and IOF requests. 3.5 PMIx Datatype Value String Representations 20 21 Provide a string representation for several types of values. Note that the provided string is statically defined 22 and must NOT be free'd. 23 Summarv 24 String representation of a **pmix_status_t**. PMIx v1.0 25 const char* 26 PMIx_Error_string(pmix_status_t status); 27 Summary String representation of a **pmix_proc_state_t**. 28 PMIx v2.029 const char* 30 PMIx_Proc_state_string(pmix_proc_state_t state);

```
Summary
 1
 2
              String representation of a pmix_scope_t.
 3
              const char*
 4
              PMIx_Scope_string(pmix_scope_t scope);
              Summary
 5
 6
              String representation of a pmix_persistence_t.
    PMIx v2.0
 7
              const char*
 8
              PMIx_Persistence_string(pmix_persistence_t persist);
 9
              Summary
10
              String representation of a pmix_data_range_t.
    PMIx v2.0
11
              const char*
12
              PMIx_Data_range_string(pmix_data_range_t range);
13
              Summary
14
              String representation of a pmix_info_directives_t.
    PMIx v2.0
15
              const char*
16
              PMIx_Info_directives_string(pmix_info_directives_t directives);
17
              Summary
18
              String representation of a pmix_data_type_t.
    PMIx v2.0
19
              const char*
              PMIx_Data_type_string(pmix_data_type_t type);
20
21
              Summary
22
              String representation of a pmix_alloc_directive_t.
    PMIx v2.0
23
              const char*
              PMIx_Alloc_directive_string(pmix_alloc_directive_t directive);
24
```

```
Summary
 1
 2
               String representation of a pmix_iof_channel_t.
 3
               const char*
               PMIx_IOF_channel_string(pmix_iof_channel_t channel);
 4
               Summary
 5
 6
               String representation of a pmix_job_state_t.
  PMIx v4.0
 7
               const char*
 8
               PMIx_Job_state_string(pmix_job_state_t state);
 9
               Summary
10
               String representation of a PMIx attribute.
  PMIx v4.0
11
               const char*
12
               PMIx_Get_attribute_string(char *attributename);
               Summary
13
14
               Return the PMIx attribute name corresponding to the given attribute string.
  PMIx v4.0
15
               const char*
16
               PMIx_Get_attribute_name(char *attributestring);
17
               Summary
18
               String representation of a pmix_link_state_t.
  PMIx v4.0
19
               const char*
               PMIx_Link_state_string(pmix_link_state_t state);
20
21
               Summary
22
               String representation of a pmix_device_type_t.
  PMIx v4.0
23
               const char*
               PMIx_Device_type_string(pmix_device_type_t type);
24
```

CHAPTER 4

Client Initialization and Finalization

1 The PMIx library is required to be initialized and finalized around the usage of most PMIx functions or 2 macros. The APIs that may be used outside of the initialized and finalized region are noted. All other APIs 3 must be used inside this region. There are three sets of initialization and finalization functions depending upon the role of the process in the 5 PMIx Standard - those associated with the PMIx client are defined in this chapter. Similar functions 6 corresponding to the roles of server and tool are defined in Chapters 16 and 17, respectively. 7 Note that a process can only call *one* of the initialization/finalization functional pairs from the set of three -8 e.g., a process that calls the client initialization function cannot also call the tool or server initialization 9 functions, and must call the corresponding client finalization function. Regardless of the role assumed by the 10 process, all processes have access to the client APIs. Thus, the server and tool roles can be considered 11 supersets of the PMIx client. PMIx Initialized Summary 13 Determine if the PMIx library has been initialized. This function may be used outside of the initialized and 14 15 finalized region, and is usable by servers and tools in addition to clients. 16 Format PMIx v1.0 17 int PMIx_Initialized(void) A value of 1 (true) will be returned if the PMIx library has been initialized, and 0 (false) otherwise. 18 19 The return value is an integer for historical reasons as that was the signature of prior PMI libraries. Description 20 21 Check to see if the PMIx library has been initialized using any of the init functions: PMIx_Init, 22 PMIx server init, or PMIx tool init.

4.2 PMIx Get version

```
2
              Summary
              Get the PMIx version information. This function may be used outside of the initialized and finalized region,
 3
              and is usable by servers and tools in addition to clients.
              Format
 5
6
              const char* PMIx Get version(void)
              Description
 7
8
              Get the PMIx version string. Note that the provided string is statically defined and must not be free'd.
            PMIx Init
10
              Summary
11
              Initialize the PMIx client library
12 _{PMIx\ v1.2}
              Format
13
              pmix status t
14
              PMIx Init (pmix proc t *proc,
                           ______ C ______
15
                         pmix_info_t info[], size_t ninfo)
              INOUT proc
16
17
                   proc structure (handle)
18
              IN
19
                  Array of pmix info t structures (array of handles)
              IN ninfo
20
                  Number of elements in the info array (size_t)
21
22
              Returns PMIX_SUCCESS or a negative value corresponding to a PMIx error constant.
              Optional Attributes
23
              The following attributes are optional for implementers of PMIx libraries:
24
              PMIX_USOCK_DISABLE "pmix.usock.disable" (bool)
25
                    attribute may be supported for disabling it.
26
27
              PMIX_SOCKET_MODE "pmix.sockmode" (uint32 t)
28
                    POSIX mode_t (9 bits valid). If the library supports socket connections, this attribute may be
29
                    supported for setting the socket mode.
30
              PMIX SINGLE LISTENER "pmix.sing.listnr" (bool)
```

Use only one rendezvous socket, letting priorities and/or environment parameters select the active 1 2 transport. If the library supports multiple methods for clients to connect to servers, this attribute may 3 be supported for disabling all but one of them. 4 PMIX_TCP_REPORT_URI "pmix.tcp.repuri" (char*) 5 If provided, directs that the TCP Uniform Resource Identifier (URI) be reported and indicates the desired method of reporting: '-' for stdout, '+' for stderr, or filename. If the library supports TCP 6 7 socket connections, this attribute may be supported for reporting the URI. 8 PMIX_TCP_IF_INCLUDE "pmix.tcp.ifinclude" (char*) 9 Comma-delimited list of devices and/or Classless Inter-Domain Routing (CIDR) notation to include when establishing the TCP connection. If the library supports TCP socket connections, this attribute 10 may be supported for specifying the interfaces to be used. 11 12 PMIX_TCP_IF_EXCLUDE "pmix.tcp.ifexclude" (char*) 13 Comma-delimited list of devices and/or CIDR notation to exclude when establishing the TCP 14 connection. If the library supports TCP socket connections, this attribute may be supported for specifying the interfaces that are not to be used. 15 16 PMIX_TCP_IPV4_PORT "pmix.tcp.ipv4" (int) 17 The IPv4 port to be used.. If the library supports IPV4 connections, this attribute may be supported for specifying the port to be used. 18 PMIX_TCP_IPV6_PORT "pmix.tcp.ipv6" (int) 19 The IPv6 port to be used. If the library supports IPV6 connections, this attribute may be supported 20 21 for specifying the port to be used. 22 PMIX_TCP_DISABLE_IPV4 "pmix.tcp.disipv4" (bool) 23 Set to true to disable IPv4 family of addresses. If the library supports IPV4 connections, this 24 attribute may be supported for disabling it. 25 PMIX_TCP_DISABLE_IPV6 "pmix.tcp.disipv6" (bool) 26 Set to true to disable IPv6 family of addresses. If the library supports IPV6 connections, this 27 attribute may be supported for disabling it. 28 PMIX EXTERNAL PROGRESS "pmix.evext" (bool) 29 The host shall progress the PMIx library via calls to PMIx_Progress 30 PMIX_EVENT_BASE "pmix.evbase" (void*) 31 Pointer to an **event** base to use in place of the internal progress thread. All PMIx library events are 32 to be assigned to the provided event base. The event base *must* be compatible with the event library 33 used by the PMIx implementation - e.g., either both the host and PMIx library must use libevent, or 34 both must use libev. Cross-matches are unlikely to work and should be avoided - it is the responsibility of the host to ensure that the PMIx implementation supports (and was built with) the appropriate event 35 36 library. 37 If provided, the following attributes are used by the event notification system for inter-library coordination: 38 PMIX PROGRAMMING MODEL "pmix.pqm.model" (char*) 39 Programming model being initialized (e.g., "MPI" or "OpenMP").

PMIX MODEL LIBRARY NAME "pmix.mdl.name" (char*)

Programming model implementation ID (e.g., "OpenMPI" or "MPICH"). PMIX MODEL LIBRARY VERSION "pmix.mld.vrs" (char*) Programming model version string (e.g., "2.1.1"). PMIX THREADING MODEL "pmix.threads" (char*) Threading model used (e.g., "pthreads"). PMIX MODEL NUM THREADS "pmix.mdl.nthrds" (uint64_t) Number of active threads being used by the model. PMIX MODEL NUM CPUS "pmix.mdl.ncpu" (uint64 t) Number of cpus being used by the model. PMIX_MODEL_CPU_TYPE "pmix.mdl.cputype" (char*) Granularity - "hwthread", "core", etc. PMIX_MODEL_AFFINITY_POLICY "pmix.mdl.tap" (char*) Thread affinity policy - e.g.: "master" (thread co-located with master thread), "close" (thread located on cpu close to master thread), "spread" (threads load-balanced across available cpus).

Description

Initialize the PMIx client, returning the process identifier assigned to this client's application in the provided <code>pmix_proc_t</code> struct. Passing a value of **NULL** for this parameter is allowed if the user wishes solely to initialize the PMIx system and does not require return of the identifier at that time.

When called, the PMIx client shall check for the required connection information of the local PMIx server and establish the connection. If the information is not found, or the server connection fails, then an appropriate error constant shall be returned.

If successful, the function shall return **PMIX_SUCCESS** and fill the *proc* structure (if provided) with the server-assigned namespace and rank of the process within the application. In addition, all startup information provided by the resource manager shall be made available to the client process via subsequent calls to **PMIX Get.**

The PMIx client library shall be reference counted, and so multiple calls to **PMIx_Init** are allowed by the standard. Thus, one way for an application process to obtain its namespace and rank is to simply call **PMIx_Init** with a non-NULL *proc* parameter. Note that each call to **PMIx_Init** must be balanced with a call to **PMIx_Finalize** to maintain the reference count.

Each call to **PMIx_Init** may contain an array of **pmix_info_t** structures passing directives to the PMIx client library as per the above attributes.

Multiple calls to **PMIx_Init** shall not include conflicting directives. The **PMIx_Init** function will return an error when directives that conflict with prior directives are encountered.

1 4.3.1 Initialization events

4

6

7 8

9

11 12

13 14

15

16

17

18

19

20

21

22

23

24

25

26

27

28

29

30

31

32 33

34

35

36

37

38

39

40

- The following events are typically associated with calls to **PMIx_Init**:
- 3 **PMIX_MODEL_DECLARED** Model declared.
 - **PMIX_MODEL_RESOURCES** Resource usage by a programming model has changed.
- 5 PMIX_OPENMP_PARALLEL_ENTERED An OpenMP parallel code region has been entered.
 - PMIX_OPENMP_PARALLEL_EXITED An OpenMP parallel code region has completed.

4.3.2 Initialization attributes

The following attributes influence the behavior of **PMIx_Init**.

4.3.2.1 Connection attributes

These attributes are used to describe a TCP socket for rendezvous with the local RM by passing them into the relevant initialization API - thus, they are not typically accessed via the **PMIx_Get** API.

PMIX_TCP_REPORT_URI "pmix.tcp.repuri" (char*)

If provided, directs that the TCP URI be reported and indicates the desired method of reporting: '-' for stdout, '+' for stderr, or filename.

PMIX_TCP_URI "pmix.tcp.uri" (char*)

The URI of the PMIx server to connect to, or a file name containing it in the form of **file:<name** of file containing it>.

PMIX_TCP_IF_INCLUDE "pmix.tcp.ifinclude" (char*)

Comma-delimited list of devices and/or CIDR notation to include when establishing the TCP connection.

PMIX_TCP_IF_EXCLUDE "pmix.tcp.ifexclude" (char*)

Comma-delimited list of devices and/or CIDR notation to exclude when establishing the TCP connection.

PMIX_TCP_IPV4_PORT "pmix.tcp.ipv4" (int)

The IPv4 port to be used..

PMIX TCP IPV6 PORT "pmix.tcp.ipv6" (int)

The IPv6 port to be used.

PMIX_TCP_DISABLE_IPV4 "pmix.tcp.disipv4" (bool)

Set to true to disable IPv4 family of addresses.

PMIX_TCP_DISABLE_IPV6 "pmix.tcp.disipv6" (bool)

Set to true to disable IPv6 family of addresses.

4.3.2.2 Programming model attributes

These attributes are associated with programming models.

PMIX_PROGRAMMING_MODEL "pmix.pgm.model" (char*)

Programming model being initialized (e.g., "MPI" or "OpenMP").

PMIX_MODEL_LIBRARY_NAME "pmix.mdl.name" (char*)

Programming model implementation ID (e.g., "OpenMPI" or "MPICH").

PMIX_MODEL_LIBRARY_VERSION "pmix.mld.vrs" (char*)

Programming model version string (e.g., "2.1.1").

PMIX_THREADING_MODEL "pmix.threads" (char*)

```
1
                      Threading model used (e.g., "pthreads").
 2
                PMIX MODEL NUM THREADS "pmix.mdl.nthrds" (uint64_t)
 3
                      Number of active threads being used by the model.
 4
                PMIX_MODEL_NUM_CPUS "pmix.mdl.ncpu" (uint64_t)
 5
                      Number of cpus being used by the model.
 6
                PMIX MODEL CPU TYPE "pmix.mdl.cputype" (char*)
                      Granularity - "hwthread", "core", etc.
 7
                PMIX_MODEL_PHASE_NAME "pmix.mdl.phase" (char*)
 8
 9
                      User-assigned name for a phase in the application execution (e.g., "cfd reduction").
10
                PMIX_MODEL_PHASE_TYPE "pmix.mdl.ptype" (char*)
                      Type of phase being executed (e.g., "matrix multiply").
11
                PMIX_MODEL_AFFINITY_POLICY "pmix.mdl.tap" (char*)
12
13
                      Thread affinity policy - e.g.: "master" (thread co-located with master thread), "close" (thread located
14
                      on cpu close to master thread), "spread" (threads load-balanced across available cpus).
     4.4
              PMIx Finalize
15
                Summary
16
17
                Finalize the PMIx client library.
                Format
18 _{PMIx \ v1.0}
19
                pmix_status_t
20
                PMIx_Finalize(const pmix_info_t info[], size_t ninfo)
21
                IN info
22
                     Array of pmix_info_t structures (array of handles)
23
                IN
24
                     Number of elements in the info array (size_t)
25
                Returns PMIX_SUCCESS or a negative value corresponding to a PMIx error constant.
                                                  Optional Attributes
26
                The following attributes are optional for implementers of PMIx libraries:
27
                PMIX EMBED BARRIER "pmix.embed.barrier" (bool)
                      Execute a blocking fence operation before executing the specified operation. PMIx Finalize does
28
29
                      not include an internal barrier operation by default. This attribute directs PMIx_Finalize to
30
                      execute a barrier as part of the finalize operation.
                ^ -----
                Description
31
32
                Decrement the PMIx client library reference count. When the reference count reaches zero, the library will
33
                finalize the PMIx client, closing the connection with the local PMIx server and releasing all internally
34
                allocated memory.
```

4.4.1 Finalize attributes

The following attribute influences the behavior of **PMIx_Finalize**.

PMIX_EMBED_BARRIER "pmix.embed.barrier" (bool)

Execute a blocking fence operation before executing the specified operation. **PMIx_Finalize** does not include an internal barrier operation by default. This attribute directs **PMIx_Finalize** to execute a barrier as part of the finalize operation.

4.5 PMIx_Progress

Summary

Progress the PMIx library.

10 PMIx v4.0 Format

1

3

4

5

6

8

9

11

12

13

void

PMIx_Progress(void)

Description

14 Progress the PMIx library. Note that special care must be taken to avoid deadlocking in PMIx callback

15 functions and acpAPI.

CHAPTER 5

1

2

3

4

5

6

7

8

10

Synchronization and Data Access **Operations**

Applications may need to synchronize their operations at various points in their execution. Depending on a variety of factors (e.g., the programming model and where the synchronization point lies), the application may choose to execute the operation using PMIx. This is particularly useful in situations where communication by other means is not yet available since PMIx relies on the host environment's infrastructure for such operations.

Synchronization operations also offer an opportunity for processes to exchange data at a known point in their execution. Where required, this can include information on communication endpoints for subsequent wireup of various messaging protocols.

This chapter covers both the synchronization and data retrieval functions provided under the PMIx Standard.

5.1 PMIx Fence

```
Summary
11
                 Execute a blocking barrier across the processes identified in the specified array, collecting information posted
12
                 via PMIx Put as directed.
13 _{PMIx\ v1.0}
                 Format
14
                 pmix status t
15
                 PMIx_Fence(const pmix_proc_t procs[], size_t nprocs,
16
                               const pmix_info_t info[], size_t ninfo);
17
                 IN
                      procs
18
                      Array of pmix proc t structures (array of handles)
19
20
                      Number of elements in the procs array (integer)
21
                 IN
22
                      Array of info structures (array of handles)
23
                 IN
                      ninfo
24
                      Number of elements in the info array (integer)
25
                 Returns PMIX_SUCCESS or a negative value corresponding to a PMIx error constant.
```

Required Attributes The following attributes are required to be supported by all PMIx libraries: PMIX COLLECT DATA "pmix.collect" (bool) Collect all data posted by the participants using PMIx_Put that has been committed via **PMIx_Commit**, making the collection locally available to each participant at the end of the operation. By default, this will include all job-level information that was locally generated by PMIx servers unless excluded using the PMIX_COLLECT_GENERATED_JOB_INFO attribute. PMIX_COLLECT_GENERATED_JOB_INFO "pmix.collect.gen" (bool) Collect all job-level information (i.e., reserved keys) that was locally generated by PMIx servers. Some job-level information (e.g., distance between processes and fabric devices) is best determined on a distributed basis as it primarily pertains to local processes. Should remote processes need to access the information, it can either be obtained collectively using the PMIx_Fence operation with this directive, or can be retrieved one peer at a time using PMIx Get without first having performed the job-wide collection. ______ Optional Attributes -----The following attributes are optional for PMIx implementations: PMIX ALL CLONES PARTICIPATE "pmix.clone.part" (bool) All *clones* of the calling process must participate in the collective operation. The following attributes are optional for host environments: PMIX_TIMEOUT "pmix.timeout" (int) Time in seconds before the specified operation should time out (zero indicating infinite) and return the PMIX ERR TIMEOUT error. Care should be taken to avoid race conditions caused by multiple layers (client, server, and host) simultaneously timing the operation.

1

2

3

4

5

6 7

8

9

10

11 12

13

14

15

16

17

18

19

20

Description

1

3

4

5

6

7

8

9

10

11

12

13

15

16

17

Passing a **NULL** pointer as the *procs* parameter indicates that the fence is to span all processes in the client's namespace. Each provided **pmix_proc_t** struct can pass **PMIX_RANK_WILDCARD** to indicate that all processes in the given namespace are participating.

The *info* array is used to pass user directives regarding the behavior of the fence operation. Note that for scalability reasons, the default behavior for **PMIx_Fence** is to not collect data posted by the operation's participants.

-Advice to PMIx library implementers-

PMIx_Fence and its non-blocking form are both *collective* operations. Accordingly, the PMIx server library is required to aggregate participation by local clients, passing the request to the host environment once all local participants have executed the API.

-Advice to PMIx server hosts-

The host will receive a single call for each collective operation. It is the responsibility of the host to identify the nodes containing participating processes, execute the collective across all participating nodes, and notify the local PMIx server library upon completion of the global collective.

5.2 PMIx_Fence_nb

Summary

Execute a nonblocking **PMIx_Fence** across the processes identified in the specified array of processes, collecting information posted via **PMIx_Put** as directed.

C

IN procs

Format

Array of pmix_proc_t structures (array of handles)

IN nprocs

Number of elements in the *procs* array (integer)

IN info

Array of info structures (array of handles)

IN ninfo

Number of elements in the *info* array (integer)

IN cbfunc

Callback function (function reference)

IN cbdata

Data to be passed to the callback function (memory reference)

Returns one of the following:

- PMIX_SUCCESS, indicating that the request is being processed by the host environment result will be returned in the provided *cbfunc*. Note that the library must not invoke the callback function prior to returning from the API.
- PMIX_OPERATION_SUCCEEDED, indicating that the request was immediately processed and returned
 success the cbfunc will not be called. This can occur if the collective involved only processes on the local
 node.
- a PMIx error constant indicating either an error in the input or that the request was immediately processed and failed the *cbfunc* will *not* be called.

Required Attributes

The following attributes are required to be supported by all PMIx libraries:

```
PMIX_COLLECT_DATA "pmix.collect" (bool)
```

Collect all data posted by the participants using PMIx_Put that has been committed via PMIx_Commit, making the collection locally available to each participant at the end of the operation. By default, this will include all job-level information that was locally generated by PMIx servers unless excluded using the PMIX_COLLECT_GENERATED_JOB_INFO attribute.

```
PMIX_COLLECT_GENERATED_JOB_INFO "pmix.collect.gen" (bool)
```

Collect all job-level information (i.e., reserved keys) that was locally generated by PMIx servers. Some job-level information (e.g., distance between processes and fabric devices) is best determined on a distributed basis as it primarily pertains to local processes. Should remote processes need to access the information, it can either be obtained collectively using the PMIx_Fence operation with this directive, or can be retrieved one peer at a time using PMIx_Get without first having performed the job-wide collection.

Optional Attributes -----

The following attributes are optional for PMIx implementations:

PMIX_ALL_CLONES_PARTICIPATE "pmix.clone.part" (bool)

All *clones* of the calling process must participate in the collective operation.

The following attributes are optional for host environments that support this operation:

```
PMIX_TIMEOUT "pmix.timeout" (int)
```

Time in seconds before the specified operation should time out (zero indicating infinite) and return the **PMIX_ERR_TIMEOUT** error. Care should be taken to avoid race conditions caused by multiple layers (client, server, and host) simultaneously timing the operation.

Description

Nonblocking version of the PMIx_Fence routine. See the PMIx_Fence description for further details.

5.2.1 Fence-related attributes

The following attributes are defined specifically to support the fence operation:

PMIX_COLLECT_DATA "pmix.collect" (bool)

Collect all data posted by the participants using PMIx_Put that has been committed via PMIx_Commit, making the collection locally available to each participant at the end of the operation. By default, this will include all job-level information that was locally generated by PMIx servers unless excluded using the PMIX_COLLECT_GENERATED_JOB_INFO attribute.

PMIX_LOCAL_COLLECTIVE_STATUS "pmix.loc.col.st" (pmix_status_t) (Provisional)

Status code for local collective operation being reported to the host by the server library. PMIx servers may aggregate the participation by local client processes in a collective operation - e.g., instead of passing individual client calls to PMIx_Fence up to the host environment, the server may pass only a single call to the host when all local participants have executed their PMIx_Fence call, thereby reducing the burden placed on the host. However, in cases where the operation locally fails (e.g., if a participating client abnormally terminates prior to calling the operation), the server upcall functions to the host do not include a pmix_status_t by which the PMIx server can alert the host to that failure. This attribute resolves that problem by allowing the server to pass the status information regarding the local collective operation.

Advice to PMIx server hosts

The PMIx server is allowed to pass **PMIX_SUCCESS** using this attribute, but is not required to do so. PMIx implementations may choose to only report errors in this manner. The lack of an included status shall therefore be taken to indicate that the collective operation locally succeeded.

```
1
                 PMIX_COLLECT_GENERATED_JOB_INFO "pmix.collect.gen" (bool)
 2
                        Collect all job-level information (i.e., reserved keys) that was locally generated by PMIx servers. Some
 3
                        job-level information (e.g., distance between processes and fabric devices) is best determined on a
 4
                        distributed basis as it primarily pertains to local processes. Should remote processes need to access the
 5
                        information, it can either be obtained collectively using the PMIx_Fence operation with this
 6
                        directive, or can be retrieved one peer at a time using PMIx_Get without first having performed the
 7
                        job-wide collection.
 8
                 PMIX_ALL_CLONES_PARTICIPATE "pmix.clone.part" (bool)
 9
                        All clones of the calling process must participate in the collective operation.
      5.3
               PMIx Get
10
                 Summary
11
12
                 Retrieve a key/value pair from the client's namespace.
                 Format
13
    PMIx v1.0
14
                 pmix status t
15
                 PMIx_Get(const pmix_proc_t *proc, const pmix_key_t key,
16
                             const pmix_info_t info[], size_t ninfo,
17
                             pmix_value_t **val);
18
                 IN
                      proc
19
                       Process identifier - a NULL value may be used in place of the caller's ID (handle)
20
                 IN
21
                       Key to retrieve (pmix key t)
22
                 IN
23
                      Array of info structures (array of handles)
24
                 IN ninfo
25
                       Number of elements in the info array (integer)
26
                 OUT val
                       value (handle)
27
28
                 Returns one of the following:
29
                 • PMIX SUCCESS The requested data has been returned in the manner requested (i.e., in a provided static
30
                    memory location)
31
                 • PMIX ERR BAD PARAM A bad parameter was passed to the function call - e.g., the request included the
                    PMIX GET STATIC VALUES directive, but the provided storage location was NULL
32
33
                 • PMIX ERR EXISTS OUTSIDE SCOPE The requested key exists, but was posted in a scope (see Section
34
                    7.1.1.1) that does not include the requester.
35
                 • PMIX_ERR_NOT_FOUND The requested data was not available.
36
                 • a non-zero PMIx error constant indicating a reason for the request's failure.
```

Required Attributes

The following attributes are required to be supported by all PMIx libraries:

PMIX_OPTIONAL "pmix.optional" (bool)

Look only in the client's local data store for the requested value - do not request data from the PMIx server if not found.

PMIX_IMMEDIATE "pmix.immediate" (bool)

Specified operation should immediately return an error from the PMIx server if the requested data cannot be found - do not request it from the host RM.

PMIX_DATA_SCOPE "pmix.scope" (pmix_scope_t)

Scope of the data to be searched in a **PMIx_Get** call.

PMIX_SESSION_INFO "pmix.ssn.info" (bool)

Return information regarding the session realm of the target process.

PMIX_JOB_INFO "pmix.job.info" (bool)

Return information regarding the job realm corresponding to the namespace in the target process' identifier.

PMIX_APP_INFO "pmix.app.info" (bool)

Return information regarding the application realm to which the target process belongs - the namespace of the target process serves to identify the job containing the target application. If information about an application other than the one containing the target process is desired, then the attribute array must contain a PMIX_APPNUM attribute identifying the desired target application. This is useful in cases where there are multiple applications and the mapping of processes to applications is unclear.

PMIX_NODE_INFO "pmix.node.info" (bool)

Return information from the node realm regarding the node upon which the specified process is executing. If information about a node other than the one containing the specified process is desired, then the attribute array must also contain either the <code>PMIX_NODEID</code> or <code>PMIX_HOSTNAME</code> attribute identifying the desired target. This is useful for requesting information about a specific node even if the identity of processes running on that node are not known..

PMIX_GET_STATIC_VALUES "pmix.get.static" (bool)

Request that the data be returned in the provided storage location. The caller is responsible for destructing the **pmix_value_t** using the **PMIX_VALUE_DESTRUCT** macro when done.

PMIX_GET_POINTER_VALUES "pmix.get.pntrs" (bool)

Request that any pointers in the returned value point directly to values in the key-value store. The user *must not* release any returned data pointers.

PMIX_GET_REFRESH_CACHE "pmix.get.refresh" (bool)

When retrieving data for a remote process, refresh the existing local data cache for the process in case new values have been put and committed by the process since the last refresh. Local process information is assumed to be automatically updated upon posting by the process. A **NULL** key will cause all values associated with the process to be refreshed - otherwise, only the indicated key will be updated. A process rank of **PMIX_RANK_WILDCARD** can be used to update job-related information in

1 dynamic environments. The user is responsible for subsequently updating refreshed values they may 2 have cached in their own local memory. ______ Optional Attributes ------3 The following attributes are optional for host environments: 4 PMIX_TIMEOUT "pmix.timeout" (int) 5 Time in seconds before the specified operation should time out (zero indicating infinite) and return the PMIX ERR TIMEOUT error. Care should be taken to avoid race conditions caused by multiple layers 6 7 (client, server, and host) simultaneously timing the operation. Description 8 9 Retrieve information for the specified key associated with the process identified in the given pmix_proc_t. 10 See Chapters 6 and 7 for details on rules governing retrieval of information. Information will be returned according to provided directives: 11 • In the absence of any directive, the returned **pmix_value_t** shall be an allocated memory object. The 12 13 caller is responsible for releasing the object when done. 14 • If PMIX GET POINTER VALUES is given, then the function shall return a pointer to a pmix value t in the PMIx library's memory that contains the requested information. 15 16 • If PMIX GET STATIC VALUES is given, then the function shall return the information in the provided 17 pmix_value_t pointer. In this case, the caller must provide storage for the structure and pass the pointer 18 to that storage in the val parameter. If the implementation cannot return a static value, then the call to PMIx Get must return the PMIX_ERR_NOT_SUPPORTED status. 19 20 This is a blocking operation - the caller will block until the retrieval rules of Chapters 6 or 7 are met.

The *info* array is used to pass user directives regarding the get operation.

22 **5.3.1** PMIx Get_nb

21

23

24

Summary

Nonblocking **PMIx Get** operation.

1	Format C
2 3 4 5	<pre>pmix_status_t PMIx_Get_nb(const pmix_proc_t *proc, const pmix_key_t key,</pre>
6 7 8 9 10 11 12 13 14 15	IN proc Process identifier - a NULL value may be used in place of the caller's ID (handle) IN key Key to retrieve (string) IN info Array of info structures (array of handles) IN ninfo Number of elements in the info array (integer) IN cbfunc Callback function (function reference) IN cbdata Data to be pressed to the callback function (mamory reference)
17 18	Data to be passed to the callback function (memory reference) Returns one of the following:
19 20 21	 PMIX_SUCCESS, indicating that the request is being processed by the host environment - result will be returned in the provided <i>cbfunc</i>. Note that the library must not invoke the callback function prior to returning from the API.
22 23	 a PMIx error constant indicating either an error in the input or that the request was immediately processed and failed - the <i>cbfunc</i> will <i>not</i> be called.
24	If executed, the status returned in the provided callback function will be one of the following constants:
25	• PMIX_SUCCESS The requested data has been returned.
26 27	• PMIX_ERR_EXISTS_OUTSIDE_SCOPE The requested key exists, but was posted in a <i>scope</i> (see Section 7.1.1.1) that does not include the requester.
28	• PMIX_ERR_NOT_FOUND The requested data was not available.
29	• a non-zero PMIx error constant indicating a reason for the request's failure. Required Attributes
30	The following attributes are required to be supported by all PMIx libraries:
31 32 33	<pre>PMIX_OPTIONAL "pmix.optional" (bool) Look only in the client's local data store for the requested value - do not request data from the PMIx server if not found.</pre>
34 35	PMIX_IMMEDIATE "pmix.immediate" (bool) Specified operation should immediately return an error from the PMIx server if the requested data cannot be found, do not request it from the best PM

```
1
2
3
```

4

5 6 7

8

13 14

20 21 22

23

19

30 31 32

33 34 35

```
PMIX_DATA_SCOPE "pmix.scope" (pmix_scope_t)
```

Scope of the data to be searched in a **PMIx Get** call.

PMIX_SESSION_INFO "pmix.ssn.info" (bool)

Return information regarding the session realm of the target process.

PMIX_JOB_INFO "pmix.job.info" (bool)

Return information regarding the job realm corresponding to the namespace in the target process' identifier.

PMIX_APP_INFO "pmix.app.info" (bool)

Return information regarding the application realm to which the target process belongs - the namespace of the target process serves to identify the job containing the target application. If information about an application other than the one containing the target process is desired, then the attribute array must contain a PMIX APPNUM attribute identifying the desired target application. This is useful in cases where there are multiple applications and the mapping of processes to applications is unclear.

PMIX NODE INFO "pmix.node.info" (bool)

Return information from the node realm regarding the node upon which the specified process is executing. If information about a node other than the one containing the specified process is desired, then the attribute array must also contain either the PMIX NODEID or PMIX HOSTNAME attribute identifying the desired target. This is useful for requesting information about a specific node even if the identity of processes running on that node are not known..

PMIX_GET_POINTER_VALUES "pmix.get.pntrs" (bool)

Request that any pointers in the returned value point directly to values in the key-value store. The user must not release any returned data pointers.

PMIX_GET_REFRESH_CACHE "pmix.get.refresh" (bool)

When retrieving data for a remote process, refresh the existing local data cache for the process in case new values have been put and committed by the process since the last refresh. Local process information is assumed to be automatically updated upon posting by the process. A NULL key will cause all values associated with the process to be refreshed - otherwise, only the indicated key will be updated. A process rank of PMIX_RANK_WILDCARD can be used to update job-related information in dynamic environments. The user is responsible for subsequently updating refreshed values they may have cached in their own local memory.

The following attributes are required for host environments that support this operation:

```
PMIX WAIT "pmix.wait" (int)
```

Caller requests that the PMIx server wait until at least the specified number of values are found (a value of zero indicates *all* and is the default).

Optional Attributes

The following attributes are optional for host environments that support this operation:

```
PMIX_TIMEOUT "pmix.timeout" (int)
```

Time in seconds before the specified operation should time out (zero indicating infinite) and return the **PMIX_ERR_TIMEOUT** error. Care should be taken to avoid race conditions caused by multiple layers (client, server, and host) simultaneously timing the operation.

Description

The callback function will be executed once the retrieval rules of Chapters 6 or 7 are met. See **PMIx_Get** for a full description. Note that the non-blocking form of this function cannot support the **PMIX_GET_STATIC_VALUES** attribute as the user cannot pass in the required pointer to storage for the result.

5.3.2 Retrieval attributes

The following attributes are defined for use by retrieval APIs:

```
PMIX_OPTIONAL "pmix.optional" (bool)
```

Look only in the client's local data store for the requested value - do not request data from the PMIx server if not found.

```
PMIX_IMMEDIATE "pmix.immediate" (bool)
```

Specified operation should immediately return an error from the PMIx server if the requested data cannot be found - do not request it from the host RM.

```
PMIX GET POINTER VALUES "pmix.get.pntrs" (bool)
```

Request that any pointers in the returned value point directly to values in the key-value store. The user *must not* release any returned data pointers.

```
PMIX GET STATIC VALUES "pmix.get.static" (bool)
```

Request that the data be returned in the provided storage location. The caller is responsible for destructing the **pmix_value_t** using the **PMIX_VALUE_DESTRUCT** macro when done.

```
PMIX GET_REFRESH_CACHE "pmix.get.refresh" (bool)
```

When retrieving data for a remote process, refresh the existing local data cache for the process in case new values have been put and committed by the process since the last refresh. Local process information is assumed to be automatically updated upon posting by the process. A **NULL** key will cause all values associated with the process to be refreshed - otherwise, only the indicated key will be updated. A process rank of **PMIX_RANK_WILDCARD** can be used to update job-related information in dynamic environments. The user is responsible for subsequently updating refreshed values they may have cached in their own local memory.

```
{\tt PMIX\_DATA\_SCOPE} \ "pmix.scope" \ (pmix\_scope\_t)
```

Scope of the data to be searched in a PMIx_Get call.

```
PMIX_TIMEOUT "pmix.timeout" (int)
```

Time in seconds before the specified operation should time out (zero indicating infinite) and return the **PMIX_ERR_TIMEOUT** error. Care should be taken to avoid race conditions caused by multiple layers (client, server, and host) simultaneously timing the operation.

```
PMIX_WAIT "pmix.wait" (int)
```

Caller requests that the PMIx server wait until at least the specified number of values are found (a value of zero indicates *all* and is the default).

5.4 Query

1

2

3

4

5

6

7

8

9

10

11

12

13

14

15

16 17

18

19

20

21

22

23

24

38

As the level of interaction between applications and the host SMS grows, so too does the need for the application to query the SMS regarding its capabilities and state information. PMIx provides a generalized query interface for this purpose, along with a set of standardized attribute keys to support a range of requests. This includes requests to determine the status of scheduling queues and active allocations, the scope of API and attribute support offered by the SMS, namespaces of active jobs, location and information about a job's processes, and information regarding available resources.

An example use-case for the <code>PMIx_Query_info_nb</code> API is to ensure clean job completion. Time-shared systems frequently impose maximum run times when assigning jobs to resource allocations. To shut down gracefully (e.g., to write a checkpoint before termination) it is necessary for an application to periodically query the resource manager for the time remaining in its allocation. This is especially true on systems for which allocation times may be shortened or lengthened from the original time limit. Many resource managers provide APIs to dynamically obtain this information, but each API is specific to the resource manager.

PMIx supports this use-case by defining an attribute key (PMIX_TIME_REMAINING) that can be used with the PMIx_Query_info_nb interface to obtain the number of seconds remaining in the current job allocation. Note that one could alternatively use the PMIx_Register_event_handler API to register for an event indicating incipient job termination, and then use the PMIx_Job_control_nb API to request that the host SMS generate an event a specified amount of time prior to reaching the maximum run time. PMIx provides such alternate methods as a means of maximizing the probability of a host system supporting at least one method by which the application can obtain the desired service.

The following APIs support query of various session and environment values.

5.4.1 PMIx_Resolve_peers

Summary

Obtain the array of processes within the specified namespace that are executing on a given node.

```
25
               Format
    PMIx v1.0
26
               pmix_status_t
27
               PMIx Resolve peers (const char *nodename,
28
                                       const pmix_nspace_t nspace,
29
                                       pmix_proc_t **procs, size_t *nprocs);
                                                            C -
30
               IN
                    nodename
31
                    Name of the node to query - NULL can be used to denote the current local node (string)
32
               IN
                    nspace
33
                    namespace (string)
34
               OUT procs
35
                    Array of process structures (array of handles)
36
               OUT nprocs
37
                    Number of elements in the procs array (integer)
```

Returns **PMIX SUCCESS** or a negative value corresponding to a PMIx error constant.

Description 1 2 Given a *nodename*, return the array of processes within the specified *nspace* that are executing on that node. If 3 the nspace is **NULL**, then all processes on the node will be returned. If the specified node does not currently 4 host any processes, then the returned array will be NULL, and nprocs will be zero. The caller is responsible for 5 releasing the procs array when done with it. The PMIX_PROC_FREE macro is provided for this purpose. 5.4.2 PMIx Resolve nodes 7 Summary 8 Return a list of nodes hosting processes within the given namespace. 9 $_{PMIx\ v1.0}$ 10 pmix status t PMIx_Resolve_nodes(const char *nspace, char **nodelist); 11 12 IN nspace 13 Namespace (string) 14 **OUT** nodelist 15 Comma-delimited list of nodenames (string) 16 Returns **PMIX_SUCCESS** or a negative value corresponding to a PMIx error constant. 17 **Description** 18 Given a *nspace*, return the list of nodes hosting processes within that namespace. The returned string will 19 contain a comma-delimited list of nodenames. The caller is responsible for releasing the string when done 20 with it. 5.4.3 PMIx_Query_info 21 22 Summary 23 Query information about the system in general. 24 _{PMIx v4.0} Format 25 pmix_status_t 26 PMIx_Query_info(pmix_query_t queries[], size_t nqueries, 27 pmix_info_t *info[], size_t *ninfo); _____ C ____ 28 queries 29 Array of query structures (array of handles) 30 IN nqueries 31 Number of elements in the *queries* array (integer)

Address where a pointer to an array of **pmix_info_t** containing the results of the query can be

returned (memory reference)

INOUT info

32

33

34

INOUT ninfo

1

3

4

5

6

7

8

9

10

11

12

13 14

15

16

17

18

19

20

21

22

23

24

25

26

27

28

29

30

31 32

33

34

35

36

37

Address where the number of elements in *info* can be returned (handle)

Returns one of the following:

- PMIX SUCCESS All data was found and has been returned.
- PMIX_ERR_NOT_FOUND None of the requested data was available. The info array will be NULL and ninfo zero.
- PMIX_ERR_PARTIAL_SUCCESS Some of the requested data was found. The *info* array shall contain an element for each query key that returned a value.
- PMIX_ERR_NOT_SUPPORTED The host RM does not support this function. The *info* array will be **NULL** and *ninfo* zero.
- a non-zero PMIx error constant indicating a reason for the request's failure. The info array will be NULL
 and ninfo zero.

Required Attributes ------

PMIx libraries and host environments that support this API are required to support the following attributes:

```
{\color{red} {\tt PMIX\_QUERY\_REFRESH\_CACHE}} \quad "{\tt pmix.qry.rfsh"} \ ({\tt bool})
```

Retrieve updated information from server. NO QUALIFIERS.

```
PMIX_SESSION_INFO "pmix.ssn.info" (bool)
```

Return information regarding the session realm of the target process.

```
PMIX_JOB_INFO "pmix.job.info" (bool)
```

Return information regarding the job realm corresponding to the namespace in the target process' identifier.

```
PMIX_APP_INFO "pmix.app.info" (bool)
```

Return information regarding the application realm to which the target process belongs - the namespace of the target process serves to identify the job containing the target application. If information about an application other than the one containing the target process is desired, then the attribute array must contain a **PMIX_APPNUM** attribute identifying the desired target application. This is useful in cases where there are multiple applications and the mapping of processes to applications is unclear.

PMIX_NODE_INFO "pmix.node.info" (bool)

Return information from the node realm regarding the node upon which the specified process is executing. If information about a node other than the one containing the specified process is desired, then the attribute array must also contain either the PMIX_NODEID or PMIX_HOSTNAME attribute identifying the desired target. This is useful for requesting information about a specific node even if the identity of processes running on that node are not known.

PMIX_PROC_INFO "pmix.proc.info" (bool)

Return information regarding the target process. This attribute is technically not required as the **PMI**×_Get API specifically identifies the target process in its parameters. However, it is included here for completeness.

PMIX_PROCID "pmix.procid" (pmix_proc_t)

Process identifier. Used as a key in **PMIx_Get** to retrieve the caller's own process identifier in a portion of the program that doesn't have access to the memory location in which it was originally stored (e.g., due to a call to **PMIx_Init**). The process identifier in the **PMIx_Get** call is ignored in this instance. In this context, specifies the process ID whose information is being requested - e.g., a query asking for the **pmix_proc_info_t** of a specified process. Only required when the request is for information on a specific process.

PMIX_NSPACE "pmix.nspace" (char*)

Namespace of the job - may be a numerical value expressed as a string, but is often an alphanumeric string carrying information solely of use to the system. Required to be unique within the scope of the host environment. Specifies the namespace of the process whose information is being requested. Must be accompanied by the PMIX_RANK attribute. Only required when the request is for information on a specific process.

PMIX_RANK "pmix.rank" (pmix_rank_t)

Process rank within the job, starting from zero. Specifies the rank of the process whose information is being requested. Must be accompanied by the **PMIX_NSPACE** attribute. Only required when the request is for information on a specific process.

PMIX_QUERY_ATTRIBUTE_SUPPORT "pmix.qry.attrs" (bool)

Query list of supported attributes for specified APIs. REQUIRED QUALIFIERS: one or more of PMIX_CLIENT_FUNCTIONS, PMIX_SERVER_FUNCTIONS, PMIX_TOOL_FUNCTIONS, and PMIX HOST FUNCTIONS.

PMIX_CLIENT_ATTRIBUTES "pmix.client.attrs" (bool)

Request attributes supported by the PMIx client library.

PMIX_SERVER_ATTRIBUTES "pmix.srvr.attrs" (bool)

Request attributes supported by the PMIx server library.

```
PMIX_HOST_ATTRIBUTES "pmix.host.attrs" (bool)
```

Request attributes supported by the host environment.

```
PMIX TOOL ATTRIBUTES "pmix.setup.env" (bool)
```

Request attributes supported by the PMIx tool library functions.

Note that inclusion of both the PMIX_PROCID directive and either the PMIX_NSPACE or the PMIX_RANK attribute will return a PMIX_ERR_BAD_PARAM result, and that the inclusion of a process identifier must apply to all keys in that pmix_query_t. Queries for information on multiple specific processes therefore requires submitting multiple pmix_query_t structures, each referencing one process.

PMIx libraries are not required to directly support any other attributes for this function. However, all provided attributes must be passed to the host SMS daemon for processing. The PMIx library is *required* to add the PMIX_USERID and the PMIX_GRPID attributes of the client process making the request.

	▼ Optional Attributes
1	The following attributes are optional for host environments that support this operation:
2 3	<pre>PMIX_QUERY_NAMESPACES "pmix.qry.ns" (char*) Request a comma-delimited list of active namespaces. NO QUALIFIERS.</pre>
4 5 6	PMIX_QUERY_JOB_STATUS "pmix.qry.jst" (pmix_status_t) Status of a specified, currently executing job. REQUIRED QUALIFIER: PMIX_NSPACE indicating the namespace whose status is being queried.
7 8	<pre>PMIX_QUERY_QUEUE_LIST "pmix.qry.qlst" (char*) Request a comma-delimited list of scheduler queues. NO QUALIFIERS.</pre>
9 10 11	PMIX_QUERY_QUEUE_STATUS "pmix.qry.qst" (char*) Returns status of a specified scheduler queue, expressed as a string. OPTIONAL QUALIFIERS: PMIX_ALLOC_QUEUE naming specific queue whose status is being requested.
12 13 14 15	PMIX_QUERY_PROC_TABLE "pmix.qry.ptable" (char*) Returns a (pmix_data_array_t) array of pmix_proc_info_t, one entry for each process in the specified namespace, ordered by process job rank. REQUIRED QUALIFIER: PMIX_NSPACE indicating the namespace whose process table is being queried.
16 17 18 19 20 21	PMIX_QUERY_LOCAL_PROC_TABLE "pmix.qry.lptable" (char*) Returns a (pmix_data_array_t) array of pmix_proc_info_t, one entry for each process in the specified namespace executing on the same node as the requester, ordered by process job rank. REQUIRED QUALIFIER: PMIX_NSPACE indicating the namespace whose local process table is being queried. OPTIONAL QUALIFIER: PMIX_HOSTNAME indicating the host whose local process table is being queried. By default, the query assumes that the host upon which the request was made is to be used.
23 24	PMIX_QUERY_SPAWN_SUPPORT "pmix.qry.spawn" (boo1) Return a comma-delimited list of supported spawn attributes. NO QUALIFIERS.
25 26	PMIX_QUERY_DEBUG_SUPPORT "pmix.qry.debug" (boo1) Return a comma-delimited list of supported debug attributes. NO QUALIFIERS.
27 28 29 30	PMIX_QUERY_MEMORY_USAGE "pmix.qry.mem" (bool) Return information on memory usage for the processes indicated in the qualifiers. OPTIONAL QUALIFIERS: PMIX_NSPACE and PMIX_RANK, or PMIX_PROCID of specific process(es) whose memory usage is being requested.
31 32	PMIX_QUERY_REPORT_AVG "pmix.qry.avg" (bool) Report only average values for sampled information. NO QUALIFIERS.
33 34	PMIX_QUERY_REPORT_MINMAX "pmix.qry.minmax" (bool) Report minimum and maximum values. NO QUALIFIERS.
35 36	<pre>PMIX_QUERY_ALLOC_STATUS "pmix.query.alloc" (char*) String identifier of the allocation whose status is being requested. NO QUALIFIERS.</pre>
37	<pre>PMIX_TIME_REMAINING "pmix.time.remaining" (char*)</pre>

 Query number of seconds (uint32_t) remaining in allocation for the specified namespace.

OPTIONAL QUALIFIERS: PMIX_NSPACE of the namespace whose info is being requested (defaults to allocation containing the caller).

PMIX SERVER URI "pmix.srvr.uri" (char*)

URI of the PMIx server to be contacted. Requests the URI of the specified PMIx server's PMIx connection. Defaults to requesting the information for the local PMIx server.

PMIX CLIENT AVG MEMORY "pmix.cl.mem.avg" (float)

Average Megabytes of memory used by client processes on node. OPTIONAL QUALIFERS: **PMIX HOSTNAME** or **PMIX NODEID** (defaults to caller's node).

```
PMIX_DAEMON_MEMORY "pmix.dmn.mem" (float)
```

Megabytes of memory currently used by the RM daemon on the node. OPTIONAL QUALIFERS: **PMIX_HOSTNAME** or **PMIX_NODEID** (defaults to caller's node).

```
PMIX_QUERY_AUTHORIZATIONS "pmix.qry.auths" (bool)
```

Return operations the PMIx tool is authorized to perform. NO QUALIFIERS.

```
PMIX_PROC_PID "pmix.ppid" (pid_t)
```

Operating system PID of specified process.

```
PMIX PROC STATE STATUS "pmix.proc.state" (pmix proc state t)
```

State of the specified process as of the last report - may not be the actual current state based on update rate.

Description

Query information about the system in general. This can include a list of active namespaces, fabric topology, etc. Also can be used to query node-specific info such as the list of peers executing on a given node. The host environment is responsible for exercising appropriate access control on the information.

The returned *status* indicates if requested data was found or not. The returned *info* array will contain a **PMIX_QUERY_RESULTS** element for each query of the *queries* array. If qualifiers were included in the query, then the first element of each results array shall contain the **PMIX_QUERY_QUALIFIERS** key with a **pmix_data_array_t** containing the qualifiers. The remaining **pmix_info_t** shall contain the results of the query, one entry for each key that was found. Note that duplicate keys in the *queries* array shall result in duplicate responses within the constraints of the accompanying qualifiers. The caller is responsible for releasing the returned array.

Advice to PMIx library implementers

Information returned from PMIx_Query_info shall be locally cached so that retrieval by subsequent calls to PMIx_Get, PMIx_Query_info, or PMIx_Query_info_nb can succeed with minimal overhead. The local cache shall be checked prior to querying the PMIx server and/or the host environment. Queries that include the PMIX_QUERY_REFRESH_CACHE attribute shall bypass the local cache and retrieve a new value for the query, refreshing the values in the cache upon return.

PMIx Query info nb Summary 2 3 Query information about the system in general. Format PMIx v2.05 pmix_status t 6 PMIx_Query_info_nb(pmix_query_t queries[], size_t nqueries, pmix_info_cbfunc_t cbfunc, void *cbdata); 7 C 8 IN queries 9 Array of query structures (array of handles) 10 IN ngueries 11 Number of elements in the *queries* array (integer) 12 cbfunc IN 13 Callback function **pmix info cbfunc t** (function reference) IN cbdata 14 15 Data to be passed to the callback function (memory reference) 16 Returns one of the following: 17 • PMIX SUCCESS indicating that the request has been accepted for processing and the provided callback 18 function will be executed upon completion of the operation. Note that the library must not invoke the 19 callback function prior to returning from the API. 20 • a non-zero PMIx error constant indicating a reason for the request to have been rejected. In this case, the 21 provided callback function will not be executed. 22 If executed, the status returned in the provided callback function will be one of the following constants: 23 • PMIX SUCCESS All data was found and has been returned. 24 • PMIX_ERR_NOT_FOUND None of the requested data was available. The *info* array will be **NULL** and *ninfo* 25 zero. 26 • PMIX_ERR_PARTIAL_SUCCESS Some of the requested data was found. The info array shall contain an element for each query key that returned a value. 27 28 • PMIX ERR NOT SUPPORTED The host RM does not support this function. The *info* array will be NULL 29 and *ninfo* zero. 30 • a non-zero PMIx error constant indicating a reason for the request's failure. The *info* array will be **NULL** 31 and ninfo zero. Required Attributes 32 PMIx libraries and host environments that support this API are required to support the following attributes: 33 PMIX QUERY REFRESH CACHE "pmix.grv.rfsh" (bool) 34 Retrieve updated information from server. NO QUALIFIERS. 35 PMIX_SESSION_INFO "pmix.ssn.info" (bool)

5.4.4

Return information regarding the session realm of the target process.

PMIX_JOB_INFO "pmix.job.info" (bool)

Return information regarding the job realm corresponding to the namespace in the target process' identifier.

PMIX_APP_INFO "pmix.app.info" (bool)

Return information regarding the application realm to which the target process belongs - the namespace of the target process serves to identify the job containing the target application. If information about an application other than the one containing the target process is desired, then the attribute array must contain a PMIX_APPNUM attribute identifying the desired target application. This is useful in cases where there are multiple applications and the mapping of processes to applications is unclear.

PMIX_NODE_INFO "pmix.node.info" (bool)

Return information from the node realm regarding the node upon which the specified process is executing. If information about a node other than the one containing the specified process is desired, then the attribute array must also contain either the <code>PMIX_NODEID</code> or <code>PMIX_HOSTNAME</code> attribute identifying the desired target. This is useful for requesting information about a specific node even if the identity of processes running on that node are not known..

PMIX PROC INFO "pmix.proc.info" (bool)

Return information regarding the target process. This attribute is technically not required as the **PMIx_Get** API specifically identifies the target process in its parameters. However, it is included here for completeness.

PMIX_PROCID "pmix.procid" (pmix_proc_t)

Process identifier. Used as a key in **PMIx_Get** to retrieve the caller's own process identifier in a portion of the program that doesn't have access to the memory location in which it was originally stored (e.g., due to a call to **PMIx_Init**). The process identifier in the **PMIx_Get** call is ignored in this instance. In this context, specifies the process ID whose information is being requested - e.g., a query asking for the **pmix_proc_info_t** of a specified process. Only required when the request is for information on a specific process.

PMIX_NSPACE "pmix.nspace" (char*)

Namespace of the job - may be a numerical value expressed as a string, but is often an alphanumeric string carrying information solely of use to the system. Required to be unique within the scope of the host environment. Specifies the namespace of the process whose information is being requested. Must be accompanied by the PMIX_RANK attribute. Only required when the request is for information on a specific process.

PMIX_RANK "pmix.rank" (pmix_rank_t)

Process rank within the job, starting from zero. Specifies the rank of the process whose information is being requested. Must be accompanied by the **PMIX_NSPACE** attribute. Only required when the request is for information on a specific process.

PMIX_QUERY_ATTRIBUTE_SUPPORT "pmix.qry.attrs" (bool)

Query list of supported attributes for specified APIs. REQUIRED QUALIFIERS: one or more of PMIX_CLIENT_FUNCTIONS, PMIX_SERVER_FUNCTIONS, PMIX_TOOL_FUNCTIONS, and PMIX_HOST_FUNCTIONS.

```
PMIX CLIENT ATTRIBUTES "pmix.client.attrs" (bool)
```

1	Request attributes supported by the PMIx client library.
2 3	PMIX_SERVER_ATTRIBUTES "pmix.srvr.attrs" (bool) Request attributes supported by the PMIx server library.
4 5	PMIX_HOST_ATTRIBUTES "pmix.host.attrs" (bool) Request attributes supported by the host environment.
6 7	PMIX_TOOL_ATTRIBUTES "pmix.setup.env" (bool) Request attributes supported by the PMIx tool library functions.
8 9 10 11	Note that inclusion of both the PMIX_PROCID directive and either the PMIX_NSPACE or the PMIX_RANK attribute will return a PMIX_ERR_BAD_PARAM result, and that the inclusion of a process identifier must apply to all keys in that pmix_query_t. Queries for information on multiple specific processes therefore requires submitting multiple pmix_query_t structures, each referencing one process.
12 13 14	PMIx libraries are not required to directly support any other attributes for this function. However, all provided attributes must be passed to the host SMS daemon for processing. The PMIx library is <i>required</i> to add the PMIX_USERID and the PMIX_GRPID attributes of the client process making the request.
	▼ Optional Attributes
15	The following attributes are optional for host environments that support this operation:
16 17	<pre>PMIX_QUERY_NAMESPACES "pmix.qry.ns" (char*) Request a comma-delimited list of active namespaces. NO QUALIFIERS.</pre>
18 19 20	PMIX_QUERY_JOB_STATUS "pmix.qry.jst" (pmix_status_t) Status of a specified, currently executing job. REQUIRED QUALIFIER: PMIX_NSPACE indicating the namespace whose status is being queried.
21 22	PMIX_QUERY_QUEUE_LIST "pmix.qry.qlst" (char*) Request a comma-delimited list of scheduler queues. NO QUALIFIERS.
23 24 25	PMIX_QUERY_QUEUE_STATUS "pmix.qry.qst" (char*) Returns status of a specified scheduler queue, expressed as a string. OPTIONAL QUALIFIERS: PMIX_ALLOC_QUEUE naming specific queue whose status is being requested.
26 27 28 29	PMIX_QUERY_PROC_TABLE "pmix.qry.ptable" (char*) Returns a (pmix_data_array_t) array of pmix_proc_info_t, one entry for each process in the specified namespace, ordered by process job rank. REQUIRED QUALIFIER: PMIX_NSPACE indicating the namespace whose process table is being queried.
30 31 32 33 34 35 36	PMIX_QUERY_LOCAL_PROC_TABLE "pmix.qry.lptable" (char*) Returns a (pmix_data_array_t) array of pmix_proc_info_t, one entry for each process in the specified namespace executing on the same node as the requester, ordered by process job rank. REQUIRED QUALIFIER: PMIX_NSPACE indicating the namespace whose local process table is being queried. OPTIONAL QUALIFIER: PMIX_HOSTNAME indicating the host whose local process table is being queried. By default, the query assumes that the host upon which the request was made is to be used.
37	PMIX_QUERY_SPAWN_SUPPORT "pmix.qry.spawn" (bool)

1	Return a comma-delimited list of supported spawn attributes. NO QUALIFIERS.
2	<pre>PMIX_QUERY_DEBUG_SUPPORT "pmix.qry.debug" (bool) Return a comma-delimited list of supported debug attributes. NO QUALIFIERS.</pre>
4 5 6 7	PMIX_QUERY_MEMORY_USAGE "pmix.qry.mem" (bool) Return information on memory usage for the processes indicated in the qualifiers. OPTIONAL QUALIFIERS: PMIX_NSPACE and PMIX_RANK, or PMIX_PROCID of specific process(es) whose memory usage is being requested.
8 9	PMIX_QUERY_REPORT_AVG "pmix.qry.avg" (bool) Report only average values for sampled information. NO QUALIFIERS.
10 11	PMIX_QUERY_REPORT_MINMAX "pmix.qry.minmax" (bool) Report minimum and maximum values. NO QUALIFIERS.
12 13	<pre>PMIX_QUERY_ALLOC_STATUS "pmix.query.alloc" (char*) String identifier of the allocation whose status is being requested. NO QUALIFIERS.</pre>
14 15 16 17	<pre>PMIX_TIME_REMAINING "pmix.time.remaining" (char*) Query number of seconds (uint32_t) remaining in allocation for the specified namespace. OPTIONAL QUALIFIERS: PMIX_NSPACE of the namespace whose info is being requested (defaults to allocation containing the caller).</pre>
18 19 20	PMIX_SERVER_URI "pmix.srvr.uri" (char*) URI of the PMIx server to be contacted. Requests the URI of the specified PMIx server's PMIx connection. Defaults to requesting the information for the local PMIx server.
21 22 23	PMIX_CLIENT_AVG_MEMORY "pmix.cl.mem.avg" (float) Average Megabytes of memory used by client processes on node. OPTIONAL QUALIFERS: PMIX_HOSTNAME or PMIX_NODEID (defaults to caller's node).
24 25 26	PMIX_DAEMON_MEMORY "pmix.dmn.mem" (float) Megabytes of memory currently used by the RM daemon on the node. OPTIONAL QUALIFERS: PMIX_HOSTNAME or PMIX_NODEID (defaults to caller's node).
27 28	PMIX_QUERY_AUTHORIZATIONS "pmix.qry.auths" (bool) Return operations the PMIx tool is authorized to perform. NO QUALIFIERS.
29 30	PMIX_PROC_PID "pmix.ppid" (pid_t) Operating system PID of specified process.
31 32 33	PMIX_PROC_STATE_STATUS "pmix.proc.state" (pmix_proc_state_t) State of the specified process as of the last report - may not be the actual current state based on update rate.
34	Description

DescriptionNon-blocking form of the **PMIx_Query_info** API.

5.4.5 Query-specific constants

PMIX QUERY PARTIAL SUCCESS Some, but not all, of the requested information was returned.

5.4.6 Query attributes

2

4 5

6

7

8

9

10

11 12

13

14

15

16

17

18

19

20 21

22 23

24

25

26

27

28

29

30

31 32

33

34

35

36

37

38

39

40

41

42

Attributes used to direct behavior of the **PMIx_Query_info** APIs.

PMIX_QUERY_RESULTS "pmix.qry.res" (pmix_data_array_t)

Contains an array of query results for a given <code>pmix_query_t</code> passed to the <code>PMIx_Query_info</code> APIs. If qualifiers were included in the query, then the first element of the array shall be the <code>PMIX_QUERY_QUALIFIERS</code> attribute containing those qualifiers. Each of the remaining elements of the array is a <code>pmix_info_t</code> containing the query key and the corresponding value returned by the query. This attribute is solely for reporting purposes and cannot be used in <code>PMIx_Get</code> or other query operations.

PMIX_QUERY_QUALIFIERS "pmix.qry.quals" (pmix_data_array_t)

Contains an array of qualifiers that were included in the query that produced the provided results. This attribute is solely for reporting purposes and cannot be used in **PMIx_Get** or other query operations.

PMIX_QUERY_SUPPORTED_KEYS "pmix.qry.keys" (char*)

Returns comma-delimited list of keys supported by the query function. NO QUALIFIERS.

PMIX QUERY SUPPORTED QUALIFIERS "pmix.qry.quals" (char*)

Return comma-delimited list of qualifiers supported by a query on the provided key, instead of actually performing the query on the key. NO QUALIFIERS.

 ${\tt PMIX_QUERY_REFRESH_CACHE~"pmix.qry.rfsh"~(bool)}$

Retrieve updated information from server. NO QUALIFIERS.

PMIX_QUERY_NAMESPACES "pmix.qry.ns" (char*)

Request a comma-delimited list of active namespaces. NO QUALIFIERS.

PMIX_QUERY_NAMESPACE_INFO "pmix.qry.nsinfo" (pmix_data_array_t*)

Return an array of active namespace information - each element will itself contain an array including the namespace plus the command line of the application executing within it. OPTIONAL

QUALIFIERS: **PMIX_NSPACE** of specific namespace whose info is being requested.

PMIX_QUERY_JOB_STATUS "pmix.qry.jst" (pmix_status_t)

Status of a specified, currently executing job. REQUIRED QUALIFIER: **PMIX_NSPACE** indicating the namespace whose status is being queried.

PMIX_QUERY_QUEUE_LIST "pmix.qry.qlst" (char*)

Request a comma-delimited list of scheduler queues. NO QUALIFIERS.

PMIX_QUERY_QUEUE_STATUS "pmix.qry.qst" (char*)

Returns status of a specified scheduler queue, expressed as a string. OPTIONAL QUALIFIERS: **PMIX ALLOC QUEUE** naming specific queue whose status is being requested.

PMIX_QUERY_PROC_TABLE "pmix.qry.ptable" (char*)

Returns a (pmix_data_array_t) array of pmix_proc_info_t, one entry for each process in the specified namespace, ordered by process job rank. REQUIRED QUALIFIER: PMIX_NSPACE indicating the namespace whose process table is being queried.

PMIX_QUERY_LOCAL_PROC_TABLE "pmix.qry.lptable" (char*)

Returns a (pmix_data_array_t) array of pmix_proc_info_t, one entry for each process in the specified namespace executing on the same node as the requester, ordered by process job rank.

1 2 3 4	REQUIRED QUALIFIER: PMIX_NSPACE indicating the namespace whose local process table is being queried. OPTIONAL QUALIFIER: PMIX_HOSTNAME indicating the host whose local process table is being queried. By default, the query assumes that the host upon which the request was made i to be used.
5	PMIX_QUERY_AUTHORIZATIONS "pmix.qry.auths" (bool)
6	Return operations the PMIx tool is authorized to perform. NO QUALIFIERS.
7	PMIX_QUERY_SPAWN_SUPPORT "pmix.qry.spawn" (bool)
8	Return a comma-delimited list of supported spawn attributes. NO QUALIFIERS.
9	PMIX_QUERY_DEBUG_SUPPORT "pmix.qry.debug" (bool)
0	Return a comma-delimited list of supported debug attributes. NO QUALIFIERS.
1	PMIX_QUERY_MEMORY_USAGE "pmix.qry.mem" (bool)
2	Return information on memory usage for the processes indicated in the qualifiers. OPTIONAL
3	QUALIFIERS: PMIX_NSPACE and PMIX_RANK, or PMIX_PROCID of specific process(es) whose
4	memory usage is being requested.
5	PMIX_QUERY_LOCAL_ONLY "pmix.qry.local" (bool)
6	Constrain the query to local information only. NO QUALIFIERS.
7	PMIX_QUERY_REPORT_AVG "pmix.qry.avg" (bool)
8	Report only average values for sampled information. NO QUALIFIERS.
9	PMIX_QUERY_REPORT_MINMAX "pmix.qry.minmax" (bool)
20	Report minimum and maximum values. NO QUALIFIERS.
?1 ?2	PMIX_QUERY_ALLOC_STATUS "pmix.query.alloc" (char*)
	String identifier of the allocation whose status is being requested. NO QUALIFIERS. PMIX TIME REMAINING "pmix.time.remaining" (char*)
23 24	Query number of seconds (uint32_t) remaining in allocation for the specified namespace.
. 4 !5	OPTIONAL QUALIFIERS: PMIX_NSPACE of the namespace whose info is being requested (default
26	to allocation containing the caller).
27	PMIX_QUERY_ATTRIBUTE_SUPPORT "pmix.qry.attrs" (bool)
., 28	Query list of supported attributes for specified APIs. REQUIRED QUALIFIERS: one or more of
29	PMIX_CLIENT_FUNCTIONS, PMIX_SERVER_FUNCTIONS, PMIX_TOOL_FUNCTIONS, and
80	PMIX HOST FUNCTIONS.
81	PMIX_QUERY_NUM_PSETS "pmix.qry.psetnum" (size_t)
32	Return the number of process sets defined in the specified range (defaults to
3	PMIX_RANGE_SESSION).
34	<pre>PMIX_QUERY_PSET_NAMES "pmix.qry.psets" (pmix_data_array_t*)</pre>
35	Return a pmix_data_array_t containing an array of strings of the process set names defined in
86	the specified range (defaults to PMIX_RANGE_SESSION).
37	PMIX_QUERY_PSET_MEMBERSHIP "pmix.qry.pmems" (pmix_data_array_t*)
88	Return an array of pmix_proc_t containing the members of the specified process set.
19	<pre>PMIX_QUERY_AVAIL_SERVERS "pmix.qry.asrvrs" (pmix_data_array_t*)</pre>
-0	Return an array of pmix_info_t, each element itself containing a PMIX_SERVER_INFO_ARRAY
-1	entry holding all available data for a server on this node to which the caller might be able to connect.
2	<pre>PMIX_SERVER_INFO_ARRAY "pmix.srv.arr" (pmix_data_array_t)</pre>
-3	Array of pmix_info_t about a given server, starting with its PMIX_NSPACE and including at leas
4	one of the rendezvous-required pieces of information.

```
1
                These attributes are used to query memory available and used in the system.
 2
                PMIX_AVAIL_PHYS_MEMORY "pmix.pmem" (uint64_t)
 3
                      Total available physical memory on a node. OPTIONAL QUALIFERS: PMIX_HOSTNAME or
 4
                      PMIX NODEID (defaults to caller's node).
 5
                PMIX_DAEMON_MEMORY "pmix.dmn.mem" (float)
 6
                      Megabytes of memory currently used by the RM daemon on the node. OPTIONAL QUALIFERS:
 7
                      PMIX HOSTNAME or PMIX NODEID (defaults to caller's node).
 8
                PMIX_CLIENT_AVG_MEMORY "pmix.cl.mem.avg" (float)
 9
                      Average Megabytes of memory used by client processes on node. OPTIONAL QUALIFERS:
                      PMIX_HOSTNAME or PMIX_NODEID (defaults to caller's node).
10
11
                The following attributes are used as qualifiers in queries regarding attribute support within the PMIx
12
                implementation and/or the host environment:
13
                PMIX_CLIENT_FUNCTIONS "pmix.client.fns" (bool)
14
                      Request a list of functions supported by the PMIx client library.
15
                PMIX_CLIENT_ATTRIBUTES "pmix.client.attrs" (bool)
16
                      Request attributes supported by the PMIx client library.
17
                PMIX_SERVER_FUNCTIONS "pmix.srvr.fns" (bool)
18
                      Request a list of functions supported by the PMIx server library.
19
                PMIX_SERVER_ATTRIBUTES "pmix.srvr.attrs" (bool)
20
                      Request attributes supported by the PMIx server library.
21
                PMIX_HOST_FUNCTIONS "pmix.srvr.fns" (bool)
22
                      Request a list of functions supported by the host environment.
23
                PMIX_HOST_ATTRIBUTES "pmix.host.attrs" (bool)
24
                      Request attributes supported by the host environment.
25
                PMIX_TOOL_FUNCTIONS "pmix.tool.fns" (bool)
26
                      Request a list of functions supported by the PMIx tool library.
27
                PMIX_TOOL_ATTRIBUTES "pmix.setup.env" (bool)
28
                      Request attributes supported by the PMIx tool library functions.
     5.4.7
                Query Structure
29
30
                The pmix query t structure is used by the PMIx Query info APIs to describe a single query
31
                operation.
    PMIx v2.0
32
                typedef struct pmix_query {
33
                     char **keys;
34
                     pmix_info_t *qualifiers;
35
                     size_t nqual;
36
                } pmix_query_t;
37
                where:
38
                • keys is a NULL-terminated argv-style array of strings
```

```
1
                • qualifiers is an array of pmix_info_t describing constraints on the query
 2
                • nqual is the number of elements in the qualifiers array
     5.4.7.1 Query structure support macros
 3
                The following macros are provided to support the pmix_query_t structure.
 4
                Static initializer for the guery structure
 5
 6
                (Provisional)
                Provide a static initializer for the pmix query t fields.
   PMIx v4.2
                PMIX QUERY STATIC INIT
 8
                Initialize the query structure
 9
                Initialize the pmix_query_t fields
10
   PMIx v2.0
11
                PMIX QUERY CONSTRUCT (m)
12
13
                      Pointer to the structure to be initialized (pointer to pmix_query_t
                Destruct the query structure
14
15
                Destruct the pmix_query_t fields
   PMIx v2.0
                PMIX QUERY DESTRUCT (m)
16
                IN
17
18
                      Pointer to the structure to be destructed (pointer to pmix_query_t)
                Create a query array
19
                Allocate and initialize an array of pmix_query_t structures
20
   PMIx v2.0
21
                PMIX QUERY CREATE (m, n)
22
                INOUT m
                      Address where the pointer to the array of pmix_query_t structures shall be stored (handle)
23
                IN
24
25
                      Number of structures to be allocated (size_t)
```

1 2		Release a pmix_query_t structure
3		PMIX_QUERY_RELEASE (m)
4 5		IN m Pointer to a pmix_query_t structure (handle)
6 7	PMIx v2.0	Free a query array Release an array of pmix_query_t structures C
8		PMIX_QUERY_FREE(m, n)
9 10 11		 IN m Pointer to the array of pmix_query_t structures (handle) IN n Number of structures in the array (size_t)
13 14 15	PMIx v2.2	Create the info array of query qualifiers Create an array of pmix_info_t structures for passing query qualifiers, updating the nqual field of the pmix_query_t structure.
16		PMIX_QUERY_QUALIFIERS_CREATE(m, n)
17 18 19 20		 IN m Pointer to the pmix_query_t structure (handle) IN n Number of qualifiers to be allocated (size_t)
21	5.5	Using Get vs Query
22 23		Both PMIx_Get and PMIx_Query_info can be used to retrieve information about the system. In general, the <i>get</i> operation should be used to retrieve:
24 25		• information provided by the host environment at time of job start. This includes information on the number of processes in the job, their location, and possibly their communication endpoints.
26		• information posted by processes via the PMTx. Put function

This information is largely considered to be *static*, although this will not necessarily be true for environments supporting dynamic programming models or fault tolerance. Note that the **PMIx_Get** function only accesses information about execution environments - i.e., its scope is limited to values pertaining to a specific *session*, *job*, *application*, *process*, or *node*. It cannot be used to obtain information about areas such as the status of queues in the WLM.

In contrast, the *query* option should be used to access:

- system-level information (such as the available WLM queues) that would generally not be included in job-level information provided at job start.
- dynamic information such as application and queue status, and resource utilization statistics. Note that the
 PMIX_QUERY_REFRESH_CACHE attribute must be provided on each query to ensure current data is
 returned.
- information created post job start, such as process tables.
- information requiring more complex search criteria than supported by the simpler PMIx_Get API.
- queries focused on retrieving multi-attribute blocks of data with a single request, thus bypassing the single-key limitation of the PMIx_Get API.

In theory, all information can be accessed via **PMIx_Query_info** as the local cache is typically the same datastore searched by **PMIx_Get**. However, in practice, the overhead associated with the *query* operation may (depending upon implementation) be higher than the simpler *get* operation due to the need to construct and process the more complex **pmix_query_t** structure. Thus, requests for a single key value are likely to be accomplished faster with **PMIx_Get** versus the *query* operation.

5.6 Accessing attribute support information

Information as to which attributes are supported by either the PMIx implementation or its host environment can be obtained via the PMIx_Query_info APIs. The PMIX_QUERY_ATTRIBUTE_SUPPORT attribute must be listed as the first entry in the keys field of the pmix_query_t structure, followed by the name of the function whose attribute support is being requested - support for multiple functions can be requested simultaneously by simply adding the function names to the array of keys. Function names must be given as user-level API names - e.g., "PMIx_Get", "PMIx_server_setup_application", or "PMIx_tool_attach_to_server".

The desired levels of attribute support are provided as qualifiers. Multiple levels can be requested simultaneously by simply adding elements to the *qualifiers* array. Each qualifier should contain the desired level attribute with the boolean value set to indicate whether or not that level is to be included in the returned information. Failure to provide any levels is equivalent to a request for all levels. Supported levels include:

- PMIX_CLIENT_FUNCTIONS "pmix.client.fns" (bool)

 Request a list of functions supported by the PMIx client library.
- PMIX_CLIENT_ATTRIBUTES "pmix.client.attrs" (bool)

 Request attributes supported by the PMIx client library.
- PMIX_SERVER_FUNCTIONS "pmix.srvr.fns" (bool)

 Request a list of functions supported by the PMIx server library.

- PMIX_SERVER_ATTRIBUTES "pmix.srvr.attrs" (bool)
 Request attributes supported by the PMIx server library.
- PMIX_HOST_FUNCTIONS "pmix.srvr.fns" (bool)

 Request a list of functions supported by the host environment.
- PMIX_HOST_ATTRIBUTES "pmix.host.attrs" (bool)
 Request attributes supported by the host environment.
- PMIX_TOOL_FUNCTIONS "pmix.tool.fns" (bool)
 Request a list of functions supported by the PMIx tool library.
- PMIX_TOOL_ATTRIBUTES "pmix.setup.env" (bool)

 Request attributes supported by the PMIx tool library functions.

Unlike other queries, queries for attribute support can result in the number of returned <code>pmix_info_t</code> structures being different from the number of queries. Each element in the returned array will correspond to a pair of specified attribute level and function in the query, where the <code>key</code> is the function and the <code>value</code> contains a <code>pmix_data_array_t</code> of <code>pmix_info_t</code>. Each element of the array is marked by a <code>key</code> indicating the requested attribute <code>level</code> with a <code>value</code> composed of a <code>pmix_data_array_t</code> of <code>pmix_regattr_t</code>, each describing a supported attribute for that function, as illustrated in Fig. 5.1 below where the requestor asked for supported attributes of <code>PMIx_Get</code> at the <code>client</code> and <code>server</code> levels, plus attributes of <code>PMIx_Allocation_request</code> at all levels.




Figure 5.1.: Returned information hierarchy for attribute support request

The array of returned structures, and their child arrays, are subject to the return rules for the PMIx_Query_info_nb API. For example, a request for supported attributes of the PMIx_Get function that includes the *host* level will return values for the *client* and *server* levels, plus an array element with a *key* of PMIX_HOST_ATTRIBUTES and a value type of PMIX_UNDEF indicating that no attributes are supported at that level.

CHAPTER 6

Reserved Keys

Reserved keys are keys whose string representation begin with a prefix of "pmix". By definition, reserved keys are provided by the host environment and the PMIx server, and are required to be available at client start of execution. PMIx clients and tools are therefore prohibited from posting reserved keys using the PMIx_Put API.

PMIx implementations may choose to define their own custom-prefixed keys which may adhere to either the *reserved* or the *non-reserved* retrieval rules at the discretion of the implementation. Implementations may choose to provide such custom keys at client start of execution, but this is not required.

Host environments may also opt to define their own custom keys. However, PMIx implementations are unlikely to recognize such host-defined keys and will therefore treat them according to the *non-reserved* rules described in Chapter 7. Users are advised to check both the local PMIx implementation and host environment documentation for a list of any custom prefixes they must avoid, and to learn of any non-standard keys that may require special handling.

6.1 Data realms

PMIx information spans a wide range of sources. In some cases, there are multiple overlapping sources for the same type of data - e.g., the session, job, and application can each provide information on the number of nodes involved in their respective area. In order to resolve the ambiguity, a *data realm* is used to identify the scope to which the referenced data applies. Thus, a reference to an attribute that isn't specific to a realm (e.g., the PMIX_NUM_NODES attribute) must be accompanied by a corresponding attribute identifying the realm to which the request pertains if it differs from the default.

PMIx defines five *data realms* to resolve the ambiguities, as captured in the following attributes used in **PMIx_Get** for retrieving information from each of the realms:

```
PMIX_SESSION_INFO "pmix.ssn.info" (bool)
```

Return information regarding the session realm of the target process.

```
PMIX_JOB_INFO "pmix.job.info" (bool)
```

Return information regarding the job realm corresponding to the namespace in the target process' identifier.

```
PMIX_APP_INFO "pmix.app.info" (bool)
```

Return information regarding the application realm to which the target process belongs - the namespace of the target process serves to identify the job containing the target application. If information about an application other than the one containing the target process is desired, then the attribute array must contain a PMIX_APPNUM attribute identifying the desired target application. This is useful in cases where there are multiple applications and the mapping of processes to applications is unclear.

PMIX PROC INFO "pmix.proc.info" (bool)

Return information regarding the target process. This attribute is technically not required as the 1 2 PMIx Get API specifically identifies the target process in its parameters. However, it is included here 3 for completeness. 4 PMIX_NODE_INFO "pmix.node.info" (bool) 5 Return information from the node realm regarding the node upon which the specified process is 6 executing. If information about a node other than the one containing the specified process is desired, 7 then the attribute array must also contain either the PMIX NODEID or PMIX HOSTNAME attribute 8 identifying the desired target. This is useful for requesting information about a specific node even if the 9 identity of processes running on that node are not known.. Advice to users · 10 If information about a session other than the one containing the requesting process is desired, then the attribute 11 array must contain a PMIX_SESSION_ID attribute identifying the desired target session. This is required as 12 many environments only guarantee unique namespaces within a session, and not across sessions. 13 The PMIx server has corresponding attributes the host can use to specify the realm of information that it 14 provides during namespace registration (see Section 16.2.3.2). Session realm attributes 6.1.1 15 16 If information about a session other than the one containing the requesting process is desired, then the info 17 array passed to PMIx Get must contain a PMIX SESSION ID attribute identifying the desired target 18 session. This is required as many environments only guarantee unique namespaces within a session, and not 19 across sessions. 20 Note that the *proc* argument of **PMIx_Get** is ignored when referencing session-related information. 21 Session-level information includes the following attributes: 22 PMIX_SESSION_ID "pmix.session.id" (uint32_t) 23 Session identifier assigned by the scheduler. PMIX_CLUSTER_ID "pmix.clid" (char*) 24 25 A string name for the cluster this allocation is on. PMIX_UNIV_SIZE "pmix.univ.size" (uint32_t) 26 27 Maximum number of process that can be simultaneously executing in a session. Note that this attribute 28 is equivalent to the PMIX MAX PROCS attribute for the session realm - it is included in the PMIx 29 Standard for historical reasons. 30 PMIX_TMPDIR "pmix.tmpdir" (char*) 31

Full path to the top-level temporary directory assigned to the session.

PMIX_TDIR_RMCLEAN "pmix.tdir.rmclean" (bool)

Resource Manager will cleanup assigned temporary directory trees.

PMIX HOSTNAME_KEEP_FQDN "pmix.fqdn" (bool)

Fully Qualified Domain Names (FQDNs) are being retained by the PMIx library.

The following attributes are used to describe the RM - these are values assigned by the host environment to the session:

PMIX RM NAME "pmix.rm.name" (char*)

32

33

34 35

36

37

38

1 2 3		String name of the RM. PMIX_RM_VERSION "pmix.rm.version" (char*) RM version string.
4 5		The remaining session-related information can only be retrieved by including the PMIX_SESSION_INFO attribute in the <i>info</i> array passed to PMIx_Get :
6 7 8		<pre>PMIX_ALLOCATED_NODELIST "pmix.alist" (char*) Comma-delimited list or regular expression of all nodes in the specified realm regardless of whether or not they currently host processes. Defaults to the job realm.</pre>
9 10 11		PMIX_NUM_ALLOCATED_NODES "pmix.num.anodes" (uint32_t) Number of nodes in the specified realm regardless of whether or not they currently host processes. Defaults to the job realm.
12 13 14 15 16		PMIX_MAX_PROCS "pmix.max.size" (uint32_t) Maximum number of processes that can be executed in the specified realm. Typically, this is a constraint imposed by a scheduler or by user settings in a hostfile or other resource description. Defaults to the job realm. PMIX_NODE_LIST "pmix.nlist" (char*)
17 18		Comma-delimited list of nodes currently hosting processes in the specified realm. Defaults to the <i>job</i> realm.
19 20 21 22		PMIX_NUM_SLOTS "pmix.num.slots" (uint32_t) Maximum number of processes that can simultaneously be executing in the specified realm. Note that this attribute is the equivalent to PMIX_MAX_PROCS - it is included in the PMIx Standard for historical reasons. Defaults to the <i>job</i> realm.
23 24 25		PMIX_NUM_NODES "pmix.num.nodes" (uint32_t) Number of nodes currently hosting processes in the specified realm. Defaults to the <i>job</i> realm. PMIX_NODE_MAP "pmix.nmap" (char*)
26 27 28		Regular expression of nodes currently hosting processes in the specified realm - see 16.2.3.2 for an explanation of its generation. Defaults to the <i>job</i> realm. PMIX_NODE_MAP_RAW "pmix.nmap.raw" (char*)
29 30		Comma-delimited list of nodes containing procs within the specified realm. Defaults to the <i>job</i> realm. PMIX_PROC_MAP "pmix.pmap" (char*)
31 32 33		Regular expression describing processes on each node in the specified realm - see 16.2.3.2 for an explanation of its generation. Defaults to the <i>job</i> realm. PMIX_PROC_MAP_RAW "pmix.pmap.raw" (char*)
34 35 36		Semi-colon delimited list of strings, each string containing a comma-delimited list of ranks on the corresponding node within the specified realm. Defaults to the <i>job</i> realm. PMIX_ANL_MAP "pmix.anlmap" (char*)
37 38		Process map equivalent to PMIX_PROC_MAP expressed in Argonne National Laboratory's PMI-1/PMI-2 notation. Defaults to the <i>job</i> realm.
39	6.1.2	Job realm attributes
10 11 12 13		Job-related information is retrieved by including the namespace of the target job and a rank of <code>PMIX_RANK_WILDCARD</code> in the <i>proc</i> argument passed to <code>PMIX_Get</code> . If desired for code clarity, the caller can also include the <code>PMIX_JOB_INFO</code> attribute in the <i>info</i> array, though this is not required. If information is requested about a namespace in a session other than the one containing the requesting process, then the <i>info</i>

array must contain a PMIX_SESSION_ID attribute identifying the desired target session. This is required as many environments only guarantee unique namespaces within a session, and not across sessions.

Job-level information includes the following attributes:

PMIX_NSPACE "pmix.nspace" (char*)

1

2

3

4

5

6

7

8 9

10

11

12

13 14

15

16 17

18

19

20

21

22

23

24

25

26

27

28

29

30

31

32

33

34

35 36

37

38 39

40

41

42

43

Namespace of the job - may be a numerical value expressed as a string, but is often an alphanumeric string carrying information solely of use to the system. Required to be unique within the scope of the host environment.

PMIX_JOBID "pmix.jobid" (char*)

Job identifier assigned by the scheduler to the specified job - may be identical to the namespace, but is often a numerical value expressed as a string (e.g., "12345.3").

PMIX_NPROC_OFFSET "pmix.offset" (pmix_rank_t) Starting global rank of the specified job.

PMIX MAX PROCS "pmix.max.size" (uint32 t)

Maximum number of processes that can be executed in the specified realm. Typically, this is a constraint imposed by a scheduler or by user settings in a hostfile or other resource description. Defaults to the *job* realm. In this context, this is the maximum number of processes that can be simultaneously executed in the specified job, which may be a subset of the number allocated to the overall session.

PMIX_NUM_SLOTS "pmix.num.slots" (uint32_t)

Maximum number of processes that can simultaneously be executing in the specified realm. Note that this attribute is the equivalent to PMIX_MAX_PROCS - it is included in the PMIx Standard for historical reasons. Defaults to the *job* realm. In this context, this is the maximum number of process that can be simultaneously executing within the specified job, which may be a subset of the number allocated to the overall session. Jobs may reserve a subset of their assigned maximum processes for dynamic operations such as PMIx Spawn.

PMIX_NUM_NODES "pmix.num.nodes" (uint32_t)

Number of nodes currently hosting processes in the specified realm. Defaults to the job realm. In this context, this is the number of nodes currently hosting processes in the specified job, which may be a subset of the nodes allocated to the overall session. Jobs may reserve a subset of their assigned nodes for dynamic operations such as PMIx Spawn - i.e., not all nodes may have executing processes from this job at a given point in time.

PMIX_NODE_MAP "pmix.nmap" (char*)

Regular expression of nodes currently hosting processes in the specified realm - see 16.2.3.2 for an explanation of its generation. Defaults to the job realm. In this context, this is the regular expression of nodes currently hosting processes in the specified job.

PMIX_NODE_LIST "pmix.nlist" (char*)

Comma-delimited list of nodes currently hosting processes in the specified realm. Defaults to the job realm. In this context, this is the comma-delimited list of nodes currently hosting processes in the specified job.

PMIX_PROC_MAP "pmix.pmap" (char*)

Regular expression describing processes on each node in the specified realm - see 16.2.3.2 for an explanation of its generation. Defaults to the *job* realm. In this context, this is the regular expression describing processes on each node in the specified job.

```
1 PMIX_ANL_MAP "pmix.anlmap" (char*)
2 Process map equivalent to PMIX_PROC_M
```

Process map equivalent to **PMIX_PROC_MAP** expressed in Argonne National Laboratory's PMI-1/PMI-2 notation. Defaults to the *job* realm. In this context, this is the process mapping in Argonne National Laboratory's PMI-1/PMI-2 notation of the processes in the specified job.

PMIX_CMD_LINE "pmix.cmd.line" (char*)

Command line used to execute the specified job (e.g., "mpirun -n 2 -map-by foo ./myapp: -n 4 ./myapp2"). If the job was created by a call to **PMIx_Spawn**, the string is an inorder concatenation of the values of **PMIX_APP_ARGV** for each application in the job using the character ':' as a separator.

PMIX_NSDIR "pmix.nsdir" (char*)

Full path to the temporary directory assigned to the specified job, under PMIX_TMPDIR.

PMIX_JOB_SIZE "pmix.job.size" (uint32_t)

Total number of processes in the specified job across all contained applications. Note that this value can be different from **PMIX_MAX_PROCS**. For example, users may choose to subdivide an allocation (running several jobs in parallel within it), and dynamic programming models may support adding and removing processes from a running *job* on-the-fly. In the latter case, PMIx events may be used to notify processes within the job that the job size has changed.

PMIX_JOB_NUM_APPS "pmix.job.napps" (uint32_t)

Number of applications in the specified job.

6.1.3 Application realm attributes

Application-related information can only be retrieved by including the PMIX_APP_INFO attribute in the *info* array passed to PMIX_Get. If the PMIX_APPNUM qualifier is given, then the query shall return the corresponding value for the given application within the namespace specified in the *proc* argument of the query (a NULL value for the *proc* argument equates to the namespace of the caller). If the PMIX_APPNUM qualifier is not included, then the retrieval shall default to the application containing the specified process. If the rank of the specified process is PMIX_RANK_WILDCARD, then the application number shall default to that of the calling process if the namespace is its own job, or a value of zero if the namespace is that of a different job.

Application-level information includes the following attributes:

```
PMIX_APPNUM "pmix.appnum" (uint32_t)
```

The application number within the job in which the specified process is a member.

```
PMIX_NUM_NODES "pmix.num.nodes" (uint32_t)
```

Number of nodes currently hosting processes in the specified realm. Defaults to the *job* realm. In this context, this is the number of nodes currently hosting processes in the specified application, which may be a subset of the nodes allocated to the overall session.

```
PMIX_APPLDR "pmix.aldr" (pmix_rank_t)
```

Lowest rank in the specified application.

```
PMIX_APP_SIZE "pmix.app.size" (uint32_t)
```

Number of processes in the specified application, regardless of their execution state - i.e., this number may include processes that either failed to start or have already terminated.

```
PMIX_APP_ARGV "pmix.app.argv" (char*)
```

Consolidated argy passed to the spawn command for the given application (e.g., "./myapp arg1 arg2 arg3").

```
PMIX_MAX_PROCS "pmix.max.size" (uint32_t)
```

Maximum number of processes that can be executed in the specified realm. Typically, this is a constraint imposed by a scheduler or by user settings in a hostfile or other resource description. Defaults to the *job* realm. In this context, this is the maximum number of processes that can be executed in the specified application, which may be a subset of the number allocated to the overall session and job.

PMIX_NUM_SLOTS "pmix.num.slots" (uint32_t)

 Maximum number of processes that can simultaneously be executing in the specified realm. Note that this attribute is the equivalent to <code>PMIX_MAX_PROCS</code> - it is included in the PMIx Standard for historical reasons. Defaults to the *job* realm. In this context, this is the number of slots assigned to the specified application, which may be a subset of the slots allocated to the overall session and job.

```
PMIX_NODE_MAP "pmix.nmap" (char*)
```

Regular expression of nodes currently hosting processes in the specified realm - see 16.2.3.2 for an explanation of its generation. Defaults to the *job* realm. In this context, this is the regular expression of nodes currently hosting processes in the specified application.

```
PMIX_NODE_LIST "pmix.nlist" (char*)
```

 Comma-delimited list of nodes currently hosting processes in the specified realm. Defaults to the *job* realm. In this context, this is the comma-delimited list of nodes currently hosting processes in the specified application.

```
PMIX_PROC_MAP "pmix.pmap" (char*)
```

 Regular expression describing processes on each node in the specified realm - see 16.2.3.2 for an explanation of its generation. Defaults to the *job* realm. In this context, this is the regular expression describing processes on each node in the specified application.

```
PMIX_APP_MAP_TYPE "pmix.apmap.type" (char*)
```

Type of mapping used to layout the application (e.g., cyclic).

PMIX_APP_MAP_REGEX "pmix.apmap.regex" (char*)

Regular expression describing the result of the process mapping.

6.1.4 Process realm attributes

Process-related information is retrieved by referencing the namespace and rank of the target process in the call to **PMIx_Get**. If information is requested about a process in a session other than the one containing the requesting process, then an attribute identifying the target session must be provided. This is required as many environments only guarantee unique namespaces within a session, and not across sessions.

Process-level information includes the following attributes:

PMIX_APPNUM "pmix.appnum" (uint32_t)

The application number within the job in which the specified process is a member.

```
PMIX_RANK "pmix.rank" (pmix_rank_t)
Process rank within the job, starting from zero.
```

PMIX GLOBAL RANK "pmix.grank" (pmix rank t)

 Rank of the specified process spanning across all jobs in this session, starting with zero. Note that no ordering of the jobs is implied when computing this value. As jobs can start and end at random times, this is defined as a continually growing number - i.e., it is not dynamically adjusted as individual jobs and processes are started or terminated.

PMIX_APP_RANK "pmix.apprank" (pmix_rank_t)

Rank of the specified process within its application.

PMIX_PARENT_ID "pmix.parent" (pmix_proc_t)

Process identifier of the parent process of the specified process - typically used to identify the application process that caused the job containing the specified process to be spawned (e.g., the process that called PMIx_Spawn). This attribute is only provided for a process if it was created by a call to PMIx_Spawn or PMIx_Spawn_nb.

PMIX_EXIT_CODE "pmix.exit.code" (int)

Exit code returned when the specified process terminated.

PMIX_PROCID "pmix.procid" (pmix_proc_t)

Process identifier. Used as a key in **PMIx_Get** to retrieve the caller's own process identifier in a portion of the program that doesn't have access to the memory location in which it was originally stored (e.g., due to a call to **PMIx_Init**). The process identifier in the **PMIx_Get** call is ignored in this instance.

PMIX_LOCAL_RANK "pmix.lrank" (uint16_t)

Rank of the specified process on its node - refers to the numerical location (starting from zero) of the process on its node when counting only those processes from the same job that share the node, ordered by their overall rank within that job.

PMIX_NODE_RANK "pmix.nrank" (uint16_t)

Rank of the specified process on its node spanning all jobs- refers to the numerical location (starting from zero) of the process on its node when counting all processes (regardless of job) that share the node, ordered by their overall rank within the job. The value represents a snapshot in time when the specified process was started on its node and is not dynamically adjusted as processes from other jobs are started or terminated on the node.

PMIX_PACKAGE_RANK "pmix.pkgrank" (uint16_t)

Rank of the specified process on the *package* where this process resides - refers to the numerical location (starting from zero) of the process on its package when counting only those processes from the same job that share the package, ordered by their overall rank within that job. Note that processes that are not bound to Processing Units (PUs) within a single specific package cannot have a package rank.

PMIX_PROC_PID "pmix.ppid" (pid_t)

Operating system PID of specified process.

PMIX_PROCDIR "pmix.pdir" (char*)

Full path to the subdirectory under **PMIX_NSDIR** assigned to the specified process.

PMIX_CPUSET "pmix.cpuset" (char*)

A string representation of the PU binding bitmap applied to the process upon launch. The string shall begin with the name of the library that generated it (e.g., "hwloc") followed by a colon and the bitmap string itself.

PMIX_CPUSET_BITMAP "pmix.bitmap" (pmix_cpuset_t*)

Bitmap applied to the process upon launch.

PMIX_CREDENTIAL "pmix.cred" (char*)

Security credential assigned to the process.

PMIX_SPAWNED "pmix.spawned" (bool)

true if this process resulted from a call to **PMIx_Spawn**. Lack of inclusion (i.e., a return status of **PMIX_ERR_NOT_FOUND**) corresponds to a value of **false** for this attribute.

```
PMIX_REINCARNATION "pmix.reinc" (uint32_t)
```

Number of times this process has been re-instantiated - i.e, a value of zero indicates that the process has never been restarted. 5

In addition, process-level information includes functional attributes directly associated with a process - for example, the process-related fabric attributes included in Section 14.3 or the distance attributes of Section 11.4.11.

6.1.5 Node realm keys

Information regarding the local node can be retrieved by directly requesting the node realm key in the call to <code>PMIx_Get</code> - the keys for node-related information are not shared across other realms. The target process identifier will be ignored for keys that are not dependent upon it. Information about a node other than the local node can be retrieved by specifying the <code>PMIX_NODE_INFO</code> attribute in the <code>info</code> array along with either the <code>PMIX_HOSTNAME</code> or <code>PMIX_NODEID</code> qualifiers for the node of interest.

Node-level information includes the following keys:

```
PMIX_HOSTNAME "pmix.hname" (char*)
```

Name of the host, as returned by the **gethostname** utility or its equivalent.

```
PMIX HOSTNAME ALIASES "pmix.alias" (char*)
```

Comma-delimited list of names by which the target node is known.

```
PMIX_NODEID "pmix.nodeid" (uint32_t)
```

Node identifier expressed as the node's index (beginning at zero) in an array of nodes within the active session. The value must be unique and directly correlate to the **PMIX_HOSTNAME** of the node - i.e., users can interchangeably reference the same location using either the **PMIX_HOSTNAME** or corresponding **PMIX_NODEID**.

```
PMIX_NODE_SIZE "pmix.node.size" (uint32_t)
```

Number of processes across all jobs executing upon the node, independent of whether the process has or will use PMIx.

```
PMIX_AVAIL_PHYS_MEMORY "pmix.pmem" (uint64_t)
```

Total available physical memory on a node.

The following attributes only return information regarding the *caller's* node - any node-related qualifiers shall be ignored. In addition, these attributes require specification of the namespace in the target process identifier except where noted - the value of the rank is ignored in all cases.

```
PMIX_LOCAL_PEERS "pmix.lpeers" (char*)
```

Comma-delimited list of ranks that are executing on the local node within the specified namespace – shortcut for **PMIx** Resolve peers for the local node.

```
PMIX_LOCAL_PROCS "pmix.lprocs" (pmix_proc_t array)
```

Array of pmix_proc_t of all processes executing on the local node – shortcut for
PMIx_Resolve_peers for the local node and a NULL namespace argument. The process identifier
is ignored for this attribute.

```
PMIX_LOCALLDR "pmix.lldr" (pmix_rank_t)
```

Lowest rank within the specified job on the node (defaults to current node in absence of **PMIX_HOSTNAME** or **PMIX_NODEID** qualifier).

```
PMIX_LOCAL_CPUSETS "pmix.lcpus" (pmix_data_array_t)
```

 A pmix_data_array_t array of string representations of the PU binding bitmaps applied to each local *peer* on the caller's node upon launch. Each string shall begin with the name of the library that generated it (e.g., "hwloc") followed by a colon and the bitmap string itself. The array shall be in the same order as the processes returned by PMIX_LOCAL_PEERS for that namespace.

PMIX_LOCAL_SIZE "pmix.local.size" (uint32_t)

Number of processes in the specified job or application realm on the caller's node. Defaults to job realm unless the **PMIX APP INFO** and the **PMIX APPNUM** qualifiers are given.

PMIX NODE OVERSUBSCRIBED "pmix.ndosub" (bool) (Provisional)

True if the number of processes from this job on this node exceeds the number of slots allocated to it

In addition, node-level information includes functional attributes directly associated with a node - for example, the node-related fabric attributes included in Section 14.3.

6.2 Retrieval rules for reserved keys

The retrieval rules for reserved keys are relatively simple as the keys are required, by definition, to be available when the client begins execution. Accordingly, <code>PMIx_Get</code> for a reserved key first checks the local PMIx Client cache (per the data realm rules of the prior section) for the target key. If the information is not found, then the <code>PMIX_ERR_NOT_FOUND</code> error constant is returned unless the target process belongs to a different namespace from that of the requester.

In the case where the target and requester's namespaces differ, then the request is forwarded to the local PMIx server. Upon receiving the request, the server shall check its data storage for the specified namespace. If it already knows about this namespace, then it shall attempt to lookup the specified key, returning the value if it is found or the PMIX_ERR_NOT_FOUND error constant.

If the server does not have a copy of the information for the specified namespace, then the server shall take one of the following actions:

- If the request included the PMIX_IMMEDIATE attribute, then the server will respond to the client with the PMIX_ERR_NOT_FOUND status.
- 2. If the host has provided the Direct Business Card Exchange (DBCX) module function interface (pmix_server_dmodex_req_fn_t), then the server shall pass the request to its host for servicing. The host is responsible for identifying a source of information on the specified namespace and retrieving it. The host is required to retrieve all of the information regarding the target namespace and return it to the requesting server in anticipation of follow-on requests. If the host cannot retrieve the namespace information, then it must respond with the PMIX_ERR_NOT_FOUND error constant unless the PMIX_TIMEOUT is given and reached (in which case, the host must respond with the PMIX_ERR_TIMEOUT constant).

Once the PMIx server receives the namespace information, the server shall search it (again adhering to the prior data realm rules) for the requested key, returning the value if it is found or the PMIX ERR NOT FOUND error constant.

3. If the host does not support the DBCX interface, then the server will respond to the client with the PMIX ERR NOT FOUND status

6.2.1 Accessing information: examples

This section provides examples illustrating methods for accessing information from the various realms. The intent of the examples is not to provide comprehensive coding guidance, but rather to further illustrate the use of **PMI**×_**Get** for obtaining information on a *session*, *job*, *application*, *process*, and *node*.

6.2.1.1 Session-level information

The **PMIx_Get** API does not include an argument for specifying the *session* associated with the information being requested. Thus, requests for keys that are not specifically for session-level information must be accompanied by the **PMIX_SESSION_INFO** qualifier.

Example requests are shown below:

```
pmix_info_t info;
pmix_value_t *value;
pmix_status_t rc;
pmix_proc_t myproc, wildcard;

/* initialize the client library */
PMIx_Init(&myproc, NULL, 0);

/* get the #slots in our session */
PMIX_PROC_LOAD(&wildcard, myproc.nspace, PMIX_RANK_WILDCARD);
rc = PMIx_Get(&wildcard, PMIX_UNIV_SIZE, NULL, 0, &value);

/* get the #nodes in our session */
PMIx_Info_load(&info, PMIX_SESSION_INFO, NULL, PMIX_BOOL);
rc = PMIx_Get(&wildcard, PMIX_NUM_NODES, &info, 1, &value);
```

Information regarding a different session can be requested by adding the **PMIX_SESSION_ID** attribute identifying the target session. In this case, the *proc* argument to **PMIX_Get** will be ignored:

```
pmix_info_t info[2];
pmix_value_t *value;
pmix_status_t rc;
pmix_proc_t myproc;
uint32_t sid;

/* initialize the client library */
PMIx_Init(&myproc, NULL, 0);

/* get the #nodes in a different session */
sid = 12345;
PMIx_Info_load(&info[0], PMIX_SESSION_INFO, NULL, PMIX_BOOL);
PMIx_Info_load(&info[1], PMIX_SESSION_ID, &sid, PMIX_UINT32);
rc = PMIx_Get(NULL, PMIX_NUM_NODES, info, 2, &value);
```

6.2.1.2 Job-level information

 Information regarding a job can be obtained by the methods detailed in Section 6.1.2. Example requests are shown below:

```
pmix_info_t info;
pmix_value_t *value;
pmix_status_t rc;
pmix_proc_t myproc, wildcard;

/* initialize the client library */
PMIx_Init(&myproc, NULL, 0);

/* get the #apps in our job */
PMIX_PROC_LOAD(&wildcard, myproc.nspace, PMIX_RANK_WILDCARD);
rc = PMIx_Get(&wildcard, PMIX_JOB_NUM_APPS, NULL, 0, &value);

/* get the #nodes in our job */
PMIx_Info_load(&info, PMIX_JOB_INFO, NULL, PMIX_BOOL);
rc = PMIx_Get(&wildcard, PMIX_NUM_NODES, &info, 1, &value);
```

6.2.1.3 Application-level information

Information regarding an application can be obtained by the methods described in Section 6.1.3. Example requests are shown below:

```
pmix_info_t info;
pmix_value_t *value;
pmix_status_t rc;
pmix_proc_t myproc, otherproc;
uint32_t appsize, appnum;

/* initialize the client library */
PMIx_Init(&myproc, NULL, 0);

/* get the #processes in our application */
rc = PMIx_Get(&myproc, PMIX_APP_SIZE, NULL, 0, &value);
appsize = value->data.uint32;

/* get the #nodes in an application containing "otherproc".
   * For this use-case, assume that we are in the first application
   * and we want the #nodes in the second application - use the
   * rank of the first process in that application, remembering
   * that ranks start at zero */
```

```
1
             PMIX_PROC_LOAD(&otherproc, myproc.nspace, appsize);
2
3
             /* Since "otherproc" refers to a process in the second application,
4
              * we can simply mark that we want the info for this key from the
5
              * application realm */
6
             PMIx Info load(&info, PMIX APP INFO, NULL, PMIX BOOL);
7
             rc = PMIx_Get(&otherproc, PMIX_NUM_NODES, &info, 1, &value);
8
9
             /* alternatively, we can directly ask for the #nodes in
10
              * the second application in our job, again remembering that
11
              * application numbers start with zero. Since we are asking
12
              * for application realm information about a specific appnum
              * within our own namespace, the process identifier can be NULL */
13
14
             appnum = 1;
15
             PMIx_Info_load(&appinfo[0], PMIX_APP_INFO, NULL, PMIX_BOOL);
16
             PMIx_Info_load(&appinfo[1], PMIX_APPNUM, &appnum, PMIX_UINT32);
17
             rc = PMIx_Get(NULL, PMIX_NUM_NODES, appinfo, 2, &value);
```

6.2.1.4 Process-level information

18 19

20

21

22 23

24

Process-level information is accessed by providing the namespace and rank of the target process. In the absence of any directive as to the level of information being requested, the PMIx library will always return the process-level value. See Section 6.1.4 for details.

6.2.1.5 Node-level information

Information regarding a node within the system can be obtained by the methods described in Section 6.1.5. Example requests are shown below:

```
25
             pmix_info_t info[2];
26
             pmix_value_t *value;
27
             pmix status t rc;
28
             pmix_proc_t myproc, otherproc;
29
             uint32_t nodeid;
30
31
             /* initialize the client library */
32
             PMIx_Init(&myproc, NULL, 0);
33
34
             /* get the #procs on our node */
35
             rc = PMIx_Get(&myproc, PMIX_NODE_SIZE, NULL, 0, &value);
36
37
             /* get the #slots on another node */
38
             PMIx_Info_load(&info[0], PMIX_NODE_INFO, NULL, PMIX_BOOL);
39
             PMIx_Info_load(&info[1], PMIX_HOSTNAME, "remotehost", PMIX_STRING);
40
             rc = PMIx_Get(NULL, PMIX_MAX_PROCS, info, 2, &value);
41
42
             /* get the total #procs on the remote node - note that we don't
```

```
* actually need to include the "PMIX_NODE_INFO" attribute here,

but (a) it does no harm and (b) it allowed us to simply reuse

the prior info array

rc = PMIx_Get(NULL, PMIX_NODE_SIZE, info, 2, &value);
```

CHAPTER 7

Process-Related Non-Reserved Keys

Non-reserved keys are keys whose string representation begin with a prefix other than "pmix". Such keys are typically defined by an application when information needs to be exchanged between processes (e.g., where connection information is required and the host environment does not support the *instant on* option) or where the host environment does not provide a required piece of data. Beyond the restriction on name prefix, non-reserved keys are required to be unique across conflicting *scopes* as defined in Section 7.1.1.1 - e,g., a non-reserved key cannot be posted by the same process in both the PMIX_LOCAL and PMIX_REMOTE scopes (note that posting the key in the PMIX_GLOBAL scope would have met the desired objective).

PMIx provides support for two methods of exchanging non-reserved keys:

- Global, collective exchange of the information prior to retrieval. This is accomplished by executing a
 barrier operation that includes collection and exchange of the data provided by each process such that each
 process has access to the full set of data from all participants once the operation has completed. PMIx
 provides the PMIx_Fence function (or its non-blocking equivalent) for this purpose, accompanied by the
 PMIX_COLLECT_DATA qualifier.
- Direct, on-demand retrieval of the information. No barrier or global exchange is conducted in this case.
 Instead, information is retrieved from the host where that process is executing upon request i.e., a call to PMIx_Get results in a data exchange with the PMIx server on the remote host. Various caching strategies may be employed by the host environment and/or PMIx implementation to reduce the number of retrievals. Note that this method requires that the host environment both know the location of the posting process and support direct information retrieval.

Both of the above methods are based on retrieval from a specific process - i.e., the *proc* argument to **PMIx_Get** must include both the namespace and the rank of the process that posted the information. However, in some cases, non-reserved keys are provided on a globally unique basis and the retrieving process has no knowledge of the identity of the process posting the key. This is typically found in legacy applications (where the originating process identifier is often embedded in the key itself) and in unstructured applications that lack rank-related behavior. In these cases, the key remains associated with the namespace of the process that posted it, but is retrieved by use of the **PMIX_RANK_UNDEF** rank. In addition, the keys must be globally exchanged prior to retrieval as there is no way for the host to otherwise locate the source for the information.

Note that the retrieval rules for non-reserved keys (detailed in Section 7.2) differ significantly from those used for reserved keys.

7.1 Posting Key/Value Pairs

PMIx clients can post non-reserved key-value pairs associated with themselves by using PMIx_Put. Alternatively, PMIx clients can cache arbitrary key-value pairs accessible only by the caller via the PMIx_Store_internal API.

7.1.1 PMIx_Put

2	Summary Post a key/value pair for distribution.
4 _{PMIx v1.0}	Format C
5	pmix_status_t
6	PMIx_Put(pmix_scope_t scope,
7	const pmix_key_t key,
8	<pre>pmix_value_t *val);</pre>
	C
9	IN scope
10	Distribution scope of the provided value (handle)
11	IN key
12	key(pmix_key_t)
13	IN value
14	Reference to a pmix_value_t structure (handle)
15	Returns PMIX SUCCESS or a negative value corresponding to a PMIx error constant. If a reserved key is
16	provided in the key argument then PMIx_Put will return PMIX_ERR_BAD_PARAM.
17	Description
18	Post a key-value pair for distribution. Depending upon the PMIx implementation, the posted value may be
19	locally cached in the client's PMIx library until PMIx_Commit is called.
20	The provided <i>scope</i> determines the ability of other processes to access the posted data, as defined in
21	Section 7.1.1.1 on page 107. Specific implementations may support different scope values, but all
22	implementations must support at least PMIX_GLOBAL.
23	The pmix value t structure supports both string and binary values. PMIx implementations are required to
24	support heterogeneous environments by properly converting binary values between host architectures, and will
25	copy the provided <i>value</i> into internal memory prior to returning from PMIx_Put .
	Advice to users
26	Note that keys starting with a string of "pmix" must not be used in calls to PMIx_Put. Thus, applications
27	should never use a defined "PMIX" attribute as the key in a call to PMIX_Put.

7.1.1.1 Scope of Put Data 1 2 The pmix_scope_t structure is a uint8_t type that defines the availability of data passed to PMIx_Put. 3 The following constants can be used to set a variable of the type pmix scope t. All definitions were 4 introduced in version 1 of the standard unless otherwise marked. 5 Specific implementations may support different scope values, but all implementations must support at least 6 PMIX_GLOBAL. If a specified scope value is not supported, then the PMIx_Put call must return 7 PMIX_ERR_NOT_SUPPORTED. 8 PMIX SCOPE UNDEF Undefined scope. 9 PMIX LOCAL The data is intended only for other application processes on the same node. Data marked in 10 this way will not be included in data packages sent to remote requesters - i.e., it is only available to 11 processes on the local node. 12 PMIX REMOTE The data is intended solely for applications processes on remote nodes. Data marked in 13 this way will not be shared with other processes on the same node - i.e., it is only available to processes 14 on remote nodes. 15 *PMIx v2.0* PMIX GLOBAL The data is to be shared with all other requesting processes, regardless of location. 16 PMIX_INTERNAL The data is intended solely for this process and is not shared with other processes. 7.1.2 PMIx Store internal 17 Summary 18 19 Store some data locally for retrieval by other areas of the process. **Format** 20 PMIx v1.0 21 pmix_status_t PMIx_Store_internal(const pmix_proc_t *proc, 22 23 const pmix_key_t key, 24 pmix value t *val); 25 IN proc 26 process reference (handle) 27 IN 28 key to retrieve (string) 29 IN 30 Value to store (handle) 31 Returns **PMIX** SUCCESS or a negative value corresponding to a PMIx error constant. If a reserved key is 32 provided in the key argument then PMIx_Store_internal will return PMIX_ERR_BAD_PARAM. 33 Description 34 Store some data locally for retrieval by other areas of the process. This is data that has only internal scope - it 35 will never be posted externally. Typically used to cache data obtained by means outside of PMIx so that it can 36 be accessed by various areas of the process.

7.1.3 PMIx_Commit

Summary

Post all previously **PMIx_Put** values for distribution.

$4_{PMIx v1.0}$

2

3

5

6 7

8

9

10

11

12

13

14

15 16

17

18

19

20

21

22

23

24

25 26

27

28

29

30

31

32

33

34

pmix status t PMIx Commit(void);

Returns PMIX_SUCCESS or a negative value corresponding to a PMIx error constant.

Description

PMIx implementations may choose to locally cache non-reserved keys prior to submitting them for distribution. Accordingly, PMIx provides a second API specifically to stage all previously posted data for distribution - e.g., by transmitting the entire collection of data posted by the process to a server in one operation. This is an asynchronous operation that will immediately return to the caller while the data is staged in the background.

Advice to users ————

Users are advised to always include the call to PMIx Commit in case the local implementation requires it. Note that posted data will not be circulated during PMIx Commit. Availability of the data by other processes upon completion of PMIx Commit therefore still relies upon the exchange mechanisms described at the beginning of this chapter.

7.2 Retrieval rules for non-reserved keys

Since non-reserved keys cannot, by definition, have been provided by the host environment, their retrieval follows significantly different rules than those defined for reserved keys (as detailed in Section 6.2). **PMIx_Get** for a non-reserved key will obey the following precedence search:

- 1. If the PMIX GET REFRESH CACHE attribute is given, then the request is first forwarded to the local PMIx server which will then update the client's cache. Note that this may not, depending upon implementation details, result in any action.
- 2. Check the local PMIx client cache for the requested key if not found and either the PMIX_OPTIONAL or PMIX_GET_REFRESH_CACHE attribute was given, the search will stop at this point and return the PMIX ERR NOT FOUND status.
- 3. Request the information from the local PMIx server. The server will check its cache for the specified key within the appropriate scope as defined by the process that originally posted the key. If the value exists in a scope that contains the requesting process, then the value shall be returned. If the value exists, but in a scope that excludes the requesting process, then the server shall immediately return the PMIX ERR EXISTS OUTSIDE SCOPE.

If the value still isn't found and the PMIX IMMEDIATE attribute was given, then the library shall return the PMIX_ERR_NOT_FOUND error constant to the requester. Otherwise, the PMIx server library will take one of the following actions:

- If the target process has a rank of PMIX_RANK_UNDEF, then this indicates that the key being requested is globally unique and *not* associated with a specific process. In this case, the server shall hold the request until either the data appears at the server or, if given, the PMIX_TIMEOUT is reached. In the latter case, the server will return the PMIX_ERR_TIMEOUT status. Note that the server may, depending on PMIx implementation, never respond if the caller failed to specify a PMIX_TIMEOUT and the requested key fails to arrive at the server.
- If the target process is *local* (i.e., attached to the same PMIx server), then the server will hold the request until either the target process provides the data or, if given, the PMIX_TIMEOUT is reached. In the latter case, the server will return the PMIX_ERR_TIMEOUT status. Note that data which is posted via PMIx_Put but not staged with PMIx_Commit may, depending upon implementation, never appear at the server.
- If the target process is *remote* (i.e., not attached to the same PMIx server), the server will either:
 - If the host has provided the pmix_server_dmodex_req_fn_t module function interface, then
 the server shall pass the request to its host for servicing. The host is responsible for determining the
 location of the target process and passing the request to the PMIx server at that location.

When the remote data request is received, the target PMIx server will check its cache for the specified key. If the key is not present, the request shall be held until either the target process provides the data or, if given, the <code>PMIX_TIMEOUT</code> is reached. In the latter case, the server will return the <code>PMIX_ERR_TIMEOUT</code> status. The host shall convey the result back to the originating PMIx server, which will reply to the requesting client with the result of the request when the host provides it.

Note that the target server may, depending on PMIx implementation, never respond if the caller failed to specify a **PMIX_TIMEOUT** and the target process fails to post the requested key.

if the host does not support the pmix_server_dmodex_req_fn_t interface, then the server will immediately respond to the client with the PMIX_ERR_NOT_FOUND status

-Advice to PMIx library implementers-

While there is no requirement that all PMIx implementations follow the client-server paradigm used in the above description, implementers are required to provide behaviors consistent with the described search pattern.

Advice to users ——

Users are advised to always specify the **PMIX_TIMEOUT** value when retrieving non-reserved keys to avoid potential deadlocks should the specified key not become available.

CHAPTER 8

Publish/Lookup Operations

Chapter 6 and Chapter 7 discussed how reserved and non-reserved keys dealt with information that either was associated with a specific process (i.e., the retrieving process knew the identifier of the process that posted it) or required a synchronization operation prior to retrieval (e.g., the case of globally unique non-reserved keys). However, another requirement exists for an asynchronous exchange of data where neither the posting nor the retrieving process is known in advance. For example, two separate namespaces may need to rendezvous with each other without knowing in advance the identity of the other namespace or when that namespace might become active.

The APIs defined in this section focus on resolving that specific situation by allowing processes to publish data that can subsequently be retrieved solely by referral to its key. Mechanisms for constraining availability of the information are also provided as a means for better targeting of the eventual recipient(s).

Note that no presumption is made regarding how the published information is to be stored, nor as to the entity (host environment or PMIx implementation) that shall act as the datastore. The descriptions in the remainder of this chapter shall simply refer to that entity as the *datastore*.

8.1 PMIx Publish

Summary

Format

Publish data for later access via PMIx_Lookup.

PMIx v1.0

pmix_status_t

PMIx_Publish(const pmix_info_t info[], size_t ninfo);

IN 21

Array of info structures containing both data to be published and directives (array of handles)

IN ninfo

Number of elements in the *info* array (integer)

Returns **PMIX_SUCCESS** or a negative value corresponding to a PMIx error constant.

----- Required Attributes

There are no required attributes for this API. PMIx implementations that do not directly support the operation but are hosted by environments that do support it must pass any attributes that are provided by the client to the host environment for processing. In addition, the PMIx library is required to add the PMIX_USERID and the PMIX_GRPID attributes of the client process that published the information to the *info* array passed to the host environment.

Optional Attributes -----

The following attributes are optional for host environments that support this operation:

PMIX_TIMEOUT "pmix.timeout" (int)

Time in seconds before the specified operation should time out (zero indicating infinite) and return the **PMIX_ERR_TIMEOUT** error. Care should be taken to avoid race conditions caused by multiple layers (client, server, and host) simultaneously timing the operation.

PMIX RANGE "pmix.range" (pmix data_range_t)

Define constraints on the processes that can access the provided data. Only processes that meet the constraints are allowed to access it.

PMIX_PERSISTENCE "pmix.persist" (pmix_persistence_t)

Declare how long the datastore shall retain the provided data. The datastore is to delete the data upon reaching the persistence criterion.

PMIX_ACCESS_PERMISSIONS "pmix.aperms" (pmix_data_array_t)

Define access permissions for the published data. The value shall contain an array of **pmix_info_t** structs containing the specified permissions.

Description

1

2

3

4 5

6

7

8

9

10

11

12

13

14

15 16

17

18

19

20

21

22

23

24

25

26 27 Publish the data in the *info* array for subsequent lookup. By default, the data will be published into the PMIX_RANGE_SESSION range and with PMIX_PERSIST_APP persistence. Changes to those values, and any additional directives, can be included in the pmix_info_t array. Attempts to access the data by processes outside of the provided data range shall be rejected. The PMIX_PERSISTENCE attribute instructs the datastore holding the published information as to how long that information is to be retained.

The blocking form of this call will block until it has obtained confirmation from the datastore that the data is available for lookup. The *info* array can be released upon return from the blocking function call.

Publishing duplicate keys is permitted provided they are published to different ranges. Duplicate keys being published on the same data range shall return the **PMIX_ERR_DUPLICATE_KEY** error.

8.2 PMIx Publish nb

Summary

Nonblocking **PMIx Publish** routine.

1	Format C
2	pmix_status_t
3	<pre>PMIx_Publish_nb(const pmix_info_t info[], size_t ninfo,</pre>
4	<pre>pmix_op_cbfunc_t cbfunc, void *cbdata);</pre>
	C -
5	IN info
6	Array of info structures containing both data to be published and directives (array of handles)
7	IN ninfo
8	Number of elements in the <i>info</i> array (integer)
9	IN cbfunc
10	Callback function pmix_op_cbfunc_t (function reference)
11	IN cbdata
12	Data to be passed to the callback function (memory reference)
13	Returns one of the following:
14	• PMIX SUCCESS, indicating that the request is being processed by the host environment - result will be
15	returned in the provided <i>cbfunc</i> . Note that the library must not invoke the callback function prior to
16	returning from the API.
17	PMIX_OPERATION_SUCCEEDED, indicating that the request was immediately processed and returned
18	success - the cbfunc will not be called.
19	• a DMIV array constant indicating aither an array in the input or that the request was immediately processed
20	• a PMIx error constant indicating either an error in the input or that the request was immediately processed and failed - the <i>cbfunc</i> will <i>not</i> be called.
	→ Required Attributes
21	There are no required attributes for this API. PMIx implementations that do not directly support the operation
22	but are hosted by environments that do support it must pass any attributes that are provided by the client to the
23	host environment for processing. In addition, the PMIx library is required to add the PMIX_USERID and the
24	PMIX_GRPID attributes of the client process that published the information to the <i>info</i> array passed to the
25	host environment.
	▼ Optional Attributes
ne.	·
26	The following attributes are optional for host environments that support this operation:
27	PMIX_TIMEOUT "pmix.timeout" (int)
28	Time in seconds before the specified operation should time out (zero indicating infinite) and return the
29	PMIX_ERR_TIMEOUT error. Care should be taken to avoid race conditions caused by multiple layers
30	(client, server, and host) simultaneously timing the operation.
31	<pre>PMIX_RANGE "pmix.range" (pmix_data_range_t)</pre>
32	Define constraints on the processes that can access the provided data. Only processes that meet the
33	constraints are allowed to access it.
24	DMIV DEDCISIENCE "priv porgist" (priv porgistore t)

1 Declare how long the datastore shall retain the provided data. The datastore is to delete the data upon 2 reaching the persistence criterion. 3 PMIX_ACCESS_PERMISSIONS "pmix.aperms" (pmix_data_array_t) 4 Define access permissions for the published data. The value shall contain an array of pmix info t 5 structs containing the specified permissions. **Description** 6 7 Nonblocking **PMIx_Publish** routine. 8.3 **Publish-specific constants** 9 The following constants are defined for use with the **PMIx Publish** APIs: 10 PMIX ERR DUPLICATE KEY The provided key has already been published on the same data range. 8.4 Publish-specific attributes 12 The following attributes are defined for use with the PMIx_Publish APIs: 13 PMIX_RANGE "pmix.range" (pmix_data_range_t) 14 Define constraints on the processes that can access the provided data. Only processes that meet the 15 constraints are allowed to access it. 16 PMIX_PERSISTENCE "pmix.persist" (pmix_persistence_t) Declare how long the datastore shall retain the provided data. The datastore is to delete the data upon 17 18 reaching the persistence criterion. 19 PMIX_ACCESS_PERMISSIONS "pmix.aperms" (pmix_data_array_t) 20 Define access permissions for the published data. The value shall contain an array of pmix_info_t 21 structs containing the specified permissions. PMIX_ACCESS_USERIDS "pmix.auids" (pmix_data_array_t) 22 23 Array of effective User IDs (UIDs) that are allowed to access the published data. 24 PMIX_ACCESS_GRPIDS "pmix.agids" (pmix_data_array_t) 25 Array of effective Group IDs (GIDs) that are allowed to access the published data.

8.5 Publish-Lookup Datatypes

26 27

The following data types are defined for use with the **PMIx_Publish** APIs.

8.5.1 Range of Published Data

1

3

4

5

6

7

8

9

10

11

12

13

14

15

16

17

18

19

20

24

25

26

27

28

29

30

31

33

The pmix_data_range_t structure is a uint8_t type that defines a range for both data published via the PMIx_Publish API and generated events. The following constants can be used to set a variable of the type pmix_data_range_t.

PMIX_RANGE_UNDEF Undefined range.

PMIX_RANGE_RM Data is intended for the host environment, or lookup is restricted to data published by the host environment.

PMIX_RANGE_LOCAL Data is only available to processes on the local node, or lookup is restricted to data published by processes on the local node of the requester.

PMIX_RANGE_NAMESPACE Data is only available to processes in the same namespace, or lookup is restricted to data published by processes in the same namespace as the requester.

PMIX_RANGE_SESSION Data is only available to all processes in the session, or lookup is restricted to data published by other processes in the same session as the requester.

PMIX_RANGE_GLOBAL Data is available to all processes, or lookup is open to data published by anyone.

PMIX_RANGE_CUSTOM Data is available only to processes as specified in the **pmix_info_t** associated with this call, or lookup is restricted to data published by processes as specified in the **pmix_info_t**.

PMIX_RANGE_PROC_LOCAL Data is only available to this process, or lookup is restricted to data published by this process.

PMIX_RANGE_INVALID Invalid value - typically used to indicate that a range has not yet been set.

8.5.2 Data Persistence Structure

21 PMIx v1.0

The pmix_persistence_t structure is a uint8_t type that defines the policy for data published by clients via the PMIx_Publish API. The following constants can be used to set a variable of the type pmix_persistence_t.

PMIX_PERSIST_INDEF Retain data until specifically deleted.

PMIX_PERSIST_FIRST_READ Retain data until the first access, then the data is deleted.

PMIX_PERSIST_PROC Retain data until the publishing process terminates.

PMIX_PERSIST_APP Retain data until the application terminates.

PMIX_PERSIST_SESSION Retain data until the session/allocation terminates.

PMIX_PERSIST_INVALID Invalid value - typically used to indicate that a persistence has not yet been set.

8.6 PMIx_Lookup

32 Summary

Lookup information published by this or another process with PMIx_Publish or PMIx_Publish_nb.

1	Format C
2 3 4	<pre>pmix_status_t PMIx_Lookup(pmix_pdata_t data[], size_t ndata,</pre>
5 6 7 8 9 0 1 2	INOUT data Array of publishable data structures (array of pmix_pdata_t) IN ndata Number of elements in the data array (integer) IN info Array of info structures (array of pmix_info_t) IN ninfo Number of elements in the info array (integer)
3	Number of elements in the <i>info</i> array (integer) Returns one of the following: • PMIX SUCCESS All data was found and has been returned.
5 6 7 8 9	 PMIX_ERR_NOT_FOUND None of the requested data could be found within the requester's range. PMIX_ERR_PARTIAL_SUCCESS Some of the requested data was found. Any key that cannot be found will return with a data type of PMIX_UNDEF in the associated <i>value</i> struct. Note that the specific reason for a particular piece of missing information (e.g., lack of permissions) cannot be communicated back to the requester in this situation.
20 21 22 23	 PMIX_ERR_NOT_SUPPORTED There is no available datastore (either at the host environment or PMIx implementation level) on this system that supports this function. PMIX_ERR_NO_PERMISSIONS All of the requested data was found and range restrictions were met for each specified key, but none of the matching data could be returned due to lack of access permissions.
25 26 27	• a non-zero PMIx error constant indicating a reason for the request's failure. Required Attributes PMIx libraries are not required to directly support any attributes for this function. However, any provided attributes must be passed to the host environment for processing, and the PMIx library is required to add the PMIX_USERID and the PMIX_GRPID attributes of the client process that is requesting the info.

Optional Attributes

The following attributes are optional for host environments that support this operation:

PMIX_TIMEOUT "pmix.timeout" (int)

Time in seconds before the specified operation should time out (zero indicating infinite) and return the **PMIX_ERR_TIMEOUT** error. Care should be taken to avoid race conditions caused by multiple layers (client, server, and host) simultaneously timing the operation.

PMIX_RANGE "pmix.range" (pmix_data_range_t)

Define constraints on the processes that can access the provided data. Only processes that meet the constraints are allowed to access it.

PMIX_WAIT "pmix.wait" (int)

Caller requests that the PMIx server wait until at least the specified number of values are found (a value of zero indicates *all* and is the default).

Description

Lookup information published by this or another process. By default, the search will be constrained to publishers that fall within the PMIX_RANGE_SESSION range in case duplicate keys exist on different ranges. Changes to the range (e.g., expanding the search to all potential publishers via the PMIX_RANGE_GLOBAL constant), and any additional directives, can be provided in the pmix_info_t array. Data is returned per the retrieval rules of Section 8.8.

The *data* parameter consists of an array of <code>pmix_pdata_t</code> structures with the keys specifying the requested information. Data will be returned for each <code>key</code> field in the associated <code>value</code> field of this structure as per the above description of return values. The <code>proc</code> field in each <code>pmix_pdata_t</code> structure will contain the namespace/rank of the process that published the data.

Advice to users –

Although this is a blocking function, it will not wait by default for the requested data to be published. Instead, it will block for the time required by the datastore to lookup its current data and return any found items. Thus, the caller is responsible for either ensuring that data is published prior to executing a lookup, using <code>PMIX_WAIT</code> to instruct the datastore to wait for the data to be published, or retrying until the requested data is found.

8.7 PMIx_Lookup_nb

Summary

Nonblocking version of **PMIx** Lookup.

Optional Attributes

The following attributes are optional for host environments that support this operation:

```
PMIX_TIMEOUT "pmix.timeout" (int)
```

Time in seconds before the specified operation should time out (zero indicating infinite) and return the **PMIX_ERR_TIMEOUT** error. Care should be taken to avoid race conditions caused by multiple layers (client, server, and host) simultaneously timing the operation.

```
PMIX_RANGE "pmix.range" (pmix_data_range_t)
```

Define constraints on the processes that can access the provided data. Only processes that meet the constraints are allowed to access it.

```
PMIX WAIT "pmix.wait" (int)
```

Caller requests that the PMIx server wait until at least the specified number of values are found (a value of zero indicates *all* and is the default).

Description

Non-blocking form of the **PMIx** Lookup function.

8.7.1 Lookup Returned Data Structure

```
The pmix_pdata_t structure is used by PMIx_Lookup to describe the data being accessed.

PMIx v1.0
```

21 where:

2

3

4

5

6

7

8

9

10

11

12 13

22

23

24

25 26

- proc is the process identifier of the data publisher.
- key is the string key of the published data.
- *value* is the value associated with the *key*.

8.7.1.1 Lookup data structure support macros

The following macros are provided to support the **pmix pdata** t structure.

1 2		Static initializer for the pdata structure (Provisional)
3		Provide a static initializer for the pmix_pdata_t fields.
4		PMIX_LOOKUP_STATIC_INIT
5 6	PMIx v1.0	Initialize the pdata structure Initialize the pmix_pdata_t fields C
7		PMIX_PDATA_CONSTRUCT (m)
8 9		<pre>IN m Pointer to the structure to be initialized (pointer to pmix_pdata_t)</pre>
10 11	PMIx v1.0	Destruct the pdata structure Destruct the pmix_pdata_t fields C
12		PMIX_PDATA_DESTRUCT (m)
13 14		<pre>IN m Pointer to the structure to be destructed (pointer to pmix_pdata_t)</pre>
15 16	PMIx v1.0	Create a pdata array Allocate and initialize an array of pmix_pdata_t structures C
17		PMIX_PDATA_CREATE(m, n)
18 19 20 21		<pre>INOUT m</pre>
22 23	PMIx v4.0	Free a pdata structure Release a pmix_pdata_t structure C
24		PMIX_PDATA_RELEASE (m)
25 26		IN m Pointer to a pmix_pdata_t structure (handle)

1	Free a pdata array
2	Release an array of pmix_pdata_t structures
	C
3	PMIX_PDATA_FREE(m, n)
4	IN m
5	Pointer to the array of pmix_pdata_t structures (handle)
6	IN n
7	Number of structures in the array (size_t)
8	Load a lookup data structure
9	This macro simplifies the loading of key, process identifier, and data into a pmix_pdata_t by correctly
10	assigning values to the structure's fields.
PMIx v1.0	C
11	PMIX_PDATA_LOAD(m, p, k, d, t);
12	IN m
13	Pointer to the pmix_pdata_t structure into which the key and data are to be loaded (pointer to
14	pmix_pdata_t)
15	IN p
16	Pointer to the pmix_proc_t structure containing the identifier of the process being referenced (pointer
17	topmix_proc_t)
18	IN k
19	String key to be loaded - must be less than or equal to PMIX_MAX_KEYLEN in length (handle)
20	IN d
21	Pointer to the data value to be loaded (handle)
22	IN t
23	Type of the provided data value (pmix_data_type_t)
	▼ Advice to users
24	Key, process identifier, and data will all be copied into the pmix_pdata_t - thus, the source information can
25	be modified or free'd without affecting the copied data once the macro has completed.
	The second of th

Transfer a lookup data structure 1 2 This macro simplifies the transfer of key, process identifier, and data value between twopmix pdata t 3 structures. 4 PMIX_PDATA_XFER(d, s); 5 IN 6 Pointer to the destination pmix pdata t (pointer to pmix pdata t) 7 IN 8 Pointer to the source pmix_pdata_t (pointer to pmix_pdata_t) Advice to users —— 9 Key, process identifier, and data will all be copied into the destination pmix_pdata_t - thus, the source 10 pmix_pdata_t may free'd without affecting the copied data once the macro has completed. 8.7.2 **Lookup Callback Function** 11 12 Summary The pmix_lookup_cbfunc_t is used by PMIx_Lookup_nb to return data. 13 PMIx v1.0 typedef void (*pmix_lookup_cbfunc_t) 14 15 (pmix_status_t status, pmix_pdata_t data[], size_t ndata, 16 17 void *cbdata); 18 IN status 19 Status associated with the operation (handle) 20 IN 21 Array of data returned (pmix_pdata_t) 22 ndata Number of elements in the *data* array (size_t) 23 24 IN 25 Callback data passed to original API call (memory reference) 26 Description 27 A callback function for calls to PMIx_Lookup_nb. The function will be called upon completion of the 28 PMIx_Lookup_nb API with the status indicating the success or failure of the request. Any retrieved data will be returned in an array of pmix_pdata_t structs. The namespace and rank of the process that provided 29 30 each data element is also returned. 31 Note that the pmix pdata t structures will be released upon return from the callback function, so the

receiver must copy/protect the data prior to returning if it needs to be retained.

32

8.8 Retrieval rules for published data

The retrieval rules for published data primarily revolve around enforcing data access permissions and range constraints. The datastore shall search its stored information for each specified key according to the following precedence logic:

- 1. If the requester specified the range, then the search shall be constrained to data where the publishing process falls within the specified range.
- 2. If the key of the stored information does not match the specified key, then the search will continue.
- 3. If the requester's identifier does not fall within the range specified by the publisher, then the search will continue.
- 4. If the publisher specified access permissions, the effective UID and GID of the requester shall be checked against those permissions, with the datastore rejecting the match if the requester fails to meet the requirements.
- 5. If all of the above checks pass, then the value is added to the information that is to be returned.

The status returned by the datastore shall be set to:

- PMIX SUCCESS All data was found and is included in the returned information.
- PMIX_ERR_NOT_FOUND None of the requested data could be found within a requester's range.
- PMIX_ERR_PARTIAL_SUCCESS Some of the requested data was found. Only found data will be
 included in the returned information. Note that the specific reason for a particular piece of missing
 information (e.g., lack of permissions) cannot be communicated back to the requester in this situation.
- a non-zero PMIx error constant indicating a reason for the request's failure.

In the case where data was found and range restrictions were met for each specified key, but none of the matching data could be returned due to lack of access permissions, the datastore must return the **PMIX ERR NO PERMISSIONS** error.

Advice to users -

Note that duplicate keys are allowed to exist on different ranges, and that ranges do overlap each other. Thus, if duplicate keys are published on overlapping ranges, it is possible for the datastore to successfully find multiple responses for a given key should publisher and requester specify sufficiently broad ranges. In this situation, the choice of resolving the duplication is left to the datastore implementation - e.g., it may return the first value found in its search, or the value corresponding to the most limited range of the found values, or it may choose to simply return an error.

Users are advised to avoid this ambiguity by careful selection of key values and ranges - e.g., by creating range-specific keys where necessary.

8.9 PMIx_Unpublish

Summary

Unpublish data posted by this process using the given keys.

- 1	PMIx v1.0	Format C
2 3 4	Tinix vi.o	<pre>pmix_status_t PMIx_Unpublish(char **keys,</pre>
5 6 7 8 9 10		IN keys NULL-terminated array of keys (array of strings) IN info Array of info structures (array of handles) IN ninfo Number of elements in the <i>info</i> array (integer) Returns PMIX_SUCCESS or a negative value corresponding to a PMIx error constant. PMIx libraries are not required to directly support any attributes for this function. However, any provided attributes must be passed to the host environment for processing, and the PMIx library is required to add the
14 15		PMIX_USERID and the PMIX_GRPID attributes of the client process that is requesting the operation. Optional Attributes The following attributes are optional for host environments that support this operation:
16 17 18 19		PMIX_TIMEOUT "pmix.timeout" (int) Time in seconds before the specified operation should time out (zero indicating infinite) and return the PMIX_ERR_TIMEOUT error. Care should be taken to avoid race conditions caused by multiple layers (client, server, and host) simultaneously timing the operation.
20 21 22		PMIX_RANGE "pmix.range" (pmix_data_range_t) Define constraints on the processes that can access the provided data. Only processes that meet the constraints are allowed to access it.
23 24 25 26		Description Unpublish data posted by this process using the given <i>keys</i> . The function will block until the data has been removed by the server (i.e., it is safe to publish that key again within the specified range). A value of NULL for the <i>keys</i> parameter instructs the server to remove all data published by this process.
27 28 29	8.10	By default, the range is assumed to be PMIX_RANGE_SESSION. Changes to the range, and any additional directives, can be provided in the <i>info</i> array. PMIx_Unpublish_nb
	00	
30 31		Summary Nonblocking version of BMTs. Happyblich

1	Format C
2 3 4 5	<pre>pmix_status_t PMIx_Unpublish_nb(char **keys,</pre>
6 7 8 9 10 11 12 13 14	IN keys NULL-terminated array of keys (array of strings) IN info Array of info structures (array of handles) IN ninfo Number of elements in the info array (integer) IN cbfunc Callback function pmix_op_cbfunc_t (function reference) IN cbdata Data to be passed to the callback function (memory reference)
16	Returns one of the following:
17 18 19	• PMIX_SUCCESS , indicating that the request is being processed by the host environment - result will be returned in the provided <i>cbfunc</i> . Note that the library must not invoke the callback function prior to returning from the API.
20 21	 PMIX_OPERATION_SUCCEEDED, indicating that the request was immediately processed and returned success - the cbfunc will not be called.
22 23	• a PMIx error constant indicating either an error in the input or that the request was immediately processed and failed - the <i>cbfunc</i> will <i>not</i> be called.
	Required Attributes
24 25 26	PMIx libraries are not required to directly support any attributes for this function. However, any provided attributes must be passed to the host environment for processing, and the PMIx library is required to add the PMIX_USERID and the PMIX_GRPID attributes of the client process that is requesting the operation.
	▼ Optional Attributes
27	The following attributes are optional for host environments that support this operation:
28 29 30 31	PMIX_TIMEOUT "pmix.timeout" (int) Time in seconds before the specified operation should time out (zero indicating infinite) and return the PMIX_ERR_TIMEOUT error. Care should be taken to avoid race conditions caused by multiple layers (client, server, and host) simultaneously timing the operation.
32 33 34	<pre>PMIX_RANGE "pmix.range" (pmix_data_range_t) Define constraints on the processes that can access the provided data. Only processes that meet the constraints are allowed to access it.</pre>

1 2

Non-blocking form of the **PMIx_Unpublish** function. The callback function will be executed once the server confirms removal of the specified data. The *info* array must be maintained until the callback is provided.

CHAPTER 9

Event Notification

This chapter defines the PMIx event notification system. These interfaces are designed to support the reporting of events to/from clients and servers, and between library layers within a single process.

9.1 Notification and Management

PMIx event notification provides an asynchronous out-of-band mechanism for communicating events between application processes and/or elements of the SMS. Its uses span a wide range including fault notification, coordination between multiple programming libraries within a single process, and workflow orchestration for non-synchronous programming models. Events can be divided into two distinct classes:

- Job-specific events directly relate to a job executing within the session, such as a debugger attachment, process failure within a related job, or events generated by an application process. Events in this category are to be immediately delivered to the PMIx server library for relay to the related local processes.
- Environment events indirectly relate to a job but do not specifically target the job itself. This category includes SMS-generated events such as Error Check and Correction (ECC) errors, temperature excursions, and other non-job conditions that might directly affect a session's resources, but would never include an event generated by an application process. Note that although these do potentially impact the session's jobs, they are not directly tied to those jobs. Thus, events in this category are to be delivered to the PMIx server library only upon request.

Both SMS elements and applications can register for events of either type.

Advice to PMIx library implementers

Race conditions can cause the registration to come after events of possible interest (e.g., a memory ECC event that occurs after start of execution but prior to registration, or an application process generating an event prior to another process registering to receive it). SMS vendors are *requested* to cache environment events for some time to mitigate this situation, but are not *required* to do so. However, PMIx implementers are *required* to cache all events received by the PMIx server library and to deliver them to registering clients in the same order in which they were received

Advice to users –

Applications must be aware that they may not receive environment events that occur prior to registration, depending upon the capabilities of the host SMS.

The generator of an event can specify the *target range* for delivery of that event. Thus, the generator can choose to limit notification to processes on the local node, processes within the same job as the generator, processes within the same allocation, other threads within the same process, only the SMS (i.e., not to any application processes), all application processes, or to a custom range based on specific process identifiers. Only processes within the given range that register for the provided event code will be notified. In addition, the generator can use attributes to direct that the event not be delivered to any default event handlers, or to any multi-code handler (as defined below).

Event notifications provide the process identifier of the source of the event plus the event code and any additional information provided by the generator. When an event notification is received by a process, the registered handlers are scanned for their event code(s), with matching handlers assembled into an *event chain* for servicing. Note that users can also specify a *source range* when registering an event (using the same range designators described above) to further limit when they are to be invoked. When assembled, PMIx event chains are ordered based on both the specificity of the event handler and user directives at time of handler registration. By default, handlers are grouped into three categories based on the number of event codes that can trigger the callback:

- *single-code* handlers are serviced first as they are the most specific. These are handlers that are registered against one specific event code.
- *multi-code* handlers are serviced once all single-code handlers have completed. The handler will be included in the chain upon receipt of an event matching any of the provided codes.
- *default* handlers are serviced once all multi-code handlers have completed. These handlers are always included in the chain unless the generator specifically excludes them.

Users can specify the callback order of a handler within its category at the time of registration. Ordering can be specified by providing the relevant event handler names, if the user specified an event handler name when registering the corresponding event. Thus, users can specify that a given handler be executed before or after another handler should both handlers appear in an event chain (the ordering is ignored if the other handler isn't included). Note that ordering does not imply immediate relationships. For example, multiple handlers registered to be serviced after event handler *A* will all be executed after *A*, but are not guaranteed to be executed in any particular order amongst themselves.

In addition, one event handler can be declared as the *first* handler to be executed in the chain. This handler will *always* be called prior to any other handler, regardless of category, provided the incoming event matches both the specified range and event code. Only one handler can be so designated — attempts to designate additional handlers as *first* will return an error. Deregistration of the declared *first* handler will re-open the position for subsequent assignment.

Similarly, one event handler can be declared as the *last* handler to be executed in the chain. This handler will *always* be called after all other handlers have executed, regardless of category, provided the incoming event matches both the specified range and event code. Note that this handler will not be called if the chain is terminated by an earlier handler. Only one handler can be designated as *last* — attempts to designate additional handlers as *last* will return an error. Deregistration of the declared *last* handler will re-open the position for subsequent assignment.

Advice to users

Note that the *last* handler is called *after* all registered default handlers that match the specified range of the incoming event unless a handler prior to it terminates the chain. Thus, if the application intends to define a *last* handler, it should ensure that no default handler aborts the process before it.

Upon completing its work and prior to returning, each handler *must* call the event handler completion function provided when it was invoked (including a status code plus any information to be passed to later handlers) so that the chain can continue being progressed. PMIx automatically aggregates the status and any results of each handler (as provided in the completion callback) with status from all prior handlers so that each step in the chain has full knowledge of what preceded it. An event handler can terminate all further progress along the chain by passing the **PMIX EVENT ACTION COMPLETE** status to the completion callback function.

9.1.1 Events versus status constants

Return status constants (see Section 3.1.1) represent values that can be returned from or passed into PMIx APIs. These are distinct from PMIx *events* in that they are not values that can be registered against event handlers. In general, the two types of constants are distinguished by inclusion of an "ERR" in the name of error constants versus an "EVENT" in events, though there are exceptions (e.g, the **PMIX_SUCCESS** constant).

9.1.2 PMIx_Register_event_handler

Summary

Register an event handler.

```
18 PMIx v2.0 Format
```

pmix_hdlr_reg_cbfunc_t cbfunc,

void *cbdata);

IN codes

Array of status codes (array of pmix status t)

IN ncodes

Number of elements in the *codes* array (size_t)

IN info

Array of info structures (array of handles)

IN ninfo

Number of elements in the *info* array (size_t)

IN evhdlr

Event handler to be called **pmix notification fn t** (function reference)

IN 1 cbfunc 2 Callback function pmix hdlr reg cbfunc t (function reference) 3 IN 4 Data to be passed to the cbfunc callback function (memory reference) 5 If cbfunc is **NULL**, the function call will be treated as a blocking call. In this case, the returned status will be 6 either (a) the event handler reference identifier if the value is greater than or equal to zero, or (b) a negative 7 error code indicative of the reason for the failure. 8 If the *cbfunc* is non-**NULL**, the function call will be treated as a *non-blocking* call and will return the following: 9 • PMIX SUCCESS indicating that the request has been accepted for processing and the provided callback 10 function will be executed upon completion of the operation. Note that the library must not invoke the 11 callback function prior to returning from the API. The result of the registration operation shall be returned 12 in the provided callback function along with the assigned event handler identifier. 13 • PMIX_ERR_EVENT_REGISTRATION indicating that the registration has failed for an undetermined 14 reason. 15 • a non-zero PMIx error constant indicating a reason for the request to have been rejected. In this case, the 16 provided callback function will not be executed. 17 The callback function must not be executed prior to returning from the API, and no events corresponding to 18 this registration may be delivered prior to the completion of the registration callback function (cbfunc). Required Attributes 19 The following attributes are required to be supported by all PMIx libraries: 20 PMIX EVENT HDLR NAME "pmix.evname" (char*) 21 String name identifying this handler. 22 PMIX_EVENT_HDLR_FIRST "pmix.evfirst" (bool) 23 Invoke this event handler before any other handlers. 24 PMIX_EVENT_HDLR_LAST "pmix.evlast" (bool) 25 Invoke this event handler after all other handlers have been called. 26 PMIX EVENT HDLR FIRST IN CATEGORY "pmix.evfirstcat" (bool) 27 Invoke this event handler before any other handlers in this category. 28 PMIX EVENT HDLR LAST IN CATEGORY "pmix.evlastcat" (bool) 29 Invoke this event handler after all other handlers in this category have been called. 30 PMIX EVENT HDLR BEFORE "pmix.evbefore" (char*) Put this event handler immediately before the one specified in the (char*) value. 31 32 PMIX EVENT HDLR AFTER "pmix.evafter" (char*) 33 Put this event handler immediately after the one specified in the (char*) value. 34 PMIX_EVENT_HDLR_PREPEND "pmix.evprepend" (bool) 35 Prepend this handler to the precedence list within its category. PMIX_EVENT_HDLR_APPEND "pmix.evappend" (bool) 36

Append this handler to the precedence list within its category.

PMIX_EVENT_CUSTOM_RANGE "pmix.evrange" (pmix_data_array_t*)

Array of pmix_proc_t defining range of event notification.

```
PMIX_RANGE "pmix.range" (pmix_data_range_t)
```

Define constraints on the processes that can access the provided data. Only processes that meet the constraints are allowed to access it.

```
PMIX_EVENT_RETURN_OBJECT "pmix.evobject" (void *)
```

Object to be returned whenever the registered callback function **cbfunc** is invoked. The object will only be returned to the process that registered it.

Host environments that implement support for PMIx event notification are required to support the following attributes when registering handlers - these attributes are used to direct that the handler should be invoked only when the event affects the indicated process(es):

```
PMIX_EVENT_AFFECTED_PROC "pmix.evproc" (pmix_proc_t)
```

The single process that was affected.

```
PMIX EVENT AFFECTED PROCS "pmix.evaffected" (pmix data array t*)
```

Array of pmix_proc_t defining affected processes.

Description

Register an event handler to report events. Note that the codes being registered do *not* need to be PMIx error constants — any integer value can be registered. This allows for registration of non-PMIx events such as those defined by a particular SMS vendor or by an application itself.

——— Advice to users ———

In order to avoid potential conflicts, users are advised to only define codes that lie outside the range of the PMIx standard's error codes. Thus, SMS vendors and application developers should constrain their definitions to positive values or negative values beyond the PMIX_EXTERNAL_ERR_BASE boundary.

— Advice to users —

As previously stated, upon completing its work, and prior to returning, each handler *must* call the event handler completion function provided when it was invoked (including a status code plus any information to be passed to later handlers) so that the chain can continue being progressed. An event handler can terminate all further progress along the chain by passing the <code>PMIX_EVENT_ACTION_COMPLETE</code> status to the completion callback function. Note that the parameters passed to the event handler (e.g., the *info* and *results* arrays) will cease to be valid once the completion function has been called - thus, any information in the incoming parameters that will be referenced following the call to the completion function must be copied.

9.1.3 Event registration constants

PMIX ERR EVENT REGISTRATION Error in event registration.

9.1.4 System events

2

3

5

6

7

8

9

10

11 12

13

14

15

16

17 18

19

20

21 22

23

24

25

26

27

28

29

30

31

32

33

34

35

36

PMIx v2.2

PMIX_EVENT_SYS_BASE Mark the beginning of a dedicated range of constants for system event reporting.

PMIX_EVENT_NODE_DOWN A node has gone down - the identifier of the affected node will be included in the notification.

PMIX_EVENT_NODE_OFFLINE A node has been marked as offline - the identifier of the affected node will be included in the notification.

PMIX_EVENT_SYS_OTHER Mark the end of a dedicated range of constants for system event reporting.

Detect system event constant

Test a given event constant to see if it falls within the dedicated range of constants for system event reporting.

PMIX SYSTEM EVENT(a)

IN a

Error constant to be checked (pmix_status_t)

Returns **true** if the provided values falls within the dedicated range of events for system event reporting.

9.1.5 Event handler registration and notification attributes

Attributes to support event registration and notification.

PMIX_EVENT_HDLR_NAME "pmix.evname" (char*)

String name identifying this handler.

PMIX_EVENT_HDLR_FIRST "pmix.evfirst" (bool)

Invoke this event handler before any other handlers.

PMIX_EVENT_HDLR_LAST "pmix.evlast" (bool)

Invoke this event handler after all other handlers have been called.

PMIX_EVENT_HDLR_FIRST_IN_CATEGORY "pmix.evfirstcat" (bool)

Invoke this event handler before any other handlers in this category.

 ${\tt PMIX_EVENT_HDLR_LAST_IN_CATEGORY \ "pmix.evlastcat" \ (bool)}$

Invoke this event handler after all other handlers in this category have been called.

PMIX EVENT HDLR BEFORE "pmix.evbefore" (char*)

Put this event handler immediately before the one specified in the (char*) value.

 ${\tt PMIX_EVENT_HDLR_AFTER} \quad "{\tt pmix.evafter"} \ ({\tt char*})$

Put this event handler immediately after the one specified in the (char*) value.

PMIX_EVENT_HDLR_PREPEND "pmix.evprepend" (bool)

Prepend this handler to the precedence list within its category.

PMIX_EVENT_HDLR_APPEND "pmix.evappend" (bool)

Append this handler to the precedence list within its category.

```
PMIX_EVENT_CUSTOM_RANGE "pmix.evrange" (pmix_data_array_t*)
 1
 2
                      Array of pmix proc t defining range of event notification.
 3
                PMIX EVENT AFFECTED PROC "pmix.evproc" (pmix proc t)
 4
                      The single process that was affected.
 5
                PMIX_EVENT_AFFECTED_PROCS "pmix.evaffected" (pmix_data_array_t*)
                      Array of pmix_proc_t defining affected processes.
 6
 7
                PMIX_EVENT_NON_DEFAULT "pmix.evnondef" (bool)
 8
                      Event is not to be delivered to default event handlers.
 9
                PMIX_EVENT_RETURN_OBJECT "pmix.evobject" (void *)
10
                      Object to be returned whenever the registered callback function cbfunc is invoked. The object will
11
                      only be returned to the process that registered it.
12
                PMIX_EVENT_DO_NOT_CACHE "pmix.evnocache" (bool)
13
                      Instruct the PMIx server not to cache the event.
14
                PMIX_EVENT_PROXY "pmix.evproxy" (pmix_proc_t*)
                      PMIx server that sourced the event.
15
16
                PMIX EVENT TEXT MESSAGE "pmix.evtext" (char*)
17
                      Text message suitable for output by recipient - e.g., describing the cause of the event.
                PMIX_EVENT_TIMESTAMP "pmix.evtstamp" (time_t)
18
19
                      System time when the associated event occurred.
     9.1.5.1
                Fault tolerance event attributes
20
21
                The following attributes may be used by the host environment when providing an event notification as
22
                qualifiers indicating the action it intends to take in response to the event:
23
                PMIX_EVENT_TERMINATE_SESSION "pmix.evterm.sess" (bool)
24
                      The RM intends to terminate this session.
25
                PMIX_EVENT_TERMINATE_JOB "pmix.evterm.job" (bool)
26
                      The RM intends to terminate this job.
                PMIX_EVENT_TERMINATE_NODE "pmix.evterm.node" (bool)
27
28
                      The RM intends to terminate all processes on this node.
29
                PMIX_EVENT_TERMINATE_PROC "pmix.evterm.proc" (bool)
30
                      The RM intends to terminate just this process.
                PMIX_EVENT_ACTION_TIMEOUT "pmix.evtimeout" (int)
31
32
                      The time in seconds before the RM will execute the indicated operation.
     9.1.5.2 Hybrid programming event attributes
33
34
                The following attributes may be used by programming models to coordinate their use of common resources
35
                within a process in conjunction with the PMIX_OPENMP_PARALLEL_ENTERED event:
36
                PMIX MODEL PHASE NAME "pmix.mdl.phase" (char*)
37
                      User-assigned name for a phase in the application execution (e.g., "cfd reduction").
38
```

PMIX_MODEL_PHASE_TYPE "pmix.mdl.ptype" (char*)

Type of phase being executed (e.g., "matrix multiply").

9.1.6 Notification Function

36

2 Summary 3 The pmix_notification_fn_t is called by PMIx to deliver notification of an event. Advice to users ——— The PMIx ad hoc v1.0 Standard defined an error notification function with an identical name, but different 4 5 signature than the v2.0 Standard described below. The ad hoc v1.0 version was removed from the v2.0 6 Standard is not included in this document to avoid confusion. PMIx v2.07 typedef void (*pmix_notification_fn_t) 8 (size t evhdlr registration id, 9 pmix_status_t status, 10 const pmix_proc_t *source, pmix_info_t info[], size_t ninfo, 11 12 pmix_info_t results[], size_t nresults, pmix_event_notification_cbfunc_fn_t cbfunc, 13 14 void *cbdata); 15 evhdlr_registration_id 16 Registration number of the handler being called (size_t) 17 IN status 18 Status associated with the operation (pmix_status_t) 19 IN 20 Identifier of the process that generated the event (pmix_proc_t). If the source is the SMS, then the nspace will be empty and the rank will be PMIX_RANK_UNDEF 21 22 IN 23 Information describing the event (pmix_info_t). This argument will be NULL if no additional information was provided by the event generator. 24 25 IN 26 Number of elements in the info array (size_t) 27 results 28 Aggregated results from prior event handlers servicing this event (pmix info t). This argument will be **NULL** if this is the first handler servicing the event, or if no prior handlers provided results. 29 30 IN nresults Number of elements in the results array (size_t) 31 32 cbfunc IN pmix event notification cbfunc fn t callback function to be executed upon completion 33 34 of the handler's operation and prior to handler return (function reference). 35 IN cbdata

Callback data to be passed to cbfunc (memory reference)

1 2

3

4

5

6

7

8

9 10

11

12 13

14

15

16 17

18

19

Note that different RMs may provide differing levels of support for event notification to application processes. Thus, the *info* array may be **NULL** or may contain detailed information of the event. It is the responsibility of the application to parse any provided info array for defined key-values if it so desires.

Advice to users -

Possible uses of the info array include:

- for the host RM to alert the process as to planned actions, such as aborting the session, in response to the reported event
- provide a timeout for alternative action to occur, such as for the application to request an alternate response

For example, the RM might alert the application to the failure of a node that resulted in termination of several processes, and indicate that the overall session will be aborted unless the application requests an alternative behavior in the next 5 seconds. The application then has time to respond with a checkpoint request, or a request to recover from the failure by obtaining replacement nodes and restarting from some earlier checkpoint.

Support for these options is left to the discretion of the host RM. Info keys are included in the common definitions above but may be augmented by environment vendors.

-Advice to PMIx server hosts-

On the server side, the notification function is used to inform the PMIx server library's host of a detected event in the PMIx server library. Events generated by PMIx clients are communicated to the PMIx server library, but will be relayed to the host via the pmix_server_notify_event_fn_t function pointer, if provided.

9.1.7 PMIx Deregister event handler

Summary 20 21

Deregister an event handler.

1		Format C
2		pmix_status_t
3		PMIx_Deregister_event_handler(size_t evhdlr_ref,
4		pmix_op_cbfunc_t cbfunc,
5		<pre>void *cbdata);</pre>
		C
6		<pre>IN evhdlr_ref</pre>
7		Event handler ID returned by registration (size_t)
8		IN cbfunc
9 10		Callback function to be executed upon completion of operation pmix_op_cbfunc_t (function reference)
11		IN cbdata
12		Data to be passed to the cbfunc callback function (memory reference)
13		If <i>cbfunc</i> is NULL , the function will be treated as a <i>blocking</i> call and the result of the operation returned in the
14		status code.
15		If <i>cbfunc</i> is non-NULL, the function will be treated as a <i>non-blocking</i> call and return one of the following:
16		• PMIX_SUCCESS, indicating that the request is being processed - result will be returned in the provided
17		cbfunc. Note that the library must not invoke the callback function prior to returning from the API.
18		• PMIX_OPERATION_SUCCEEDED, indicating that the request was immediately processed and returned
19		success - the cbfunc will not be called
20		• a PMIx error constant indicating either an error in the input or that the request was immediately processed
21		and failed - the <i>cbfunc</i> will <i>not</i> be called
22		The returned status code will be one of the following:
23		• PMIX_SUCCESS The event handler was successfully deregistered.
24		• PMIX_ERR_BAD_PARAM The provided <i>evhdlr_ref</i> was unrecognized.
25		• PMIX_ERR_NOT_SUPPORTED The PMIx implementation does not support event notification.
26		Description
27		Deregister an event handler. Note that no events corresponding to the referenced registration may be delivered
28		following completion of the deregistration operation (either return from the API with
29		PMIX_OPERATION_SUCCEEDED or execution of the <i>cbfunc</i>).
20	9.1.8	PMTy Notify overt
30	ð. I.O	PMIx_Notify_event
31		Summary

SummaryReport an event for notification via any registered event handler.

 IN status

Status code of the event (pmix_status_t)

IN source

Pointer to a pmix_proc_t identifying the original reporter of the event (handle)

IN range

Range across which this notification shall be delivered (pmix_data_range_t)

IN info

Array of **pmix_info_t** structures containing any further info provided by the originator of the event (array of handles)

IN ninfo

Number of elements in the *info* array (size_t)

IN cbfunc

Callback function to be executed upon completion of operation **pmix_op_cbfunc_t** (function reference)

IN cbdata

Data to be passed to the cbfunc callback function (memory reference)

If *cbfunc* is **NULL**, the function will be treated as a *blocking* call and the result of the operation returned in the status code.

If *cbfunc* is non-**NULL**, the function will be treated as a *non-blocking* call and return one of the following:

- PMIX_SUCCESS The notification request is valid and is being processed. The callback function will be called when the process-local operation is complete and will provide the resulting status of that operation. Note that this does *not* reflect the success or failure of delivering the event to any recipients. The callback function must not be executed prior to returning from the API.
- PMIX_OPERATION_SUCCEEDED, indicating that the request was immediately processed and returned success - the cbfunc will not be called
- PMIX_ERR_BAD_PARAM The request contains at least one incorrect entry that prevents it from being
 processed. The callback function will not be called.
- PMIX_ERR_NOT_SUPPORTED The PMIx implementation does not support event notification, or in the
 case of a PMIx server calling the API, the range extended beyond the local node and the host SMS
 environment does not support event notification. The callback function will not be called.

	Required Attributes
1	The following attributes are required to be supported by all PMIx libraries:
2 3	<pre>PMIX_EVENT_NON_DEFAULT "pmix.evnondef" (bool) Event is not to be delivered to default event handlers.</pre>
4 5	<pre>PMIX_EVENT_CUSTOM_RANGE "pmix.evrange" (pmix_data_array_t*) Array of pmix_proc_t defining range of event notification.</pre>
6 7	PMIX_EVENT_DO_NOT_CACHE "pmix.evnocache" (bool) Instruct the PMIx server not to cache the event.
8 9	<pre>PMIX_EVENT_PROXY "pmix.evproxy" (pmix_proc_t*) PMIx server that sourced the event.</pre>
10 11	<pre>PMIX_EVENT_TEXT_MESSAGE "pmix.evtext" (char*) Text message suitable for output by recipient - e.g., describing the cause of the event.</pre>
12	
13 14	Host environments that implement support for PMIx event notification are required to provide the following attributes for all events generated by the environment:
15 16	<pre>PMIX_EVENT_AFFECTED_PROC "pmix.evproc" (pmix_proc_t) The single process that was affected.</pre>
17 18	<pre>PMIX_EVENT_AFFECTED_PROCS "pmix.evaffected" (pmix_data_array_t*)</pre>
	▼ Optional Attributes
19 20 21	Host environments that support PMIx event notification may offer notifications for environmental events impacting the job and for SMS events relating to the job. The following attributes may optionally be included to indicate the host environment's intended response to the event:
22 23	<pre>PMIX_EVENT_TERMINATE_SESSION "pmix.evterm.sess" (bool) The RM intends to terminate this session.</pre>
24 25	<pre>PMIX_EVENT_TERMINATE_JOB "pmix.evterm.job" (bool) The RM intends to terminate this job.</pre>
26 27	<pre>PMIX_EVENT_TERMINATE_NODE "pmix.evterm.node" (bool) The RM intends to terminate all processes on this node.</pre>
28 29	<pre>PMIX_EVENT_TERMINATE_PROC "pmix.evterm.proc" (bool) The RM intends to terminate just this process.</pre>
30 31	<pre>PMIX_EVENT_ACTION_TIMEOUT "pmix.evtimeout" (int) The time in seconds before the RM will execute the indicated operation.</pre>

Report an event for notification via any registered event handler. This function can be called by any PMIx process, including application processes, PMIx servers, and SMS elements. The PMIx server calls this API to report events it detected itself so that the host SMS daemon distribute and handle them, and to pass events given to it by its host down to any attached client processes for processing. Examples might include notification of the failure of another process, detection of an impending node failure due to rising temperatures, or an intent to preempt the application. Events may be locally generated or come from anywhere in the system.

Host SMS daemons call the API to pass events down to its embedded PMIx server both for transmittal to local client processes and for the host's own internal processing where the host has registered its own event handlers. The PMIx server library is not allowed to echo any event given to it by its host via this API back to the host through the <code>pmix_server_notify_event_fn_t</code> server module function. The host is required to deliver the event to all PMIx servers where the targeted processes either are currently running, or (if they haven't started yet) might be running at some point in the future as the events are required to be cached by the PMIx server library.

Client application processes can call this function to notify the SMS and/or other application processes of an event it encountered. Note that processes are not constrained to report status values defined in the official PMIx standard — any integer value can be used. Thus, applications are free to define their own internal events and use the notification system for their own internal purposes.

Advice to users ———

The callback function will be called upon completion of the **notify_event** function's actions. At that time, any messages required for executing the operation (e.g., to send the notification to the local PMIx server) will have been queued, but may not yet have been transmitted. The caller is required to maintain the input data until the callback function has been executed — the sole purpose of the callback function is to indicate when the input data is no longer required.

9.1.9 Notification Handler Completion Callback Function

Summary

The pmix_event_notification_cbfunc_fn_t is called by event handlers to indicate completion of their operations.

```
PMIx v2.0
```

\boldsymbol{c}			
(
(
(
(
(
(
(
(
(
•			
•			
ı			

1		IN status
2		Status returned by the event handler's operation (pmix_status_t)
3		IN results
4		Results from this event handler's operation on the event (pmix_info_t)
5		IN nresults
6		Number of elements in the results array (size_t)
7		IN cbfunc
8 9		<pre>pmix_op_cbfunc_t function to be executed when PMIx completes processing the callback (function reference)</pre>
10		IN thischdata
11		Callback data that was passed in to the handler (memory reference)
12		IN cbdata
13		Callback data to be returned when PMIx executes cbfunc (memory reference)
14		Description
15		Define a callback by which an event handler can notify the PMIx library that it has completed its response to
16		the notification. The handler is <i>required</i> to execute this callback so the library can determine if additional
17		handlers need to be called. The handler shall return PMIX_EVENT_ACTION_COMPLETE if no further action
18		is required. The return status of each event handler and any returned ${\tt pmix_info_t}$ structures will be added
19		to the <i>results</i> array of pmix_info_t passed to any subsequent event handlers to help guide their operation.
20		If non-NULL, the provided callback function will be called to allow the event handler to release the provided
21		info array and execute any other required cleanup operations.
22	9.1.9.1	Completion Callback Function Status Codes
23		The following status code may be returned indicating various actions taken by other event handlers.
24		PMIX_EVENT_NO_ACTION_TAKEN Event handler: No action taken.

PMIX_EVENT_NO_ACTION_TAKEN Event handler: No action taken.

PMIX_EVENT_PARTIAL_ACTION_TAKEN Event handler: Partial action taken.

PMIX_EVENT_ACTION_DEFERRED Event handler: Action deferred.

PMIX_EVENT_ACTION_COMPLETE Event handler: Action complete.

CHAPTER 10

1

2

3

5

6

29

Data Packing and Unpacking

PMIx intentionally does not include support for internode communications in the standard, instead relying on its host SMS environment to transfer any needed data and/or requests between nodes. These operations frequently involve PMIx-defined public data structures that include binary data. Many HPC clusters are homogeneous, and so transferring the structures can be done rather simply. However, greater effort is required in heterogeneous environments to ensure binary data is correctly transferred. PMIx buffer manipulation functions are provided for this purpose via standardized interfaces to ease adoption.

10.1 Data Buffer Type

```
8
              The pmix_data_buffer_t structure describes a data buffer used for packing and unpacking.
  PMIx v2.0
                                               — С
9
              typedef struct pmix_data_buffer {
10
                  /** Start of my memory */
11
                  char *base ptr;
12
                  /** Where the next data will be packed to
13
                       (within the allocated memory starting
14
                      at base_ptr) */
15
                  char *pack ptr;
16
                  /** Where the next data will be unpacked
17
                      from (within the allocated memory
18
                      starting as base_ptr) */
19
                  char *unpack_ptr;
20
                  /** Number of bytes allocated (starting
21
                      at base ptr) */
22
                  size_t bytes_allocated;
23
                  /** Number of bytes used by the buffer
24
                       (i.e., amount of data -- including
25
                      overhead -- packed in the buffer) */
26
                  size t bytes used;
27
              } pmix data buffer t;
```

10.2 Support Macros

PMIx provides a set of convenience macros for creating, initiating, and releasing data buffers.

1 2		Static initializer for the data buffer structure (Provisional)
3		Provide a static initializer for the pmix_data_buffer_t fields.
4		PMIX_DATA_BUFFER_STATIC_INIT C
5 6 7	PMIx v2.0	PMIX_DATA_BUFFER_CREATE Allocate memory for a pmix_data_buffer_t object and initialize it. This macro uses calloc to allocate memory for the buffer and initialize all fields in it C
8		PMIX_DATA_BUFFER_CREATE (buffer);
9 10		OUT buffer Variable to be assigned the pointer to the allocated pmix_data_buffer_t (handle)
11 12 13	PMIx v2.0	PMIX_DATA_BUFFER_RELEASE Free a pmix_data_buffer_t object and the data it contains. Free's the data contained in the buffer, and then free's the buffer itself C PMIX_DATA_BUFFER_RELEASE (buffer);
17		C C
15 16		IN buffer Pointer to the pmix_data_buffer_t to be released (handle)
17 18	PMIx v2.0	PMIX_DATA_BUFFER_CONSTRUCT Initialize a statically declared pmix_data_buffer_t object.
19		PMIX_DATA_BUFFER_CONSTRUCT(buffer);
20 21		IN buffer Pointer to the allocated pmix_data_buffer_t that is to be initialized (handle)
22 23	PMIx v2.0	PMIX_DATA_BUFFER_DESTRUCT Release the data contained in a pmix_data_buffer_t object.
24		PMIX_DATA_BUFFER_DESTRUCT (buffer);
25 26		IN buffer Pointer to the pmix_data_buffer_t whose data is to be released (handle)

```
1
                 PMIX_DATA_BUFFER_LOAD
 2
                 Load a blob into a pmix_data_buffer_t object. Load the given data into the provided
 3
                 pmix_data_buffer_t object, usually done in preparation for unpacking the provided data. Note that the
 4
                 data is not copied into the buffer - thus, the blob must not be released until after operations on the buffer have
 5
                 completed.
   PMIx v2.0
                 PMIX DATA BUFFER LOAD (buffer, data, size);
 6
 7
                 IN buffer
 8
                       Pointer to a pre-allocated pmix_data_buffer_t (handle)
 9
10
                       Pointer to a blob (char*)
                 IN
11
12
                       Number of bytes in the blob size_t
13
                 PMIX DATA BUFFER UNLOAD
14
                 Unload the data from a pmix_data_buffer_t object. Extract the data in a buffer, assigning the pointer to
15
                 the data (and the number of bytes in the blob) to the provided variables, usually done to transmit the blob to a
16
                 remote process for unpacking. The buffer's internal pointer will be set to NULL to protect the data upon buffer
17
                 destruct or release - thus, the user is responsible for releasing the blob when done with it.
   PMIx v2.0
                 PMIX_DATA_BUFFER_UNLOAD (buffer, data, size);
18
19
                 IN buffer
20
                       Pointer to the pmix_data_buffer_t whose data is to be extracted (handle)
21
                 OUT data
22
                       Variable to be assigned the pointer to the extracted blob (void*)
23
                 OUT size
24
                       Variable to be assigned the number of bytes in the blob size t
```

10.3 General Routines

The following routines are provided to support internode transfers in heterogeneous environments.

27 10.3.1 PMIx_Data_pack

28 Summary

Pack one or more values of a specified type into a buffer, usually for transmission to another process.

25

26

Format

IN target

Pointer to a **pmix_proc_t** containing the nspace/rank of the process that will be unpacking the final buffer. A NULL value may be used to indicate that the target is based on the same PMIx version as the caller. Note that only the target's nspace is relevant. (handle)

IN buffer

Pointer to a pmix_data_buffer_t where the packed data is to be stored (handle)

IN src

Pointer to a location where the data resides. Strings are to be passed as (char **) — i.e., the caller must pass the address of the pointer to the string as the (void*). This allows the caller to pass multiple strings in a single call. (memory reference)

IN num vals

Number of elements pointed to by the *src* pointer. A string value is counted as a single value regardless of length. The values must be contiguous in memory. Arrays of pointers (e.g., string arrays) should be contiguous, although the data pointed to need not be contiguous across array entries.(int32_t)

IN type

The type of the data to be packed (pmix_data_type_t)

Returns one of the following:

```
PMIX_SUCCESS The data has been packed as requested

PMIX_ERR_NOT_SUPPORTED The PMIx implementation does not support this function.

PMIX_ERR_BAD_PARAM The provided buffer or src is NULL

PMIX_ERR_UNKNOWN_DATA_TYPE The specified data type is not known to this implementation

PMIX_ERR_OUT_OF_RESOURCE Not enough memory to support the operation

PMIX_ERROR General error
```

Description

The pack function packs one or more values of a specified type into the specified buffer. The buffer must have already been initialized via the PMIX_DATA_BUFFER_CREATE or PMIX_DATA_BUFFER_CONSTRUCT macros — otherwise, PMIx_Data_pack will return an error. Providing an unsupported type flag will likewise be reported as an error.

Note that any data to be packed that is not hard type cast (i.e., not type cast to a specific size) may lose precision when unpacked by a non-homogeneous recipient. The <code>PMIx_Data_pack</code> function will do its best to deal with heterogeneity issues between the packer and unpacker in such cases. Sending a number larger than can be handled by the recipient will return an error code (generated upon unpacking) — the error cannot be detected during packing.

The namespace of the intended recipient of the packed buffer (i.e., the process that will be unpacking it) is used solely to resolve any data type differences between PMIx versions. The recipient must, therefore, be

known to the user prior to calling the pack function so that the PMIx library is aware of the version the recipient is using. Note that all processes in a given namespace are required to use the same PMIx version thus, the caller must only know at least one process from the target's namespace.

10.3.2 PMIx_Data_unpack

Summary

Unpack values from a pmix data buffer t

$7_{PMIx v2.0}$

1

2

3

4

5

8

9

10

11

12

13

14

15

16 17

18

19 20

21

22

23

24

25

26

27 28

29 30

31

32

33 34

35

36

37 38

39

40

```
pmix_status_t
PMIx_Data_unpack(const pmix_proc_t *source,
                 pmix data buffer t *buffer, void *dest,
                 int32_t *max num values,
                 pmix data type t type);
```

IN source

Pointer to a pmix_proc_t structure containing the nspace/rank of the process that packed the provided buffer. A NULL value may be used to indicate that the source is based on the same PMIx version as the caller. Note that only the source's napace is relevant. (handle)

IN buffer

A pointer to the buffer from which the value will be extracted. (handle)

INOUT dest

A pointer to the memory location into which the data is to be stored. Note that these values will be stored contiguously in memory. For strings, this pointer must be to (char**) to provide a means of supporting multiple string operations. The unpack function will allocate memory for each string in the array - the caller must only provide adequate memory for the array of pointers. (void*)

INOUT max num values

The number of values to be unpacked — upon completion, the parameter will be set to the actual number of values unpacked. In most cases, this should match the maximum number provided in the parameters — but in no case will it exceed the value of this parameter. Note that unpacking fewer values than are actually available will leave the buffer in an unpackable state — the function will return an error code to warn of this condition.(int32_t)

IN tvpe

The type of the data to be unpacked — must be one of the PMIx defined data types (pmix_data_type_t)

Returns one of the following:

```
PMIX_SUCCESS The data has been unpacked as requested
PMIX ERR NOT SUPPORTED The PMIx implementation does not support this function.
PMIX_ERR_BAD_PARAM The provided buffer or dest is NULL
PMIX ERR UNKNOWN DATA TYPE The specified data type is not known to this implementation
```

PMIX ERR OUT OF RESOURCE Not enough memory to support the operation

PMIX ERROR General error

The unpack function unpacks the next value (or values) of a specified type from the given buffer. The buffer must have already been initialized via an PMIX_DATA_BUFFER_CREATE or PMIX_DATA_BUFFER_CONSTRUCT call (and assumedly filled with some data) — otherwise, the unpack_value function will return an error. Providing an unsupported type flag will likewise be reported as an error, as will specifying a data type that *does not* match the type of the next item in the buffer. An attempt to read beyond the end of the stored data held in the buffer will also return an error.

Note that it is possible for the buffer to be corrupted and that PMIx will *think* there is a proper variable type at the beginning of an unpack region — but that the value is bogus (e.g., just a byte field in a string array that so happens to have a value that matches the specified data type flag). Therefore, the data type error check is *not* completely safe.

Unpacking values is a "nondestructive" process — i.e., the values are not removed from the buffer. It is therefore possible for the caller to re-unpack a value from the same buffer by resetting the unpack_ptr.

Warning: The caller is responsible for providing adequate memory storage for the requested data. The user must provide a parameter indicating the maximum number of values that can be unpacked into the allocated memory. If more values exist in the buffer than can fit into the memory storage, then the function will unpack what it can fit into that location and return an error code indicating that the buffer was only partially unpacked.

Note that any data that was not hard type cast (i.e., not type cast to a specific size) when packed may lose precision when unpacked by a non-homogeneous recipient. PMIx will do its best to deal with heterogeneity issues between the packer and unpacker in such cases. Sending a number larger than can be handled by the recipient will return an error code generated upon unpacking — these errors cannot be detected during packing.

The namespace of the process that packed the buffer is used solely to resolve any data type differences between PMIx versions. The packer must, therefore, be known to the user prior to calling the pack function so that the PMIx library is aware of the version the packer is using. Note that all processes in a given namespace are *required* to use the same PMIx version — thus, the caller must only know at least one process from the packer's namespace.

10.3.3 PMIx Data copy

Summary

IN

Copy a data value from one location to another.

```
30 PMIx v2.0 Format C

31 pmix_status_t
32 PMIx_Data_copy(void **dest, void *src,
33 pmix_data_type_t type);
C

34 IN dest
35 The address of a pointer into which the address of the resulting data is to be stored. (void**)
```

A pointer to the memory location from which the data is to be copied (handle)

```
IN
 1
                      type
 2
                       The type of the data to be copied — must be one of the PMIx defined data types.
 3
                       (pmix_data_type_t)
 4
                 Returns one of the following:
 5
                   PMIX_SUCCESS The data has been copied as requested
 6
                  PMIX_ERR_NOT_SUPPORTED The PMIx implementation does not support this function.
 7
                   PMIX ERR BAD PARAM The provided src or dest is NULL
 8
                   PMIX_ERR_UNKNOWN_DATA_TYPE The specified data type is not known to this implementation
 9
                   PMIX_ERR_OUT_OF_RESOURCE Not enough memory to support the operation
10
                   PMIX ERROR General error
                 Description
11
                 Since registered data types can be complex structures, the system needs some way to know how to copy the
12
13
                 data from one location to another (e.g., for storage in the registry). This function, which can call other copy
14
                 functions to build up complex data types, defines the method for making a copy of the specified data type.
      10.3.4
15
                   PMIx Data print
                 Summary
16
17
                 Pretty-print a data value.
                 Format
18 <sub>PMIx v2.0</sub>
19
                 pmix_status_t
20
                 PMIx_Data_print(char **output, char *prefix,
21
                                      void *src, pmix_data_type_t type);
22
                 IN
                       output
                       The address of a pointer into which the address of the resulting output is to be stored. (char**)
23
24
                 IN
25
                       String to be prepended to the resulting output (char*)
                 IN
26
27
                       A pointer to the memory location of the data value to be printed (handle)
28
                 IN
                       type
29
                       The type of the data value to be printed — must be one of the PMIx defined data types.
30
                       (pmix data type t)
31
                 Returns one of the following:
32
                  PMIX_SUCCESS The data has been printed as requested
                   PMIX ERR BAD PARAM The provided data type is not recognized.
33
34
                   PMIX_ERR_NOT_SUPPORTED The PMIx implementation does not support this function.
                 Description
35
36
                 Since registered data types can be complex structures, the system needs some way to know how to print them
37
                 (i.e., convert them to a string representation). Primarily for debug purposes.
```

10.3.5 PMIx_Data_copy_payload

```
2
                Summary
 3
                Copy a payload from one buffer to another
                Format
    PMIr v20
 5
                pmix_status_t
 6
                PMIx_Data_copy_payload(pmix_data_buffer_t *dest,
 7
                                             pmix data buffer t *src);
                IN
 8
                    dest
 9
                     Pointer to the destination pmix data buffer t (handle)
10
                IN
11
                     Pointer to the source pmix_data_buffer_t (handle)
                Returns one of the following:
12
13
                 PMIX SUCCESS The data has been copied as requested
14
                 PMIX ERR BAD PARAM The src and dest pmix data buffer t types do not match
15
                 PMIX_ERR_NOT_SUPPORTED The PMIx implementation does not support this function.
                Description
16
17
                This function will append a copy of the payload in one buffer into another buffer. Note that this is not a
18
                destructive procedure — the source buffer's payload will remain intact, as will any pre-existing payload in the
                destination's buffer. Only the unpacked portion of the source payload will be copied.
19
     10.3.6
20
                  PMIx Data load
21
                Summary
22
                Load a buffer with the provided payload
23
                Format
    PMIx v4.1
24
                pmix_status_t
25
                PMIx_Data_load(pmix_data_buffer_t *dest,
26
                                   pmix_byte_object_t *src);
27
                IN
28
                     Pointer to the destination pmix data buffer t (handle)
                IN
29
                     Pointer to the source pmix_byte_object_t (handle)
30
31
                Returns one of the following:
32
                 PMIX SUCCESS The data has been loaded as requested
33
                 PMIX ERR BAD PARAM The dest structure pointer is NULL
34
                 PMIX_ERR_NOT_SUPPORTED The PMIx implementation does not support this function.
```

1 2

3

4

5

6

7

8

9

10

11

13

14

15

16

17

18

19

20

21

22

23

24 25

26 27

28

29

30 31 The load function allows the caller to transfer the contents of the *src* <code>pmix_byte_object_t</code> to the *dest* target buffer. If a payload already exists in the buffer, the function will "free" the existing data to release it, and then replace the data payload with the one provided by the caller.

Advice to users —

The buffer must be allocated or constructed in advance - failing to do so will cause the load function to return an error code.

The caller is responsible for pre-packing the provided payload. For example, the load function cannot convert to network byte order any data contained in the provided payload.

10.3.7 PMIx_Data_unload

Summary

Unload a buffer into a byte object

12 PMIx v4.1

pmix status t

PMIx_Data_unload(pmix_data_buffer_t *src,

pmix_byte_object_t *dest);

IN src

Pointer to the source **pmix_data_buffer_t** (handle)

IN dest.

Pointer to the destination pmix_byte_object_t (handle)

Returns one of the following:

PMIX SUCCESS The data has been copied as requested

PMIX ERR BAD PARAM The destination and/or source pointer is NULL

PMIX_ERR_NOT_SUPPORTED The PMIx implementation does not support this function.

Description

The unload function provides the caller with a pointer to the portion of the data payload within the buffer that has not yet been unpacked, along with the size of that region. Any portion of the payload that was previously unpacked using the <code>PMIx_Data_unpack</code> routine will be ignored. This allows the user to directly access the payload.

—— Advice to users —

This is a destructive operation. While the payload returned in the destination <code>pmix_byte_object_t</code> is undisturbed, the function will clear the *src*'s pointers to the payload. Thus, the *src* and the payload are completely separated, leaving the caller able to free or destruct the *src*.

2 Summary 3 Perform a lossless compression on the provided data **Format** PMIx v4.1 5 bool 6 PMIx_Data_compress(const uint8_t *inbytes, size_t size, uint8_t **outbytes, size_t *nbytes); 7 C 8 IN inbytes 9 Pointer to the source data (handle) 10 IN 11 Number of bytes in the source data region (size_t) 12 **OUT** outbytes 13 Address where the pointer to the compressed data region is to be returned (handle) 14 OUT nbytes 15 Address where the number of bytes in the compressed data region is to be returned (handle) Returns one of the following: 16 17 • True The data has been compressed as requested 18 • False The data has not been compressed 19 **Description** Compress the provided data block. Destination memory will be allocated if operation is successfully 20 concluded. Caller is responsible for release of the allocated region. The input data block will remain unaltered. 21 22 Note: the compress function will return **False** if the operation would not result in a smaller data block. 10.3.9 PMIx Data decompress 23 24 Summary 25 Decompress the provided data 26 **Format** PMIx v4.1

10.3.8

1

PMIx Data compress

```
1
                 bool
 2
                 PMIx_Data_decompress(const uint8_t *inbytes, size_t size,
 3
                                            uint8_t **outbytes, size_t *nbytes);
                                                  ____ C -
 4
                 OUT outbytes
 5
                      Address where the pointer to the decompressed data region is to be returned (handle)
 6
                 OUT nbvtes
 7
                      Address where the number of bytes in the decompressed data region is to be returned (handle)
 8
                      inbytes
 9
                      Pointer to the source data (handle)
10
                 IN
                      size
                      Number of bytes in the source data region (size_t)
11
12
                 Returns one of the following:
13
                 • True The data has been decompressed as requested
14
                 • False The data has not been decompressed
                 Description
15
                 Decompress the provided data block. Destination memory will be allocated if operation is successfully
16
17
                 concluded. Caller is responsible for release of the allocated region. The input data block will remain unaltered.
18
                 Only data compressed by the PMIx Data compress API can be decompressed by this function. Passing
                 data that has not been compressed by PMIx Data compress will lead to unexpected and potentially
19
20
                 catastrophic results.
      10.3.10
                    PMIx Data embed
22
                 (Provisional)
23
                 Summary
24
                 Embed a data payload into a buffer
25 <sub>PMIx v4.2</sub>
                 Format
26
                 pmix status t
27
                 PMIx Data embed(pmix data buffer t *buffer,
28
                                     const pmix_byte_object_t *payload);
29
                 OUT buffer
30
                      Address of the buffer where the payload is to be embedded (handle)
31
                     payload
32
                      Address of the pmix byte object t structure containing the data to be embedded into the buffer
33
                      (handle)
```

- 1 Returns one of the following:
- 2 PMIX_SUCCESS The data has been embedded as requested
- 3 PMIX_ERR_BAD_PARAM The destination and/or source pointer is NULL
- 4 PMIX_ERR_NOT_SUPPORTED The PMIx implementation does not support this function.

5 6

7

The embed function is identical in operation to **PMIx_Data_load** except that it does *not* clear the payload object upon completion.

CHAPTER 11

Process Management

This chapter defines functionality processes can use to abort processes, spawn processes, and determine the 1 2 relative locality of local processes. 11.1 Abort 3 PMIx provides a dedicated API by which an application can request that specified processes be aborted by the 4 5 system. 11.1.1 PMIx Abort 6 Summary Abort the specified processes 9 _{PMIx v1.0} **Format** 10 pmix status t PMIx_Abort(int status, const char msq[], 11 pmix_proc_t procs[], size_t nprocs) 12 C 13 status Error code to return to invoking environment (integer) 14 15 IN String message to be returned to user (string) 16 17 IN procs 18 Array of pmix proc t structures (array of handles) 19 IN nprocs 20 Number of elements in the *procs* array (integer) 21 Returns one of the following: 22 • PMIX SUCCESS if the operation was successfully completed. Note that the function shall not return in this 23 situation if the caller's own process was included in the request. 24 • PMIX_ERR_PARAM_VALUE_NOT_SUPPORTED if the PMIx implementation and host environment

support this API, but the request includes processes that the host environment cannot abort - e.g., if the

namespace, and the host environment does not permit such operations. In this case, none of the specified

request is to abort subsets of processes from a namespace, or processes outside of the caller's own

processes will be terminated.

• a PMIx error constant indicating an error in the request.

25

26

27

28

 Request that the host resource manager print the provided message and abort the provided array of *procs*. A Unix or POSIX environment should handle the provided status as a return error code from the main program that launched the application. A **NULL** for the *procs* array indicates that all processes in the caller's namespace are to be aborted, including itself - this is the equivalent of passing a **pmix_proc_t** array element containing the caller's namespace and a rank value of **PMIX_RANK_WILDCARD**. While it is permitted for a caller to request abort of processes from namespaces other than its own, not all environments will support such requests. Passing a **NULL** *msg* parameter is allowed.

The function shall not return until the host environment has carried out the operation on the specified processes. If the caller is included in the array of targets, then the function will not return unless the host is unable to execute the operation.

Advice to users -

The response to this request is somewhat dependent on the specific RM and its configuration (e.g., some resource managers will not abort the application if the provided status is zero unless specifically configured to do so, some cannot abort subsets of processes in an application, and some may not permit termination of processes outside of the caller's own namespace), and thus lies outside the control of PMIx itself. However, the PMIx client library shall inform the RM of the request that the specified *procs* be aborted, regardless of the value of the provided status.

Note that race conditions caused by multiple processes calling **PMIx_Abort** are left to the server implementation to resolve with regard to which status is returned and what messages (if any) are printed.

11.2 Process Creation

The PMIx_Spawn commands spawn new processes and/or applications in the PMIx universe. This may include requests to extend the existing resource allocation or obtain a new one, depending upon provided and supported attributes.

11.2.1 PMIx_Spawn

Summary

Spawn a new job.

Format 1 2 pmix status t 3 PMIx_Spawn(const pmix_info_t job_info[], size_t ninfo, 4 const pmix_app_t apps[], size_t napps, 5 char nspace[]) 6 IN job info 7 Array of info structures (array of handles) 8 IN 9 Number of elements in the *job_info* array (integer) IN 10 Array of **pmix** app t structures (array of handles) 11 12 IN napps 13 Number of elements in the *apps* array (integer) 14 OUT nspace 15 Namespace of the new job (string) 16 Returns **PMIX SUCCESS** or a negative value corresponding to a PMIx error constant. Required Attributes ------_____ 17 PMIx libraries are not required to directly support any attributes for this function. However, any provided 18 attributes must be passed to the host environment for processing. Host environments are required to support the following attributes when present in either the job_info or the 19 info array of an element of the apps array: 20 21 PMIX WDIR "pmix.wdir" (char*) 22 Working directory for spawned processes. 23 PMIX SET SESSION CWD "pmix.ssncwd" (bool) 24 Set the current working directory to the session working directory assigned by the RM - can be assigned to the entire job (by including attribute in the job_info array) or on a per-application basis in 25 the *info* array for each **pmix_app_t**. 26 27 PMIX_PREFIX "pmix.prefix" (char*) 28 Prefix to use for starting spawned processes - i.e., the directory where the executables can be found. 29 PMIX_HOST "pmix.host" (char*) 30 Comma-delimited list of hosts to use for spawned processes. 31 PMIX HOSTFILE "pmix.hostfile" (char*) Hostfile to use for spawned processes. 32

	▼ Optional Attributes
1	The following attributes are optional for host environments that support this operation:
2	<pre>PMIX_ADD_HOSTFILE "pmix.addhostfile" (char*) Hostfile containing hosts to add to existing allocation.</pre>
4 5	<pre>PMIX_ADD_HOST "pmix.addhost" (char*) Comma-delimited list of hosts to add to the allocation.</pre>
6 7	<pre>PMIX_PRELOAD_BIN "pmix.preloadbin" (bool) Preload executables onto nodes prior to executing launch procedure.</pre>
8 9	<pre>PMIX_PRELOAD_FILES "pmix.preloadfiles" (char*) Comma-delimited list of files to pre-position on nodes prior to executing launch procedure.</pre>
10 11 12	<pre>PMIX_PERSONALITY "pmix.pers" (char*) Name of personality corresponding to programming model used by application - supported values depend upon PMIx implementation.</pre>
13 14	PMIX_DISPLAY_MAP "pmix.dispmap" (bool) Display process mapping upon spawn.
15 16	<pre>PMIX_PPR "pmix.ppr" (char*) Number of processes to spawn on each identified resource.</pre>
17 18 19 20	<pre>PMIX_MAPBY "pmix.mapby" (char*) Process mapping policy - when accessed using PMIx_Get, use the PMIX_RANK_WILDCARD value for the rank to discover the mapping policy used for the provided namespace. Supported values are launcher specific.</pre>
21 22 23 24	<pre>PMIX_RANKBY "pmix.rankby" (char*) Process ranking policy - when accessed using PMIx_Get, use the PMIX_RANK_WILDCARD value for the rank to discover the ranking algorithm used for the provided namespace. Supported values are launcher specific.</pre>
25 26 27 28	<pre>PMIX_BINDTO "pmix.bindto" (char*) Process binding policy - when accessed using PMIx_Get, use the PMIX_RANK_WILDCARD value for the rank to discover the binding policy used for the provided namespace. Supported values are launcher specific.</pre>
29 30	PMIX_STDIN_TGT "pmix.stdin" (uint32_t) Spawned process rank that is to receive any forwarded stdin.
31 32 33 34	<pre>PMIX_TAG_OUTPUT "pmix.tagout" (bool) Tag stdout/stderr with the identity of the source process - can be assigned to the entire job (by including attribute in the job_info array) or on a per-application basis in the info array for each pmix_app_t.</pre>
35 36 37	<pre>PMIX_TIMESTAMP_OUTPUT "pmix.tsout" (bool) Timestamp output - can be assigned to the entire job (by including attribute in the job_info array) or on a per-application basis in the info array for each pmix_app_t.</pre>

1 2 3	PMIX_MERGE_STDERR_STDOUT "pmix.mergeerrout" (bool) Merge stdout and stderr streams - can be assigned to the entire job (by including attribute in the job_info array) or on a per-application basis in the info array for each pmix_app_t.
4 5 6 7	<pre>PMIX_OUTPUT_TO_FILE "pmix.outfile" (char*) Direct output (both stdout and stderr) into files of form "<filename>.rank" - can be assigned to the entire job (by including attribute in the job_info array) or on a per-application basis in the info array for each pmix_app_t.</filename></pre>
8 9	PMIX_INDEX_ARGV "pmix.indxargv" (bool) Mark the argv with the rank of the process.
10 11 12 13	PMIX_CPUS_PER_PROC "pmix.cpuperproc" (uint32_t) Number of PUs to assign to each rank - when accessed using PMIx_Get, use the PMIX_RANK_WILDCARD value for the rank to discover the PUs/process assigned to the provided namespace.
14 15	PMIX_NO_PROCS_ON_HEAD "pmix.nolocal" (bool) Do not place processes on the head node.
16 17	<pre>PMIX_NO_OVERSUBSCRIBE "pmix.noover" (bool) Do not oversubscribe the nodes - i.e., do not place more processes than allocated slots on a node.</pre>
18 19	PMIX_REPORT_BINDINGS "pmix.repbind" (bool) Report bindings of the individual processes.
20 21 22	PMIX_CPU_LIST "pmix.cpulist" (char*) List of PUs to use for this job - when accessed using PMIx_Get, use the PMIX_RANK_WILDCARD value for the rank to discover the PU list used for the provided namespace.
23 24	PMIX_JOB_RECOVERABLE "pmix.recover" (bool) Application supports recoverable operations.
25 26	PMIX_JOB_CONTINUOUS "pmix.continuous" (bool) Application is continuous, all failed processes should be immediately restarted.
27 28 29	PMIX_MAX_RESTARTS "pmix.maxrestarts" (uint32_t) Maximum number of times to restart a process - when accessed using PMIx_Get, use the PMIX_RANK_WILDCARD value for the rank to discover the max restarts for the provided namespace.
30 31	<pre>PMIX_SET_ENVAR "pmix.envar.set" (pmix_envar_t*) Set the envar to the given value, overwriting any pre-existing one</pre>
32 33	<pre>PMIX_UNSET_ENVAR "pmix.envar.unset" (char*) Unset the environment variable specified in the string.</pre>
34 35	<pre>PMIX_ADD_ENVAR "pmix.envar.add" (pmix_envar_t*) Add the environment variable, but do not overwrite any pre-existing one</pre>
36 37 38	PMIX_PREPEND_ENVAR "pmix.envar.prepnd" (pmix_envar_t*) Prepend the given value to the specified environmental value using the given separator character, creating the variable if it doesn't already exist

1 2 3	PMIX_APPEND_ENVAR "pmix.envar.appnd" (pmix_envar_t*) Append the given value to the specified environmental value using the given separator character, creating the variable if it doesn't already exist
4 5 6	<pre>PMIX_FIRST_ENVAR "pmix.envar.first" (pmix_envar_t*)</pre>
7 8 9	<pre>PMIX_ALLOC_QUEUE "pmix.alloc.queue" (char*) Name of the WLM queue to which the allocation request is to be directed, or the queue being referenced in a query.</pre>
0	<pre>PMIX_ALLOC_TIME "pmix.alloc.time" (uint32_t) Total session time (in seconds) being requested in an allocation request.</pre>
2	PMIX_ALLOC_NUM_NODES "pmix.alloc.nnodes" (uint64_t) The number of nodes being requested in an allocation request.
4 5	<pre>PMIX_ALLOC_NODE_LIST "pmix.alloc.nlist" (char*) Regular expression of the specific nodes being requested in an allocation request.</pre>
6 7	PMIX_ALLOC_NUM_CPUS "pmix.alloc.ncpus" (uint64_t) Number of PUs being requested in an allocation request.
8 9	PMIX_ALLOC_NUM_CPU_LIST "pmix.alloc.ncpulist" (char*) Regular expression of the number of PUs for each node being requested in an allocation request.
20 21	<pre>PMIX_ALLOC_CPU_LIST "pmix.alloc.cpulist" (char*) Regular expression of the specific PUs being requested in an allocation request.</pre>
22 23	PMIX_ALLOC_MEM_SIZE "pmix.alloc.msize" (float) Number of Megabytes[base2] of memory (per process) being requested in an allocation request.
24 25	PMIX_ALLOC_BANDWIDTH "pmix.alloc.bw" (float) Fabric bandwidth (in Megabits[base2]/sec) for the job being requested in an allocation request.
26 27	<pre>PMIX_ALLOC_FABRIC_QOS "pmix.alloc.netqos" (char*)</pre>
28 29	PMIX_ALLOC_FABRIC_TYPE "pmix.alloc.nettype" (char*) Type of desired transport (e.g., "tcp", "udp") being requested in an allocation request.
30 31	PMIX_ALLOC_FABRIC_PLANE "pmix.alloc.netplane" (char*) ID string for the <i>fabric plane</i> to be used for the requested allocation.
32 3	PMIX_ALLOC_FABRIC_ENDPTS "pmix.alloc.endpts" (size_t) Number of endpoints to allocate per <i>process</i> in the job.
34 35	<pre>PMIX_ALLOC_FABRIC_ENDPTS_NODE "pmix.alloc.endpts.nd" (size_t) Number of endpoints to allocate per node for the job.</pre>
86	PMIX_COSPAWN_APP "pmix.cospawn" (bool)

Designated application is to be spawned as a disconnected job - i.e., the launcher shall not include the application in any of the job-level values (e.g., **PMIX_RANK** within the job) provided to any other application process generated by the same spawn request. Typically used to cospawn debugger daemons alongside an application.

```
{\color{red} \textbf{PMIX\_SPAWN\_TOOL}} \quad "\texttt{pmix.spwn.tool"} \ (\texttt{bool})
```

Indicate that the job being spawned is a tool.

PMIX EVENT SILENT TERMINATION "pmix.evsilentterm" (bool)

Do not generate an event when this job normally terminates.

PMIX_ENVARS_HARVESTED "pmix.evar.hvstd" (bool)

Environmental parameters have been harvested by the spawn requestor - the server does not need to harvest them.

```
PMIX_JOB_TIMEOUT "pmix.job.time" (int)
```

Time in seconds before the spawned job should time out and be terminated (0 => infinite), defined as the total runtime of the job (equivalent to the walltime limit of typical batch schedulers).

```
PMIX_SPAWN_TIMEOUT "pmix.sp.time" (int)
```

Time in seconds before spawn operation should time out (0 => infinite). Logically equivalent to passing the **PMIX_TIMEOUT** attribute to the **PMIX_Spawn** API, it is provided as a separate attribute to distinguish it from the **PMIX_JOB_TIMEOUT** attribute

Description

Spawn a new job. The assigned namespace of the spawned applications is returned in the *nspace* parameter. A **NULL** value in that location indicates that the caller doesn't wish to have the namespace returned. The *nspace* array must be at least of size one more than **PMIX_MAX_NSLEN**.

By default, the spawned processes will be PMIx "connected" to the parent process upon successful launch (see Section 11.3 for details). This includes that (a) the parent process will be given a copy of the new job's information so it can query job-level info without incurring any communication penalties, (b) newly spawned child processes will receive a copy of the parent processes job-level info, and (c) both the parent process and members of the child job will receive notification of errors from processes in their combined assemblage.

Advice to users —

Behavior of individual resource managers may differ, but it is expected that failure of any application process to start will result in termination/cleanup of all processes in the newly spawned job and return of an error code to the caller.

—Advice to PMIx library implementers

Tools may utilize **PMIx_Spawn** to start intermediate launchers as described in Section 17.2.2. For times where the tool is not attached to a PMIx server, internal support for fork/exec of the specified applications would allow the tool to maintain a single code path for both the connected and disconnected cases. Inclusion of such support is recommended, but not required.

1 11.2.2 PMIx_Spawn_nb

2		Summary Nonblocking version of the PMIx_Spawn routine.
4	PMIx v1.0	Format C
5 6 7 8		<pre>pmix_status_t PMIx_Spawn_nb(const pmix_info_t job_info[], size_t ninfo,</pre>
9 10 11 12 13 14 15 16 17		 IN job_info Array of info structures (array of handles) IN ninfo Number of elements in the job_info array (integer) IN apps Array of pmix_app_t structures (array of handles) IN cbfunc Callback function pmix_spawn_cbfunc_t (function reference) IN cbdata Data to be passed to the callback function (memory reference)
19 20 21 22		 PMIX_SUCCESS, indicating that the request is being processed by the host environment - result will be returned in the provided <i>cbfunc</i>. Note that the library must not invoke the callback function prior to returning from the API.
23		• a PMIx error constant indicating an error in the request - the <i>cbfunc</i> will <i>not</i> be called
		Required Attributes
24 25		PMIx libraries are not required to directly support any attributes for this function. However, any provided attributes must be passed to the host SMS daemon for processing.
26 27		Host environments are required to support the following attributes when present in either the <i>job_info</i> or the <i>info</i> array of an element of the <i>apps</i> array:
28 29		PMIX_WDIR "pmix.wdir" (char*) Working directory for spawned processes.
30 31 32 33		PMIX_SET_SESSION_CWD "pmix.ssncwd" (bool) Set the current working directory to the session working directory assigned by the RM - can be assigned to the entire job (by including attribute in the <i>job_info</i> array) or on a per-application basis in the <i>info</i> array for each pmix_app_t.
34 35		PMIX_PREFIX "pmix.prefix" (char*) Prefix to use for starting spawned processes - i.e., the directory where the executables can be found.
36		<pre>PMIX_HOST "pmix.host" (char*)</pre>

1 Comma-delimited list of hosts to use for spawned processes. 2 PMIX_HOSTFILE "pmix.hostfile" (char*) 3 Hostfile to use for spawned processes. ----- Optional Attributes The following attributes are optional for host environments that support this operation: 4 5 PMIX ADD HOSTFILE "pmix.addhostfile" (char*) Hostfile containing hosts to add to existing allocation. 6 7 PMIX ADD HOST "pmix.addhost" (char*) 8 Comma-delimited list of hosts to add to the allocation. 9 PMIX_PRELOAD_BIN "pmix.preloadbin" (bool) 10 Preload executables onto nodes prior to executing launch procedure. 11 PMIX_PRELOAD_FILES "pmix.preloadfiles" (char*) 12 Comma-delimited list of files to pre-position on nodes prior to executing launch procedure. 13 PMIX_PERSONALITY "pmix.pers" (char*) 14 Name of personality corresponding to programming model used by application - supported values 15 depend upon PMIx implementation. PMIX_DISPLAY_MAP "pmix.dispmap" (bool) 16 17 Display process mapping upon spawn. 18 PMIX_PPR "pmix.ppr" (char*) 19 Number of processes to spawn on each identified resource. 20 PMIX_MAPBY "pmix.mapby" (char*) 21 Process mapping policy - when accessed using PMIx Get, use the PMIX RANK WILDCARD value 22 for the rank to discover the mapping policy used for the provided namespace. Supported values are launcher specific. 23 24 PMIX_RANKBY "pmix.rankby" (char*) 25 Process ranking policy - when accessed using PMIx_Get, use the PMIX_RANK_WILDCARD value 26 for the rank to discover the ranking algorithm used for the provided namespace. Supported values are 27 launcher specific. 28 PMIX_BINDTO "pmix.bindto" (char*) 29 Process binding policy - when accessed using PMIx Get, use the PMIX RANK WILDCARD value for the rank to discover the binding policy used for the provided namespace. Supported values are 30 31 launcher specific. 32 PMIX STDIN TGT "pmix.stdin" (uint32 t) Spawned process rank that is to receive any forwarded stdin. 33 34 PMIX TAG OUTPUT "pmix.tagout" (bool)

1 2 3	Tag stdout/stderr with the identity of the source process - can be assigned to the entire job (by including attribute in the <i>job_info</i> array) or on a per-application basis in the <i>info</i> array for each pmix_app_t .
4 5 6	PMIX_TIMESTAMP_OUTPUT "pmix.tsout" (bool) Timestamp output - can be assigned to the entire job (by including attribute in the <i>job_info</i> array) or on a per-application basis in the <i>info</i> array for each pmix_app_t.
7 8 9	PMIX_MERGE_STDERR_STDOUT "pmix.mergeerrout" (bool) Merge stdout and stderr streams - can be assigned to the entire job (by including attribute in the job_info array) or on a per-application basis in the info array for each pmix_app_t.
0 1 2 3	<pre>PMIX_OUTPUT_TO_FILE "pmix.outfile" (char*) Direct output (both stdout and stderr) into files of form "<filename>.rank" - can be assigned to the entire job (by including attribute in the job_info array) or on a per-application basis in the info array for each pmix_app_t.</filename></pre>
4 5	PMIX_INDEX_ARGV "pmix.indxargv" (bool) Mark the argv with the rank of the process.
6 7 8 9	PMIX_CPUS_PER_PROC "pmix.cpuperproc" (uint32_t) Number of PUs to assign to each rank - when accessed using PMIx_Get, use the PMIX_RANK_WILDCARD value for the rank to discover the PUs/process assigned to the provided namespace.
20 21	PMIX_NO_PROCS_ON_HEAD "pmix.nolocal" (bool) Do not place processes on the head node.
22 23	<pre>PMIX_NO_OVERSUBSCRIBE "pmix.noover" (bool)</pre>
24 25	PMIX_REPORT_BINDINGS "pmix.repbind" (bool) Report bindings of the individual processes.
26 27 28	<pre>PMIX_CPU_LIST "pmix.cpulist" (char*) List of PUs to use for this job - when accessed using PMIx_Get, use the PMIX_RANK_WILDCARD value for the rank to discover the PU list used for the provided namespace.</pre>
9 80	PMIX_JOB_RECOVERABLE "pmix.recover" (bool) Application supports recoverable operations.
31 32	PMIX_JOB_CONTINUOUS "pmix.continuous" (bool) Application is continuous, all failed processes should be immediately restarted.
33 34 35	PMIX_MAX_RESTARTS "pmix.maxrestarts" (uint32_t) Maximum number of times to restart a process - when accessed using PMIx_Get, use the PMIX_RANK_WILDCARD value for the rank to discover the max restarts for the provided namespace.
36 37	<pre>PMIX_SET_ENVAR "pmix.envar.set" (pmix_envar_t*)</pre> Set the envar to the given value, overwriting any pre-existing one
88 9	PMIX_UNSET_ENVAR "pmix.envar.unset" (char*) Unset the environment variable specified in the string.

1 2	<pre>PMIX_ADD_ENVAR "pmix.envar.add" (pmix_envar_t*) Add the environment variable, but do not overwrite any pre-existing one</pre>
3 4 5	<pre>PMIX_PREPEND_ENVAR "pmix.envar.prepnd" (pmix_envar_t*) Prepend the given value to the specified environmental value using the given separator character, creating the variable if it doesn't already exist</pre>
6 7 8	<pre>PMIX_APPEND_ENVAR "pmix.envar.appnd" (pmix_envar_t*) Append the given value to the specified environmental value using the given separator character, creating the variable if it doesn't already exist</pre>
9 10 11	<pre>PMIX_FIRST_ENVAR "pmix.envar.first" (pmix_envar_t*)</pre> Ensure the given value appears first in the specified envar using the separator character, creating the envar if it doesn't already exist
12 13 14	<pre>PMIX_ALLOC_QUEUE "pmix.alloc.queue" (char*) Name of the WLM queue to which the allocation request is to be directed, or the queue being referenced in a query.</pre>
15 16	<pre>PMIX_ALLOC_TIME "pmix.alloc.time" (uint32_t) Total session time (in seconds) being requested in an allocation request.</pre>
17 18	<pre>PMIX_ALLOC_NUM_NODES "pmix.alloc.nnodes" (uint64_t) The number of nodes being requested in an allocation request.</pre>
19 20	<pre>PMIX_ALLOC_NODE_LIST "pmix.alloc.nlist" (char*) Regular expression of the specific nodes being requested in an allocation request.</pre>
21 22	PMIX_ALLOC_NUM_CPUS "pmix.alloc.ncpus" (uint64_t) Number of PUs being requested in an allocation request.
23 24	PMIX_ALLOC_NUM_CPU_LIST "pmix.alloc.ncpulist" (char*) Regular expression of the number of PUs for each node being requested in an allocation request.
25 26	PMIX_ALLOC_CPU_LIST "pmix.alloc.cpulist" (char*) Regular expression of the specific PUs being requested in an allocation request.
27 28	PMIX_ALLOC_MEM_SIZE "pmix.alloc.msize" (float) Number of Megabytes[base2] of memory (per process) being requested in an allocation request.
29 30	PMIX_ALLOC_BANDWIDTH "pmix.alloc.bw" (float) Fabric bandwidth (in Megabits[base2]/sec) for the job being requested in an allocation request.
31 32	<pre>PMIX_ALLOC_FABRIC_QOS "pmix.alloc.netqos" (char*) Fabric quality of service level for the job being requested in an allocation request.</pre>
33 34	<pre>PMIX_ALLOC_FABRIC_TYPE "pmix.alloc.nettype" (char*)</pre>
35 36	PMIX_ALLOC_FABRIC_PLANE "pmix.alloc.netplane" (char*) ID string for the <i>fabric plane</i> to be used for the requested allocation.
37	<pre>PMIX_ALLOC_FABRIC_ENDPTS "pmix.alloc.endpts" (size_t)</pre>

Number of endpoints to allocate per *process* in the job. PMIX_ALLOC_FABRIC_ENDPTS_NODE "pmix.alloc.endpts.nd" (size_t) Number of endpoints to allocate per *node* for the job. PMIX COSPAWN APP "pmix.cospawn" (bool) Designated application is to be spawned as a disconnected job - i.e., the launcher shall not include the application in any of the job-level values (e.g., PMIX RANK within the job) provided to any other application process generated by the same spawn request. Typically used to cospawn debugger daemons alongside an application. PMIX SPAWN TOOL "pmix.spwn.tool" (bool) Indicate that the job being spawned is a tool. PMIX EVENT SILENT TERMINATION "pmix.evsilentterm" (bool) Do not generate an event when this job normally terminates. PMIX_ENVARS_HARVESTED "pmix.evar.hvstd" (bool) Environmental parameters have been harvested by the spawn requestor - the server does not need to harvest them. PMIX_JOB_TIMEOUT "pmix.job.time" (int) Time in seconds before the spawned job should time out and be terminated (0 => infinite), defined as the total runtime of the job (equivalent to the walltime limit of typical batch schedulers). PMIX SPAWN TIMEOUT "pmix.sp.time" (int) Time in seconds before spawn operation should time out (0 => infinite). Logically equivalent to passing the PMIX_TIMEOUT attribute to the PMIx_Spawn API, it is provided as a separate attribute to distinguish it from the **PMIX_JOB_TIMEOUT** attribute **Description** Nonblocking version of the PMIx Spawn routine. The provided callback function will be executed upon successful start of all specified application processes. Advice to users ———— Behavior of individual resource managers may differ, but it is expected that failure of any application process

1

2

3

4 5

6

7

8

9

10

11

12

13

14

15 16

17

18

19

20

21 22

23

24

25

26

27

28

Behavior of individual resource managers may differ, but it is expected that failure of any application process to start will result in termination/cleanup of all processes in the newly spawned job and return of an error code to the caller.

11.2.3 Spawn-specific constants

1

3

4

5

6

7

8

9

10

11

12

13

14

15

16 17

18

19

20

21

22

23

24

25

26

27

28

29

30 31

32

33

34

35

36

37

38

39

40

41

42

In addition to the generic error constants, the following spawn-specific error constants may be returned by the spawn APIs:

PMIX_ERR_JOB_ALLOC_FAILED The job request could not be executed due to failure to obtain the

specified allocation

The job request could not be executed due to failure to obtain the

PMIX_ERR_JOB_APP_NOT_EXECUTABLE The specified application executable either could not be found, or lacks execution privileges.

PMIX_ERR_JOB_NO_EXE_SPECIFIED The job request did not specify an executable.

PMIX_ERR_JOB_FAILED_TO_MAP The launcher was unable to map the processes for the specified job request.

PMIX_ERR_JOB_FAILED_TO_LAUNCH One or more processes in the job request failed to launch

PMIX_ERR_JOB_EXE_NOT_FOUND (*Provisional*) Specified executable not found

PMIX_ERR_JOB_INSUFFICIENT_RESOURCES (Provisional) Insufficient resources to spawn job

PMIX_ERR_JOB_SYS_OP_FAILED (*Provisional*) System library operation failed

PMIX_ERR_JOB_WDIR_NOT_FOUND (Provisional) Specified working directory not found

11.2.4 Spawn attributes

Attributes used to describe <code>PMIx_Spawn</code> behavior - they are values passed to the <code>PMIx_Spawn</code> API and therefore are not accessed using the <code>PMIx_Get</code> APIs when used in that context. However, some of the attributes defined in this section can be provided by the host environment for other purposes - e.g., the host might provide the <code>PMIX_MAPBY</code> attribute in the job-related information so that an application can use <code>PMIx_Get</code> to discover the mapping used for determining process locations. Multi-use attributes and their respective access reference rank are denoted below.

```
PMIX_PERSONALITY "pmix.pers" (char*)
```

Name of personality corresponding to programming model used by application - supported values depend upon PMIx implementation.

PMIX_HOST "pmix.host" (char*)

Comma-delimited list of hosts to use for spawned processes.

PMIX_HOSTFILE "pmix.hostfile" (char*)

Hostfile to use for spawned processes.

PMIX_ADD_HOST "pmix.addhost" (char*)

Comma-delimited list of hosts to add to the allocation.

PMIX_ADD_HOSTFILE "pmix.addhostfile" (char*)

Hostfile containing hosts to add to existing allocation.

PMIX_PREFIX "pmix.prefix" (char*)

Prefix to use for starting spawned processes - i.e., the directory where the executables can be found.

PMIX_WDIR "pmix.wdir" (char*)

Working directory for spawned processes.

PMIX_DISPLAY_MAP "pmix.dispmap" (bool)

Display process mapping upon spawn.

PMIX_PPR "pmix.ppr" (char*)

Number of processes to spawn on each identified resource.

PMIX_MAPBY "pmix.mapby" (char*)

Process mapping policy - when accessed using **PMIx_Get**, use the **PMIX_RANK_WILDCARD** value for the rank to discover the mapping policy used for the provided namespace. Supported values are launcher specific.

PMIX_RANKBY "pmix.rankby" (char*)

Process ranking policy - when accessed using PMIx_Get, use the PMIX_RANK_WILDCARD value for the rank to discover the ranking algorithm used for the provided namespace. Supported values are launcher specific.

PMIX_BINDTO "pmix.bindto" (char*)

Process binding policy - when accessed using **PMIx_Get**, use the **PMIX_RANK_WILDCARD** value for the rank to discover the binding policy used for the provided namespace. Supported values are launcher specific.

PMIX_PRELOAD_BIN "pmix.preloadbin" (bool)

Preload executables onto nodes prior to executing launch procedure.

PMIX_PRELOAD_FILES "pmix.preloadfiles" (char*)

Comma-delimited list of files to pre-position on nodes prior to executing launch procedure.

PMIX_STDIN_TGT "pmix.stdin" (uint32_t)

Spawned process rank that is to receive any forwarded stdin.

PMIX_SET_SESSION_CWD "pmix.ssncwd" (bool)

Set the current working directory to the session working directory assigned by the RM - can be assigned to the entire job (by including attribute in the *job_info* array) or on a per-application basis in the *info* array for each **pmix_app_t**.

PMIX_TAG_OUTPUT "pmix.tagout" (bool)

Tag **stdout/stderr** with the identity of the source process - can be assigned to the entire job (by including attribute in the *job_info* array) or on a per-application basis in the *info* array for each **pmix app t**.

PMIX_TIMESTAMP_OUTPUT "pmix.tsout" (bool)

Timestamp output - can be assigned to the entire job (by including attribute in the *job_info* array) or on a per-application basis in the *info* array for each **pmix_app_t**.

PMIX MERGE STDERR STDOUT "pmix.mergeerrout" (bool)

Merge **stdout** and **stderr** streams - can be assigned to the entire job (by including attribute in the *job_info* array) or on a per-application basis in the *info* array for each **pmix_app_t**.

PMIX_OUTPUT_TO_FILE "pmix.outfile" (char*)

Direct output (both stdout and stderr) into files of form "<filename>.rank" - can be assigned to the entire job (by including attribute in the *job_info* array) or on a per-application basis in the *info* array for each pmix_app_t.

PMIX_OUTPUT_TO_DIRECTORY "pmix.outdir" (char*)

Direct output into files of form "<directory>/<jobid>/rank.<rank>/stdout[err]" - can be assigned to the entire job (by including attribute in the *job_info* array) or on a per-application basis in the *info* array for each pmix_app_t.

PMIX_INDEX_ARGV "pmix.indxargv" (bool)

Mark the **argv** with the rank of the process.

PMIX_CPUS_PER_PROC "pmix.cpuperproc" (uint32_t)

Number of PUs to assign to each rank - when accessed using **PMIx_Get**, use the **PMIX_RANK_WILDCARD** value for the rank to discover the PUs/process assigned to the provided namespace.

PMIX_NO_PROCS_ON_HEAD "pmix.nolocal" (bool)


```
1
                       Do not place processes on the head node.
 2
                PMIX_NO_OVERSUBSCRIBE "pmix.noover" (bool)
 3
                       Do not oversubscribe the nodes - i.e., do not place more processes than allocated slots on a node.
 4
                PMIX_REPORT_BINDINGS "pmix.repbind" (bool)
 5
                       Report bindings of the individual processes.
 6
                PMIX CPU LIST "pmix.cpulist" (char*)
 7
                       List of PUs to use for this job - when accessed using PMIx Get, use the PMIX RANK WILDCARD
 8
                       value for the rank to discover the PU list used for the provided namespace.
 9
                PMIX_JOB_RECOVERABLE "pmix.recover" (bool)
10
                       Application supports recoverable operations.
                PMIX JOB CONTINUOUS "pmix.continuous" (bool)
11
12
                       Application is continuous, all failed processes should be immediately restarted.
13
                PMIX MAX RESTARTS "pmix.maxrestarts" (uint32 t)
14
                       Maximum number of times to restart a process - when accessed using PMIx Get, use the
15
                       PMIX_RANK_WILDCARD value for the rank to discover the max restarts for the provided namespace.
                PMIX_SPAWN_TOOL "pmix.spwn.tool" (bool)
16
17
                       Indicate that the job being spawned is a tool.
                PMIX TIMEOUT STACKTRACES "pmix.tim.stack" (bool)
18
19
                       Include process stacktraces in timeout report from a job.
20
                PMIX TIMEOUT REPORT STATE "pmix.tim.state" (bool)
21
                       Report process states in timeout report from a job.
                PMIX NOTIFY JOB EVENTS "pmix.note.jev" (bool)
22
23
                       Requests that the launcher generate the PMIX_EVENT_JOB_START, PMIX_LAUNCH_COMPLETE,
24
                       and PMIX EVENT JOB END events. Each event is to include at least the namespace of the
25
                       corresponding job and a PMIX_EVENT_TIMESTAMP indicating the time the event occurred. Note
26
                       that the requester must register for these individual events, or capture and process them by registering a
27
                       default event handler instead of individual handlers and then process the events based on the returned
28
                       status code. Another common method is to register one event handler for all job-related events, with a
29
                       separate handler for non-job events - see PMIx Register event handler for details.
                PMIX_NOTIFY_COMPLETION "pmix.notecomp" (bool)
30
                       Requests that the launcher generate the PMIX_EVENT_JOB_END event for normal or abnormal
31
                       termination of the spawned job. The event shall include the returned status code
32
33
                       (PMIX_JOB_TERM_STATUS) for the corresponding job; the identity (PMIX_PROCID) and exit
34
                       status (PMIX EXIT CODE) of the first failed process, if applicable; and a
35
                       PMIX EVENT TIMESTAMP indicating the time the termination occurred. Note that the requester
36
                       must register for the event or capture and process it within a default event handler.
37
                PMIX NOTIFY PROC TERMINATION "pmix.noteproc" (bool)
                       Requests that the launcher generate the PMIX_EVENT_PROC_TERMINATED event whenever a
38
39
                       process either normally or abnormally terminates.
                PMIX NOTIFY_PROC_ABNORMAL_TERMINATION "pmix.noteabproc" (bool)
40
41
                       Requests that the launcher generate the PMIX_EVENT_PROC_TERMINATED event only when a
42
                       process abnormally terminates.
43
                PMIX_LOG_PROC_TERMINATION "pmix.logproc" (bool)
44
                       Requests that the launcher log the PMIX_EVENT_PROC_TERMINATED event whenever a process
45
                       either normally or abnormally terminates.
46
                PMIX LOG PROC ABNORMAL TERMINATION "pmix.logabproc" (bool)
```

1		Requests that the launcher log the PMIX_EVENT_PROC_TERMINATED event only when a process
2		abnormally terminates.
3	PM:	IX_LOG_JOB_EVENTS "pmix.log.jev" (bool)
4		Requests that the launcher log the PMIX_EVENT_JOB_START, PMIX_LAUNCH_COMPLETE, and
5		PMIX_EVENT_JOB_END events using PMIx_Log, subject to the logging attributes of Section 12.4.3
6	PM:	IX_LOG_COMPLETION "pmix.logcomp" (bool)
7		Requests that the launcher log the PMIX_EVENT_JOB_END event for normal or abnormal
8		termination of the spawned job using PMIx_Log , subject to the logging attributes of Section 12.4.3.
9		The event shall include the returned status code (PMIX_JOB_TERM_STATUS) for the corresponding
10		job; the identity (PMIX_PROCID) and exit status (PMIX_EXIT_CODE) of the first failed process, if
11		applicable; and a PMIX_EVENT_TIMESTAMP indicating the time the termination occurred.
12	PM:	IX_EVENT_SILENT_TERMINATION "pmix.evsilentterm" (bool)
13		Do not generate an event when this job normally terminates.
14	PM:	IX_ENVARS_HARVESTED "pmix.evar.hvstd" (bool) (Provisional)
15		Environmental parameters have been harvested by the spawn requestor - the server does not need to
16		harvest them.
17	PM:	IX_JOB_TIMEOUT "pmix.job.time" (int) (Provisional)
18		Time in seconds before the spawned job should time out and be terminated $(0 \Rightarrow infinite)$, defined as
19		the total runtime of the job (equivalent to the walltime limit of typical batch schedulers).
20	PM:	IX_SPAWN_TIMEOUT "pmix.sp.time" (int) (Provisional)
21		Time in seconds before spawn operation should time out $(0 \Rightarrow infinite)$. Logically equivalent to
22		passing the PMIX_TIMEOUT attribute to the PMIx_Spawn API, it is provided as a separate attribute
23		to distinguish it from the PMIX_JOB_TIMEOUT attribute
24	Attr	ributes used to adjust remote environment variables prior to spawning the specified application processes.
25	PM:	IX_SET_ENVAR "pmix.envar.set" (pmix_envar_t*)
26		Set the envar to the given value, overwriting any pre-existing one
27	PM:	IX_UNSET_ENVAR "pmix.envar.unset" (char*)
28		Unset the environment variable specified in the string.
29	PM:	IX_ADD_ENVAR "pmix.envar.add" (pmix_envar_t*)
30		Add the environment variable, but do not overwrite any pre-existing one
31	PM:	IX PREPEND ENVAR "pmix.envar.prepnd" (pmix envar t*)
32		Prepend the given value to the specified environmental value using the given separator character,
33		creating the variable if it doesn't already exist
34	PM.	IX_APPEND_ENVAR "pmix.envar.appnd" (pmix_envar_t*)
35		Append the given value to the specified environmental value using the given separator character,
36		creating the variable if it doesn't already exist
37	PM:	IX_FIRST_ENVAR "pmix.envar.first" (pmix_envar_t*)
38		Ensure the given value appears first in the specified envar using the separator character, creating the
39		envar if it doesn't already exist
10	11 25 /	Application Structure
ŧU	11.2.5	application of acture
1 1	The	e pmix_app_t structure describes the application context for the PMIx_Spawn and PMIx_Spawn_nb
12		rations.

PMIx v1.0

```
1
              typedef struct pmix_app {
 2
                   /** Executable */
 3
                   char *cmd;
 4
                   /** Argument set, NULL terminated */
 5
                   char **argv;
 6
                   /** Environment set, NULL terminated */
 7
                   char **env;
 8
                   /** Current working directory */
 9
                   char *cwd;
10
                   /** Maximum processes with this profile */
11
                   int maxprocs;
12
                   /** Array of info keys describing this application*/
13
                   pmix_info_t *info;
14
                   /** Number of info keys in 'info' array */
15
                   size_t ninfo;
16
              } pmix_app_t;
     11.2.5.1 App structure support macros
17
18
              The following macros are provided to support the pmix_app_t structure.
              Static initializer for the app structure
19
20
              (Provisional)
21
              Provide a static initializer for the pmix_app_t fields.
  PMIx v4.2
22
              PMIX_APP_STATIC_INIT
23
              Initialize the app structure
24
              Initialize the pmix_app_t fields
  PMIx v1.0
25
              PMIX APP CONSTRUCT (m)
              IN
26
```

Pointer to the structure to be initialized (pointer to pmix_app_t



```
Create the info array of application directives
 1
 2
                 Create an array of pmix_info_t structures for passing application-level directives, updating the ninfo field
 3
                 of the pmix_app_t structure.
                 PMIX_APP_INFO_CREATE(m, n)
 4
 5
                 IN
 6
                      Pointer to the pmix_app_t structure (handle)
 7
                 IN
 8
                      Number of directives to be allocated (size_t)
      11.2.5.2 Spawn Callback Function
 9
                 Summary
10
                 The pmix_spawn_cbfunc_t is used on the PMIx client side by PMIx_Spawn_nb and on the PMIx
11
12
                 server side by pmix server spawn fn t.
   PMIx v1.0
13
                 typedef void (*pmix_spawn_cbfunc_t)
                      (pmix_status_t status,
14
15
                       pmix_nspace_t nspace, void *cbdata);
16
                 IN
                      status
17
                      Status associated with the operation (handle)
18
                 IN
                      Namespace string (pmix_nspace_t)
19
                 IN
                      cbdata
20
21
                      Callback data passed to original API call (memory reference)
22
                 Description
23
                 The callback will be executed upon launch of the specified applications in PMIx Spawn nb, or upon failure
24
                 to launch any of them.
25
                 The status of the callback will indicate whether or not the spawn succeeded. The nspace of the spawned
                 processes will be returned, along with any provided callback data. Note that the returned nspace value will not
26
27
                 be protected upon return from the callback function, so the receiver must copy it if it needs to be retained.
```

11.3 Connecting and Disconnecting Processes

This section defines functions to connect and disconnect processes in two or more separate PMIx namespaces. The PMIx definition of *connected* solely implies that the host environment should treat the failure of any process in the assemblage as a reportable event, taking action on the assemblage as if it were a single application. For example, if the environment defaults (in the absence of any application directives) to terminating an application upon failure of any process in that application, then the environment should terminate all processes in the connected assemblage upon failure of any member.

The host environment may choose to assign a new namespace to the connected assemblage and/or assign new ranks for its members for its own internal tracking purposes. However, it is not required to communicate such assignments to the participants (e.g., in response to an appropriate call to <code>PMIx_Query_info_nb</code>). The host environment is required to generate a <code>PMIX_ERR_PROC_TERM_WO_SYNC</code> event should any process in the assemblage terminate or call <code>PMIx_Finalize</code> without first disconnecting from the assemblage. If the job including the process is terminated as a result of that action, then the host environment is required to also generate the <code>PMIX_ERR_JOB_TERM_WO_SYNC</code> for all jobs that were terminated as a result.

-Advice to PMIx server hosts-

The *connect* operation does not require the exchange of job-level information nor the inclusion of information posted by participating processes via PMIx_Put. Indeed, the callback function utilized in pmix_server_connect_fn_t cannot pass information back into the PMIx server library. However, host environments are advised that collecting such information at the participating daemons represents an optimization opportunity as participating processes are likely to request such information after the connect operation completes.

Advice to users

Attempting to *connect* processes solely within the same namespace is essentially a *no-op* operation. While not explicitly prohibited, users are advised that a PMIx implementation or host environment may return an error in such cases.

Neither the PMIx implementation nor host environment are required to provide any tracking support for the assemblage. Thus, the application is responsible for maintaining the membership list of the assemblage.

11.3.1 PMIx_Connect

Summary

Connect namespaces.

1	Format C
2 3 4	<pre>pmix_status_t PMIx_Connect(const pmix_proc_t procs[], size_t nprocs,</pre>
5 6 7 8 9 0 1	IN procs Array of proc structures (array of handles) IN nprocs Number of elements in the procs array (integer) IN info Array of info structures (array of handles) IN ninfo Number of elements in the info array (integer)
3	Returns PMIX_SUCCESS or a negative value corresponding to a PMIx error constant. Required Attributes
4 5	PMIx libraries are not required to directly support any attributes for this function. However, any provided attributes must be passed to the host SMS daemon for processing.
	▼ Optional Attributes
6	The following attributes are optional for PMIx implementations:
7 8	PMIX_ALL_CLONES_PARTICIPATE "pmix.clone.part" (bool) All <i>clones</i> of the calling process must participate in the collective operation.
9	The following attributes are optional for host environments that support this operation:
20 21 22 23	PMIX_TIMEOUT "pmix.timeout" (int) Time in seconds before the specified operation should time out (zero indicating infinite) and return the PMIX_ERR_TIMEOUT error. Care should be taken to avoid race conditions caused by multiple layers (client, server, and host) simultaneously timing the operation.

1 Description

Record the processes specified by the *procs* array as *connected* as per the PMIx definition. The function will return once all processes identified in *procs* have called either PMIx_Connect or its non-blocking version, *and* the host environment has completed any supporting operations required to meet the terms of the PMIx definition of *connected* processes.

A process can only engage in one connect operation involving the identical *procs* array at a time. However, a process can be simultaneously engaged in multiple connect operations, each involving a different *procs* array.

As in the case of the **PMIx_Fence** operation, the *info* array can be used to pass user-level directives regarding timeout constraints and other options available from the host RM.

Advice to users –

All processes engaged in a given **PMIx_Connect** operation must provide the identical *procs* array as ordering of entries in the array and the method by which those processes are identified (e.g., use of **PMIX_RANK_WILDCARD** versus listing the individual processes) *may* impact the host environment's algorithm for uniquely identifying an operation.

-Advice to PMIx library implementers-

PMIx_Connect and its non-blocking form are both *collective* operations. Accordingly, the PMIx server library is required to aggregate participation by local clients, passing the request to the host environment once all local participants have executed the API.

-Advice to PMIx server hosts-

The host will receive a single call for each collective operation. It is the responsibility of the host to identify the nodes containing participating processes, execute the collective across all participating nodes, and notify the local PMIx server library upon completion of the global collective.

11.3.2 PMIx_Connect_nb

Summary

Nonblocking **PMIx_Connect_nb** routine.

1	Format C
2 3 4 5	<pre>pmix_status_t PMIx_Connect_nb(const pmix_proc_t procs[], size_t nprocs,</pre>
6 7 8 9 10 11 12 13 14 15 16	 IN procs Array of proc structures (array of handles) IN nprocs Number of elements in the procs array (integer) IN info Array of info structures (array of handles) IN ninfo Number of elements in the info array (integer) IN cbfunc Callback function pmix_op_cbfunc_t (function reference) IN cbdata Data to be passed to the callback function (memory reference)
18 19 20 21	Returns one of the following: • PMIX_SUCCESS, indicating that the request is being processed by the host environment - result will be returned in the provided <i>cbfunc</i> . Note that the library must not invoke the callback function prior to returning from the API.
22 23 24 25	 PMIX_OPERATION_SUCCEEDED, indicating that the request was immediately processed and returned success - the cbfunc will not be called a PMIx error constant indicating either an error in the input or that the request was immediately processed and failed - the cbfunc will not be called Required Attributes
26 27	PMIx libraries are not required to directly support any attributes for this function. However, any provided attributes must be passed to the host SMS daemon for processing. Optional Attributes
28	The following attributes are optional for PMIx implementations:
29 30	PMIX_ALL_CLONES_PARTICIPATE "pmix.clone.part" (bool) All clones of the calling process must participate in the collective operation.
31	The following attributes are optional for host environments that support this operation:
32 33 34 35	PMIX_TIMEOUT "pmix.timeout" (int) Time in seconds before the specified operation should time out (zero indicating infinite) and return the PMIX_ERR_TIMEOUT error. Care should be taken to avoid race conditions caused by multiple layers (client, server, and host) simultaneously timing the operation.

1 2 3 4 5		Description Nonblocking version of PMIx_Connect. The callback function is called once all processes identified in <i>procs</i> have called either PMIx_Connect or its non-blocking version, <i>and</i> the host environment has completed any supporting operations required to meet the terms of the PMIx definition of <i>connected</i> processes. See the advice provided in the description for PMIx_Connect for more information.
6	11.3.3	PMIx_Disconnect
7 8		Summary Disconnect a previously connected set of processes.
9	PMIx v1.0	Format C
10 11 12		<pre>pmix_status_t PMIx_Disconnect(const pmix_proc_t procs[], size_t nprocs,</pre>
13 14 15 16 17 18 19 20		IN procs Array of proc structures (array of handles) IN nprocs Number of elements in the procs array (integer) IN info Array of info structures (array of handles) IN ninfo Number of elements in the info array (integer)
21		Returns one of the following:
22		• PMIX_SUCCESS, indicating that the request was successfully executed
23 24		 the PMIX_ERR_INVALID_OPERATION error indicating that the specified set of procs was not previously connected via a call to PMIx_Connect or its non-blocking form.
25		• a PMIx error constant indicating either an error in the input or that the request failed
		▼
26 27		PMIx libraries are not required to directly support any attributes for this function. However, any provided attributes must be passed to the host SMS daemon for processing.

Optional Attributes

The following attributes are optional for PMIx implementations:

PMIX_ALL_CLONES_PARTICIPATE "pmix.clone.part" (bool)

All *clones* of the calling process must participate in the collective operation.

The following attributes are optional for host environments that support this operation:

PMIX_TIMEOUT "pmix.timeout" (int)

Time in seconds before the specified operation should time out (zero indicating infinite) and return the **PMIX_ERR_TIMEOUT** error. Care should be taken to avoid race conditions caused by multiple layers (client, server, and host) simultaneously timing the operation.

Description

 Disconnect a previously connected set of processes. The function will return once all processes identified in *procs* have called either **PMIx_Disconnect** or its non-blocking version, *and* the host environment has completed any required supporting operations.

A process can only engage in one disconnect operation involving the identical *procs* array at a time. However, a process can be simultaneously engaged in multiple disconnect operations, each involving a different *procs* array.

As in the case of the **PMIx_Fence** operation, the *info* array can be used to pass user-level directives regarding the algorithm to be used for any collective operation involved in the operation, timeout constraints, and other options available from the host RM.

------ Advice to users -

All processes engaged in a given **PMIx_Disconnect** operation must provide the identical *procs* array as ordering of entries in the array and the method by which those processes are identified (e.g., use of **PMIX_RANK_WILDCARD** versus listing the individual processes) *may* impact the host environment's algorithm for uniquely identifying an operation.

-Advice to PMIx library implementers-

PMIx_Disconnect and its non-blocking form are both *collective* operations. Accordingly, the PMIx server library is required to aggregate participation by local clients, passing the request to the host environment once all local participants have executed the API.

-Advice to PMIx server hosts-

The host will receive a single call for each collective operation. The host will receive a single call for each collective operation. It is the responsibility of the host to identify the nodes containing participating processes, execute the collective across all participating nodes, and notify the local PMIx server library upon completion of the global collective.

1 11.3.4 PMIx_Disconnect_nb

2		Summary Nonblocking PMIx_Disconnect routine.
4	PMIx v1.0	Format C
5 6 7 8		<pre>pmix_status_t PMIx_Disconnect_nb(const pmix_proc_t procs[], size_t nprocs,</pre>
9		IN procs Array of proc structures (array of handles)
1 2 3		 IN nprocs Number of elements in the procs array (integer) IN info
14 15		Array of info structures (array of handles) IN ninfo
16 17 18		Number of elements in the <i>info</i> array (integer) IN cbfunc Callback function pmix_op_cbfunc_t (function reference)
19 20		IN cbdata Data to be passed to the callback function (memory reference)
21		Returns one of the following:
22 23 24		• PMIX_SUCCESS, indicating that the request is being processed by the host environment - result will be returned in the provided <i>cbfunc</i> . Note that the library must not invoke the callback function prior to returning from the API.
25 26		• PMIX_OPERATION_SUCCEEDED, indicating that the request was immediately processed and returned success - the cbfunc will not be called
27 28		• a PMIx error constant indicating either an error in the input or that the request was immediately processed and failed - the <i>cbfunc</i> will <i>not</i> be called
		▼ Required Attributes
29 30		PMIx libraries are not required to directly support any attributes for this function. However, any provided attributes must be passed to the host SMS daemon for processing.

Optional Attributes

The following attributes are optional for PMIx implementations:

PMIX_ALL_CLONES_PARTICIPATE "pmix.clone.part" (bool)

All *clones* of the calling process must participate in the collective operation.

The following attributes are optional for host environments that support this operation:

```
PMIX_TIMEOUT "pmix.timeout" (int)
```

Time in seconds before the specified operation should time out (zero indicating infinite) and return the **PMIX_ERR_TIMEOUT** error. Care should be taken to avoid race conditions caused by multiple layers (client, server, and host) simultaneously timing the operation.

Description

Nonblocking **PMIx_Disconnect** routine. The callback function is called either:

- to return the PMIX_ERR_INVALID_OPERATION error indicating that the specified set of procs was not
 previously connected via a call to PMIx_Connect or its non-blocking form;
- to return a PMIx error constant indicating that the operation failed; or
- once all processes identified in *procs* have called either PMIx_Disconnect_nb or its blocking version,
 and the host environment has completed any required supporting operations.

See the advice provided in the description for **PMIx_Disconnect** for more information.

11.4 Process Locality

The relative locality of processes is often used to optimize their interactions with the hardware and other processes. PMIx provides a means by which the host environment can communicate the locality of a given process using the <code>PMIx_server_generate_locality_string</code> to generate an abstracted representation of that value. This provides a human-readable format and allows the client to parse the locality string with a method of its choice that may differ from the one used by the server that generated it.

There are times, however, when relative locality and other PMIx-provided information doesn't include some element required by the application. In these instances, the application may need access to the full description of the local hardware topology. PMIx does not itself generate such descriptions - there are multiple third-party libraries that fulfill that role. Instead, PMIx offers an abstraction method by which users can obtain a pointer to the description. This transparently enables support for different methods of sharing the topology between the host environment (which may well have already generated it prior to local start of application processes) and the clients - e.g., through passing of a shared memory region.

11.4.1 PMIx_Load_topology

Summary

Load the local hardware topology description

1		Format
2		<pre>pmix_status_t PMIx_Load_topology(pmix_topology_t *topo);</pre>
4 5		INOUT topo Address of a pmix_topology_t structure where the topology information is to be loaded (handle)
6 7		Returns PMIX_SUCCESS , indicating that the <i>topo</i> was successfully loaded, or an appropriate PMIx error constant.
8 9 10 11		Description Obtain a pointer to the topology description of the local node. If the <i>source</i> field of the provided <code>pmix_topology_t</code> is set, then the PMIx library must return a description from the specified implementation or else indicate that the implementation is not available by returning the <code>PMIX_ERR_NOT_SUPPORTED</code> error constant.
13 14 15 16		The returned pointer may point to a shared memory region or an actual instance of the topology description. In either case, the description shall be treated as a "read-only" object - attempts to modify the object are likely to fail and return an error. The PMIx library is responsible for performing any required cleanup when the client library finalizes.
		Advice to users
17 18 19		It is the responsibility of the user to ensure that the <i>topo</i> argument is properly initialized prior to calling this API, and to check the returned <i>source</i> to verify that the returned topology description is compatible with the user's code.
20	11.4.2	PMIx_Get_relative_locality
21 22		Summary Get the relative locality of two local processes given their locality strings.
23	PMIx v4.0	Format C
24 25 26 27		<pre>pmix_status_t PMIx_Get_relative_locality(const char *locality1,</pre>
28 29 30 31 32 33		IN locality1 String returned by the PMIx_server_generate_locality_string API (handle) IN locality2 String returned by the PMIx_server_generate_locality_string API (handle) INOUT locality Location where the relative locality bitmask is to be constructed (memory reference)
34 35		Returns PMIX_SUCCESS , indicating that the <i>locality</i> was successfully loaded, or an appropriate PMIx error constant.

```
Description
 1
 2
                Parse the locality strings of two processes (as returned by PMIx_Get using the PMIX_LOCALITY_STRING
 3
                key) and set the appropriate pmix_locality_t locality bits in the provided memory location.
      11.4.2.1 Topology description
 4
 5
                The pmix topology t structure contains a (case-insensitive) string identifying the source of the topology
 6
                (e.g., "hwloc") and a pointer to the corresponding implementation-specific topology description.
   PMIx v4.0
 7
                typedef struct pmix_topology {
 8
                     char *source;
 9
                     void *topology;
10
                } pmix_topoology_t;
      11.4.2.2 Topology support macros
11
12
                The following macros support the pmix_topology_t structure.
                Static initializer for the topology structure
13
14
                (Provisional)
                Provide a static initializer for the pmix topology t fields.
15
   PMIx v4.2
16
                PMIX_TOPOLOGY_STATIC_INIT
17
                Initialize the topology structure
                Initialize the pmix topology t fields to NULL
18
   PMIx v4.0
19
                PMIX TOPOLOGY CONSTRUCT (m)
                IN
20
21
                     Pointer to the structure to be initialized (pointer to pmix_topology_t)
                Destruct a topology structure
22
23
                Summary
24
                Destruct a pmix_topology_t fields
25 <sub>PMIx v4.2</sub>
                Format
26
27
                PMIx Topology destruct(pmix topology t *topo);
                IN
28
                     topo
29
                     Pointer to the structure to be destructed (pointer to pmix_topology_t)
```

Description 1 2 Release any memory storage held by the pmix_topology_t structure Create a topology array 3 Allocate and initialize a pmix_topology_t array. 4 PMIx v4.0 5 PMIX_TOPOLOGY_CREATE(m, n) 6 INOUT m 7 Address where the pointer to the array of **pmix_topology_t** structures shall be stored (handle) 8 IN 9 Number of structures to be allocated (size_t) 11.4.2.3 Relative locality of two processes PMIx v4.0 The pmix_locality_t datatype is a uint16_t bitmask that defines the relative locality of two processes 12 on a node. The following constants represent specific bits in the mask and can be used to test a locality value 13 using standard bit-test methods. 14 PMIX_LOCALITY_UNKNOWN All bits are set to zero, indicating that the relative locality of the two 15 processes is unknown 16 PMIX_LOCALITY_NONLOCAL The two processes do not share any common locations 17 PMIX_LOCALITY_SHARE_HWTHREAD The two processes share at least one hardware thread 18 PMIX_LOCALITY_SHARE_CORE The two processes share at least one core 19 PMIX_LOCALITY_SHARE_L1CACHE The two processes share at least an L1 cache 20 PMIX LOCALITY SHARE L2CACHE The two processes share at least an L2 cache 21 PMIX_LOCALITY_SHARE_L3CACHE The two processes share at least an L3 cache 22 PMIX LOCALITY SHARE PACKAGE The two processes share at least a package 23 PMIX LOCALITY SHARE NUMA The two processes share at least one Non-Uniform Memory 24 Access (NUMA) region 25 PMIX LOCALITY SHARE NODE The two processes are executing on the same node 26 Implementers and vendors may choose to extend these definitions as needed to describe a particular system. 11.4.2.4 Locality keys 27 28 PMIX_LOCALITY_STRING "pmix.locstr" (char*) 29 String describing a process's bound location - referenced using the process's rank. The string is prefixed by the implementation that created it (e.g., "hwloc") followed by a colon. The remainder of the 30 31 string represents the corresponding locality as expressed by the underlying implementation. The entire 32 string must be passed to PMIx_Get_relative_locality for processing. Note that hosts are 33 only required to provide locality strings for local client processes - thus, a call to PMIx_Get for the 34 locality string of a process that returns PMIX ERR NOT FOUND indicates that the process is not 35 executing on the same node.

11.4.3 PMIx_Parse_cpuset_string

Summary

36

37

38

Parse the PU binding bitmap from its string representation.

```
Format
 1
 2
                 pmix status t
                 PMIx_Parse_cpuset_string(const char *cpuset_string,
 3
 4
                                                 pmix_cpuset_t *cpuset);
                                                                \mathsf{c} —
 5
                 IN
                      cpuset_string
 6
                      String returned by the PMIx server generate cpuset string API (handle)
 7
                 INOUT cpuset
 8
                      Address of an object where the bitmap is to be stored (memory reference)
 9
                 Returns PMIX_SUCCESS, indicating that the cpuset was successfully loaded, or an appropriate PMIx error
10
                 constant.
                 Description
11
12
                 Parse the string representation of the binding bitmap (as returned by PMIx Get using the PMIX CPUSET
13
                 key) and set the appropriate PU binding location information in the provided memory location.
      11.4.4 PMIx_Get_cpuset
14
15
                 Summary
16
                 Get the PU binding bitmap of the current process.
17 <sub>PMIx v4.0</sub>
                 Format
18
                 pmix status t
19
                 PMIx_Get_cpuset(pmix_cpuset_t *cpuset, pmix_bind_envelope_t ref);
20
                 INOUT cpuset
21
                      Address of an object where the bitmap is to be stored (memory reference)
22
                 IN
                      The binding envelope to be considered when formulating the bitmap (pmix_bind_envelope_t)
23
24
                 Returns PMIX SUCCESS, indicating that the cpuset was successfully loaded, or an appropriate PMIx error
25
                 constant.
26
                 Description
27
                 Obtain and set the appropriate PU binding location information in the provided memory location based on the
                 specified binding envelope.
28
      11.4.4.1 Binding envelope
29
  PMIx v4.0
30
                 The pmix_bind_envelope_t data type defines the envelope of threads within a possibly multi-threaded
31
                 process that are to be considered when getting the cpuset associated with the process. Valid values include:
32
                 PMIX CPUBIND PROCESS
                                               Use the location of all threads in the possibly multi-threaded process.
33
                 PMIX_CPUBIND_THREAD
                                              Use only the location of the thread calling the API.
```

11.4.5 PMIx_Compute_distances

Summary

Compute distances from specified process location to local devices.

PMIx v4.0

1

2

3

5

6

7

8

9

10

11

12

13

14 15

16 17

18

19 20

21

22

23

24 25

26

27

28 29

30

31

32

33 34

```
Format
```

C

IN topo

Pointer to the topology description of the node where the process is located (**NULL** indicates the local node) (**pmix_topology_t**)

IN cpuset

Pointer to the location of the process (pmix cpuset t)

IN info

Array of **pmix_info_t** describing the devices whose distance is to be computed (handle)

IN ninfo

Number of elements in *info* (integer)

INOUT distances

Pointer to an address where the array of **pmix_device_distance_t** structures containing the distances from the caller to the specified devices is to be returned (handle)

INOUT ndist

Pointer to an address where the number of elements in the distances array is to be returned (handle)

Returns one of the following:

- PMIX SUCCESS indicating that the distances were returned.
- a non-zero PMIx error constant indicating the reason the request failed.

Description

Both the minimum and maximum distance fields in the elements of the array shall be filled with the respective distances between the current process location and the types of devices or specific device identified in the *info* directives. In the absence of directives, distances to all supported device types shall be returned.

——— Advice to users ———

A process whose threads are not all bound to the same location may return inconsistent results from calls to this API by different threads if the **PMIX_CPUBIND_THREAD** binding envelope was used when generating the *cpuset*.

11.4.6 PMIx Compute distances nb

2 Summary 3 Compute distances from specified process location to local devices. 4 *PMIx v4.0* Format 5 pmix_status t 6 PMIx_Compute_distances_nb(pmix_topology_t *topo, 7 pmix_cpuset_t *cpuset, 8 pmix_info_t info[], size_t ninfo[], 9 pmix_device_dist_cbfunc_t cbfunc, 10 void *cbdata); IN 11 topo Pointer to the topology description of the node where the process is located (NULL indicates the local 12 13 node) (pmix_topology_t) cpuset 14 IN 15 Pointer to the location of the process (pmix cpuset t) 16 IN 17 Array of pmix info t describing the devices whose distance is to be computed (handle) 18 ninfo 19 Number of elements in *info* (integer) 20 IN cbfunc 21 Callback function **pmix** info **cbfunc** t (function reference) 22 IN Data to be passed to the callback function (memory reference) 23 24 Returns one of the following: 25 • PMIX SUCCESS indicating that the request has been accepted for processing and the provided callback function will be executed upon completion of the operation. Note that the library must not invoke the 26 27 callback function prior to returning from the API. 28 • a non-zero PMIx error constant indicating a reason for the request to have been rejected. In this case, the 29 provided callback function will not be executed Description 30 Non-blocking form of the PMIx_Compute_distances API. 31 32

Device Distance Callback Function 11.4.7

```
33
                Summary
34
                The pmix device dist cbfunc t is used to return an array of device distances.
   PMIx v4.0
```

```
1
                typedef void (*pmix device dist_cbfunc_t)
 2
                      (pmix_status_t status,
 3
                       pmix_device_distance_t *dist,
 4
                       size_t ndist,
 5
                       void *cbdata,
 6
                       pmix_release_cbfunc_t release_fn,
 7
                       void *release_cbdata);
 8
                      status
 9
                      Status associated with the operation (pmix status t)
10
                IN
                      Array of pmix device distance t returned by the operation (pointer)
11
12
                IN
                      ndist
13
                      Number of elements in the dist array (size_t)
                IN
                      cbdata
14
                      Callback data passed to original API call (memory reference)
15
16
                IN
                      release fn
17
                      Function to be called when done with the dist data (function pointer)
                IN
                      release cbdata
18
                      Callback data to be passed to release_fn (memory reference)
19
                Description
20
21
                The status indicates if requested data was found or not. The array of pmix_device_distance_t will
                contain the distance information.
22
      11.4.8
                  Device type
23
24
                The pmix device type t is a uint 64 t bitmask for identifying the type(s) whose distances are being
                requested, or the type of a specific device being referenced (e.g., in a pmix_device_distance_t object).
25
    PMIx v1.0
26
                typedef uint16_t pmix_device_type_t;
27
                The following constants can be used to set a variable of the type pmix device type t.
28
                                               The device is of an unknown type - will not be included in returned device
                PMIX DEVTYPE UNKNOWN
29
                      distances.
30
                PMIX DEVTYPE BLOCK
                                            Operating system block device, or non-volatile memory device (e.g., "sda" or
31
                      "dax2.0" on Linux).
32
                PMIX DEVTYPE GPU
                                         Operating system Graphics Processing Unit (GPU) device (e.g., "card0" for a
33
                      Linux Direct Rendering Manager (DRM) device).
34
                PMIX DEVTYPE NETWORK
                                               Operating system network device (e.g., the "eth0" interface on Linux).
35
                PMIX DEVTYPE OPENFABRICS
                                                    Operating system OpenFabrics device (e.g., an "mlx4_0" InfiniBand
36
                      Host Channel Adapter (HCA), or "hfi1_0" Omni-Path interface on Linux).
```

```
1 PMIX_DEVTYPE_DMA Operating system Direct Memory Access (DMA) engine device (e.g., the
2 "dma0chan0" DMA channel on Linux).
3 PMIX_DEVTYPE_COPROC Operating system co-processor device (e.g., "mic0" for a Xeon Phi on Linux,
4 "opencl0d0" for a OpenCL device, or "cuda0" for a Compute Unified Device Architecture (CUDA)
5 device).
```

11.4.9 Device Distance Structure

} pmix_device_distance_t;

7 The pmix device distance t structure contains the minimum and maximum relative distance from 8 the caller to a given device. PMIx v4.0 9 typedef struct pmix_device_distance { 10 char *uuid: 11 char *osname; 12 pmix_device_type_t type; 13 uint16_t mindist; uint16_t maxdist; 14

The *uuid* is a string identifier guaranteed to be unique within the cluster and is typically assembled from discovered device attributes (e.g., the Internet Protocol (IP) address of the device). The *osname* is the local operating system name of the device and is only unique to that node.

The two distance fields provide the minimum and maximum relative distance to the device from the specified location of the process, expressed as a 16-bit integer value where a smaller number indicates that this device is closer to the process than a device with a larger distance value. Note that relative distance values are not necessarily correlated to a physical property - e.g., a device at twice the distance from another device does not necessarily have twice the latency for communication with it.

Relative distances only apply to similar devices and cannot be used to compare devices of different types. Both minimum and maximum distances are provided to support cases where the process may be bound to more than one location, and the locations are at different distances from the device.

A relative distance value of **UINT16_MAX** indicates that the distance from the process to the device could not be provided. This may be due to lack of available information (e.g., the PMIx library not having access to device locations) or other factors.

11.4.10 Device distance support macros

The following macros are provided to support the **pmix_device_distance_t** structure.

6

15

16

17

18 19

20

21

22

23

24

25

26

27

28

29



Release an device distance array 1 2 Release an array of **pmix_device_distance_t** structures. PMIX_DEVICE_DIST_FREE(m, n) 3 4 IN 5 Pointer to the array of pmix_device_distance_t structures (handle) 6 IN 7 Number of structures in the array (size_t) **Device distance attributes** 11.4.11 8 9 The following attributes can be used to retrieve device distances from the PMIx data store. Note that distances 10 stored by the host environment are based on the process location at the time of start of execution and may not reflect changes to location imposed by the process itself. PMIX_DEVICE_DISTANCES 11 12 "pmix.dev.dist" (pmix_data_array_t) 13 Return an array of pmix device distance t containing the minimum and maximum distances 14 of the given process location to all devices of the specified type on the local node.

Bitmask specifying the type(s) of device(s) whose information is being requested. Only used as a directive/qualifier.

PMIX_DEVICE_ID "pmix.dev.id" (string)

System-wide Universally Unique IDentifier (UUID) or node-local Operating System (OS) name of a particular device.

15

16

17

18

CHAPTER 12

1

6

7

8

10

11

12 13

14

16

24 25

26

27

Job Management and Reporting

2 3		with the SMS. Members of this category include the PMIx_Allocation_request, PMIx_Job_control, and PMIx_Process_monitor APIs.
4	12.1	Allocation Requests
5		This section defines functionality to request new allocations from the RM, and request modifications to

This section defines functionality to request new allocations from the RM, and request modifications to existing allocations. These are primarily used in the following scenarios:

The job management APIs provide an application with the ability to orchestrate its operation in partnership

- Evolving applications that dynamically request and return resources as they execute.
- *Malleable* environments where the scheduler redirects resources away from executing applications for higher priority jobs or load balancing.
- Resilient applications that need to request replacement resources in the face of failures.
- *Rigid* jobs where the user has requested a static allocation of resources for a fixed period of time, but realizes that they underestimated their required time while executing.
- PMIx attempts to address this range of use-cases with a flexible API.

12.1.1 PMIx Allocation request

15 **Summary**

Request an allocation operation from the host resource manager.

```
Format
17
    PMIx v3.0
18
              pmix_status_t
19
              PMIx Allocation request (pmix alloc directive t directive,
20
                                        pmix info t info[], size t ninfo,
21
                                        pmix_info_t *results[], size_t *nresults);
22
              IN
                  directive
23
                  Allocation directive (pmix_alloc_directive_t)
```

- Allocation directive (pmix_alloc_directive_t)

 IN info
 Array of pmix_info_t structures (array of handles)

 IN ninfo
 - Number of elements in the info array (integer)

1 2 3 4 5	 INOUT results Address where a pointer to an array of pmix_info_t containing the results of the request can be returned (memory reference) INOUT nresults Address where the number of elements in results can be returned (handle)
6	Returns one of the following:
7	 PMIX_SUCCESS, indicating that the request was processed and returned success
8	• a PMIx error constant indicating either an error in the input or that the request was refused
	▼ Required Attributes
9 10 11	PMIx libraries are not required to directly support any attributes for this function. However, any provided attributes must be passed to the host SMS daemon for processing, and the PMIx library is <i>required</i> to add the PMIX_USERID and the PMIX_GRPID attributes of the client process making the request.
12	Host environments that implement support for this operation are required to support the following attributes:
13 14 15	<pre>PMIX_ALLOC_REQ_ID "pmix.alloc.reqid" (char*) User-provided string identifier for this allocation request which can later be used to query status of the request.</pre>
16 17	<pre>PMIX_ALLOC_NUM_NODES "pmix.alloc.nnodes" (uint64_t) The number of nodes being requested in an allocation request.</pre>
18 19	PMIX_ALLOC_NUM_CPUS "pmix.alloc.ncpus" (uint64_t) Number of PUs being requested in an allocation request.
20 21	PMIX_ALLOC_TIME "pmix.alloc.time" (uint32_t) Total session time (in seconds) being requested in an allocation request.
	→ Optional Attributes
22	The following attributes are optional for host environments that support this operation:
23 24	<pre>PMIX_ALLOC_NODE_LIST "pmix.alloc.nlist" (char*) Regular expression of the specific nodes being requested in an allocation request.</pre>
25 26	<pre>PMIX_ALLOC_NUM_CPU_LIST "pmix.alloc.ncpulist" (char*) Regular expression of the number of PUs for each node being requested in an allocation request.</pre>
27 28	<pre>PMIX_ALLOC_CPU_LIST "pmix.alloc.cpulist" (char*) Regular expression of the specific PUs being requested in an allocation request.</pre>
29 30	PMIX_ALLOC_MEM_SIZE "pmix.alloc.msize" (float) Number of Megabytes[base2] of memory (per process) being requested in an allocation request.
31 32 33 34	<pre>PMIX_ALLOC_FABRIC "pmix.alloc.net" (array) Array of pmix_info_t describing requested fabric resources. This must include at least: PMIX_ALLOC_FABRIC_ID, PMIX_ALLOC_FABRIC_TYPE, and PMIX_ALLOC_FABRIC_ENDPTS, plus whatever other descriptors are desired.</pre>

PMIX_ALLOC_FABRIC_ID "pmix.alloc.netid" (char*)

Description

1

2

3

4

5

6

7

8

9

10

11

12 13

14

15

16

17

18

19

20 21

22

23

24

25 26

27

28

29

30 31

32

33 34

35

36 37

38

39

40

Request an allocation operation from the host resource manager. Several broad categories are envisioned, including the ability to:

- Request allocation of additional resources, including memory, bandwidth, and compute. This should be accomplished in a non-blocking manner so that the application can continue to progress while waiting for resources to become available. Note that the new allocation will be disjoint from (i.e., not affiliated with) the allocation of the requestor thus the termination of one allocation will not impact the other.
- Extend the reservation on currently allocated resources, subject to scheduling availability and priorities. This includes extending the time limit on current resources, and/or requesting additional resources be allocated to the requesting job. Any additional allocated resources will be considered as part of the current allocation, and thus will be released at the same time.
- Return no-longer-required resources to the scheduler. This includes the "loan" of resources back to the scheduler with a promise to return them upon subsequent request.

1 If successful, the returned results for a request for additional resources must include the host resource 2 manager's identifier (PMIX ALLOC ID) that the requester can use to specify the resources in, for example, a 3 call to PMIx Spawn. 12.1.2 PMIx Allocation request nb 4 Summarv 5 6 Request an allocation operation from the host resource manager. $7_{PMIx v2.0}$ 8 pmix_status_t 9 PMIx Allocation_request_nb(pmix_alloc_directive_t directive, pmix_info_t info[], size_t ninfo, 10 11 pmix_info_cbfunc_t cbfunc, void *cbdata); 12 IN directive 13 Allocation directive (pmix alloc directive t) IN 14 15 Array of **pmix_info_t** structures (array of handles) 16 IN ninfo 17 Number of elements in the *info* array (integer) 18 cbfunc 19 Callback function pmix_info_cbfunc_t (function reference) 20 IN 21 Data to be passed to the callback function (memory reference) 22 Returns one of the following: 23 • PMIX SUCCESS, indicating that the request is being processed by the host environment - result will be 24 returned in the provided cbfunc. Note that the library must not invoke the callback function prior to 25 returning from the API. 26 • PMIX OPERATION SUCCEEDED, indicating that the request was immediately processed and returned 27 success - the cbfunc will not be called 28 • a PMIx error constant indicating either an error in the input or that the request was immediately processed 29 and failed - the cbfunc will not be called _____ Required Attributes PMIx libraries are not required to directly support any attributes for this function. However, any provided 30 31 attributes must be passed to the host SMS daemon for processing, and the PMIx library is required to add the 32 PMIX_USERID and the PMIX_GRPID attributes of the client process making the request. 33 Host environments that implement support for this operation are required to support the following attributes:

192 PMIx Standard – Version 4.2rc2 – April 2024

request.

PMIX_ALLOC_REQ_ID "pmix.alloc.reqid" (char*)

User-provided string identifier for this allocation request which can later be used to query status of the

34

35

```
1
                PMIX_ALLOC_NUM_NODES "pmix.alloc.nnodes" (uint64_t)
 2
                       The number of nodes being requested in an allocation request.
 3
                PMIX_ALLOC_NUM_CPUS "pmix.alloc.ncpus" (uint64_t)
 4
                       Number of PUs being requested in an allocation request.
 5
                PMIX ALLOC TIME "pmix.alloc.time" (uint32 t)
 6
                       Total session time (in seconds) being requested in an allocation request.
                   ----- Optional Attributes -----
 7
                The following attributes are optional for host environments that support this operation:
 8
                PMIX_ALLOC_NODE_LIST "pmix.alloc.nlist" (char*)
 9
                       Regular expression of the specific nodes being requested in an allocation request.
10
                PMIX ALLOC NUM CPU LIST "pmix.alloc.ncpulist" (char*)
11
                       Regular expression of the number of PUs for each node being requested in an allocation request.
12
                PMIX_ALLOC_CPU_LIST "pmix.alloc.cpulist" (char*)
13
                       Regular expression of the specific PUs being requested in an allocation request.
14
                PMIX ALLOC MEM SIZE "pmix.alloc.msize" (float)
15
                       Number of Megabytes[base2] of memory (per process) being requested in an allocation request.
16
                PMIX_ALLOC_FABRIC "pmix.alloc.net" (array)
17
                       Array of pmix info t describing requested fabric resources. This must include at least:
18
                       PMIX ALLOC FABRIC ID, PMIX ALLOC FABRIC TYPE, and
19
                       PMIX ALLOC FABRIC ENDPTS, plus whatever other descriptors are desired.
20
                PMIX_ALLOC_FABRIC_ID "pmix.alloc.netid" (char*)
21
                       The key to be used when accessing this requested fabric allocation. The fabric allocation will be
22
                       returned/stored as a pmix_data_array_t of pmix_info_t whose first element is composed of
23
                       this key and the allocated resource description. The type of the included value depends upon the fabric
24
                       support. For example, a TCP allocation might consist of a comma-delimited string of socket ranges
25
                       such as "32000-32100, 33005, 38123-38146". Additional array entries will consist of any
26
                       provided resource request directives, along with their assigned values. Examples include:
27
                       PMIX ALLOC FABRIC TYPE - the type of resources provided; PMIX ALLOC FABRIC PLANE -
28
                       if applicable, what plane the resources were assigned from; PMIX_ALLOC_FABRIC_QOS - the
29
                       assigned QoS; PMIX ALLOC BANDWIDTH - the allocated bandwidth;
30
                       PMIX ALLOC FABRIC SEC KEY - a security key for the requested fabric allocation. NOTE: the
                       array contents may differ from those requested, especially if PMIX_INFO_REQD was not set in the
31
32
                       request.
33
                PMIX_ALLOC_BANDWIDTH "pmix.alloc.bw" (float)
34
                       Fabric bandwidth (in Megabits[base2]/sec) for the job being requested in an allocation request.
                PMIX ALLOC_FABRIC_QOS "pmix.alloc.netqos" (char*)
35
36
                       Fabric quality of service level for the job being requested in an allocation request.
37
                PMIX_ALLOC_FABRIC_TYPE "pmix.alloc.nettype" (char*)
```

```
1
                       Type of desired transport (e.g., "tcp", "udp") being requested in an allocation request.
 2
                PMIX ALLOC FABRIC PLANE "pmix.alloc.netplane" (char*)
 3
                       ID string for the fabric plane to be used for the requested allocation.
                PMIX ALLOC FABRIC ENDPTS "pmix.alloc.endpts" (size_t)
 4
 5
                       Number of endpoints to allocate per process in the job.
 6
                PMIX ALLOC FABRIC ENDPTS NODE "pmix.alloc.endpts.nd" (size t)
 7
                       Number of endpoints to allocate per node for the job.
 8
                PMIX_ALLOC_FABRIC_SEC_KEY "pmix.alloc.nsec" (pmix_byte_object_t)
 9
                       Request that the allocation include a fabric security key for the spawned job.
                Description
10
                Non-blocking form of the PMIx_Allocation_request API.
11
                  Job Allocation attributes
      12.1.3
12
13
                Attributes used to describe the job allocation - these are values passed to and/or returned by the
14
                PMIx_Allocation_request_nb and PMIx_Allocation_request APIs and are not accessed
15
                using the PMIx Get API.
16
                PMIX_ALLOC_REQ_ID "pmix.alloc.reqid" (char*)
17
                       User-provided string identifier for this allocation request which can later be used to query status of the
18
                       request.
19
                PMIX ALLOC ID "pmix.alloc.id" (char*)
20
                       A string identifier (provided by the host environment) for the resulting allocation which can later be
21
                       used to reference the allocated resources in, for example, a call to PMIx_Spawn.
22
                PMIX ALLOC QUEUE "pmix.alloc.queue" (char*)
23
                       Name of the WLM queue to which the allocation request is to be directed, or the queue being
24
                       referenced in a query.
                PMIX_ALLOC_NUM_NODES "pmix.alloc.nnodes" (uint64_t)
25
26
                       The number of nodes being requested in an allocation request.
27
                PMIX_ALLOC_NODE_LIST "pmix.alloc.nlist" (char*)
28
                       Regular expression of the specific nodes being requested in an allocation request.
29
                PMIX_ALLOC_NUM_CPUS "pmix.alloc.ncpus" (uint64_t)
30
                       Number of PUs being requested in an allocation request.
                PMIX_ALLOC_NUM_CPU_LIST "pmix.alloc.ncpulist" (char*)
31
32
                       Regular expression of the number of PUs for each node being requested in an allocation request.
33
                PMIX_ALLOC_CPU_LIST "pmix.alloc.cpulist" (char*)
                       Regular expression of the specific PUs being requested in an allocation request.
34
35
                PMIX_ALLOC_MEM_SIZE "pmix.alloc.msize" (float)
36
                       Number of Megabytes[base2] of memory (per process) being requested in an allocation request.
37
                PMIX_ALLOC_FABRIC "pmix.alloc.net" (array)
```

```
1
                        Array of pmix_info_t describing requested fabric resources. This must include at least:
 2
                        PMIX ALLOC FABRIC ID, PMIX ALLOC FABRIC TYPE, and
 3
                        PMIX_ALLOC_FABRIC_ENDPTS, plus whatever other descriptors are desired.
 4
                 PMIX_ALLOC_FABRIC_ID "pmix.alloc.netid" (char*)
 5
                        The key to be used when accessing this requested fabric allocation. The fabric allocation will be
 6
                        returned/stored as a pmix_data_array_t of pmix_info_t whose first element is composed of
 7
                        this key and the allocated resource description. The type of the included value depends upon the fabric
 8
                        support. For example, a TCP allocation might consist of a comma-delimited string of socket ranges
 9
                        such as "32000-32100, 33005, 38123-38146". Additional array entries will consist of any
10
                        provided resource request directives, along with their assigned values. Examples include:
11
                        PMIX_ALLOC_FABRIC_TYPE - the type of resources provided; PMIX_ALLOC_FABRIC_PLANE -
                        if applicable, what plane the resources were assigned from; PMIX ALLOC FABRIC QOS - the
12
13
                        assigned QoS; PMIX_ALLOC_BANDWIDTH - the allocated bandwidth;
14
                        PMIX ALLOC FABRIC SEC KEY - a security key for the requested fabric allocation. NOTE: the
15
                        array contents may differ from those requested, especially if PMIX INFO REOD was not set in the
16
                        request.
17
                 PMIX_ALLOC_BANDWIDTH "pmix.alloc.bw" (float)
18
                        Fabric bandwidth (in Megabits[base2]/sec) for the job being requested in an allocation request.
19
                 PMIX ALLOC FABRIC QOS "pmix.alloc.netgos" (char*)
20
                        Fabric quality of service level for the job being requested in an allocation request.
21
                 PMIX_ALLOC_TIME "pmix.alloc.time" (uint32_t)
22
                        Total session time (in seconds) being requested in an allocation request.
23
                 PMIX_ALLOC_FABRIC_TYPE "pmix.alloc.nettype" (char*)
24
                        Type of desired transport (e.g., "tcp", "udp") being requested in an allocation request.
25
                 PMIX_ALLOC_FABRIC_PLANE "pmix.alloc.netplane" (char*)
26
                        ID string for the fabric plane to be used for the requested allocation.
27
                 PMIX_ALLOC_FABRIC_ENDPTS "pmix.alloc.endpts" (size_t)
28
                        Number of endpoints to allocate per process in the job.
29
                 PMIX ALLOC FABRIC ENDPTS NODE "pmix.alloc.endpts.nd" (size t)
30
                        Number of endpoints to allocate per node for the job.
31
                 PMIX_ALLOC_FABRIC_SEC_KEY "pmix.alloc.nsec" (pmix_byte_object_t)
32
                        Request that the allocation include a fabric security key for the spawned job.
      12.1.4
                  Job Allocation Directives
33
    PMIx v2.0
34
                 The pmix_alloc_directive_t structure is a uint8_t type that defines the behavior of allocation
35
                 requests. The following constants can be used to set a variable of the type pmix_alloc_directive_t.
                 All definitions were introduced in version 2 of the standard unless otherwise marked.
36
37
                                        A new allocation is being requested. The resulting allocation will be disjoint (i.e.,
                 PMIX ALLOC NEW
38
                      not connected in a job sense) from the requesting allocation.
39
                 PMIX ALLOC EXTEND
                                            Extend the existing allocation, either in time or as additional resources.
40
                 PMIX ALLOC RELEASE
                                             Release part of the existing allocation. Attributes in the accompanying
41
                      pmix_info_t array may be used to specify permanent release of the identified resources, or "lending"
42
                      of those resources for some period of time.
43
                 PMIX ALLOC REAQUIRE
                                              Reacquire resources that were previously "lent" back to the scheduler.
44
                 PMIX ALLOC EXTERNAL
                                              A value boundary above which implementers are free to define their own
```

45

directive values.

12.2 Job Control

This section defines APIs that enable the application and host environment to coordinate the response to failures and other events. This can include requesting termination of the entire job or a subset of processes within a job, but can also be used in combination with other PMIx capabilities (e.g., allocation support and event notification) for more nuanced responses. For example, an application notified of an incipient over-temperature condition on a node could use the PMIx_Allocation_request_nb interface to request replacement nodes while simultaneously using the PMIx_Job_control_nb interface to direct that a checkpoint event be delivered to all processes in the application. If replacement resources are not available, the application might use the PMIx_Job_control_nb interface to request that the job continue at a lower power setting, perhaps sufficient to avoid the over-temperature failure.

The job control APIs can also be used by an application to register itself as available for preemption when operating in an environment such as a cloud or where incentives, financial or otherwise, are provided to jobs willing to be preempted. Registration can include attributes indicating how many resources are being offered for preemption (e.g., all or only some portion), whether the application will require time to prepare for preemption, etc. Jobs that request a warning will receive an event notifying them of an impending preemption (possibly including information as to the resources that will be taken away, how much time the application will be given prior to being preempted, whether the preemption will be a suspension or full termination, etc.) so they have an opportunity to save their work. Once the application is ready, it calls the provided event completion callback function to indicate that the SMS is free to suspend or terminate it, and can include directives regarding any desired restart.

12.2.1 PMIx Job control

Request a job control action.

Summary

```
24 <sub>PMIx v3.0</sub> Format
```

IN targets

Array of proc structures (array of handles)

IN ntargets

Number of elements in the *targets* array (integer)

IN directives

Array of info structures (array of handles)

IN ndirs

Number of elements in the *directives* array (integer)

INOUT results

Address where a pointer to an array of **pmix_info_t** containing the results of the request can be returned (memory reference)

1 2	INOUT nresults Address where the number of elements in <i>results</i> can be returned (handle)
3	Returns one of the following:
4 5	 PMIX_SUCCESS, indicating that the request was processed by the host environment and returned success. Details of the result will be returned in the results array
6	• a PMIx error constant indicating either an error in the input or that the request was refused
	▼ Required Attributes
7 8 9	PMIx libraries are not required to directly support any attributes for this function. However, any provided attributes must be passed to the host SMS daemon for processing, and the PMIx library is <i>required</i> to add the PMIX_USERID and the PMIX_GRPID attributes of the client process making the request.
10	Host environments that implement support for this operation are required to support the following attributes:
11 12 13 14	<pre>PMIX_JOB_CTRL_ID "pmix.jctrl.id" (char*) Provide a string identifier for this request. The user can provide an identifier for the requested operation, thus allowing them to later request status of the operation or to terminate it. The host, therefore, shall track it with the request for future reference.</pre>
15 16	<pre>PMIX_JOB_CTRL_PAUSE "pmix.jctrl.pause" (bool) Pause the specified processes.</pre>
17 18	<pre>PMIX_JOB_CTRL_RESUME "pmix.jctrl.resume" (bool) Resume ("un-pause") the specified processes.</pre>
19 20	PMIX_JOB_CTRL_KILL "pmix.jctrl.kill" (bool) Forcibly terminate the specified processes and cleanup.
21 22	<pre>PMIX_JOB_CTRL_SIGNAL "pmix.jctrl.sig" (int) Send given signal to specified processes.</pre>
23 24	<pre>PMIX_JOB_CTRL_TERMINATE "pmix.jctrl.term" (bool) Politely terminate the specified processes.</pre>
25 26	<pre>PMIX_REGISTER_CLEANUP "pmix.reg.cleanup" (char*) Comma-delimited list of files to be removed upon process termination.</pre>
27 28	<pre>PMIX_REGISTER_CLEANUP_DIR "pmix.reg.cleanupdir" (char*) Comma-delimited list of directories to be removed upon process termination.</pre>
29 30	PMIX_CLEANUP_RECURSIVE "pmix.clnup.recurse" (bool) Recursively cleanup all subdirectories under the specified one(s).
31 32	PMIX_CLEANUP_EMPTY "pmix.clnup.empty" (bool) Only remove empty subdirectories.
33 34	<pre>PMIX_CLEANUP_IGNORE "pmix.clnup.ignore" (char*) Comma-delimited list of filenames that are not to be removed.</pre>
35	PMIX_CLEANUP_LEAVE_TOPDIR "pmix.clnup.lvtop" (bool)

1 When recursively cleaning subdirectories, do not remove the top-level directory (the one given in the 2 cleanup request). **▲**-----**-**Optional Attributes 3 The following attributes are optional for host environments that support this operation: 4 PMIX_JOB_CTRL_CANCEL "pmix.jctrl.cancel" (char*) 5 Cancel the specified request - the provided request ID must match the PMIX JOB CTRL ID 6 provided to a previous call to PMIx_Job_control. An ID of NULL implies cancel all requests from 7 this requestor. 8 PMIX JOB CTRL RESTART "pmix.jctrl.restart" (char*) 9 Restart the specified processes using the given checkpoint ID. PMIX JOB CTRL CHECKPOINT "pmix.jctrl.ckpt" (char*) 10 11 Checkpoint the specified processes and assign the given ID to it. 12 PMIX JOB CTRL CHECKPOINT EVENT "pmix.jctrl.ckptev" (bool) 13 Use event notification to trigger a process checkpoint. 14 PMIX_JOB_CTRL_CHECKPOINT_SIGNAL "pmix.jctrl.ckptsig" (int) 15 Use the given signal to trigger a process checkpoint. PMIX_JOB_CTRL_CHECKPOINT_TIMEOUT "pmix.jctrl.ckptsig" (int) 16 17 Time in seconds to wait for a checkpoint to complete. PMIX_JOB_CTRL_CHECKPOINT_METHOD "pmix.jctrl.ckmethod" (pmix_data_array_t) 18 Array of **pmix** info t declaring each method and value supported by this application. 19 20 PMIX_JOB_CTRL_PROVISION "pmix.jctrl.pvn" (char*) 21 Regular expression identifying nodes that are to be provisioned. 22 PMIX_JOB_CTRL_PROVISION_IMAGE "pmix.jctrl.pvnimg" (char*) Name of the image that is to be provisioned. 23 24 PMIX JOB CTRL PREEMPTIBLE "pmix.jctrl.preempt" (bool) Indicate that the job can be pre-empted. 25 **▲**-----**-**

Description

Request a job control action. The *targets* array identifies the processes to which the requested job control action is to be applied. All *clones* of an identified process are to have the requested action applied to them. A **NULL** value can be used to indicate all processes in the caller's namespace. The use of **PMIX_RANK_WILDCARD** can also be used to indicate that all processes in the given namespace are to be included.

The directives are provided as **pmix_info_t** structures in the *directives* array. The returned *status* indicates whether or not the request was granted, and information as to the reason for any denial of the request shall be returned in the *results* array.

26

27 28

29

30

31

32

12.2.2 PMIx_Job_control_nb

```
2
                 Summary
 3
                 Request a job control action.
 4
                 Format
    PMIx v2.0
 5
                 pmix status t
 6
                 PMIx_Job_control_nb(const pmix_proc_t targets[], size_t ntargets,
 7
                                            const pmix_info_t directives[], size_t ndirs,
 8
                                            pmix_info_cbfunc_t cbfunc, void *cbdata);
                                                        — C
 9
                 IN
                      targets
10
                       Array of proc structures (array of handles)
11
                       ntargets
12
                       Number of elements in the targets array (integer)
13
                 IN
                       directives
14
                       Array of info structures (array of handles)
15
                 IN
                       ndirs
16
                       Number of elements in the directives array (integer)
17
                 IN
                       cbfunc
18
                       Callback function pmix info cbfunc t (function reference)
19
                 IN
20
                       Data to be passed to the callback function (memory reference)
21
                 Returns one of the following:
22
                 • PMIX_SUCCESS, indicating that the request is being processed by the host environment - result will be
23
                    returned in the provided cbfunc. Note that the library must not invoke the callback function prior to
24
                    returning from the API.
25
                 • PMIX OPERATION SUCCEEDED, indicating that the request was immediately processed and returned
26
                    success - the cbfunc will not be called
27
                 • a PMIx error constant indicating either an error in the input or that the request was immediately processed
28
                    and failed - the cbfunc will not be called
                                                       Required Attributes
29
                 PMIx libraries are not required to directly support any attributes for this function. However, any provided
30
                 attributes must be passed to the host SMS daemon for processing, and the PMIx library is required to add the
31
                 PMIX_USERID and the PMIX_GRPID attributes of the client process making the request.
32
                 Host environments that implement support for this operation are required to support the following attributes:
33
                 PMIX_JOB_CTRL_ID "pmix.jctrl.id" (char*)
34
                        Provide a string identifier for this request. The user can provide an identifier for the requested
35
                        operation, thus allowing them to later request status of the operation or to terminate it. The host,
                        therefore, shall track it with the request for future reference.
36
37
                 PMIX_JOB_CTRL_PAUSE "pmix.jctrl.pause" (bool)
```

```
1
                     Pause the specified processes.
 2
               PMIX JOB CTRL RESUME "pmix.jctrl.resume" (bool)
 3
                     Resume ("un-pause") the specified processes.
               PMIX JOB CTRL KILL "pmix.jctrl.kill" (bool)
 4
 5
                     Forcibly terminate the specified processes and cleanup.
 6
               PMIX JOB CTRL SIGNAL "pmix.jctrl.sig" (int)
 7
                     Send given signal to specified processes.
 8
               PMIX JOB CTRL TERMINATE "pmix.jctrl.term" (bool)
 9
                     Politely terminate the specified processes.
10
               PMIX_REGISTER_CLEANUP "pmix.reg.cleanup" (char*)
11
                     Comma-delimited list of files to be removed upon process termination.
               PMIX_REGISTER_CLEANUP_DIR "pmix.reg.cleanupdir" (char*)
12
                     Comma-delimited list of directories to be removed upon process termination.
13
14
               PMIX CLEANUP RECURSIVE "pmix.clnup.recurse" (bool)
15
                     Recursively cleanup all subdirectories under the specified one(s).
               PMIX CLEANUP_EMPTY "pmix.clnup.empty" (bool)
16
17
                     Only remove empty subdirectories.
18
               PMIX_CLEANUP_IGNORE "pmix.clnup.ignore" (char*)
19
                     Comma-delimited list of filenames that are not to be removed.
20
               PMIX_CLEANUP_LEAVE_TOPDIR "pmix.clnup.lvtop" (bool)
21
                     When recursively cleaning subdirectories, do not remove the top-level directory (the one given in the
22
                     cleanup request).
                ▲------
                                               Optional Attributes
                _____
23
               The following attributes are optional for host environments that support this operation:
24
               PMIX JOB CTRL CANCEL "pmix.jctrl.cancel" (char*)
25
                     Cancel the specified request - the provided request ID must match the PMIX_JOB_CTRL_ID
26
                     provided to a previous call to PMIx Job control. An ID of NULL implies cancel all requests from
27
                     this requestor.
28
               PMIX_JOB_CTRL_RESTART "pmix.jctrl.restart" (char*)
29
                     Restart the specified processes using the given checkpoint ID.
30
               PMIX_JOB_CTRL_CHECKPOINT "pmix.jctrl.ckpt" (char*)
31
                     Checkpoint the specified processes and assign the given ID to it.
32
               PMIX JOB CTRL CHECKPOINT EVENT "pmix.jctrl.ckptev" (bool)
33
                     Use event notification to trigger a process checkpoint.
34
               PMIX JOB CTRL CHECKPOINT SIGNAL "pmix.jctrl.ckptsiq" (int)
35
                     Use the given signal to trigger a process checkpoint.
```

```
1
               PMIX_JOB_CTRL_CHECKPOINT_TIMEOUT "pmix.jctrl.ckptsig" (int)
 2
                     Time in seconds to wait for a checkpoint to complete.
 3
               PMIX_JOB_CTRL_CHECKPOINT_METHOD "pmix.jctrl.ckmethod" (pmix_data_array_t)
 4
                     Array of pmix_info_t declaring each method and value supported by this application.
 5
               PMIX_JOB_CTRL_PROVISION "pmix.jctrl.pvn" (char*)
 6
                     Regular expression identifying nodes that are to be provisioned.
 7
               PMIX_JOB_CTRL_PROVISION_IMAGE "pmix.jctrl.pvnimg" (char*)
8
                     Name of the image that is to be provisioned.
9
               PMIX JOB CTRL PREEMPTIBLE "pmix.jctrl.preempt" (bool)
10
                     Indicate that the job can be pre-empted.
11
```

Description

12

13

14

15

16

17

18

19

20 21

22

23

24 25

26

27

28

29

30

31

32

33

34

Non-blocking form of the PMIx_Job_control API. The targets array identifies the processes to which the requested job control action is to be applied. All *clones* of an identified process are to have the requested action applied to them. A NULL value can be used to indicate all processes in the caller's namespace. The use of PMIX RANK WILDCARD can also be used to indicate that all processes in the given namespace are to be included.

The directives are provided as **pmix_info_t** structures in the *directives* array. The callback function provides a status to indicate whether or not the request was granted, and to provide some information as to the reason for any denial in the **pmix_info_cbfunc_t** array of **pmix_info_t** structures.

12.2.3 Job control constants

The following constants are specifically defined for return by the job control APIs:

PMIX ERR_CONFLICTING_CLEANUP_DIRECTIVES Conflicting directives given for job/process cleanup.

12.2.4 Job control events

The following job control events may be available for registration, depending upon implementation and host environment support:

PMIX JCTRL CHECKPOINT Monitored by PMIx client to trigger a checkpoint operation.

PMIX JCTRL CHECKPOINT COMPLETE Sent by a PMIx client and monitored by a PMIx server to notify that requested checkpoint operation has completed.

PMIX JCTRL PREEMPT ALERT Monitored by a PMIx client to detect that an RM intends to preempt the job.

PMIX_ERR_PROC_RESTART Error in process restart.

PMIX_ERR_PROC_CHECKPOINT Error in process checkpoint.

PMIX_ERR_PROC_MIGRATE Error in process migration.

12.2.5 Job control attributes

1	12.2.5	Job control attributes
2		Attributes used to request control operations on an executing application - these are values passed to the job control APIs and are not accessed using the PMIx_Get API.
4 5 6 7		PMIX_JOB_CTRL_ID "pmix.jctrl.id" (char*) Provide a string identifier for this request. The user can provide an identifier for the requested operation, thus allowing them to later request status of the operation or to terminate it. The host, therefore, shall track it with the request for future reference.
8 9		PMIX_JOB_CTRL_PAUSE "pmix.jctrl.pause" (bool) Pause the specified processes.
10 11		PMIX_JOB_CTRL_RESUME "pmix.jctrl.resume" (bool) Resume ("un-pause") the specified processes.
12 13 14 15		PMIX_JOB_CTRL_CANCEL "pmix.jctrl.cancel" (char*) Cancel the specified request - the provided request ID must match the PMIX_JOB_CTRL_ID provided to a previous call to PMIx_Job_control. An ID of NULL implies cancel all requests from this requestor.
16 17		PMIX_JOB_CTRL_KILL "pmix.jctrl.kill" (bool) Forcibly terminate the specified processes and cleanup.
18 19		PMIX_JOB_CTRL_RESTART "pmix.jctrl.restart" (char*) Restart the specified processes using the given checkpoint ID.
20 21		PMIX_JOB_CTRL_CHECKPOINT "pmix.jctrl.ckpt" (char*) Checkpoint the specified processes and assign the given ID to it.
22 23		PMIX_JOB_CTRL_CHECKPOINT_EVENT "pmix.jctrl.ckptev" (bool) Use event notification to trigger a process checkpoint.
24 25		PMIX_JOB_CTRL_CHECKPOINT_SIGNAL "pmix.jctrl.ckptsig" (int) Use the given signal to trigger a process checkpoint.
26 27		PMIX_JOB_CTRL_CHECKPOINT_TIMEOUT "pmix.jctrl.ckptsig" (int) Time in seconds to wait for a checkpoint to complete.
28 29		PMIX_JOB_CTRL_CHECKPOINT_METHOD "pmix.jctrl.ckmethod" (pmix_data_array_t) Array of pmix_info_t declaring each method and value supported by this application.
30 31		PMIX_JOB_CTRL_SIGNAL "pmix.jctrl.sig" (int) Send given signal to specified processes. PMIX_JOB_CTRL_DDOMGJON_"environments to be a constant of the constant
32 33		PMIX_JOB_CTRL_PROVISION "pmix.jctrl.pvn" (char*) Regular expression identifying nodes that are to be provisioned.
34 35 36		PMIX_JOB_CTRL_PROVISION_IMAGE "pmix.jctrl.pvnimg" (char*) Name of the image that is to be provisioned. PMIX_JOB_CTRL_PROFIBER_" pmix_ictrl_procent" (bool)
37 38		PMIX_JOB_CTRL_PREEMPTIBLE "pmix.jctrl.preempt" (bool) Indicate that the job can be pre-empted. PMIX_JOB_CTRL_TERMINATE "pmix.jctrl.term" (bool)
39 40		Politely terminate the specified processes. PMIX_REGISTER_CLEANUP "pmix.reg.cleanup" (char*)
41 42		Comma-delimited list of files to be removed upon process termination.
43		PMIX_REGISTER_CLEANUP_DIR "pmix.reg.cleanupdir" (char*) Comma-delimited list of directories to be removed upon process termination.
44 45		PMIX_CLEANUP_RECURSIVE "pmix.clnup.recurse" (bool) Recursively cleanup all subdirectories under the specified one(s).

1 PMIX_CLEANUP_EMPTY "pmix.clnup.empty" (bool) 2 Only remove empty subdirectories. 3 PMIX_CLEANUP_IGNORE "pmix.clnup.ignore" (char*) 4 Comma-delimited list of filenames that are not to be removed. 5 PMIX_CLEANUP_LEAVE_TOPDIR "pmix.clnup.lvtop" (bool) 6 When recursively cleaning subdirectories, do not remove the top-level directory (the one given in the 7 cleanup request). 12.3 **Process and Job Monitoring** 8 9

In addition to external faults, a common problem encountered in HPC applications is a failure to make progress due to some internal conflict in the computation. These situations can result in a significant waste of resources as the SMS is unaware of the problem, and thus cannot terminate the job. Various watchdog methods have been developed for detecting this situation, including requiring a periodic "heartbeat" from the application and monitoring a specified file for changes in size and/or modification time.

The following APIs allow applications to request monitoring, directing what is to be monitored, the frequency of the associated check, whether or not the application is to be notified (via the event notification subsystem) of stall detection, and other characteristics of the operation.

12.3.1 PMIx Process monitor

Summary

10

11

12 13

14

15

16

17

18

19

29

30

31

32

33

34

35

36

37

38

Request that application processes be monitored.

```
Format
20
   PMIx v3.0
21
             pmix status t
22
             PMIx_Process_monitor(const pmix_info_t *monitor,
23
                                    pmix status t error,
24
                                    const pmix_info_t directives[], size_t ndirs,
25
                                    pmix_info_t *results[], size_t *nresults);
26
             IN
                  monitor
27
                  info (handle)
28
             IN error
```

status (integer)

IN directives

Array of info structures (array of handles)

IN ndirs

Number of elements in the *directives* array (integer)

INOUT results

Address where a pointer to an array of **pmix_info_t** containing the results of the request can be returned (memory reference)

INOUT nresults

Address where the number of elements in results can be returned (handle)

1	Returns one of the following:
2 3	• PMIX_SUCCESS, indicating that the request was processed and returned <i>success</i> . Details of the result will be returned in the <i>results</i> array
4	• a PMIx error constant indicating either an error in the input or that the request was refused
	▼ Optional Attributes
5 6 7 8 9	The following attributes may be implemented by a PMIx library or by the host environment. If supported by the PMIx server library, then the library must not pass the supported attributes to the host environment. All attributes not directly supported by the server library must be passed to the host environment if it supports this operation, and the library is <i>required</i> to add the PMIX_USERID and the PMIX_GRPID attributes of the requesting process:
10 11	<pre>PMIX_MONITOR_ID "pmix.monitor.id" (char*) Provide a string identifier for this request.</pre>
12 13	<pre>PMIX_MONITOR_CANCEL "pmix.monitor.cancel" (char*) Identifier to be canceled (NULL means cancel all monitoring for this process).</pre>
14 15 16 17	PMIX_MONITOR_APP_CONTROL "pmix.monitor.appctrl" (bool) The application desires to control the response to a monitoring event - i.e., the application is requesting that the host environment not take immediate action in response to the event (e.g., terminating the job).
18 19	PMIX_MONITOR_HEARTBEAT "pmix.monitor.mbeat" (void) Register to have the PMIx server monitor the requestor for heartbeats.
20 21	<pre>PMIX_MONITOR_HEARTBEAT_TIME "pmix.monitor.btime" (uint32_t) Time in seconds before declaring heartbeat missed.</pre>
22 23	PMIX_MONITOR_HEARTBEAT_DROPS "pmix.monitor.bdrop" (uint32_t) Number of heartbeats that can be missed before generating the event.
24 25	<pre>PMIX_MONITOR_FILE "pmix.monitor.fmon" (char*) Register to monitor file for signs of life.</pre>
26 27	<pre>PMIX_MONITOR_FILE_SIZE "pmix.monitor.fsize" (bool) Monitor size of given file is growing to determine if the application is running.</pre>
28 29	<pre>PMIX_MONITOR_FILE_ACCESS "pmix.monitor.faccess" (char*)</pre>
30 31	<pre>PMIX_MONITOR_FILE_MODIFY "pmix.monitor.fmod" (char*) Monitor time since last modified of given file to determine if the application is running.</pre>
32 33	<pre>PMIX_MONITOR_FILE_CHECK_TIME "pmix.monitor.ftime" (uint32_t) Time in seconds between checking the file.</pre>
34 35	PMIX_MONITOR_FILE_DROPS "pmix.monitor.fdrop" (uint32_t) Number of file checks that can be missed before generating the event.
36	PMIX_SEND_HEARTBEAT "pmix.monitor.beat" (void)

2 Description

Request that application processes be monitored via several possible methods. For example, that the server monitor this process for periodic heartbeats as an indication that the process has not become "wedged". When a monitor detects the specified alarm condition, it will generate an event notification using the provided error code and passing along any available relevant information. It is up to the caller to register a corresponding event handler.

The *monitor* argument is an attribute indicating the type of monitor being requested. For example, **PMIX MONITOR FILE** to indicate that the requestor is asking that a file be monitored.

The *error* argument is the status code to be used when generating an event notification alerting that the monitor has been triggered. The range of the notification defaults to **PMIX_RANGE_NAMESPACE**. This can be changed by providing a **PMIX_RANGE** directive.

The *directives* argument characterizes the monitoring request (e.g., monitor file size) and frequency of checking to be done

The returned *status* indicates whether or not the request was granted, and information as to the reason for any denial of the request shall be returned in the *results* array.

12.3.2 PMIx Process monitor nb

Summary

Request that application processes be monitored.

```
Format
20
   PMIx v2.0
21
             pmix_status_t
22
             PMIx Process monitor nb (const pmix info t *monitor,
23
                                     pmix_status_t error,
24
                                     const pmix_info_t directives[],
25
                                      size t ndirs,
                                     pmix_info_cbfunc_t cbfunc, void *cbdata);
26
                                         ____ C ____
27
                 monitor
```

```
info (handle)

IN error
status (integer)

IN directives
Array of info structures (array of handles)

IN ndirs
Number of elements in the directives array (integer)

IN cbfunc
Callback function pmix_info_cbfunc_t (function reference)
```

1 2	IN cbdata Data to be passed to the callback function (memory reference)
3	Returns one of the following:
4 5 6	 PMIX_SUCCESS, indicating that the request is being processed by the host environment - result will be returned in the provided <i>cbfunc</i>. Note that the library must not invoke the callback function prior to returning from the API.
7 8	 PMIX_OPERATION_SUCCEEDED, indicating that the request was immediately processed and returned success - the cbfunc will not be called.
9 10	• a PMIx error constant indicating either an error in the input or that the request was immediately processed and failed - the <i>cbfunc</i> will <i>not</i> be called.
	→ Optional Attributes
11 12 13 14 15	The following attributes may be implemented by a PMIx library or by the host environment. If supported by the PMIx server library, then the library must not pass the supported attributes to the host environment. All attributes not directly supported by the server library must be passed to the host environment if it supports this operation, and the library is <i>required</i> to add the PMIX_USERID and the PMIX_GRPID attributes of the requesting process:
16 17	<pre>PMIX_MONITOR_ID "pmix.monitor.id" (char*) Provide a string identifier for this request.</pre>
18 19	<pre>PMIX_MONITOR_CANCEL "pmix.monitor.cancel" (char*) Identifier to be canceled (NULL means cancel all monitoring for this process).</pre>
20 21 22 23	<pre>PMIX_MONITOR_APP_CONTROL "pmix.monitor.appctrl" (bool) The application desires to control the response to a monitoring event - i.e., the application is requesting that the host environment not take immediate action in response to the event (e.g., terminating the job).</pre>
24 25	<pre>PMIX_MONITOR_HEARTBEAT "pmix.monitor.mbeat" (void) Register to have the PMIx server monitor the requestor for heartbeats.</pre>
26 27	<pre>PMIX_MONITOR_HEARTBEAT_TIME "pmix.monitor.btime" (uint32_t) Time in seconds before declaring heartbeat missed.</pre>
28 29	<pre>PMIX_MONITOR_HEARTBEAT_DROPS "pmix.monitor.bdrop" (uint32_t) Number of heartbeats that can be missed before generating the event.</pre>
30 31	<pre>PMIX_MONITOR_FILE "pmix.monitor.fmon" (char*) Register to monitor file for signs of life.</pre>
32 33	<pre>PMIX_MONITOR_FILE_SIZE "pmix.monitor.fsize" (bool) Monitor size of given file is growing to determine if the application is running.</pre>
34 35	<pre>PMIX_MONITOR_FILE_ACCESS "pmix.monitor.faccess" (char*) Monitor time since last access of given file to determine if the application is running.</pre>
36 37	<pre>PMIX_MONITOR_FILE_MODIFY "pmix.monitor.fmod" (char*) Monitor time since last modified of given file to determine if the application is running.</pre>

1 2		PMIX_MONITOR_FILE_CHECK_TIME "pmix.monitor.ftime" (uint32_t) Time in seconds between checking the file.
3 4		<pre>PMIX_MONITOR_FILE_DROPS "pmix.monitor.fdrop" (uint32_t) Number of file checks that can be missed before generating the event.</pre>
5 6		PMIX_SEND_HEARTBEAT "pmix.monitor.beat" (void) Send heartbeat to local PMIx server.
7 8 9 10		Description Non-blocking form of the PMIx_Process_monitor API. The <i>cbfunc</i> function provides a <i>status</i> to indicate whether or not the request was granted, and to provide some information as to the reason for any denial in the pmix_info_cbfunc_t array of pmix_info_t structures.
11	12.3.3	PMIx_Heartbeat
12 13		Summary Send a heartbeat to the PMIx server library
14	PMIx v2.0	Format C
15		<pre>PMIx_Heartbeat();</pre>
16 17 18		Description A simplified macro wrapping PMIx_Process_monitor_nb that sends a heartbeat to the PMIx server library.
19	12.3.4	Monitoring events
20 21		The following monitoring events may be available for registration, depending upon implementation and host environment support:
22 23 24 25		PMIX_MONITOR_HEARTBEAT_ALERT Heartbeat failed to arrive within specified window. The process that triggered this alert will be identified in the event. PMIX_MONITOR_FILE_ALERT File failed its monitoring detection criteria. The file that triggered this alert will be identified in the event.

12.3.5 Monitoring attributes

1

29

30

31

32

33

34

35

36

37 38

2 Attributes used to control monitoring of an executing application- these are values passed to the 3 PMIx Process monitor nb API and are not accessed using the PMIx Get API. PMIX_MONITOR_ID "pmix.monitor.id" (char*) 4 5 Provide a string identifier for this request. 6 PMIX MONITOR CANCEL "pmix.monitor.cancel" (char*) 7 Identifier to be canceled (**NULL** means cancel all monitoring for this process). 8 PMIX_MONITOR_APP_CONTROL "pmix.monitor.appctrl" (bool) 9 The application desires to control the response to a monitoring event - i.e., the application is requesting 10 that the host environment not take immediate action in response to the event (e.g., terminating the job). 11 PMIX MONITOR HEARTBEAT "pmix.monitor.mbeat" (void) 12 Register to have the PMIx server monitor the requestor for heartbeats. 13 PMIX_SEND_HEARTBEAT "pmix.monitor.beat" (void) 14 Send heartbeat to local PMIx server. PMIX MONITOR_HEARTBEAT_TIME "pmix.monitor.btime" (uint32_t) 15 16 Time in seconds before declaring heartbeat missed. 17 PMIX MONITOR HEARTBEAT DROPS "pmix.monitor.bdrop" (uint32 t) 18 Number of heartbeats that can be missed before generating the event. 19 PMIX MONITOR FILE "pmix.monitor.fmon" (char*) 20 Register to monitor file for signs of life. 21 PMIX MONITOR FILE SIZE "pmix.monitor.fsize" (bool) 22 Monitor size of given file is growing to determine if the application is running. 23 PMIX_MONITOR_FILE_ACCESS "pmix.monitor.faccess" (char*) 24 Monitor time since last access of given file to determine if the application is running. 25 PMIX_MONITOR_FILE_MODIFY "pmix.monitor.fmod" (char*) 26 Monitor time since last modified of given file to determine if the application is running. 27 PMIX_MONITOR_FILE_CHECK_TIME "pmix.monitor.ftime" (uint32_t) 28

12.4 Logging

The logging interface supports posting information by applications and SMS elements to persistent storage. This function is *not* intended for output of computational results, but rather for reporting status and saving state information such as inserting computation progress reports into the application's SMS job log or error reports to the local syslog.

12.4.1 PMIx_Log

Summary

Log data to a data service.

Time in seconds between checking the file.

PMIX MONITOR FILE DROPS "pmix.monitor.fdrop" (uint32 t)

Number of file checks that can be missed before generating the event.

Format 1 2 pmix status t 3 PMIx_Log(const pmix_info_t data[], size_t ndata, 4 const pmix_info_t directives[], size_t ndirs); — C – 5 IN data 6 Array of info structures (array of handles) 7 IN ndata 8 Number of elements in the *data* array (size_t) 9 directives Array of info structures (array of handles) 10 11 IN ndirs 12 Number of elements in the *directives* array (size_t) 13 Return codes are one of the following: 14 PMIX_SUCCESS The logging request was successful. 15 PMIX ERR BAD PARAM The logging request contains at least one incorrect entry. PMIX ERR NOT SUPPORTED The PMIx implementation or host environment does not support this 16 17 function. 18 other appropriate PMIx error code _____ Required Attributes 19 If the PMIx library does not itself perform this operation, then it is required to pass any attributes provided by 20 the client to the host environment for processing. In addition, it must include the following attributes in the 21 passed info array: 22 PMIX_USERID "pmix.euid" (uint32_t) 23 Effective user ID of the connecting process. 24 PMIX_GRPID "pmix.egid" (uint32_t) 25 Effective group ID of the connecting process. 26 Host environments or PMIx libraries that implement support for this operation are required to support the 27 following attributes: 28 PMIX_LOG_STDERR "pmix.log.stderr" (char*) 29 Log string to **stderr**. 30 PMIX_LOG_STDOUT "pmix.log.stdout" (char*) 31 Log string to **stdout**. 32 PMIX_LOG_SYSLOG "pmix.log.syslog" (char*) 33 Log data to syslog. Defaults to ERROR priority. Will log to global syslog if available, otherwise to 34 local syslog. 35 PMIX_LOG_LOCAL_SYSLOG "pmix.log.lsys" (char*) 36 Log data to local syslog. Defaults to **ERROR** priority.

```
PMIX_LOG_GLOBAL_SYSLOG "pmix.log.gsys" (char*)
 1
2
                    Forward data to system "gateway" and log msg to that syslog Defaults to ERROR priority.
3
              PMIX_LOG_SYSLOG_PRI "pmix.log.syspri" (int)
 4
                    Syslog priority level.
5
              PMIX LOG ONCE "pmix.log.once" (bool)
6
                    Only log this once with whichever channel can first support it, taking the channels in priority order.
              Optional Attributes -----
               7
              The following attributes are optional for host environments or PMIx libraries that support this operation:
8
              PMIX_LOG_SOURCE "pmix.log.source" (pmix_proc_t*)
                    ID of source of the log request.
9
10
              PMIX LOG TIMESTAMP "pmix.log.tstmp" (time t)
11
                    Timestamp for log report.
12
              PMIX LOG GENERATE TIMESTAMP "pmix.log.gtstmp" (bool)
13
                    Generate timestamp for log.
14
              PMIX LOG TAG OUTPUT "pmix.log.tag" (bool)
                    Label the output stream with the channel name (e.g., "stdout").
15
16
              PMIX_LOG_TIMESTAMP_OUTPUT "pmix.log.tsout" (bool)
17
                    Print timestamp in output string.
18
              PMIX LOG XML OUTPUT "pmix.log.xml" (bool)
19
                    Print the output stream in eXtensible Markup Language (XML) format.
              PMIX_LOG_EMAIL "pmix.log.email" (pmix_data_array_t)
20
21
                    Log via email based on pmix info t containing directives.
22
              PMIX LOG EMAIL ADDR "pmix.log.emaddr" (char*)
23
                    Comma-delimited list of email addresses that are to receive the message.
24
              PMIX LOG EMAIL SENDER ADDR "pmix.log.emfaddr" (char*)
25
                    Return email address of sender.
26
              PMIX LOG EMAIL SERVER "pmix.log.esrvr" (char*)
27
                    Hostname (or IP address) of SMTP server.
28
              PMIX_LOG_EMAIL_SRVR_PORT "pmix.log.esrvrprt" (int32_t)
29
                    Port the email server is listening to.
30
              PMIX_LOG_EMAIL_SUBJECT "pmix.log.emsub" (char*)
31
                    Subject line for email.
32
              PMIX_LOG_EMAIL_MSG "pmix.log.emmsg" (char*)
33
                    Message to be included in email.
34
              PMIX LOG JOB RECORD "pmix.log.jrec" (bool)
```

1 Log the provided information to the host environment's job record. 2 PMIX_LOG_GLOBAL_DATASTORE "pmix.log.gstore" (bool) 3 Store the log data in a global data store (e.g., database). **Description** 4 5 Log data subject to the services offered by the host environment. The data to be logged is provided in the data 6 array. The (optional) directives can be used to direct the choice of logging channel. Advice to users -7 It is strongly recommended that the PMIx_Log API not be used by applications for streaming data as it is not 8 a "performant" transport and can perturb the application since it involves the local PMIx server and host SMS 9 daemon. Note that a return of PMIX SUCCESS only denotes that the data was successfully handed to the 10 appropriate system call (for local channels) or the host environment and does not indicate receipt at the final 11 destination. 12.4.2 PMIx Log nb 12 13 Summary 14 Log data to a data service. Format 15 PMIx v2.016 pmix_status_t 17 PMIx Log nb(const pmix info t data[], size t ndata, 18 const pmix_info_t directives[], size_t ndirs, 19 pmix_op_cbfunc_t cbfunc, void *cbdata); 20 data 21 Array of info structures (array of handles) 22 IN ndata 23 Number of elements in the *data* array (size_t) 24 directives 25 Array of info structures (array of handles) 26 IN ndirs 27 Number of elements in the *directives* array (size_t) 28 29 Callback function **pmix_op_cbfunc_t** (function reference) 30 IN cbdata 31 Data to be passed to the callback function (memory reference)

32

Return codes are one of the following:

1 2 3	PMIX_SUCCESS The logging request is valid and is being processed. The resulting status from the operation will be provided in the callback function. Note that the library must not invoke the callback function prior to returning from the API.
4	PMIX_OPERATION_SUCCEEDED, indicating that the request was immediately processed and returned
5	success - the cbfunc will not be called
6	PMIX_ERR_BAD_PARAM The logging request contains at least one incorrect entry that prevents it from
7	being processed. The callback function will not be called.
8 9	PMIX_ERR_NOT_SUPPORTED The PMIx implementation does not support this function. The callback function will not be called.
0	other appropriate PMIx error code - the callback function will not be called.
	• Required Attributes
	·
1 2 3	If the PMIx library does not itself perform this operation, then it is required to pass any attributes provided by the client to the host environment for processing. In addition, it must include the following attributes in the passed <i>info</i> array:
4	<pre>PMIX_USERID "pmix.euid" (uint32_t)</pre>
5	Effective user ID of the connecting process.
6	PMIX_GRPID "pmix.egid" (uint32_t)
7	Effective group ID of the connecting process.
8 9	Host environments or PMIx libraries that implement support for this operation are required to support the following attributes:
20 21	<pre>PMIX_LOG_STDERR "pmix.log.stderr" (char*) Log string to stderr.</pre>
22 23	PMIX_LOG_STDOUT "pmix.log.stdout" (char*) Log string to stdout.
24	PMIX LOG SYSLOG "pmix.log.syslog" (char*)
25	Log data to syslog. Defaults to ERROR priority. Will log to global syslog if available, otherwise to
26	local syslog.
27	<pre>PMIX_LOG_LOCAL_SYSLOG "pmix.log.lsys" (char*)</pre>
28	Log data to local syslog. Defaults to ERROR priority.
29	<pre>PMIX_LOG_GLOBAL_SYSLOG "pmix.log.gsys" (char*)</pre>
80	Forward data to system "gateway" and log msg to that syslog Defaults to ERROR priority.
31 32	<pre>PMIX_LOG_SYSLOG_PRI "pmix.log.syspri" (int) Syslog priority level.</pre>
33 34	PMIX_LOG_ONCE "pmix.log.once" (bool) Only log this once with whichever channel can first support it, taking the channels in priority order.

Optional Attributes 1 The following attributes are optional for host environments or PMIx libraries that support this operation: 2 PMIX_LOG_SOURCE "pmix.log.source" (pmix_proc_t*) ID of source of the log request. 3 PMIX_LOG_TIMESTAMP "pmix.log.tstmp" (time_t) 4 5 Timestamp for log report. 6 PMIX LOG GENERATE TIMESTAMP "pmix.log.gtstmp" (bool) 7 Generate timestamp for log. 8 PMIX_LOG_TAG_OUTPUT "pmix.log.tag" (bool) 9 Label the output stream with the channel name (e.g., "stdout"). 10 PMIX_LOG_TIMESTAMP_OUTPUT "pmix.log.tsout" (bool) 11 Print timestamp in output string. 12 PMIX_LOG_XML_OUTPUT "pmix.log.xml" (bool) Print the output stream in XML format. 13 14 PMIX_LOG_EMAIL "pmix.log.email" (pmix_data_array_t) Log via email based on pmix_info_t containing directives. 15 16 PMIX LOG EMAIL ADDR "pmix.log.emaddr" (char*) 17 Comma-delimited list of email addresses that are to receive the message. PMIX LOG EMAIL SENDER ADDR "pmix.log.emfaddr" (char*) 18 Return email address of sender. 19 PMIX_LOG_EMAIL_SERVER "pmix.log.esrvr" (char*) 20 21 Hostname (or IP address) of SMTP server. 22 PMIX LOG EMAIL SRVR PORT "pmix.log.esrvrprt" (int32_t) 23 Port the email server is listening to. 24 PMIX LOG EMAIL SUBJECT "pmix.log.emsub" (char*) 25 Subject line for email. 26 PMIX LOG EMAIL MSG "pmix.log.emmsg" (char*) 27 Message to be included in email. 28 PMIX_LOG_JOB_RECORD "pmix.log.jrec" (bool) 29 Log the provided information to the host environment's job record. 30 PMIX LOG GLOBAL DATASTORE "pmix.log.gstore" (bool) 31 Store the log data in a global data store (e.g., database).

Description

Log data subject to the services offered by the host environment. The data to be logged is provided in the *data* array. The (optional) *directives* can be used to direct the choice of logging channel. The callback function will be executed when the log operation has been completed. The *data* and *directives* arrays must be maintained until the callback is provided.

Advice to users

It is strongly recommended that the **PMIx_Log_nb** API not be used by applications for streaming data as it is not a "performant" transport and can perturb the application since it involves the local PMIx server and host SMS daemon. Note that a return of **PMIX_SUCCESS** only denotes that the data was successfully handed to the appropriate system call (for local channels) or the host environment and does not indicate receipt at the final destination.

12.4.3 Log attributes

Attributes used to describe **PMIx_Log** behavior - these are values passed to the **PMIx_Log** API and therefore are not accessed using the **PMIx_Get** API.

Log data to syslog. Defaults to **ERROR** priority. Will log to global syslog if available, otherwise to local syslog.

```
{\tt PMIX\_LOG\_LOCAL\_SYSLOG~"pmix.log.lsys"~(char*)}
```

Log data to local syslog. Defaults to **ERROR** priority.

PMIX_LOG_GLOBAL_SYSLOG "pmix.log.gsys" (char*)

Forward data to system "gateway" and log msg to that syslog Defaults to **ERROR** priority.

```
{\tt PMIX\_LOG\_TIMESTAMP "pmix.log.tstmp" (time\_t)}
```

Timestamp for log report.

PMIX_LOG_GENERATE_TIMESTAMP "pmix.log.gtstmp" (bool)

Generate timestamp for log.

```
PMIX_LOG_TAG_OUTPUT "pmix.log.tag" (bool)
```

Label the output stream with the channel name (e.g., "stdout").

```
PMIX_LOG_TIMESTAMP_OUTPUT "pmix.log.tsout" (bool)
```

Print timestamp in output string.

```
PMIX_LOG_XML_OUTPUT "pmix.log.xml" (bool)
```

Print the output stream in XML format.

PMIX_LOG_ONCE "pmix.log.once" (bool)

Only log this once with whichever channel can first support it, taking the channels in priority order.

1	<pre>PMIX_LOG_MSG "pmix.log.msg" (pmix_byte_object_t)</pre>
2	Message blob to be sent somewhere.
3	<pre>PMIX_LOG_EMAIL "pmix.log.email" (pmix_data_array_t)</pre>
4	Log via email based on <pre>pmix_info_t</pre> containing directives.
5	<pre>PMIX_LOG_EMAIL_ADDR "pmix.log.emaddr" (char*)</pre>
6	Comma-delimited list of email addresses that are to receive the message.
7	<pre>PMIX_LOG_EMAIL_SENDER_ADDR "pmix.log.emfaddr" (char*)</pre>
8	Return email address of sender.
9	<pre>PMIX_LOG_EMAIL_SUBJECT "pmix.log.emsub" (char*)</pre>
0	Subject line for email.
1	<pre>PMIX_LOG_EMAIL_MSG "pmix.log.emmsg" (char*)</pre>
2	Message to be included in email.
3	<pre>PMIX_LOG_EMAIL_SERVER "pmix.log.esrvr" (char*)</pre>
4	Hostname (or IP address) of SMTP server.
5	${\tt PMIX_LOG_EMAIL_SRVR_PORT "pmix.log.esrvrprt" (int 32_t)}$
6	Port the email server is listening to.
7	PMIX_LOG_GLOBAL_DATASTORE "pmix.log.gstore" (bool)
8	Store the log data in a global data store (e.g., database).
9	<pre>PMIX_LOG_JOB_RECORD "pmix.log.jrec" (bool)</pre>
20	Log the provided information to the host environment's job record.

CHAPTER 13

Process Sets and Groups

PMIx supports two slightly related, but functionally different concepts known as *process sets* and *process groups*. This chapter defines these two concepts and describes how they are utilized, along with their corresponding APIs.

13.1 Process Sets

A PMIx *Process Set* is a user-provided or host environment assigned label associated with a given set of application processes. Processes can belong to multiple process *sets* at a time. Users may define a PMIx process set at time of application execution. For example, if using the command line parallel launcher "prun", one could specify process sets as follows:

```
$ prun -n 4 --pset ocean myoceanapp : -n 3 --pset ice myiceapp
```

In this example, the processes in the first application will be labeled with a **PMIX_PSET_NAMES** attribute with a value of *ocean* while those in the second application will be labeled with an *ice* value. During the execution, application processes could lookup the process set attribute for any process using **PMIx_Get**. Alternatively, other executing applications could utilize the **PMIx_Query_info** APIs to obtain the number of declared process sets in the system, a list of their names, and other information about them. In other words, the *process set* identifier provides a label by which an application can derive information about a process and its application - it does *not*, however, confer any operational function.

Host environments can create or delete process sets at any time through the
PMIx_server_define_process_set and PMIx_server_delete_process_set APIs. PMIx
servers shall notify all local clients of process set operations via the PMIX_PROCESS_SET_DEFINE or
PMIX_PROCESS_SET_DELETE events.

Process sets differ from process groups in several key ways:

- Process *sets* have no implied relationship between their members i.e., a process in a process set has no concept of a "pset rank" as it would in a process *group*.
- Process set identifiers are set by the host environment or by the user at time of application submission for
 execution there are no PMIx APIs provided by which an application can define a process set or change a
 process set membership. In contrast, PMIx process groups can only be defined dynamically by the
 application.
- Process sets are immutable members cannot be added or removed once the set has been defined. In contrast, PMIx process groups can dynamically change their membership using the appropriate APIs.

- Process groups can be used in calls to PMIx operations. Members of process groups that are involved in an operation are translated by their PMIx server into their native identifier prior to the operation being passed to the host environment. For example, an application can define a process group to consist of ranks 0 and 1 from the host-assigned namespace of 210456, identified by the group id of foo. If the application subsequently calls the PMIx_Fence API with a process identifier of {foo, PMIX_RANK_WILDCARD}, the PMIx server will replace that identifier with an array consisting of {210456, 0} and {210456, 1} the host-assigned identifiers of the participating processes prior to processing the request.
 - Process *groups* can request that the host environment assign a unique **size_t** Process Group Context IDentifier (PGCID) to the group at time of group construction. An Message Passing Interface (MPI) library may, for example, use the PGCID as the MPI communicator identifier for the group.

The two concepts do, however, overlap in that they both involve collections of processes. Users desiring to create a process group based on a process set could, for example, obtain the membership array of the process set and use that as input to <code>PMIx_Group_construct</code>, perhaps including the process set name as the group identifier for clarity. Note that no linkage between the set and group of the same name is implied nor maintained - e.g., changes in process group membership can not be reflected in the process set using the same identifier.

-Advice to PMIx server hosts-

- The host environment is responsible for ensuring:
 - consistent knowledge of process set membership across all involved PMIx servers; and
 - that process set names do not conflict with system-assigned namespaces within the scope of the set.

13.1.1 Process Set Constants

PMIx v4.0

The PMIx server is required to send a notification to all local clients upon creation or deletion of process sets. Client processes wishing to receive such notifications must register for the corresponding event:

PMIX_PROCESS_SET_DEFINE The host environment has defined a new process set - the event will include the process set name (PMIX_PSET_NAME) and the membership (PMIX_PSET_MEMBERS).

PMIX_PROCESS_SET_DELETE The host environment has deleted a process set - the event will include the process set name (PMIX_PSET_NAME).

13.1.2 Process Set Attributes

Several attributes are provided for querying the system regarding process sets using the **PMIx_Query_info** APIs.

```
PMIX_QUERY_NUM_PSETS "pmix.qry.psetnum" (size_t)

Return the number of process sets defined in the specified range (defaults to PMIX_RANGE_SESSION).
```

```
PMIX_QUERY_PSET_NAMES "pmix.qry.psets" (pmix_data_array_t*)
```

Return a **pmix_data_array_t** containing an array of strings of the process set names defined in the specified range (defaults to **PMIX_RANGE_SESSION**).

```
PMIX_QUERY_PSET_MEMBERSHIP "pmix.qry.pmems" (pmix_data_array_t*)

Return an array of pmix_proc_t containing the members of the specified process set.
```

The PMIX_PROCESS_SET_DEFINE event shall include the name of the newly defined process set and its members: PMIX_PSET_NAME "pmix.pset.nm" (char*)

The name of the newly defined process set.

```
PMIX_PSET_MEMBERS "pmix.pset.mems" (pmix_data_array_t*)
```

An array of **pmix_proc_t** containing the members of the newly defined process set.

In addition, a process can request (via **PMIx_Get**) the process sets to which a given process (including itself) belongs:

```
PMIX_PSET_NAMES "pmix.pset.nms" (pmix_data_array_t*)
```

Returns an array of char* string names of the process sets in which the given process is a member.

13.2 Process Groups

PMIx *Groups* are defined as a collection of processes desiring a common, unique identifier for operational purposes such as passing events or participating in PMIx fence operations. As with processes that assemble via **PMIx_Connect**, each member of the group is provided with both the job-level information of any other namespace represented in the group, and the contact information for all group members.

However, members of PMIx Groups are *loosely coupled* as opposed to *tightly connected* when constructed via **PMIx_Connect**. Thus, *groups* differ from **PMIx_Connect** assemblages in several key areas, as detailed in the following sections.

13.2.1 Relation to the host environment

Calls to PMIx Group APIs are first processed within the local PMIx server. When constructed, the server creates a tracker that associates the specified processes with the user-provided group identifier, and assigns a new *group rank* based on their relative position in the array of processes provided in the call to PMIx_Group_construct. Members of the group can subsequently utilize the group identifier in PMIx function calls to address the group's members, using either PMIX_RANK_WILDCARD to refer to all of them or the group-level rank of specific members. The PMIx server will translate the specified processes into their RM-assigned identifiers prior to passing the request up to its host. Thus, the host environment has no visibility into the group's existence or membership.

In contrast, calls to PMIx_Connect are relayed to the host environment. This means that the host RM should treat the failure of any process in the specified assemblage as a reportable event and take appropriate action. However, the environment is not required to define a new identifier for the connected assemblage or any of its member processes, nor does it define a new rank for each process within that assemblage. In addition, the PMIx server does not provide any tracking support for the assemblage. Thus, the caller is responsible for addressing members of the connected assemblage using their RM-provided identifiers.

Advice to users

User-provided group identifiers must be distinct from both other group identifiers within the system and namespaces provided by the RM so as to avoid collisions between group identifiers and RM-assigned namespaces. This can usually be accomplished through the use of an application-specific prefix - e.g., "myapp-foo"

13.2.2 Construction procedure

PMI*Connect calls require that every process call the API before completing – i.e., it is modeled upon the bulk synchronous traditional MPI connect/accept methodology. Thus, a given application thread can only be involved in one connect/accept operation at a time, and is blocked in that operation until all specified processes participate. In addition, there is no provision for replacing processes in the assemblage due to failure to participate, nor a mechanism by which a process might decline participation.

In contrast, PMIx Groups are designed to be more flexible in their construction procedure by relaxing these constraints. While a standard blocking form of constructing groups is provided, the event notification system is utilized to provide a designated *group leader* with the ability to replace participants that fail to participate within a given timeout period. This provides a mechanism by which the application can, if desired, replace members on-the-fly or allow the group to proceed with partial membership. In such cases, the final group membership is returned to all participants upon completion of the operation.

Additionally, PMIx supports dynamic definition of group membership based on an invite/join model. A process can asynchronously initiate construction of a group of any processes via the PMIx_Group_invite function call. Invitations are delivered via a PMIx event (using the PMIX_GROUP_INVITED event) to the invited processes which can then either accept or decline the invitation using the PMIx_Group_join API. The initiating process tracks responses by registering for the events generated by the call to PMIx_Group_join, timeouts, or process terminations, optionally replacing processes that decline the invitation, fail to respond in time, or terminate without responding. Upon completion of the operation, the final list of participants is communicated to each member of the new group.

13.2.3 Destruct procedure

Members of a PMIx Group may depart the group at any time via the PMIx_Group_leave API. Other members are notified of the departure via the PMIX_GROUP_LEFT event to distinguish such events from those reporting process termination. This leaves the remaining members free to continue group operations. The PMIx_Group_destruct operation offers a collective method akin to PMIx_Disconnect for deconstructing the entire group.

In contrast, processes that assemble via PMIx_Connect must all depart the assemblage together – i.e., no member can depart the assemblage while leaving the remaining members in it. Even the non-blocking form of PMIx_Disconnect retains this requirement in that members remain a part of the assemblage until all members have called PMIx Disconnect nb

Note that applications supporting dynamic group behaviors such as asynchronous departure take responsibility for ensuring global consistency in the group definition prior to executing group collective operations - i.e., it is the application's responsibility to either ensure that knowledge of the current group membership is globally consistent across the participants, or to register for appropriate events to deal with the lack of consistency during the operation.

Advice to users ——

The reliance on PMIx events in the PMIx Group concept dictates that processes utilizing these APIs must register for the corresponding events. Failure to do so will likely lead to operational failures. Users are recommended to utilize the PMIX_TIMEOUT directive (or retain an internal timer) on calls to PMIx Group APIs (especially the blocking form of those functions) as processes that have not registered for required events will never respond.

13.2.4 Process Group Events

PMIx v4.0 Asynchronous process group operations rely heavily on PMIx events. The following events have been defined for that purpose.

PMIX_GROUP_INVITED The process has been invited to join a PMIx Group - the identifier of the group and the ID's of other invited (or already joined) members will be included in the notification.

PMIX_GROUP_LEFT A process has asynchronously left a PMIx Group - the process identifier of the departing process will in included in the notification.

PMIX_GROUP_MEMBER_FAILED A member of a PMIx Group has abnormally terminated (i.e., without formally leaving the group prior to termination) - the process identifier of the failed process will be included in the notification.

PMIX_GROUP_INVITE_ACCEPTED A process has accepted an invitation to join a PMIx Group - the identifier of the group being joined will be included in the notification.

PMIX_GROUP_INVITE_DECLINED A process has declined an invitation to join a PMIx Group - the identifier of the declined group will be included in the notification.

PMIX_GROUP_INVITE_FAILED An invited process failed or terminated prior to responding to the invitation - the identifier of the failed process will be included in the notification.

PMIX_GROUP_MEMBERSHIP_UPDATE The membership of a PMIx group has changed - the identifiers of the revised membership will be included in the notification.

ı		PMIX_GROUP_CONSTRUCT_ABORT Any participant in a PMIx group construct operation that returns
2		PMIX_GROUP_CONSTRUCT_ABORT from the leader failed event handler will cause all participants to
3		receive an event notifying them of that status. Similarly, the leader may elect to abort the procedure by
4		either returning this error code from the handler assigned to the PMIX_GROUP_INVITE_ACCEPTED
5		or PMIX_GROUP_INVITE_DECLINED codes, or by generating an event for the abort code. Abort
6		events will be sent to all invited or existing members of the group.
7		PMIX GROUP CONSTRUCT COMPLETE The group construct operation has completed - the final
8		membership will be included in the notification.
9		PMIX_GROUP_LEADER_FAILED The current <i>leader</i> of a group including this process has abnormally
10		terminated - the group identifier will be included in the notification.
11		PMIX_GROUP_LEADER_SELECTED A new <i>leader</i> of a group including this process has been selected -
12		the identifier of the new leader will be included in the notification.
13		
14		PMIX_GROUP_CONTEXT_ID_ASSIGNED A new PGCID has been assigned by the host environment to a group that includes this process - the group identifier will be included in the notification.
15	13.2.5	Process Group Attributes
15		Frocess Group Attributes
16	PMIx v4.0	Attributes for querying the system regarding process groups include:
17		<pre>PMIX_QUERY_NUM_GROUPS "pmix.qry.pgrpnum" (size_t)</pre>
18		Return the number of process groups defined in the specified range (defaults to session). OPTIONAL
19		QUALIFERS: PMIX_RANGE.
20		<pre>PMIX_QUERY_GROUP_NAMES "pmix.qry.pgrp" (pmix_data_array_t*)</pre>
21		Return a pmix_data_array_t containing an array of string names of the process groups defined in
22		the specified range (defaults to session). OPTIONAL QUALIFERS: PMIX_RANGE.
23		PMIX_QUERY_GROUP_MEMBERSHIP "pmix.qry.pgrpmems" (pmix_data_array_t*)
24		Return a pmix_data_array_t of pmix_proc_t containing the members of the specified process
25		group. REQUIRED QUALIFIERS: PMIX_GROUP_ID.
26		The following attributes are used as directives in PMIx Group operations:
27		<pre>PMIX_GROUP_ID "pmix.grp.id" (char*)</pre>
28		User-provided group identifier - as the group identifier may be used in PMIx operations, the user is
29		required to ensure that the provided ID is unique within the scope of the host environment (e.g., by
30		including some user-specific or application-specific prefix or suffix to the string).
31		PMIX_GROUP_LEADER "pmix.grp.ldr" (bool)
32		This process is the leader of the group.
33		PMIX_GROUP_OPTIONAL "pmix.grp.opt" (bool)
34		Participation is optional - do not return an error if any of the specified processes terminate without
35		having joined. The default is false .
36		PMIX_GROUP_NOTIFY_TERMINATION "pmix.grp.notterm" (bool)
37		Notify remaining members when another member terminates without first leaving the group.
38		PMIX_GROUP_FT_COLLECTIVE "pmix.grp.ftcoll" (bool)
39		Adjust internal tracking on-the-fly for terminated processes during a PMIx group collective operation.
40		<pre>PMIX_GROUP_MEMBERSHIP "pmix.grp.mbrs" (pmix_data_array_t*)</pre>

Array $\begin{subarray}{c} {\tt pmix_proc_t} \end{subarray}$ identifiers identifying the members of the specified group.

PMIX_GROUP_ASSIGN_CONTEXT_ID "pmix.grp.actxid" (bool)

```
1
                        Requests that the RM assign a new context identifier to the newly created group. The identifier is an
 2
                        unsigned, size t value that the RM guarantees to be unique across the range specified in the request.
 3
                        Thus, the value serves as a means of identifying the group within that range. If no range is specified,
 4
                        then the request defaults to PMIX RANGE SESSION.
 5
                 PMIX_GROUP_LOCAL_ONLY "pmix.grp.lcl" (bool)
 6
                        Group operation only involves local processes. PMIx implementations are required to automatically
 7
                        scan an array of group members for local vs remote processes - if only local processes are detected, the
 8
                        implementation need not execute a global collective for the operation unless a context ID has been
 9
                        requested from the host environment. This can result in significant time savings. This attribute can be
10
                        used to optimize the operation by indicating whether or not only local processes are represented, thus
11
                        allowing the implementation to bypass the scan.
12
                 The following attributes are used to return information at the conclusion of a PMIx Group operation and/or in
13
                 event notifications:
14
                 PMIX GROUP_CONTEXT_ID "pmix.grp.ctxid" (size_t)
                        Context identifier assigned to the group by the host RM.
15
                 PMIX GROUP_ENDPT_DATA "pmix.grp.endpt" (pmix_byte_object_t)
16
17
                        Data collected during group construction to ensure communication between group members is
                        supported upon completion of the operation.
18
19
                 In addition, a process can request (via PMIx Get) the process groups to which a given process (including
20
                 itself) belongs:
21
                 PMIX_GROUP_NAMES "pmix.pgrp.nm" (pmix_data_array_t*)
22
                        Returns an array of char* string names of the process groups in which the given process is a member.
      13.2.6
                   PMIx Group construct
23
                 Summary
24
25
                 Construct a PMIx process group.
26 <sub>PMIx v4.0</sub>
                 Format
27
                 pmix_status_t
                 PMIx_Group_construct(const char grp[],
28
29
                                             const pmix_proc_t procs[], size_t nprocs,
                                              const pmix_info_t directives[],
30
31
                                              size t ndirs,
32
                                             pmix_info_t **results,
33
                                              size_t *nresults);
34
                 IN
35
                       NULL-terminated character array of maximum size PMIX MAX NSLEN containing the group identifier
36
                       (string)
37
                 IN
38
                       Array of pmix_proc_t structures containing the PMIx identifiers of the member processes (array of
39
                       handles)
```

1	IN nprocs
2	Number of elements in the <i>procs</i> array (size_t) IN directives
4	Array of pmix_info_t structures (array of handles)
5	IN ndirs
6 7	Number of elements in the <i>directives</i> array (size_t) INOUT results
8	Pointer to a location where the array of pmix_info_t describing the results of the operation is to be
9	returned (pointer to handle)
10 11	INOUT nresults Pointer to a size_t location where the number of elements in <i>results</i> is to be returned (memory
12	reference)
13	Returns one of the following:
14	• PMIX_SUCCESS, indicating that the request has been successfully completed
15	• PMIX_ERR_NOT_SUPPORTED The PMIx library and/or the host RM does not support this operation
16	• a PMIx error constant indicating either an error in the input or that the request failed to be completed
	▼
17	The following attributes are required to be supported by all PMIx libraries that support this operation:
18 19	PMIX_GROUP_LEADER "pmix.grp.ldr" (bool) This process is the leader of the group.
20 21 22	PMIX_GROUP_OPTIONAL "pmix.grp.opt" (bool) Participation is optional - do not return an error if any of the specified processes terminate without having joined. The default is false.
23 24 25 26 27 28 29	PMIX_GROUP_LOCAL_ONLY "pmix.grp.lcl" (bool) Group operation only involves local processes. PMIx implementations are <i>required</i> to automatically scan an array of group members for local vs remote processes - if only local processes are detected, the implementation need not execute a global collective for the operation unless a context ID has been requested from the host environment. This can result in significant time savings. This attribute can be used to optimize the operation by indicating whether or not only local processes are represented, thus allowing the implementation to bypass the scan.
30 31	PMIX_GROUP_FT_COLLECTIVE "pmix.grp.ftcoll" (bool) Adjust internal tracking on-the-fly for terminated processes during a PMIx group collective operation.
32	Host environments that support this operation are <i>required</i> to support the following attributes:
33 34 35 36 37	PMIX_GROUP_ASSIGN_CONTEXT_ID "pmix.grp.actxid" (bool) Requests that the RM assign a new context identifier to the newly created group. The identifier is an unsigned, size_t value that the RM guarantees to be unique across the range specified in the request. Thus, the value serves as a means of identifying the group within that range. If no range is specified, then the request defaults to PMIX_RANGE_SESSION.
38 39	PMIX_GROUP_NOTIFY_TERMINATION "pmix.grp.notterm" (bool) Notify remaining members when another member terminates without first leaving the group.

Optional Attributes

The following attributes are optional for host environments that support this operation:

PMIX_TIMEOUT "pmix.timeout" (int)

Time in seconds before the specified operation should time out (zero indicating infinite) and return the **PMIX_ERR_TIMEOUT** error. Care should be taken to avoid race conditions caused by multiple layers (client, server, and host) simultaneously timing the operation.

Description

Construct a new group composed of the specified processes and identified with the provided group identifier. The group identifier is a user-defined, **NULL**-terminated character array of length less than or equal to **PMIX_MAX_NSLEN**. Only characters accepted by standard string comparison functions (e.g., *strncmp*) are supported. Processes may engage in multiple simultaneous group construct operations so long as each is provided with a unique group ID. The *directives* array can be used to pass user-level directives regarding timeout constraints and other options available from the PMIx server.

If the PMIX_GROUP_NOTIFY_TERMINATION attribute is provided and has a value of true, then either the construct leader (if PMIX_GROUP_LEADER is provided) or all participants who register for the PMIX_GROUP_MEMBER_FAILED event will receive events whenever a process fails or terminates prior to calling PMIx_Group_construct – i.e. if a group leader is declared, only that process will receive the event. In the absence of a declared leader, all specified group members will receive the event.

The event will contain the identifier of the process that failed to join plus any other information that the host RM provided. This provides an opportunity for the leader or the collective members to react to the event – e.g., to decide to proceed with a smaller group or to abort the operation. The decision is communicated to the PMIx library in the results array at the end of the event handler. This allows PMIx to properly adjust accounting for procedure completion. When construct is complete, the participating PMIx servers will be alerted to any change in participants and each group member will receive an updated group membership (marked with the PMIX GROUP MEMBERSHIP attribute) as part of the *results* array returned by this API.

Failure of the declared leader at any time will cause a PMIX_GROUP_LEADER_FAILED event to be delivered to all participants so they can optionally declare a new leader. A new leader is identified by providing the PMIX_GROUP_LEADER attribute in the results array in the return of the event handler. Only one process is allowed to return that attribute, thereby declaring itself as the new leader. Results of the leader selection will be communicated to all participants via a PMIX_GROUP_LEADER_SELECTED event identifying the new leader. If no leader was selected, then the pmix_info_t provided to that event handler will include that information so the participants can take appropriate action.

Any participant that returns PMIX_GROUP_CONSTRUCT_ABORT from either the PMIX_GROUP_MEMBER_FAILED or the PMIX_GROUP_LEADER_FAILED event handler will cause the construct process to abort, returning from the call with a PMIX_GROUP_CONSTRUCT_ABORT status.

If the PMIX_GROUP_NOTIFY_TERMINATION attribute is not provided or has a value of false, then the PMIX_Group_construct operation will simply return an error whenever a proposed group member fails or terminates prior to calling PMIX_Group_construct.

Providing the PMIX_GROUP_OPTIONAL attribute with a value of true directs the PMIx library to consider participation by any specified group member as non-required - thus, the operation will return PMIX_SUCCESS if all members participate, or PMIX_ERR_PARTIAL_SUCCESS if some members fail to participate. The results array will contain the final group membership in the latter case. Note that this use-case can cause the operation to hang if the PMIX_TIMEOUT attribute is not specified and one or more group members fail to call PMIX_Group_construct while continuing to execute. Also, note that no leader or member failed events will be generated during the operation.

Processes in a group under construction are not allowed to leave the group until group construction is complete. Upon completion of the construct procedure, each group member will have access to the job-level information of all namespaces represented in the group plus any information posted via **PMIx_Put** (subject to the usual scoping directives) for every group member.

-Advice to PMIx library implementers-

At the conclusion of the construct operation, the PMIx library is *required* to ensure that job-related information from each participating namespace plus any information posted by group members via PMIx_Put (subject to scoping directives) is available to each member via calls to PMIx_Get.

-Advice to PMIx server hosts-

The collective nature of this API generally results in use of a fence-like operation by the backend host environment. Host environments that utilize the array of process participants as a *signature* for such operations may experience potential conflicts should both a **PMIx_Group_construct** and a **PMIx_Fence** operation involving the same participants be simultaneously executed. As PMIx allows for such use-cases, it is therefore the responsibility of the host environment to resolve any potential conflicts.

13.2.7 PMIx Group construct nb

Summary

Non-blocking form of PMIx_Group_construct.

Returns one of the following:

- PMIX_SUCCESS indicating that the request has been accepted for processing and the provided callback
 function will be executed upon completion of the operation. Note that the library must not invoke the
 callback function prior to returning from the API.
- PMIX_OPERATION_SUCCEEDED, indicating that the request was immediately processed and returned success - the cbfunc will not be called.
- PMIX_ERR_NOT_SUPPORTED The PMIx library does not support this operation the cbfunc will not be called.
- a non-zero PMIx error constant indicating a reason for the request to have been rejected the cbfunc will not be called.

If executed, the status returned in the provided callback function will be one of the following constants:

- PMIX_SUCCESS The operation succeeded and all specified members participated.
- PMIX_ERR_PARTIAL_SUCCESS The operation succeeded but not all specified members participated the final group membership is included in the callback function.
- PMIX_ERR_NOT_SUPPORTED While the PMIx server supports this operation, the host RM does not.
- a non-zero PMIx error constant indicating a reason for the request's failure.

24

25

26 27

28

29

30

31

32

33 34

35

36

37 38

	libraries that choose not to support this operation <i>must</i> return PMIX_ERR_NOT_SUPPORTED whon is called.
The fo	llowing attributes are <i>required</i> to be supported by all PMIx libraries that support this operation:
PMIX _.	_GROUP_LEADER "pmix.grp.ldr" (bool) This process is the leader of the group.
PMIX _.	_GROUP_OPTIONAL "pmix.grp.opt" (bool) Participation is optional - do not return an error if any of the specified processes terminate without having joined. The default is false.
PMIX _.	GROUP_LOCAL_ONLY "pmix.grp.lcl" (bool) Group operation only involves local processes. PMIx implementations are <i>required</i> to automatical scan an array of group members for local vs remote processes - if only local processes are detected implementation need not execute a global collective for the operation unless a context ID has been requested from the host environment. This can result in significant time savings. This attribute can used to optimize the operation by indicating whether or not only local processes are represented, allowing the implementation to bypass the scan.
PMIX.	_GROUP_FT_COLLECTIVE "pmix.grp.ftcoll" (bool) Adjust internal tracking on-the-fly for terminated processes during a PMIx group collective opera
Host e	nvironments that support this operation are <i>required</i> to provide the following attributes:
PMIX _.	GROUP_ASSIGN_CONTEXT_ID "pmix.grp.actxid" (bool) Requests that the RM assign a new context identifier to the newly created group. The identifier is unsigned, size_t value that the RM guarantees to be unique across the range specified in the re. Thus, the value serves as a means of identifying the group within that range. If no range is specific then the request defaults to PMIX_RANGE_SESSION.
PMIX.	_GROUP_NOTIFY_TERMINATION "pmix.grp.notterm" (bool) Notify remaining members when another member terminates without first leaving the group.
	Optional Attributes
The fo	llowing attributes are optional for host environments that support this operation:
DMTY	_TIMEOUT "pmix.timeout" (int) Time in seconds before the specified operation should time out (zero indicating infinite) and return

13.2.8 PMIx_Group_destruct

```
Summary
 2
               Destruct a PMIx process group.
 3
               Format
 <sup>4</sup> PMIx v4.0
 5
               pmix_status t
 6
               PMIx_Group_destruct(const char grp[],
 7
                                        const pmix_info_t directives[],
 8
                                        size_t ndirs);
 9
               IN
                    grp
10
                    NULL-terminated character array of maximum size PMIX MAX NSLEN containing the identifier of the
11
                    group to be destructed (string)
12
                    directives
13
                    Array of pmix_info_t structures (array of handles)
14
               IN
15
                    Number of elements in the directives array (size_t)
16
               Returns one of the following:
17
               • PMIX SUCCESS, indicating that the request has been successfully completed
18
               • PMIX ERR NOT SUPPORTED The PMIx library and/or the host RM does not support this operation
19
               • a PMIx error constant indicating either an error in the input or that the request failed to be completed
                                                 Required Attributes
20
               For implementations and host environments that support the operation, there are no identified required
21
               attributes for this API.
                ------ Optional Attributes ------
22
               The following attributes are optional for host environments that support this operation:
23
               PMIX_TIMEOUT "pmix.timeout" (int)
24
                      Time in seconds before the specified operation should time out (zero indicating infinite) and return the
25
                      PMIX ERR TIMEOUT error. Care should be taken to avoid race conditions caused by multiple layers
26
                      (client, server, and host) simultaneously timing the operation.
```

Description

1

3

4

5

6

7

8

9

10

11

12

13

14

15

16

17

18 19

20

21

22

23

24

25

26

27

28

29

30

31

32

33

34

35

36

Destruct a group identified by the provided group identifier. Processes may engage in multiple simultaneous group destruct operations so long as each involves a unique group ID. The *directives* array can be used to pass user-level directives regarding timeout constraints and other options available from the PMIx server.

The destruct API will return an error if any group process fails or terminates prior to calling
PMIx_Group_destruct or its non-blocking version unless the
PMIX_GROUP_NOTIFY_TERMINATION attribute was provided (with a value of false) at time of group
construction. If notification was requested, then the PMIX_GROUP_MEMBER_FAILED event will be
delivered for each process that fails to call destruct and the destruct tracker updated to account for the lack of
participation. The PMIx_Group_destruct operation will subsequently return PMIX_SUCCESS when the
remaining processes have all called destruct – i.e., the event will serve in place of return of an error.

-Advice to PMIx server hosts-

The collective nature of this API generally results in use of a fence-like operation by the backend host environment. Host environments that utilize the array of process participants as a *signature* for such operations may experience potential conflicts should both a PMIx_Group_destruct and a PMIx_Fence operation involving the same participants be simultaneously executed. As PMIx allows for such use-cases, it is therefore the responsibility of the host environment to resolve any potential conflicts.

13.2.9 PMIx_Group_destruct_nb

Summary

Non-blocking form of PMIx Group destruct.

PMIx v4.0 Format

pmix_status_t

PMIx_Group_destruct_nb(const char grp[],

const pmix_info_t directives[],

size_t ndirs,

pmix_op_cbfunc_t cbfunc, void *cbdata);

IN arp

NULL-terminated character array of maximum size **PMIX_MAX_NSLEN** containing the identifier of the group to be destructed (string)

IN directives

Array of pmix_info_t structures (array of handles)

IN ndirs

Number of elements in the *directives* array (size_t)

IN cbfunc

Callback function **pmix_op_cbfunc_t** (function reference)

IN cbdata

Data to be passed to the callback function (memory reference)

1	Returns one of the following:
2	 PMIX_SUCCESS, indicating that the request is being processed - result will be returned in the provided cbfunc. Note that the library must not invoke the callback function prior to returning from the API.
4 5	 PMIX_OPERATION_SUCCEEDED, indicating that the request was immediately processed and returned success - the cbfunc will not be called
6 7	• PMIX_ERR_NOT_SUPPORTED The PMIx library does not support this operation - the <i>cbfunc</i> will <i>not</i> be called.
8 9	• a PMIx error constant indicating either an error in the input or that the request was immediately processed and failed - the <i>cbfunc</i> will <i>not</i> be called.
10	If executed, the status returned in the provided callback function will be one of the following constants:
11	• PMIX_SUCCESS The operation was successfully completed.
12	• PMIX_ERR_NOT_SUPPORTED While the PMIx server supports this operation, the host RM does not.
13	• a non-zero PMIx error constant indicating a reason for the request's failure.
	▼ Required Attributes
14 15 16	PMIx libraries that choose not to support this operation <i>must</i> return PMIX_ERR_NOT_SUPPORTED when the function is called. For implementations and host environments that support the operation, there are no identified required attributes for this API.
	▼ Optional Attributes
17	The following attributes are optional for host environments that support this operation:
18 19 20 21	PMIX_TIMEOUT "pmix.timeout" (int) Time in seconds before the specified operation should time out (zero indicating infinite) and return the PMIX_ERR_TIMEOUT error. Care should be taken to avoid race conditions caused by multiple layers (client, server, and host) simultaneously timing the operation.
22 23	Description Non-blocking version of the PMIx_Group_destruct operation. The callback function will be called once
24	all members of the group have executed either PMIx_Group_destruct or
25	PMIx_Group_destruct_nb.
26	13.2.10 PMIx_Group_invite
27	Summary
28	Asynchronously construct a PMIx process group.

1	Format C —
2 3 4 5 6	<pre>pmix_status_t PMIx_Group_invite(const char grp[],</pre>
	C —
7 8 9	IN grp NULL-terminated character array of maximum size PMIX_MAX_NSLEN containing the group identifier (string)
10 11 12	IN procs Array of pmix_proc_t structures containing the PMIx identifiers of the processes to be invited (array of handles)
13 14	IN nprocs Number of elements in the procs array (size_t)
15	IN directives
16	Array of pmix_info_t structures (array of handles)
17 18	<pre>IN ndirs Number of elements in the directives array (size_t)</pre>
19	INOUT results
20	Pointer to a location where the array of pmix_info_t describing the results of the operation is to be
21	returned (pointer to handle)
22	INOUT nresults
23 24	Pointer to a size_t location where the number of elements in <i>results</i> is to be returned (memory reference)
25	Returns one of the following:
26	• PMIX_SUCCESS, indicating that the request has been successfully completed.
27	• PMIX_ERR_NOT_SUPPORTED The PMIx library and/or the host RM does not support this operation.
28	• a PMIx error constant indicating either an error in the input or that the request failed to be completed.
	▼
29	The following attributes are required to be supported by all PMIx libraries that support this operation:
30	PMIX_GROUP_OPTIONAL "pmix.grp.opt" (bool)
31 32	Participation is optional - do not return an error if any of the specified processes terminate without having joined. The default is false .
33 34	PMIX_GROUP_FT_COLLECTIVE "pmix.grp.ftcoll" (bool) Adjust internal tracking on-the-fly for terminated processes during a PMIx group collective operation.
35	Host environments that support this operation are required to provide the following attributes:
36	<pre>PMIX_GROUP_ASSIGN_CONTEXT_ID "pmix.grp.actxid" (bool)</pre>

 Requests that the RM assign a new context identifier to the newly created group. The identifier is an unsigned, <code>size_t</code> value that the RM guarantees to be unique across the range specified in the request. Thus, the value serves as a means of identifying the group within that range. If no range is specified, then the request defaults to <code>PMIX RANGE SESSION</code>.

PMIX_GROUP_NOTIFY_TERMINATION "pmix.grp.notterm" (bool)

Notify remaining members when another member terminates without first leaving the group.

Optional Attributes

The following attributes are optional for host environments that support this operation:

```
PMIX_TIMEOUT "pmix.timeout" (int)
```

Time in seconds before the specified operation should time out (zero indicating infinite) and return the **PMIX_ERR_TIMEOUT** error. Care should be taken to avoid race conditions caused by multiple layers (client, server, and host) simultaneously timing the operation.

Description

Explicitly invite the specified processes to join a group. The process making the PMIx_Group_invite call is automatically declared to be the *group leader*. Each invited process will be notified of the invitation via the PMIX_GROUP_INVITED event - the processes being invited must therefore register for the PMIX_GROUP_INVITED event in order to be notified of the invitation. Note that the PMIx event notification system caches events - thus, no ordering of invite versus event registration is required.

A-----

The invitation event will include the identity of the inviting process plus the name of the group. When ready to respond, each invited process provides a response using either the blocking or non-blocking form of <code>PMIx_Group_join</code>. This will notify the inviting process that the invitation was either accepted (via the <code>PMIX_GROUP_INVITE_ACCEPTED</code> event) or declined (via the <code>PMIX_GROUP_INVITE_DECLINED</code> event). The <code>PMIX_GROUP_INVITE_ACCEPTED</code> event is captured by the PMIx client library of the inviting process – i.e., the application itself does not need to register for this event. The library will track the number of accepting processes and alert the inviting process (by returning from the blocking form of <code>PMIx_Group_invite</code> or calling the callback function of the non-blocking form) when group construction completes.

The inviting process should, however, register for the <code>PMIX_GROUP_INVITE_DECLINED</code> if the application allows invited processes to decline the invitation. This provides an opportunity for the application to either invite a replacement, declare "abort", or choose to remove the declining process from the final group. The inviting process should also register to receive <code>PMIX_GROUP_INVITE_FAILED</code> events whenever a process fails or terminates prior to responding to the invitation. Actions taken by the inviting process in response to these events must be communicated at the end of the event handler by returning the corresponding result so that the PMIx library can adjust accordingly.

Upon completion of the operation, all members of the new group will receive access to the job-level information of each other's namespaces plus any information posted via **PMIx_Put** by the other members.

The inviting process is automatically considered the leader of the asynchronous group construction procedure and will receive all failure or termination events for invited members prior to completion. The inviting process is required to provide a PMIX_GROUP_CONSTRUCT_COMPLETE event once the group has been fully

assembled – this event is used by the PMIx library as a trigger to release participants from their call to **PMIx_Group_join** and provides information (e.g., the final group membership) to be returned in the *results* array.

Failure of the inviting process at any time will cause a PMIX_GROUP_LEADER_FAILED event to be delivered to all participants so they can optionally declare a new leader. A new leader is identified by providing the PMIX_GROUP_LEADER attribute in the results array in the return of the event handler. Only one process is allowed to return that attribute, declaring itself as the new leader. Results of the leader selection will be communicated to all participants via a PMIX_GROUP_LEADER_SELECTED event identifying the new leader. If no leader was selected, then the status code provided in the event handler will provide an error value so the participants can take appropriate action.

Advice to users -

Applications are not allowed to use the group in any operations until group construction is complete. This is required in order to ensure consistent knowledge of group membership across all participants.

13.2.11 PMIx Group invite nb

Summary

pmix status t

Non-blocking form of PMIx_Group_invite.

PMIx v4.0 Format

1

2

3

4

5

6

7

8

10

11

12

13

14 15

16

17

18

19

20

21

22

23

24

25

26

27

28

29 30

31

32

33

34

35

36

37

PMIx_Group_invite_nb(const char grp[],

const pmix_proc_t procs[], size_t nprocs,
const pmix_info_t directives[], size_t ndirs,

pmix_info_cbfunc_t cbfunc, void *cbdata);

IN grp

NULL-terminated character array of maximum size **PMIX_MAX_NSLEN** containing the group identifier (string)

C

IN procs

Array of **pmix_proc_t** structures containing the PMIx identifiers of the processes to be invited (array of handles)

IN nprocs

Number of elements in the *procs* array (size_t)

IN directives

Array of pmix_info_t structures (array of handles)

IN ndirs

Number of elements in the *directives* array (size_t)

IN cbfunc

Callback function pmix_info_cbfunc_t (function reference)

IN cbdata

Data to be passed to the callback function (memory reference)

1 Returns one of the following: 2 • PMIX_SUCCESS, indicating that the request is being processed - result will be returned in the provided 3 cbfunc. Note that the library must not invoke the callback function prior to returning from the API. • PMIX OPERATION SUCCEEDED, indicating that the request was immediately processed and returned 4 5 success - the cbfunc will not be called. 6 • PMIX ERR NOT SUPPORTED The PMIx library does not support this operation - the cbfunc will not be 7 called. 8 • a PMIx error constant indicating either an error in the input or that the request was immediately processed 9 and failed - the cbfunc will not be called. If executed, the status returned in the provided callback function will be one of the following constants: 10 11 • PMIX SUCCESS The operation succeeded and all specified members participated. • PMIX_ERR_PARTIAL_SUCCESS The operation succeeded but not all specified members participated -12 the final group membership is included in the callback function. 13 14 • PMIX ERR NOT SUPPORTED While the PMIx server supports this operation, the host RM does not. 15 • a non-zero PMIx error constant indicating a reason for the request's failure. Required Attributes The following attributes are *required* to be supported by all PMIx libraries that support this operation: 16 17 PMIX_GROUP_OPTIONAL "pmix.grp.opt" (bool) Participation is optional - do not return an error if any of the specified processes terminate without 18 19 having joined. The default is **false**. 20 PMIX GROUP FT COLLECTIVE "pmix.grp.ftcoll" (bool) 21 Adjust internal tracking on-the-fly for terminated processes during a PMIx group collective operation. 22 Host environments that support this operation are required to provide the following attributes: 23 PMIX_GROUP_ASSIGN_CONTEXT_ID "pmix.grp.actxid" (bool) 24 Requests that the RM assign a new context identifier to the newly created group. The identifier is an 25 unsigned, size t value that the RM guarantees to be unique across the range specified in the request. 26 Thus, the value serves as a means of identifying the group within that range. If no range is specified, 27 then the request defaults to PMIX_RANGE_SESSION. 28 PMIX_GROUP_NOTIFY_TERMINATION "pmix.grp.notterm" (bool) 29 Notify remaining members when another member terminates without first leaving the group.

Optional Attributes 1 The following attributes are optional for host environments that support this operation: 2 PMIX_TIMEOUT "pmix.timeout" (int) 3 Time in seconds before the specified operation should time out (zero indicating infinite) and return the 4 PMIX_ERR_TIMEOUT error. Care should be taken to avoid race conditions caused by multiple layers 5 (client, server, and host) simultaneously timing the operation. **Description** 6 7 Non-blocking version of the PMIx_Group_invite operation. The callback function will be called once all 8 invited members of the group (or their substitutes) have executed either PMIx_Group_join or 9 PMIx Group join nb. 13.2.12 10 PMIx Group join Summary 11 12 Accept an invitation to join a PMIx process group. Format 13 PMIx v4.0 14 pmix status t 15 PMIx Group join (const char grp[], 16 const pmix_proc_t *leader, 17 pmix group opt t opt, 18 const pmix_info_t directives[], size_t ndirs, 19 pmix_info_t **results, size_t *nresult); —— C – 20 IN grp NULL-terminated character array of maximum size PMIX_MAX_NSLEN containing the group identifier 21 22 (string) 23 IN leader 24 Process that generated the invitation (handle) 25 IN 26 Accept or decline flag (pmix_group_opt_t) 27 directives 28 Array of **pmix_info_t** structures (array of handles) 29 30 Number of elements in the *directives* array (size_t) 31 **INOUT** results 32 Pointer to a location where the array of **pmix_info_t** describing the results of the operation is to be 33 returned (pointer to handle) **INOUT** nresults 34 35 Pointer to a size t location where the number of elements in results is to be returned (memory 36 reference)

1 Returns one of the following: 2 • PMIX_SUCCESS, indicating that the request has been successfully completed. 3 • PMIX ERR NOT SUPPORTED The PMIx library and/or the host RM does not support this operation. 4 • a PMIx error constant indicating either an error in the input or that the request failed to be completed. Required Attributes 5 There are no identified required attributes for implementers. **A**-----**A** Optional Attributes -----______ 6 The following attributes are optional for host environments that support this operation: 7 PMIX_TIMEOUT "pmix.timeout" (int) 8 Time in seconds before the specified operation should time out (zero indicating infinite) and return the 9 PMIX ERR TIMEOUT error. Care should be taken to avoid race conditions caused by multiple layers 10 (client, server, and host) simultaneously timing the operation. **Description** 11 12 Respond to an invitation to join a group that is being asynchronously constructed. The process must have 13 registered for the PMIX GROUP INVITED event in order to be notified of the invitation. When called, the 14 event information will include the pmix_proc_t identifier of the process that generated the invitation along 15 with the identifier of the group being constructed. When ready to respond, the process provides a response 16 using either form of PMIx_Group_join. Advice to users — 17 Since the process is alerted to the invitation in a PMIx event handler, the process must not use the blocking 18 form of this call unless it first "thread shifts" out of the handler and into its own thread context. Likewise, 19 while it is safe to call the non-blocking form of the API from the event handler, the process must not block in

20

the handler while waiting for the callback function to be called.

Calling this function causes the inviting process (aka the *group leader*) to be notified that the process has either accepted or declined the request. The blocking form of the API will return once the group has been completely constructed or the group's construction has failed (as described below) – likewise, the callback function of the non-blocking form will be executed upon the same conditions.

Failure of the leader during the call to PMIx_Group_join will cause a PMIX_GROUP_LEADER_FAILED event to be delivered to all invited participants so they can optionally declare a new leader. A new leader is identified by providing the PMIX_GROUP_LEADER attribute in the results array in the return of the event handler. Only one process is allowed to return that attribute, declaring itself as the new leader. Results of the leader selection will be communicated to all participants via a PMIX_GROUP_LEADER_SELECTED event identifying the new leader. If no leader was selected, then the status code provided in the event handler will provide an error value so the participants can take appropriate action.

Any participant that returns PMIX_GROUP_CONSTRUCT_ABORT from the leader failed event handler will cause all participants to receive an event notifying them of that status. Similarly, the leader may elect to abort the procedure by either returning PMIX_GROUP_CONSTRUCT_ABORT from the handler assigned to the PMIX_GROUP_INVITE_ACCEPTED or PMIX_GROUP_INVITE_DECLINED codes, or by generating an event for the abort code. Abort events will be sent to all invited participants.

13.2.13 PMIx_Group_join_nb

Summary

Non-blocking form of PMIx_Group_join

PMIx v4.0

```
Format
```

pmix_status_t
PMIx_Group_join_nb(const char grp[],

PMIX_Group_join_nb (const char gip[],

const pmix_proc_t *leader,
pmix_group_opt_t opt,

const pmix_info_t directives[], size_t ndirs,

pmix_info_cbfunc_t cbfunc, void *cbdata);

IN grp

NULL-terminated character array of maximum size **PMIX_MAX_NSLEN** containing the group identifier (string)

IN leader

Process that generated the invitation (handle)

IN opt

Accept or decline flag (pmix_group_opt_t)

IN directives

Array of **pmix_info_t** structures (array of handles)

IN ndirs

Number of elements in the *directives* array (size_t)

1 2 3 4	IN cbfunc Callback function pmix_info_cbfunc_t (function reference) IN cbdata Data to be passed to the callback function (memory reference)
5	Returns one of the following:
6 7	• PMIX_SUCCESS, indicating that the request is being processed - result will be returned in the provided <i>cbfunc</i> . Note that the library <i>must not</i> invoke the callback function prior to returning from the API.
8 9	• PMIX_OPERATION_SUCCEEDED, indicating that the request was immediately processed and returned success - the cbfunc will not be called.
10 11	• PMIX_ERR_NOT_SUPPORTED The PMIx library does not support this operation - the <i>cbfunc</i> will <i>not</i> be called.
12 13	• a PMIx error constant indicating either an error in the input or that the request was immediately processed and failed - the <i>cbfunc</i> will <i>not</i> be called.
14	If executed, the status returned in the provided callback function will be one of the following constants:
15	• PMIX_SUCCESS The operation succeeded and group membership is in the callback function parameters.
16	• PMIX_ERR_NOT_SUPPORTED While the PMIx server supports this operation, the host RM does not.
17	• a non-zero PMIx error constant indicating a reason for the request's failure.
	Required Attributes
18	There are no identified required attributes for implementers.
	▼Optional Attributes
19	The following attributes are optional for host environments that support this operation:
20 21 22 23	PMIX_TIMEOUT "pmix.timeout" (int) Time in seconds before the specified operation should time out (zero indicating infinite) and return the PMIX_ERR_TIMEOUT error. Care should be taken to avoid race conditions caused by multiple layers (client, server, and host) simultaneously timing the operation.
24 25	Description Non-blocking version of the PMIx_Group_join operation. The callback function will be called once all invited by the property of t
26 27	invited members of the group (or their substitutes) have executed either PMIx_Group_join or PMIx_Group_join_nb .
28 13.2.13	.1 Group accept/decline directives
PMIx v4.0 30	The <code>pmix_group_opt_t</code> type is a <code>uint8_t</code> value used with the <code>PMIx_Group_join</code> API to indicate <code>accept</code> or <code>decline</code> of the invitation - these are provided for readability of user code:
31 32	PMIX_GROUP_DECLINE Decline the invitation. PMIX_GROUP_ACCEPT Accept the invitation.

13.2.14 PMIx Group leave

1

2 Summary 3 Leave a PMIx process group. 4 Format PMIx v4.0 5 pmix_status_t 6 PMIx_Group_leave(const char grp[], 7 const pmix_info_t directives[], 8 size t ndirs); 9 IN grp 10 NULL-terminated character array of maximum size PMIX MAX NSLEN containing the group identifier 11 (string) 12 directives 13 Array of **pmix_info_t** structures (array of handles) 14 IN 15 Number of elements in the *directives* array (size_t) 16 Returns one of the following: 17 • PMIX_SUCCESS, indicating that the request has been communicated to the local PMIx server. 18 • PMIX ERR NOT SUPPORTED The PMIx library and/or the host RM does not support this operation. 19 • a PMIx error constant indicating either an error in the input or that the request is unsupported. Required Attributes 20 There are no identified required attributes for implementers. 21 Description 22 Calls to PMIx_Group_leave (or its non-blocking form) will cause a PMIX_GROUP_LEFT event to be 23 generated notifying all members of the group of the caller's departure. The function will return (or the non-blocking function will execute the specified callback function) once the event has been locally generated 24 25 and is not indicative of remote receipt. — Advice to users — The PMIx_Group_leave API is intended solely for asynchronous departures of individual processes from 26 27 a group as it is not a scalable operation – i.e., when a process determines it should no longer be a part of a defined group, but the remainder of the group retains a valid reason to continue in existence. Developers are 28 29 advised to use PMIx Group destruct (or its non-blocking form) for all other scenarios as it represents a more scalable operation. 30

13.2.15 PMIx_Group_leave_nb

2 3	Summary Non-blocking form of PMIx_Group_leave.
4 <i>PMIx v4.0</i>	Format C
5 6 7 8 9 10	<pre>pmix_status_t PMIx_Group_leave_nb(const char grp[],</pre>
11 12 13 14 15 16 17 18 19 20 21	IN grp NULL-terminated character array of maximum size PMIX_MAX_NSLEN containing the group identifier (string) IN directives Array of pmix_info_t structures (array of handles) IN ndirs Number of elements in the directives array (size_t) IN cbfunc Callback function pmix_op_cbfunc_t (function reference) IN cbdata Data to be passed to the callback function (memory reference)
22	Returns one of the following:
23 24	• PMIX_SUCCESS, indicating that the request is being processed - result will be returned in the provided <i>cbfunc</i> . Note that the library <i>must not</i> invoke the callback function prior to returning from the API.
25 26	• PMIX_OPERATION_SUCCEEDED, indicating that the request was immediately processed and returned success - the cbfunc will not be called.
27 28	• PMIX_ERR_NOT_SUPPORTED The PMIx library does not support this operation - the <i>cbfunc</i> will <i>not</i> be called.
29 30	• a PMIx error constant indicating either an error in the input or that the request was immediately processed and failed - the <i>cbfunc</i> will <i>not</i> be called.
31	If executed, the status returned in the provided callback function will be one of the following constants:
32	• PMIX_SUCCESS The operation succeeded - i.e., the PMIX_GROUP_LEFT event was generated.
33	• PMIX_ERR_NOT_SUPPORTED While the PMIx library supports this operation, the host RM does not.
34	• a non-zero PMIx error constant indicating a reason for the request's failure. Required Attributes
35	There are no identified required attributes for implementers.

Description

1

Non-blocking version of the **PMIx_Group_leave** operation. The callback function will be called once the event has been locally generated and is not indicative of remote receipt.

CHAPTER 14

Fabric Support Definitions

As the drive for performance continues, interest has grown in scheduling algorithms that take into account network locality of the allocated resources and in optimizing collective communication patterns by structuring them to follow fabric topology. In addition, concerns over the time required to initiate execution of parallel applications and enable communication across them have grown as the size of those applications extends into the hundreds of thousands of individual processes spanning tens of thousands of nodes.

PMIx supports the communication part of these efforts by defining data types and attributes by which fabric endpoints and coordinates for processes and devices can be obtained from the host environment. When used in conjunction with other PMIx methods described in Chapter 16, this results in the ability of a process to obtain the fabric endpoint and coordinate of all other processes without incurring additional overhead associated with a global exchange of that information. This includes:

- Defining several interfaces specifically intended to support WLMs by providing access to information of
 potential use to scheduling algorithms e.g., information on communication costs between different points
 on the fabric.
- Supporting hierarchical collective operations by providing the fabric coordinates for all devices on participating nodes as well as a list of the peers sharing each fabric switch. This enables one, for example, to aggregate the contribution from all processes on a node, then again across all nodes on a common switch, and finally across all switches based on detailed knowledge of the fabric location of each participant.
- Enabling the "instant on" paradigm to mitigate the scalable launch problem by providing each process with
 a rich set of information about the environment and the application, including everything required for
 communication between peers within the application, at time of process start of execution.

Meeting these needs in the case where only a single fabric device exists on each node is relatively straightforward - PMIx and the host environment provide a single endpoint for each process plus a coordinate for the device on each node, and there is no uncertainty regarding the endpoint each process will use. Extending this to the multiple device per node case is more difficult as the choice of endpoint by any given process cannot be known in advance, and questions arise regarding reachability between devices on different nodes. Resolving these ambiguities without requiring a global operation requires that PMIx provide both (a) an endpoint for each application process on each of its local devices; and (b) the fabric coordinates of all remote and local devices on participating nodes. It also requires that each process open all of its assigned endpoints as the endpoint selected for contact by a remote peer cannot be known in advance.

While these steps ensure the ability of a process to connect to a remote peer, it leaves unanswered the question of selecting the *preferred* device for that communication. If multiple devices are present on a node, then the application can benefit from having each process utilize its "closest" fabric device (i.e., the device that minimizes the communication distance between the process' location and that device) for messaging operations. In some cases, messaging libraries prefer to also retain the ability to use non-nearest devices, prioritizing the devices based on distance to support multi-device operations (e.g., for large message transmission in parallel).

10

11

6

22 23 24

25 26

27 28

29 30

31 32 33

34 35

36 37

38 39

40

since a single process can occupy multiple processor locations. In addition, since processes can relocate themselves by changing their processor bindings, PMIx provides an API that allows the process to dynamically request an update to its distance array. However, while these measures assist a process in selecting its own best endpoint, they do not resolve the uncertainty over the choice of preferred device by a remote peer. There are two methods by which this

ambiguity can be resolved:

PMIx supports this requirement by providing the array of process-to-device distance information for each

process and local fabric device at start of execution. Both minimum and maximum distances are provided

- a) A process can select a remote endpoint to use based on its own preferred device and reachability of the peer's remote devices. Once the initial connection has been made, the two processes can exchange information and mutually determine their desired communication path going forward.
- b) The application can use knowledge of both the local and remote distance arrays to compute the best communication path and establish that connection. In some instances (e.g., a homogeneous system), a PMIx server may provide distance information for both local and remote devices. Alternatively, when this isn't available, an application can opt to collect the information using the PMIX COLLECT GENERATED JOB INFO with the PMIx Fence API, or can obtain it on a one peer-at-a-time basis using the **PMIx** Get API on systems where the host environment supports the *Direct Modex* operation.

Information on fabric coordinates, endpoints, and device distances are provided as reserved keys as detailed in Chapter 6 - i.e., they are to be available at client start of execution and are subject to the retrieval rules of Section 6.2. Examples for retrieving fabric-related information include retrieval of:

- An array of information on fabric devices for a node by passing PMIX FABRIC DEVICES as the key to PMIx Get along with the PMIX HOSTNAME of the node as a directive
- An array of information on a specific fabric device by passing PMIX FABRIC DEVICE as the key to PMIx Get along with the PMIX DEVICE ID of the device as a directive
- An array of information on a specific fabric device by passing **PMIX_FABRIC_DEVICE** as the key to PMIx Get along with both PMIX FABRIC DEVICE NAME of the device and the PMIX HOSTNAME of the node as directives

When requesting data on a device, returned data must include at least the following attributes:

- PMIX_HOSTNAME "pmix.hname" (char*) Name of the host, as returned by the **gethostname** utility or its equivalent. The **PMIX NODEID** may be returned in its place, or in addition to the hostname.
- PMIX_DEVICE_ID "pmix.dev.id" (string) System-wide UUID or node-local OS name of a particular device.
- PMIX_FABRIC_DEVICE_NAME "pmix.fabdev.nm" (string) The operating system name associated with the device. This may be a logical fabric interface name (e.g. "eth0" or "eno1") or an absolute filename.
- PMIX_FABRIC_DEVICE_VENDOR "pmix.fabdev.vndr" (string) Indicates the name of the vendor that distributes the device.
- PMIX_FABRIC_DEVICE_BUS_TYPE "pmix.fabdev.btyp" (string)

1	The type of bus to which the device is attached (e.g., "PCI", "GEN-Z").
2 3 4 5 6 7 8 9	• PMIX_FABRIC_DEVICE_PCI_DEVID "pmix.fabdev.pcidevid" (string) A node-level unique identifier for a Peripheral Component Interconnect (PCI) device. Provided only if the device is located on a PCI bus. The identifier is constructed as a four-part tuple delimited by colons comprised of the PCI 16-bit domain, 8-bit bus, 8-bit device, and 8-bit function IDs, each expressed in zero-extended hexadecimal form. Thus, an example identifier might be "abc1:0f:23:01". The combination of node identifier (PMIX_HOSTNAME or PMIX_NODEID) and PMIX_FABRIC_DEVICE_PCI_DEVID shall be unique within the overall system. This item should be included if the device bus type is PCI - the equivalent should be provided for any other bus type.
11	The returned array may optionally contain one or more of the following in addition to the above list:
12 13	 PMIX_FABRIC_DEVICE_INDEX "pmix.fabdev.idx" (uint32_t) Index of the device within an associated communication cost matrix.
14 15	 PMIX_FABRIC_DEVICE_VENDORID "pmix.fabdev.vendid" (string) This is a vendor-provided identifier for the device or product.
16 17	• PMIX_FABRIC_DEVICE_DRIVER "pmix.fabdev.driver" (string) The name of the driver associated with the device.
18 19	• PMIX_FABRIC_DEVICE_FIRMWARE "pmix.fabdev.fmwr" (string) The device's firmware version.
20 21 22	 PMIX_FABRIC_DEVICE_ADDRESS "pmix.fabdev.addr" (string) The primary link-level address associated with the device, such as a Media Access Control (MAC) address. If multiple addresses are available, only one will be reported.
23 24 25	 PMIX_FABRIC_DEVICE_COORDINATES "pmix.fab.coord" (pmix_geometry_t) The pmix_geometry_t fabric coordinates for the device, including values for all supported coordinate views.
26 27	 PMIX_FABRIC_DEVICE_MTU "pmix.fabdev.mtu" (size_t) The maximum transfer unit of link level frames or packets, in bytes.
28 29	• PMIX_FABRIC_DEVICE_SPEED "pmix.fabdev.speed" (size_t) The active link data rate, given in bits per second.
30 31 32 33	 PMIX_FABRIC_DEVICE_STATE "pmix.fabdev.state" (pmix_link_state_t) The last available physical port state for the specified device. Possible values are PMIX_LINK_STATE_UNKNOWN, PMIX_LINK_DOWN, and PMIX_LINK_UP, to indicate if the port state is unknown or not applicable (unknown), inactive (down), or active (up).
34 35	• PMIX_FABRIC_DEVICE_TYPE "pmix.fabdev.type" (string) Specifies the type of fabric interface currently active on the device, such as Ethernet or InfiniBand.
36 37	The remainder of this chapter details the events, data types, attributes, and APIs associated with fabric-related operations.

14.1 Fabric Support Events

resume.

2

3

4 5

6

7

8

9

10

11 12

13

20

21

22

23 24

25 26

27

PMIx v4.2

The following events are defined for use in fabric-related operations.

PMIX_FABRIC_UPDATE_PENDING
The PMIx server library has been alerted to a change in the fabric that requires updating of one or more registered pmix_fabric_t objects.
PMIX_FABRIC_UPDATED
The PMIx server library has completed updating the entries of all affected pmix_fabric_t objects registered with the library. Access to the entries of those objects may now

PMIX_FABRIC_UPDATE_ENDPOINTS
Endpoint assignments have been updated, usually in response to migration or restart of a process. Clients should use PMIx_Get to update any internally cached connections.

14.2 Fabric Support Datatypes

Several datatype definitions have been created to support fabric-related operations and information.

14.2.1 Fabric Endpoint Structure

```
The pmix_endpoint_t structure contains an assigned endpoint for a given fabric device.

PMIx v4.0

typedef struct pmix_endpoint {
    char *uuid;
    char *osname;
    pmix_byte_object_t endpt;
} pmix_endpoint_t;

C
```

The *uuid* field contains the UUID of the fabric device, the *osname* is the local operating system's name for the device, and the *endpt* field contains a fabric vendor-specific object identifying the communication endpoint assigned to the process.

14.2.2 Fabric endpoint support macros

The following macros are provided to support the **pmix endpoint t** structure.

Static initializer for the endpoint structure

(Provisional)

Provide a static initializer for the **pmix_endpoint_t** fields.

28 PMIX_ENDPOINT_STATIC_INIT

1 2	Initialize the endpoint structure Initialize the pmix_endpoint_t fields.
3	PMIX_ENDPOINT_CONSTRUCT (m)
4 5	IN m Pointer to the structure to be initialized (pointer to pmix_endpoint_t)
6 7 <i>PMIx v4.0</i>	Destruct the endpoint structure Destruct the pmix_endpoint_t fields.
8	PMIX_ENDPOINT_DESTRUCT (m)
9 10	<pre>IN m Pointer to the structure to be destructed (pointer to pmix_endpoint_t)</pre>
11 12 <i>PMIx v4.0</i>	Create an endpoint array Allocate and initialize a pmix_endpoint_t array. C
13	PMIX_ENDPOINT_CREATE(m, n)
14 15 16 17	INOUT m Address where the pointer to the array of pmix_endpoint_t structures shall be stored (handle) IN n Number of structures to be allocated (size_t)
18 19 <i>PMIx v4.0</i>	Release an endpoint array Release an array of pmix_endpoint_t structures.
20	PMIX_ENDPOINT_FREE (m, n)
21 22 23 24	<pre>IN m Pointer to the array of pmix_endpoint_t structures (handle) IN n Number of structures in the array (size_t)</pre>

1 14.2.3 Fabric Coordinate Structure

2		The <code>pmix_coord_t</code> structure describes the fabric coordinates of a specified device in a given view.
		C
3 4 5 6 7		<pre>typedef struct pmix_coord { pmix_coord_view_t view; uint32_t *coord; size_t dims; } pmix_coord_t;</pre>
		C
8 9 10		All coordinate values shall be expressed as unsigned integers due to their units being defined in fabric devices and not physical distances. The coordinate is therefore an indicator of connectivity and not relative communication distance. Advice to PMIx library implementers
11 12 13		Note that the <code>pmix_coord_t</code> structure does not imply nor mandate any requirement on how the coordinate data is to be stored within the PMIx library. Implementers are free to store the coordinate in whatever format they choose.
14 15 16 17		A fabric coordinate is associated with a given fabric device and must be unique within a given view. Fabric devices are associated with the operating system which hosts them - thus, fabric coordinates are logically grouped within the <i>node</i> realm (as described in Section 6.1) and can be retrieved per the rules detailed in Section 6.1.5.
18	14.2.4	Fabric coordinate support macros
19		The following macros are provided to support the <pre>pmix_coord_t</pre> structure.
20 21		Static initializer for the coord structure (Provisional)
22		Provide a static initializer for the pmix_coord_t fields.
	PMIx v4.2	G —
23		PMIX_COORD_STATIC_INIT C
24 25	PMIx v4.0	Initialize the coord structure Initialize the pmix_coord_t fields.
26	FMIX V4.0	DMTY GOODD GONGEDUCE (=)
_0		PMIX_COORD_CONSTRUCT (m)
27 28		IN m Pointer to the structure to be initialized (pointer to pmix goord t)

```
Destruct the coord structure
 1
 2
                Destruct the pmix_coord_t fields.
 3
                PMIX COORD DESTRUCT (m)
                IN
 5
                     Pointer to the structure to be destructed (pointer to pmix_coord_t)
                Create a coord array
                Allocate and initialize a pmix_coord_t array.
  PMIx v4.0
 8
                PMIX COORD CREATE (m, n)
 9
                INOUT m
10
                     Address where the pointer to the array of pmix_coord_t structures shall be stored (handle)
11
                IN
12
                     Number of structures to be allocated (size_t)
13
                Release a coord array
                Release an array of pmix_coord_t structures.
14
   PMIx v4.0
15
                PMIX COORD FREE (m, n)
16
                IN
17
                     Pointer to the array of pmix_coord_t structures (handle)
18
                IN
19
                     Number of structures in the array (size_t)
     14.2.5
                 Fabric Geometry Structure
20
21
                The pmix_geometry_t structure describes the fabric coordinates of a specified device.
   PMIx v4.0
22
                typedef struct pmix_geometry {
23
                     size_t fabric;
24
                     char *uuid;
25
                     char *osname;
26
                     pmix_coord_t *coordinates;
27
                     size_t ncoords;
28
                } pmix_geometry_t;
```

		C
1 2 3		All coordinate values shall be expressed as unsigned integers due to their units being defined in fabric devices and not physical distances. The coordinate is therefore an indicator of connectivity and not relative communication distance. Advice to PMIx library implementers
4 5 6		Note that the <code>pmix_coord_t</code> structure does not imply nor mandate any requirement on how the coordinate data is to be stored within the PMIx library. Implementers are free to store the coordinate in whatever format they choose.
7 8 9 10		A fabric coordinate is associated with a given fabric device and must be unique within a given view. Fabric devices are associated with the operating system which hosts them - thus, fabric coordinates are logically grouped within the <i>node</i> realm (as described in Section 6.1) and can be retrieved per the rules detailed in Section 6.1.5.
11	14.2.6	Fabric geometry support macros
12		The following macros are provided to support the <code>pmix_geometry_t</code> structure.
13 14		Static initializer for the geometry structure (Provisional)
15	PMIx v4.2	Provide a static initializer for the <pre>pmix_geometry_t</pre> fields.
16		PMIX_GEOMETRY_STATIC_INIT
17 18	PMIx v4.0	Initialize the geometry structure Initialize the pmix_geometry_t fields.
19		PMIX_GEOMETRY_CONSTRUCT (m)
20 21		IN m Pointer to the structure to be initialized (pointer to pmix_geometry_t)
22 23	PMIx v4.0	Destruct the geometry structure Destruct the pmix_geometry_t fields.
24		PMIX_GEOMETRY_DESTRUCT (m)
25 26		IN m Pointer to the structure to be destructed (pointer to pmix geometry t)

1	Create a geometry array	
2	Allocate and initialize a pmix_geometry_t arra	ıу. - С
3	PMIX_GEOMETRY_CREATE(m, n)	- C
4	INOUT m	
5	Address where the pointer to the array of pm	ix_geometry_t structures shall be stored (handle)
6	IN n	
7	Number of structures to be allocated (size_	_t)
8	Release a geometry array	
9	Release an array of pmix_geometry_t structure	es.
PMIx v4.0	V	- C —
10	PMIX_GEOMETRY_FREE (m, n)	
	<u> </u>	- C
11	IN m	
12	Pointer to the array of pmix geometry t	structures (handle)
13	IN n	
14	Number of structures in the array (size_t)	
14.2.	7 Fabric Coordinate Views	
PMIx v4.0	V	- C
16	<pre>typedef uint8_t pmix_coord_view_t;</pre>	
17	#define PMIX_COORD_VIEW_UNDEF	0x00
18	<pre>#define PMIX_COORD_LOGICAL_VIEW</pre>	0x01
19	<pre>#define PMIX_COORD_PHYSICAL_VIEW</pre>	0x02
	<u> </u>	- C
20	Fabric coordinates can be reported based on differe	ent <i>views</i> according to user preference at the time of request.
21	The following views have been defined:	3
22	PMIX_COORD_VIEW_UNDEF The coordinate	e view has not been defined.
23	PMIX COORD LOGICAL VIEW The coordin	nates are provided in a <i>logical</i> view, typically given in
24		the data flow in the fabric as defined by the arrangement of
)E		amentation routing domains and other similar factors
<u> </u>	the hierarchical addressing scheme, fabric se	ginentation, routing domains, and other similar factors
	the hierarchical addressing scheme, fabric se employed by that fabric.	gmentation, routing domains, and other similar factors
26	employed by that fabric.	inates are provided in a <i>physical</i> view based on the actual
26 27	employed by that fabric. PMIX_COORD_PHYSICAL_VIEW The coord	
25 26 27 28 29	employed by that fabric. PMIX_COORD_PHYSICAL_VIEW The coord	inates are provided in a <i>physical</i> view based on the actual

14.2.8 Fabric Link State

1

3

4 5

6

7

8

9

17 18

19

27

28

29

30

31

32

The pmix_link_state_t is a uint32_t type for fabric link states.

```
typedef uint8_t pmix_link_state_t;
```

The following constants can be used to set a variable of the type **pmix_link_state_t**. All definitions were introduced in version 4 of the standard unless otherwise marked. Valid link state values start at zero.

```
PMIX_LINK_STATE_UNKNOWN The port state is unknown or not applicable.

PMIX_LINK_DOWN The port is inactive.

PMIX_LINK_UP The port is active.
```

14.2.9 Fabric Operation Constants

```
PMIx v4.0
10
                 The pmix fabric operation t data type is an enumerated type for specifying fabric operations used
                 in the PMIx server module's pmix_server_fabric_fn_t API.
11
12
                 PMIX FABRIC REQUEST INFO
                                                     Request information on a specific fabric - if the fabric isn't specified
13
                      as per PMIx_Fabric_register, then return information on the default fabric of the overall system.
14
                      Information to be returned is described in pmix_fabric_t.
15
                 PMIX FABRIC UPDATE INFO
                                                    Update information on a specific fabric - the index of the fabric
16
                      (PMIX_FABRIC_INDEX) to be updated must be provided.
```

14.2.10 Fabric registration structure

The **pmix_fabric_t** structure is used by a WLM to interact with fabric-related PMIx interfaces, and to provide information about the fabric for use in scheduling algorithms or other purposes.

Note that in this structure:

- name is an optional user-supplied string name identifying the fabric being referenced by this struct. If
 provided, the field must be a NULL-terminated string composed of standard alphanumeric values supported
 by common utilities such as strcmp.;
- *index* is a PMIx-provided number identifying this object;
- *info* is an array of pmix_info_t containing information (provided by the PMIx library) about the fabric;

•	ninfo is the number of elements in the info array;
•	module points to an opaque object reserved for use by the PMIx server library.
n b	Note that only the <i>name</i> field is provided by the user - all other fields are provided by the PMIx library and must not be modified by the user. The <i>info</i> array contains a varying amount of information depending upon both the PMIx implementation and information available from the fabric vendor. At a minimum, it must contain (ordering is arbitrary):
•	r Required Attributes
P	PMIX_FABRIC_VENDOR "pmix.fab.vndr" (string) Name of the vendor (e.g., Amazon, Mellanox, HPE, Intel) for the specified fabric.
P	An identifier for the specified fabric (e.g., MgmtEthernet, Slingshot-11, OmniPath-1).
P	MIX_FABRIC_NUM_DEVICES "pmix.fab.nverts" (size_t) Total number of fabric devices in the overall system - corresponds to the number of rows or columns in the cost matrix.
a	nd may optionally contain one or more of the following:
•	r Optional Attributes
P	PMIX_FABRIC_COST_MATRIX "pmix.fab.cm" (pointer) Pointer to a two-dimensional square array of point-to-point relative communication costs expressed as uint16_t values.
Р	A string delineating the group membership of nodes in the overall system, where each fabric group consists of the group number followed by a colon and a comma-delimited list of nodes in that group, with the groups delimited by semi-colons (e.g., 0:node000, node002, node004, node006; 1:node001, node003, node005, node007)
P	Number of dimensions in the specified fabric plane/view. If no plane is specified in a request, then the dimensions of all planes in the overall system will be returned as a <pre>pmix_data_array_t</pre> containing an array of <pre>uint32_t</pre> values. Default is to provide dimensions in <pre>logical</pre> view.
P	ID string of a fabric plane (e.g., CIDR for Ethernet). When used as a modifier in a request for information, specifies the plane whose information is to be returned. When used directly as a key in a request, returns a pmix_data_array_t of string identifiers for all fabric planes in the overall system.
P	PMIX_FABRIC_SHAPE "pmix.fab.shape" (pmix_data_array_t*)

4

1 The size of each dimension in the specified fabric plane/view, returned in a pmix_data_array_t 2 containing an array of uint32 t values. The size is defined as the number of elements present in 3 that dimension - e.g., the number of devices in one dimension of a physical view of a fabric plane. If no 4 plane is specified, then the shape of each plane in the overall system will be returned in a 5 pmix_data_array_t array where each element is itself a two-element array containing the 6 PMIX FABRIC PLANE followed by that plane's fabric shape. Default is to provide the shape in 7 logical view. 8 PMIX_FABRIC_SHAPE_STRING "pmix.fab.shapestr" (string) 9 Network shape expressed as a string (e.g., "10x12x2"). If no plane is specified, then the shape of each plane in the overall system will be returned in a pmix_data_array_t array where each 10 11 element is itself a two-element array containing the PMIX FABRIC PLANE followed by that plane's 12 fabric shape string. Default is to provide the shape in logical view. 13 While unusual due to scaling issues, implementations may include an array of PMIX_FABRIC_DEVICE elements describing the device information for each device in the overall system. Each element shall contain a 14 15 pmix data array t of pmix info t values describing the device. Each array may contain one or more of the following (ordering is arbitrary): 16 17 PMIX FABRIC DEVICE NAME "pmix.fabdev.nm" (string) 18 The operating system name associated with the device. This may be a logical fabric interface name 19 (e.g. "eth0" or "eno1") or an absolute filename. 20 PMIX_FABRIC_DEVICE_VENDOR "pmix.fabdev.vndr" (string) 21 Indicates the name of the vendor that distributes the device. 22 PMIX DEVICE ID "pmix.dev.id" (string) 23 System-wide UUID or node-local OS name of a particular device. 24 PMIX_HOSTNAME "pmix.hname" (char*) 25 Name of the host, as returned by the **gethostname** utility or its equivalent. 26 PMIX_FABRIC_DEVICE_DRIVER "pmix.fabdev.driver" (string) 27 The name of the driver associated with the device. 28 PMIX FABRIC DEVICE FIRMWARE "pmix.fabdev.fmwr" (string) 29 The device's firmware version. PMIX_FABRIC_DEVICE_ADDRESS "pmix.fabdev.addr" (string) 30 31 The primary link-level address associated with the device, such as a MAC address. If multiple 32 addresses are available, only one will be reported. 33 PMIX_FABRIC_DEVICE_MTU "pmix.fabdev.mtu" (size_t) 34 The maximum transfer unit of link level frames or packets, in bytes. 35 PMIX_FABRIC_DEVICE_SPEED "pmix.fabdev.speed" (size_t) 36 The active link data rate, given in bits per second. 37 PMIX_FABRIC_DEVICE_STATE "pmix.fabdev.state" (pmix_link_state_t) 38 The last available physical port state for the specified device. Possible values are PMIX LINK STATE UNKNOWN, PMIX LINK DOWN, and PMIX LINK UP, to indicate if the port 39 40 state is unknown or not applicable (unknown), inactive (down), or active (up).

```
1
                 PMIX_FABRIC_DEVICE_TYPE "pmix.fabdev.type" (string)
 2
                        Specifies the type of fabric interface currently active on the device, such as Ethernet or InfiniBand.
 3
                 PMIX_FABRIC_DEVICE_BUS_TYPE "pmix.fabdev.btyp" (string)
 4
                        The type of bus to which the device is attached (e.g., "PCI", "GEN-Z").
 5
                 PMIX_FABRIC_DEVICE_PCI_DEVID "pmix.fabdev.pcidevid" (string)
 6
                        A node-level unique identifier for a PCI device. Provided only if the device is located on a PCI bus.
 7
                        The identifier is constructed as a four-part tuple delimited by colons comprised of the PCI 16-bit
 8
                        domain, 8-bit bus, 8-bit device, and 8-bit function IDs, each expressed in zero-extended hexadecimal
 9
                        form. Thus, an example identifier might be "abc1:0f:23:01". The combination of node identifier
                        (PMIX_HOSTNAME or PMIX_NODEID) and PMIX_FABRIC_DEVICE_PCI_DEVID shall be
10
11
                        unique within the overall system.
      14.2.10.1 Static initializer for the fabric structure
12
13
                 (Provisional)
14
                 Provide a static initializer for the pmix_fabric_t fields.
   PMIx v4.2
15
                 PMIX FABRIC STATIC INIT
      14.2.10.2 Initialize the fabric structure
16
17
                 Initialize the pmix fabric t fields.
   PMIx v4.0
18
                 PMIX FABRIC CONSTRUCT (m)
19
                 IN
20
                      Pointer to the structure to be initialized (pointer to pmix_fabric_t)
      14.3
                 Fabric Support Attributes
21
22
                 The following attribute is used by the PMIx server library supporting the system's WLM to indicate that it
                 wants access to the fabric support functions:
23
24
                 PMIX SERVER SCHEDULER "pmix.srv.sched" (bool)
25
                        Server is supporting system scheduler and desires access to appropriate WLM-supporting features.
26
                        Indicates that the library is to be initialized for scheduler support.
27
                 The following attributes may be returned in response to fabric-specific APIs or queries (e.g., PMIx_Get or
28
                 PMIx Query info). These attributes are not related to a specific data realm (as described in Section 6.1) -
29
                 the PMIx Get function shall therefore ignore the value in its proc process identifier argument when
30
                 retrieving these values.
31
                 PMIX FABRIC COST MATRIX "pmix.fab.cm" (pointer)
```

```
2
 3
 4
 5
 6
 7
 8
 9
10
11
12
13
14
15
16
17
18
19
20
21
22
23
24
25
26
27
28
29
30
31
32
33
34
35
36
37
38
39
40
41
42
43
```

Pointer to a two-dimensional square array of point-to-point relative communication costs expressed as uint16_t values.

PMIX_FABRIC_GROUPS "pmix.fab.grps" (string)

A string delineating the group membership of nodes in the overall system, where each fabric group consists of the group number followed by a colon and a comma-delimited list of nodes in that group, with the groups delimited by semi-colons (e.g., 0:node000,node002,node004,node006; 1:node001,node003,node005,node007)

PMIX_FABRIC_PLANE "pmix.fab.plane" (string)

ID string of a fabric plane (e.g., CIDR for Ethernet). When used as a modifier in a request for information, specifies the plane whose information is to be returned. When used directly as a key in a request, returns a pmix_data_array_t of string identifiers for all fabric planes in the overall system.

PMIX_FABRIC_SWITCH "pmix.fab.switch" (string)

ID string of a fabric switch. When used as a modifier in a request for information, specifies the switch whose information is to be returned. When used directly as a key in a request, returns a **pmix_data_array_t** of string identifiers for all fabric switches in the overall system.

The following attributes may be returned in response to queries (e.g., PMIx_Get or PMIx_Query_info). A qualifier (e.g., PMIX_FABRIC_INDEX) identifying the fabric whose value is being referenced must be provided for queries on systems supporting more than one fabric when values for the non-default fabric are requested. These attributes are not related to a specific *data realm* (as described in Section 6.1) - the PMIx_Get function shall therefore ignore the value in its *proc* process identifier argument when retrieving these values.

PMIX FABRIC VENDOR "pmix.fab.vndr" (string)

Name of the vendor (e.g., Amazon, Mellanox, HPE, Intel) for the specified fabric.

PMIX_FABRIC_IDENTIFIER "pmix.fab.id" (string)

An identifier for the specified fabric (e.g., MgmtEthernet, Slingshot-11, OmniPath-1).

```
PMIX_FABRIC_INDEX "pmix.fab.idx" (size_t)
```

The index of the fabric as returned in **pmix fabric t**.

PMIX FABRIC NUM DEVICES "pmix.fab.nverts" (size t)

Total number of fabric devices in the overall system - corresponds to the number of rows or columns in the cost matrix.

PMIX_FABRIC_DIMS "pmix.fab.dims" (uint32_t)

Number of dimensions in the specified fabric plane/view. If no plane is specified in a request, then the dimensions of all planes in the overall system will be returned as a **pmix_data_array_t** containing an array of **uint32_t** values. Default is to provide dimensions in *logical* view.

PMIX FABRIC SHAPE "pmix.fab.shape" (pmix_data_array_t*)

The size of each dimension in the specified fabric plane/view, returned in a <code>pmix_data_array_t</code> containing an array of <code>uint32_t</code> values. The size is defined as the number of elements present in that dimension - e.g., the number of devices in one dimension of a physical view of a fabric plane. If no plane is specified, then the shape of each plane in the overall system will be returned in a <code>pmix_data_array_t</code> array where each element is itself a two-element array containing the <code>PMIX_FABRIC_PLANE</code> followed by that plane's fabric shape. Default is to provide the shape in <code>logical</code> view.

PMIX_FABRIC_SHAPE_STRING "pmix.fab.shapestr" (string)

1 Network shape expressed as a string (e.g., "10x12x2"). If no plane is specified, then the shape of 2 each plane in the overall system will be returned in a pmix data array t array where each 3 element is itself a two-element array containing the PMIX FABRIC PLANE followed by that plane's 4 fabric shape string. Default is to provide the shape in logical view. 5 The following attributes are related to the *node realm* (as described in Section 6.1.5) and are retrieved 6 according to those rules. 7 PMIX_FABRIC_DEVICES "pmix.fab.devs" (pmix_data_array_t) 8 Array of pmix info t containing information for all devices on the specified node. Each element of 9 the array will contain a PMIX_FABRIC_DEVICE entry, which in turn will contain an array of 10 information on a given device. PMIX_FABRIC_COORDINATES "pmix.fab.coords" (pmix_data_array_t) 11 12 Array of pmix_geometry_t fabric coordinates for devices on the specified node. The array will 13 contain the coordinates of all devices on the node, including values for all supported coordinate views. 14 The information for devices on the local node shall be provided if the node is not specified in the 15 request. 16 PMIX FABRIC DEVICE "pmix.fabdev" (pmix data array t) 17 An array of **pmix_info_t** describing a particular fabric device using one or more of the attributes 18 defined below. The first element in the array shall be the PMIX DEVICE ID of the device. PMIX FABRIC_DEVICE_INDEX "pmix.fabdev.idx" (uint32_t) 19 20 Index of the device within an associated communication cost matrix. 21 PMIX FABRIC DEVICE NAME "pmix.fabdev.nm" (string) 22 The operating system name associated with the device. This may be a logical fabric interface name 23 (e.g. "eth0" or "eno1") or an absolute filename. 24 PMIX_FABRIC_DEVICE_VENDOR "pmix.fabdev.vndr" (string) 25 Indicates the name of the vendor that distributes the device. 26 PMIX FABRIC DEVICE BUS TYPE "pmix.fabdev.btyp" (string) 27 The type of bus to which the device is attached (e.g., "PCI", "GEN-Z"). 28 PMIX FABRIC DEVICE VENDORID "pmix.fabdev.vendid" (string) 29 This is a vendor-provided identifier for the device or product. 30 PMIX_FABRIC_DEVICE_DRIVER "pmix.fabdev.driver" (string) 31 The name of the driver associated with the device. 32 PMIX FABRIC DEVICE FIRMWARE "pmix.fabdev.fmwr" (string) 33 The device's firmware version. 34 PMIX_FABRIC_DEVICE ADDRESS "pmix.fabdev.addr" (string) 35 The primary link-level address associated with the device, such as a MAC address. If multiple addresses are available, only one will be reported. 36 PMIX_FABRIC_DEVICE_COORDINATES "pmix.fab.coord" (pmix_geometry_t) 37 38 The pmix geometry t fabric coordinates for the device, including values for all supported 39 coordinate views. PMIX_FABRIC_DEVICE_MTU "pmix.fabdev.mtu" (size_t) 40 The maximum transfer unit of link level frames or packets, in bytes. 41 42 PMIX_FABRIC_DEVICE_SPEED "pmix.fabdev.speed" (size_t) 43 The active link data rate, given in bits per second. 44 PMIX FABRIC DEVICE STATE "pmix.fabdev.state" (pmix link state t)

1 2 3

The last available physical port state for the specified device. Possible values are **PMIX_LINK_STATE_UNKNOWN**, **PMIX_LINK_DOWN**, and **PMIX_LINK_UP**, to indicate if the port state is unknown or not applicable (unknown), inactive (down), or active (up).

PMIX_FABRIC_DEVICE_TYPE "pmix.fabdev.type" (string)

Specifies the type of fabric interface currently active on the device, such as Ethernet or InfiniBand.

PMIX_FABRIC_DEVICE_PCI_DEVID "pmix.fabdev.pcidevid" (string)

A node-level unique identifier for a PCI device. Provided only if the device is located on a PCI bus. The identifier is constructed as a four-part tuple delimited by colons comprised of the PCI 16-bit domain, 8-bit bus, 8-bit device, and 8-bit function IDs, each expressed in zero-extended hexadecimal form. Thus, an example identifier might be "abc1:0f:23:01". The combination of node identifier (PMIX_HOSTNAME or PMIX_NODEID) and PMIX_FABRIC_DEVICE_PCI_DEVID shall be unique within the overall system.

The following attributes are related to the *process realm* (as described in Section 6.1.4) and are retrieved according to those rules.

PMIX_FABRIC_ENDPT "pmix.fab.endpt" (pmix_data_array_t)

Fabric endpoints for a specified process. As multiple endpoints may be assigned to a given process (e.g., in the case where multiple devices are associated with a package to which the process is bound), the returned values will be provided in a pmix_data_array_t of pmix_endpoint_t elements.

The following attributes are related to the *job realm* (as described in Section 6.1.2) and are retrieved according to those rules. Note that distances to fabric devices are retrieved using the **PMIX_DEVICE_DISTANCES** key with the appropriate **pmix_device_type_t** qualifier.

PMIX_SWITCH_PEERS "pmix.speers" (pmix_data_array_t)

Peer ranks that share the same switch as the process specified in the call to PMIx_Get. Returns a pmix_data_array_t array of pmix_info_t results, each element containing the PMIX_SWITCH_PEERS key with a three-element pmix_data_array_t array of pmix_info_t containing the PMIX_DEVICE_ID of the local fabric device, the PMIX_FABRIC_SWITCH identifying the switch to which it is connected, and a comma-delimited string of peer ranks sharing the switch to which that device is connected.

14.4 Fabric Support Functions

The following APIs allow the WLM to request specific services from the fabric subsystem via the PMIx library.

-Advice to PMIx server hosts-

Due to their high cost in terms of execution, memory consumption, and interactions with other SMS components (e.g., a fabric manager), it is strongly advised that the underlying implementation of these APIs be restricted to a single PMIx server in a system that is supporting the SMS component responsible for the scheduling of allocations (i.e., the system <code>scheduler</code>). The <code>PMIX_SERVER_SCHEDULER</code> attribute can be used for this purpose to control the execution path. Clients, tools, and other servers utilizing these functions are advised to have their requests forwarded to the server supporting the scheduler using the <code>pmix_server_fabric_fn_t</code> server module function, as needed.

1 14.4.1 PMIx_Fabric_register

2 3	Summary Register for access to fabric-related information.
4 _{PMIx v4.0}	Format C
5 6 7 8	<pre>pmix_status_t PMIx_Fabric_register(pmix_fabric_t *fabric,</pre>
9 0 1 2 3	 INOUT fabric address of a pmix_fabric_t (backed by storage). User may populate the "name" field at will - PMIx does not utilize this field (handle) IN directives an optional array of values indicating desired behaviors and/or fabric to be accessed. If NULL, then the
14 15 16	highest priority available fabric will be used (array of handles) IN ndirs Number of elements in the <i>directives</i> array (integer)
17	Returns PMIX_SUCCESS or a negative value corresponding to a PMIx error constant.
	Required Attributes
18 19	The following directives are required to be supported by all PMIx libraries to aid users in identifying the fabric whose data is being sought:
20 21 22 23 24	PMIX_FABRIC_PLANE "pmix.fab.plane" (string) ID string of a fabric plane (e.g., CIDR for Ethernet). When used as a modifier in a request for information, specifies the plane whose information is to be returned. When used directly as a key in a request, returns a pmix_data_array_t of string identifiers for all fabric planes in the overall system.
25 26	<pre>PMIX_FABRIC_IDENTIFIER "pmix.fab.id" (string) An identifier for the specified fabric (e.g., MgmtEthernet, Slingshot-11, OmniPath-1).</pre>
27 28	PMIX_FABRIC_VENDOR "pmix.fab.vndr" (string) Name of the vendor (e.g., Amazon, Mellanox, HPE, Intel) for the specified fabric.

Description

Register for access to fabric-related information, including the communication cost matrix. This call must be made prior to requesting information from a fabric. The caller may request access to a particular fabric using the vendor, type, or identifier, or to a specific *fabric plane* via the **PMIX_FABRIC_PLANE** attribute - otherwise, information for the default fabric will be returned. Upon successful completion of the call, information will have been filled into the fields of the provided *fabric* structure.

For performance reasons, the PMIx library does not provide thread protection for accessing the information in the <code>pmix_fabric_t</code> structure. Instead, the PMIx implementation shall provide two methods for coordinating updates to the provided fabric information:

- Users may periodically poll for updates using the PMIx Fabric update API
- Users may register for PMIX_FABRIC_UPDATE_PENDING events indicating that an update to the cost matrix is pending. When received, users are required to terminate or pause any actions involving access to the cost matrix before returning from the event. Completion of the PMIX_FABRIC_UPDATE_PENDING event handler indicates to the PMIx library that the fabric object's entries are available for updating. This may include releasing and re-allocating memory as the number of vertices may have changed (e.g., due to addition or removal of one or more devices). When the update has been completed, the PMIx library will generate a PMIX_FABRIC_UPDATED event indicating that it is safe to begin using the updated fabric object(s).

There is no requirement that the caller exclusively use either one of these options. For example, the user may choose to both register for fabric update events, but poll for an update prior to some critical operation.

14.4.2 PMIx_Fabric_register_nb

Summary

Register for access to fabric-related information.

```
PMIx v4.0

pmix_status_t

pmix_fabric_register_nb(pmix_fabric_t *fabric,

const pmix_info_t directives[],

size_t ndirs,

pmix_op_cbfunc_t cbfunc, void *cbdata);

C
```

INOUT fabric

address of a **pmix_fabric_t** (backed by storage). User may populate the "name" field at will - PMIx does not utilize this field (handle)

IN directives

an optional array of values indicating desired behaviors and/or fabric to be accessed. If **NULL**, then the highest priority available fabric will be used (array of handles)

IN ndirs

Number of elements in the *directives* array (integer)

IN cbfunc

Callback function **pmix** op **cbfunc t** (function reference)

IN cbdata

1

2

3

4 5

6

7

8

9 10

11

12

13

14 15

19

20

21

22 23

24

25

26

27

28 29 Data to be passed to the callback function (memory reference)

Returns one of the following:

- PMIX_SUCCESS indicating that the request has been accepted for processing and the provided callback function will be executed upon completion of the operation. Note that the library must not invoke the callback function prior to returning from the API.
- a non-zero PMIx error constant indicating a reason for the request to have been rejected. In this case, the
 provided callback function will not be executed

Description

Non-blocking form of **PMIx_Fabric_register**. The caller is not allowed to access the provided **pmix_fabric_t** until the callback function has been executed, at which time the fabric information will have been loaded into the provided structure.

14.4.3 PMIx_Fabric_update

Summary

Update fabric-related information.

```
Format

pmix_status_t

PMIx_Fabric_update(pmix_fabric_t *fabric);

C
```

INOUT fabric

address of a pmix fabric t (backed by storage) (handle)

Returns **PMIX_SUCCESS** or a negative value corresponding to a PMIx error constant.

Description

Update fabric-related information. This call can be made at any time to request an update of the fabric information contained in the provided **pmix_fabric_t** object. The caller is not allowed to access the provided **pmix_fabric_t** until the call has returned. Upon successful return, the information fields in the *fabric* structure will have been updated.

14.4.4 PMIx Fabric update nb

Summary

Update fabric-related information.

1		Format C
2 3 4		<pre>pmix_status_t PMIx_Fabric_update_nb(pmix_fabric_t *fabric,</pre>
5 6 7 8 9		INOUT fabric address of a pmix_fabric_t (handle) IN cbfunc Callback function pmix_op_cbfunc_t (function reference) IN cbdata Data to be passed to the callback function (memory reference)
11		Returns one of the following:
12 13 14		• PMIX_SUCCESS indicating that the request has been accepted for processing and the provided callback function will be executed upon completion of the operation. Note that the library must not invoke the callback function prior to returning from the API.
15 16		• a non-zero PMIx error constant indicating a reason for the request to have been rejected. In this case, the provided callback function will not be executed
17 18 19 20		Description Non-blocking form of PMIx_Fabric_update. The caller is not allowed to access the provided pmix_fabric_t until the callback function has been executed, at which time the fields in the provided fabric structure will have been updated.
21	14.4.5	PMIx_Fabric_deregister
22 23		Summary Deregister a fabric object.
24	PMIx v4.0	Format C
25 26		<pre>pmix_status_t PMIx_Fabric_deregister(pmix_fabric_t *fabric);</pre>
27 28		<pre>IN fabric address of a pmix_fabric_t (handle)</pre>
29		Returns PMIX_SUCCESS or a negative value corresponding to a PMIx error constant.
30 31 32 33		Description Deregister a fabric object, providing an opportunity for the PMIx library to cleanup any information (e.g., cost matrix) associated with it. Contents of the provided pmix_fabric_t will be invalidated upon function return.

14.4.6 PMIx_Fabric_deregister_nb

2 3	Summary Deregister a fabric object.	
4 <i>PMIx v4.0</i>	Format C	
5 6 7	<pre>pmix_status_t PMIx_Fabric_deregister_nb(pmix_fabric_t *fabric,</pre>	
8 9 10 11 12	 IN fabric address of a pmix_fabric_t (handle) IN cbfunc Callback function pmix_op_cbfunc_t (function reference) IN cbdata Data to be passed to the callback function (memory reference) 	
14	Returns one of the following:	
15 16 17	 PMIX_SUCCESS indicating that the request has been accepted for processing and the provided callback function will be executed upon completion of the operation. Note that the library must not invoke the callback function prior to returning from the API. 	
18 19	• a non-zero PMIx error constant indicating a reason for the request to have been rejected. In this case, the provided callback function will not be executed	
20 21 22	Description Non-blocking form of PMIx_Fabric_deregister . Provided <i>fabric</i> must not be accessed until after callback function has been executed.	

CHAPTER 15

Security

PMIx utilizes a multi-layered approach toward security that differs for client versus tool processes. By definition, *client* processes must be preregistered with the PMIx server library via the PMIx_server_register_client API before they are spawned. This API requires that the host pass the expected effective UID/GID of the client process.

When the client attempts to connect to the PMIx server, the server shall use available standard OS methods to determine the effective UID/GID of the process requesting the connection. PMIx implementations shall not rely on any values reported by the client process itself. The effective UID/GID reported by the OS is compared to the values provided by the host during registration - if the values fail to match, the PMIx server is required to drop the connection request. This ensures that the PMIx server does not allow connection from a client that doesn't at least meet some minimal security requirement.

Once the requesting client passes the initial test, the PMIx server can, at the choice of the implementor, perform additional security checks. This may involve a variety of methods such as exchange of a system-provided key or credential. At the conclusion of that process, the PMIx server reports the client connection request to the host via the <code>pmix_server_client_connected2_fn_t</code> interface, if provided. The host may perform any additional checks and operations before responding with either <code>PMIX_SUCCESS</code> to indicate that the connection is approved, or a PMIx error constant indicating that the connection request is refused. In this latter case, the PMIx server is required to drop the connection.

Tools started by the host environment are classed as a subgroup of client processes and follow the client process procedure. However, tools that are not started by the host environment must be handled differently as registration information is not available prior to the connection request. In these cases, the PMIx server library is required to use available standard OS methods to get the effective UID/GID of the tool and report them upwards as part of invoking the <code>pmix_server_tool_connection_fn_t</code> interface, deferring initial security screening to the host. Host environments willing to accept tool connections must therefore both explicitly enable them via the <code>PMIX_SERVER_TOOL_SUPPORT</code> attribute, thereby confirming acceptance of the authentication and authorization burden, and provide the <code>pmix_server_tool_connection_fn_t</code> server module function pointer.

15.1 Obtaining Credentials

Applications and tools often interact with the host environment in ways that require security beyond just verifying the user's identity - e.g., access to that user's relevant authorizations. This is particularly important when tools connect directly to a system-level PMIx server that may be operating at a privileged level. A variety of system management software packages provide authorization services, but the lack of standardized interfaces makes portability problematic.

This section defines two PMIx client-side APIs for this purpose. These are most likely to be used by user-space applications/tools, but are not restricted to that realm.

15.1.1 PMIx_Get_credential

Format	C
pmix_status_t	
	pmix_info_t info[], size_t ninfo,
pmix_	_byte_object_t *credential);
	0
IN info	otumes (amove of homelles)
Array of pmix_info_t structure IN ninfo	etures (array of nancies)
Number of elements in the <i>info</i>	array (size_t)
<pre>IN credential</pre>	• • •
Address of a pmix_byte_ob	ject_t within which to return credential (handle)
Returns one of the following:	
PMIX SUCCESS, indicating that	the credential has been returned in the provided
pmix_byte_object_t	•
• a PMIx error constant indicating e	ither an error in the input or that the request is unsupported
—	Required Attributes
There are no required attributes for the	nis API. Note that implementations may choose to internally exec
	ments (e.g., directly contacting a <i>munge</i> server).
Implementations that support the operation but cannot directly process the client's request must pass any	
1	ent to the host environment for processing. In addition, the follow
attributes are required to be included	in the info array passed from the PMIx library to the host environ
<pre>PMIX_USERID "pmix.euid" (</pre>	uint32_t)
Effective user ID of the conne	ecting process.
PMIX_GRPID "pmix.egid" (u	int32_t)
Effective group ID of the con	
A	
~	Optional Attributes
The following attributes are optional	for host environments that support this operation:
PMIX_TIMEOUT "pmix.timeou	ut" (int)
	pecified operation should time out (zero indicating infinite) and re
DMTY FDD TTMFOIT error	. Care should be taken to avoid race conditions caused by multipl

1 Description

2

3

4

5

6

7

13

14

15

16

17

18

19

20

21

22

23

24

25

26

27 28

29

30 31

32

33

34

Request a credential from the PMIx server library or the host environment. The credential is returned as a <code>pmix_byte_object_t</code> to support potential binary formats - it is therefore opaque to the caller. No information as to the source of the credential is provided.

15.1.2 PMIx_Get_credential_nb

Summary

Request a credential from the PMIx server library or the host environment.

```
Format

pmix_status_t

pmix_Get_credential_nb(const pmix_info_t info[], size_t ninfo,

pmix_credential_cbfunc_t cbfunc,

void *cbdata);

C
```

IN info

Array of **pmix_info_t** structures (array of handles)

IN ninfo

Number of elements in the *info* array (size_t)

IN cbfunc

Callback function to return credential (pmix_credential_cbfunc_t function reference)

IN cbdata

Data to be passed to the callback function (memory reference)

Returns one of the following:

- PMIX_SUCCESS, indicating that the request has been communicated to the local PMIx server result will be returned in the provided *cbfunc*
- a PMIx error constant indicating either an error in the input or that the request is unsupported the *cbfunc* will *not* be called

Required Attributes

There are no required attributes for this API. Note that implementations may choose to internally execute integration for some security environments (e.g., directly contacting a *munge* server).

Implementations that support the operation but cannot directly process the client's request must pass any attributes that are provided by the client to the host environment for processing. In addition, the following attributes are required to be included in the *info* array passed from the PMIx library to the host environment:

```
PMIX_USERID "pmix.euid" (uint32_t)

Effective user ID of the connecting process.
```

PMIX_GRPID "pmix.egid" (uint32_t)

Effective group ID of the connecting process.

Optional Attributes

The following attributes are optional for host environments that support this operation:

PMIX_TIMEOUT "pmix.timeout" (int)

Time in seconds before the specified operation should time out (zero indicating infinite) and return the **PMIX_ERR_TIMEOUT** error. Care should be taken to avoid race conditions caused by multiple layers (client, server, and host) simultaneously timing the operation.

Description

1

2

3

4

5

6 7

8

9

10

11 12

13

14

15

16

17

18

19

20

21

23

24

Request a credential from the PMIx server library or the host environment. This version of the API is generally preferred in scenarios where the host environment may have to contact a remote credential service. Thus, provision is made for the system to return additional information (e.g., the identity of the issuing agent) outside of the credential itself and visible to the application.

15.1.3 Credential Attributes

The following attributes are defined to support credential operations:

PMIX_CRED_TYPE "pmix.sec.ctype" (char*)

When passed in **PMIx_Get_credential**, a prioritized, comma-delimited list of desired credential types for use in environments where multiple authentication mechanisms may be available. When returned in a callback function, a string identifier of the credential type.

PMIX_CRYPTO_KEY "pmix.sec.key" (pmix_byte_object_t)

Blob containing crypto key.

15.2 Validating Credentials

Given a credential, PMIx provides two methods by which a caller can request that the system validate it, returning any additional information (e.g., authorizations) conveyed within the credential.

22 15.2.1 PMIx_Validate_credential

Summary

Request validation of a credential by the PMIx server library or the host environment.

Effective group ID of the connecting process.

31

Optional Attributes

The following attributes are optional for host environments that support this operation:

```
PMIX_TIMEOUT "pmix.timeout" (int)
```

Time in seconds before the specified operation should time out (zero indicating infinite) and return the **PMIX_ERR_TIMEOUT** error. Care should be taken to avoid race conditions caused by multiple layers (client, server, and host) simultaneously timing the operation.

Description

Request validation of a credential by the PMIx server library or the host environment.

15.2.2 PMIx Validate credential nb

Summary

Request validation of a credential by the PMIx server library or the host environment. Provision is made for the system to return additional information regarding possible authorization limitations beyond simple authentication.

13 $_{PMIx \ v3.0}$ Format

1

2

3

4

5

6 7

8

9

10

11 12

14

15

16

17 18

19

20

21

22

23

24

25

26 27

28

29

30

31 32

33

34

35

IN cred

Pointer to pmix_byte_object_t containing the credential (handle)

IN info

Array of pmix_info_t structures (array of handles)

IN ninfo

Number of elements in the *info* array (size_t)

IN cbfunc

Callback function to return result (pmix validation cbfunc t function reference)

IN cbdata

Data to be passed to the callback function (memory reference)

Returns one of the following:

- PMIX_SUCCESS, indicating that the request has been communicated to the local PMIx server result will be returned in the provided *cbfunc*
- a PMIx error constant indicating either an error in the input or that the request is unsupported the *cbfunc* will *not* be called

Upon completion of processing the callback function will be executed. Note that the callback function must not be executed prior to return from the API.

Required Attributes There are no required attributes for this API. Note that implementations may choose to internally execute integration for some security environments (e.g., directly contacting a munge server). Implementations that support the operation but cannot directly process the client's request must pass any attributes that are provided by the client to the host environment for processing. In addition, the following attributes are required to be included in the info array passed from the PMIx library to the host environment: PMIX_USERID "pmix.euid" (uint32_t) Effective user ID of the connecting process. PMIX_GRPID "pmix.egid" (uint32_t) Effective group ID of the connecting process. Optional Attributes The following attributes are optional for host environments that support this operation: PMIX_TIMEOUT "pmix.timeout" (int) Time in seconds before the specified operation should time out (zero indicating infinite) and return the PMIX ERR TIMEOUT error. Care should be taken to avoid race conditions caused by multiple layers (client, server, and host) simultaneously timing the operation. **Description** Request validation of a credential by the PMIx server library or the host environment. This version of the API is generally preferred in scenarios where the host environment may have to contact a remote credential service. Provision is made for the system to return additional information (e.g., possible authorization limitations) beyond simple authentication.

1

3

4

5

6

7

8

9

10

11

12

13

14

15

16

17

18

CHAPTER 16

3

4

5

6

7

8

9

10

11

12

13

14

15

28

Server-Specific Interfaces

The process that hosts the PMIx server library interacts with that library in two distinct manners. First, PMIx 1 2 provides a set of APIs by which the host can request specific services from its library. This includes:

- collecting inventory to support scheduling algorithms,
- providing subsystems with an opportunity to precondition their resources for optimized application support,
- generating regular expressions,
- registering information to be passed to client processes, and
- requesting information on behalf of a remote process.

Note that the host always has access to all PMIx client APIs - the functions listed below are in addition to those available to a PMIx client.

Second, the host can provide a set of callback functions by which the PMIx server library can pass requests upward for servicing by the host. These include notifications of client connection and finalize, as well as requests by clients for information and/or services that the PMIx server library does not itself provide.

Server Initialization and Finalization 16.1

Initialization and finalization routines for PMIx servers.

16.1.1 PMIx_server_init

```
16
            Summary
17
```

Initialize the PMIx server.

```
Format
18 <sub>PMIx v1.0</sub>
19
                pmix status t
20
                PMIx_server_init(pmix_server_module_t *module,
21
                                    pmix_info_t info[], size_t ninfo);
22
                INOUT module
23
                     pmix server module t structure (handle)
24
                     info
25
                     Array of pmix_info_t structures (array of handles)
26
                IN
                    ninfo
27
                     Number of elements in the info array (size_t)
```

Returns **PMIX SUCCESS** or a negative value corresponding to a PMIx error constant.

	▼
1	The following attributes are required to be supported by all PMIx libraries:
2 3	PMIX_SERVER_NSPACE "pmix.srv.nspace" (char*) Name of the namespace to use for this PMIx server.
4 5	<pre>PMIX_SERVER_RANK "pmix.srv.rank" (pmix_rank_t) Rank of this PMIx server.</pre>
6 7 8	<pre>PMIX_SERVER_TMPDIR "pmix.srvr.tmpdir" (char*) Top-level temporary directory for all client processes connected to this server, and where the PMIx server will place its tool rendezvous point and contact information.</pre>
9 10 11	<pre>PMIX_SYSTEM_TMPDIR "pmix.sys.tmpdir" (char*) Temporary directory for this system, and where a PMIx server that declares itself to be a system-level server will place a tool rendezvous point and contact information.</pre>
12 13	<pre>PMIX_SERVER_TOOL_SUPPORT "pmix.srvr.tool" (bool) The host RM wants to declare itself as willing to accept tool connection requests.</pre>
14 15	<pre>PMIX_SERVER_SYSTEM_SUPPORT "pmix.srvr.sys" (bool) The host RM wants to declare itself as being the local system server for PMIx connection requests.</pre>
16 17	<pre>PMIX_SERVER_SESSION_SUPPORT "pmix.srvr.sess" (bool)</pre> The host RM wants to declare itself as being the local session server for PMIx connection requests.
18 19 20	<pre>PMIX_SERVER_GATEWAY "pmix.srv.gway" (bool) Server is acting as a gateway for PMIx requests that cannot be serviced on backend nodes (e.g., logging to email).</pre>
21 22 23	PMIX_SERVER_SCHEDULER "pmix.srv.sched" (bool) Server is supporting system scheduler and desires access to appropriate WLM-supporting features. Indicates that the library is to be initialized for scheduler support.
	▼ Optional Attributes
24	The following attributes are optional for implementers of PMIx libraries:
25 26 27	<pre>PMIX_USOCK_DISABLE "pmix.usock.disable" (bool) Disable legacy UNIX socket (usock) support. If the library supports Unix socket connections, this attribute may be supported for disabling it.</pre>
28 29 30	<pre>PMIX_SOCKET_MODE "pmix.sockmode" (uint32_t) POSIX mode_t (9 bits valid). If the library supports socket connections, this attribute may be supported for setting the socket mode.</pre>
31 32 33	<pre>PMIX_SINGLE_LISTENER "pmix.sing.listnr" (bool) Use only one rendezvous socket, letting priorities and/or environment parameters select the active transport.</pre>
34	<pre>PMIX_TCP_REPORT_URI "pmix.tcp.repuri" (char*)</pre>

If provided, directs that the TCP URI be reported and indicates the desired method of reporting: '-' 1 2 for stdout, '+' for stderr, or filename. If the library supports TCP socket connections, this attribute 3 may be supported for reporting the URI. 4 PMIX_TCP_IF_INCLUDE "pmix.tcp.ifinclude" (char*) 5 Comma-delimited list of devices and/or CIDR notation to include when establishing the TCP 6 connection. If the library supports TCP socket connections, this attribute may be supported for 7 specifying the interfaces to be used. 8 PMIX_TCP_IF_EXCLUDE "pmix.tcp.ifexclude" (char*) 9 Comma-delimited list of devices and/or CIDR notation to exclude when establishing the TCP connection. If the library supports TCP socket connections, this attribute may be supported for 10 specifying the interfaces that are not to be used. 11 12 PMIX TCP IPV4 PORT "pmix.tcp.ipv4" (int) The IPv4 port to be used.. If the library supports IPV4 connections, this attribute may be supported 13 14 for specifying the port to be used. PMIX_TCP_IPV6_PORT "pmix.tcp.ipv6" (int) 15 16 The IPv6 port to be used. If the library supports IPV6 connections, this attribute may be supported 17 for specifying the port to be used. 18 PMIX_TCP_DISABLE_IPV4 "pmix.tcp.disipv4" (bool) 19 Set to true to disable IPv4 family of addresses. If the library supports IPV4 connections, this 20 attribute may be supported for disabling it. 21 PMIX_TCP_DISABLE_IPV6 "pmix.tcp.disipv6" (bool) Set to true to disable IPv6 family of addresses. If the library supports IPV6 connections, this 22 23 attribute may be supported for disabling it. 24 PMIX SERVER REMOTE CONNECTIONS "pmix.srvr.remote" (bool) 25 Allow connections from remote tools. Forces the PMIx server to not exclusively use loopback device. 26 If the library supports connections from remote tools, this attribute may be supported for enabling or 27 disabling it. PMIX_EXTERNAL_PROGRESS "pmix.evext" (bool) 28 29 The host shall progress the PMIx library via calls to PMIx_Progress 30 PMIX_EVENT_BASE "pmix.evbase" (void*) 31 Pointer to an event base to use in place of the internal progress thread. All PMIx library events are 32 to be assigned to the provided event base. The event base must be compatible with the event library 33 used by the PMIx implementation - e.g., either both the host and PMIx library must use libevent, or 34 both must use libev. Cross-matches are unlikely to work and should be avoided - it is the responsibility 35 of the host to ensure that the PMIx implementation supports (and was built with) the appropriate event 36 library.

37

38

39

PMIX_TOPOLOGY2 "pmix.topo2" (pmix_topology_t)

PMIX SERVER SHARE TOPOLOGY "pmix.srvr.share" (bool)

Provide a pointer to an implementation-specific description of the local node topology.

1 The PMIx server is to share its copy of the local node topology (whether given to it or self-discovered) 2 with any clients. The PMIx server will perform the necessary actions to scalably expose the 3 description to the local clients. This includes creating any required shared memory backing stores and/ 4 or XML representations, plus ensuring that all necessary key-value pairs for clients to access the 5 description are included in the job-level information provided to each client. All required files are to be 6 installed under the effective PMIX SERVER TMPDIR directory. The PMIx server library is 7 responsible for cleaning up any artifacts (e.g., shared memory backing files or cached key-value pairs) 8 at library finalize. 9 PMIX SERVER ENABLE MONITORING "pmix.srv.monitor" (bool) 10 Enable PMIx internal monitoring by the PMIx server. 11 PMIX HOMOGENEOUS SYSTEM "pmix.homo" (bool) The nodes comprising the session are homogeneous - i.e., they each contain the same number of 12 13 identical packages, fabric interfaces, GPUs, and other devices. 14 PMIX_SINGLETON "pmix.singleton" (char*) 15 String representation (nspace.rank) of proc ID for the singleton the server was started to support PMIX_IOF_LOCAL_OUTPUT "pmix.iof.local" (bool) 16 17 Write output streams to local stdout/err **Description** 18 19 Initialize the PMIx server support library, and provide a pointer to a pmix_server_module_t structure 20 containing the caller's callback functions. The array of **pmix info** t structs is used to pass additional info 21 that may be required by the server when initializing. For example, it may include the 22 PMIX SERVER TOOL SUPPORT attribute, thereby indicating that the daemon is willing to accept 23 connection requests from tools. Advice to PMIx server hosts 24 Providing a value of **NULL** for the *module* argument is permitted, as is passing an empty *module* structure. 25 Doing so indicates that the host environment will not provide support for multi-node operations such as PMIx_Fence, but does intend to support local clients access to information. 26 16.1.2 PMIx server finalize 27 28 Summary 29 Finalize the PMIx server library. Format 30 PMIx v1.0 31 pmix status t 32 PMIx server finalize(void); 33 Returns **PMIX SUCCESS** or a negative value corresponding to a PMIx error constant.

1 Description

2

3

4 5

6

7

8

9

10

11

12

13 14

15

16

17

18

19

20

21

22

23

24

25

26

27

28

29

30

31

32

33

34

35

36

37

38

39

40

41

42

43

44

Finalize the PMIx server support library, terminating all connections to attached tools and any local clients. All memory usage is released.

16.1.3 Server Initialization Attributes

These attributes are used to direct the configuration and operation of the PMIx server library by passing them into PMIx_server_init.

```
PMIX_TOPOLOGY2 "pmix.topo2" (pmix_topology_t)
```

Provide a pointer to an implementation-specific description of the local node topology.

PMIX_SERVER_SHARE_TOPOLOGY "pmix.srvr.share" (bool)

The PMIx server is to share its copy of the local node topology (whether given to it or self-discovered) with any clients.

PMIX_USOCK_DISABLE "pmix.usock.disable" (bool)

Disable legacy UNIX socket (usock) support.

 ${\tt PMIX_SOCKET_MODE \ "pmix.sockmode" \ (uint32_t)}$

POSIX *mode_t* (9 bits valid).

PMIX_SINGLE_LISTENER "pmix.sing.listnr" (bool)

Use only one rendezvous socket, letting priorities and/or environment parameters select the active transport.

PMIX_SERVER_TOOL_SUPPORT "pmix.srvr.tool" (bool)

The host RM wants to declare itself as willing to accept tool connection requests.

PMIX SERVER REMOTE CONNECTIONS "pmix.srvr.remote" (bool)

Allow connections from remote tools. Forces the PMIx server to not exclusively use loopback device.

PMIX_SERVER_SYSTEM_SUPPORT "pmix.srvr.sys" (bool)

The host RM wants to declare itself as being the local system server for PMIx connection requests.

PMIX_SERVER_SESSION_SUPPORT "pmix.srvr.sess" (bool)

The host RM wants to declare itself as being the local session server for PMIx connection requests.

PMIX SERVER START TIME "pmix.srvr.strtime" (char*)

Time when the server started - i.e., when the server created it's rendezvous file (given in ctime string format).

PMIX_SERVER_TMPDIR "pmix.srvr.tmpdir" (char*)

Top-level temporary directory for all client processes connected to this server, and where the PMIx server will place its tool rendezvous point and contact information.

PMIX_SYSTEM_TMPDIR "pmix.sys.tmpdir" (char*)

Temporary directory for this system, and where a PMIx server that declares itself to be a system-level server will place a tool rendezvous point and contact information.

PMIX_SERVER_ENABLE_MONITORING "pmix.srv.monitor" (bool)

Enable PMIx internal monitoring by the PMIx server.

PMIX_SERVER_NSPACE "pmix.srv.nspace" (char*)

Name of the namespace to use for this PMIx server.

PMIX_SERVER_RANK "pmix.srv.rank" (pmix_rank_t)

Rank of this PMIx server.

PMIX_SERVER_GATEWAY "pmix.srv.gway" (bool)

Server is acting as a gateway for PMIx requests that cannot be serviced on backend nodes (e.g., logging to email).

1 PMIX_SERVER_SCHEDULER "pmix.srv.sched" (bool) 2 Server is supporting system scheduler and desires access to appropriate WLM-supporting features. 3 Indicates that the library is to be initialized for scheduler support. 4 PMIX EXTERNAL PROGRESS "pmix.evext" (bool) 5 The host shall progress the PMIx library via calls to PMIx_Progress 6 PMIX_HOMOGENEOUS_SYSTEM "pmix.homo" (bool) 7 The nodes comprising the session are homogeneous - i.e., they each contain the same number of 8 identical packages, fabric interfaces, GPUs, and other devices. 9 PMIX SINGLETON "pmix.singleton" (char*) (Provisional) 10 String representation (nspace.rank) of proc ID for the singleton the server was started to support

16.2 Server Support Functions

The following APIs allow the RM daemon that hosts the PMIx server library to request specific services from the PMIx library.

16.2.1 PMIx_generate_regex

Summary

11

12

13

15

16

20

21

22

23

24

25

26

27

28

29

30

31

32

33

34

35

36

Generate a compressed representation of the input string.

```
PMIx v1.0 Format

pmix_status_t

PMIx_generate_regex(const char *input, char **output);

C
```

IN input

String to process (string)

OUT output

Compressed representation of *input* (array of bytes)

Returns **PMIX SUCCESS** or a negative value corresponding to a PMIx error constant.

Description

Given a comma-separated list of *input* values, generate a reduced size representation of the input that can be passed down to the PMIx server library's **PMIx_server_register_nspace** API for parsing. The order of the individual values in the *input* string is preserved across the operation. The caller is responsible for releasing the returned data.

The precise compressed representations will be implementation specific. The regular expression itself is not required to be a printable string nor to obey typical string constraints (e.g., include a **NULL** terminator byte). However, all PMIx implementations are required to include a colon-delimited **NULL**-terminated string at the beginning of the output representation that can be printed for diagnostic purposes and identifies the method used to generate the representation. The following identifiers are reserved by the PMIx Standard:

• "raw:\0" - indicates that the expression following the identifier is simply the comma-delimited input string (no processing was performed).

- "pmix:\0" a PMIx-unique regular expression represented as a NULL-terminated string following the 1 2 identifier.
 - "blob:\0" a PMIx-unique regular expression that is not represented as a NULL-terminated string following the identifier. Additional implementation-specific metadata may follow the identifier along with the data itself. For example, a compressed binary array format based on the zlib compression package, with the size encoded in the space immediately following the identifier.

Communicating the resulting output should be done by first packing the returned expression using the PMIx_Data_pack, declaring the input to be of type PMIX_REGEX, and then obtaining the resulting blob to be communicated using the PMIX DATA BUFFER UNLOAD macro. The reciprocal method can be used on the remote end prior to passing the regex into PMIx_server_register_nspace. The pack/unpack routines will ensure proper handling of the data based on the regex prefix.

16.2.2 PMIx_generate_ppn

Summary

3

4 5

6

7

8

9

10

11

12

13 14

19

20

21

22

23

24

25 26

27

28

29

30

31

32 33 Generate a compressed representation of the input identifying the processes on each node.

```
15 <sub>PMIx v1.0</sub>
          Format
                        _____ C ____
16
          pmix status t
          PMIx_generate_ppn(const char *input, char **ppn);
17
                              ____ c ___
18
             input
```

String to process (string)

OUT ppn

Compressed representation of *input* (array of bytes)

Returns PMIX SUCCESS or a negative value corresponding to a PMIx error constant.

Description

The input shall consist of a semicolon-separated list of ranges representing the ranks of processes on each node of the job - e.g., "1-4; 2-5; 8, 10, 11, 12; 6, 7, 9". Each field of the input must correspond to the node name provided at that position in the input to PMIx_generate_regex. Thus, in the example, ranks 1-4 would be located on the first node of the comma-separated list of names provided to **PMIx_generate_regex**, and ranks 2-5 would be on the second name in the list.

Rules governing the format of the returned regular expression are the same as those specified for PMIx generate regex, as detailed here.

16.2.3 PMIx_server_register_nspace

Summary

Setup the data about a particular namespace.

1	Format C
2 3 4 5 6 7	<pre>pmix_status_t PMIx_server_register_nspace(const pmix_nspace_t nspace,</pre>
8	IN nspace
9	Character array of maximum size PMIX_MAX_NSLEN containing the namespace identifier (string) IN nlocalprocs
11 12 13	number of local processes (integer) IN info Array of info structures (array of handles)
14 15 16 17 18 19 20 21	IN ninfo Number of elements in the <i>info</i> array (integer) IN cbfunc Callback function pmix_op_cbfunc_t to be executed upon completion of the operation. A NULL function reference indicates that the function is to be executed as a blocking operation (function reference) IN cbdata Data to be passed to the callback function (memory reference)
22	Returns one of the following:
23 24 25	 PMIX_SUCCESS, indicating that the request is being processed by the host environment - result will be returned in the provided <i>cbfunc</i>. Note that the library must not invoke the callback function prior to returning from the API.
26 27	 PMIX_OPERATION_SUCCEEDED, indicating that the request was immediately processed and returned success - the cbfunc will not be called
28 29	• a PMIx error constant indicating either an error in the input or that the request was immediately processed and failed - the <i>cbfunc</i> will not be called
	Required Attributes
30	The following attributes are required to be supported by all PMIx libraries:
31 32	PMIX_REGISTER_NODATA "pmix.reg.nodata" (bool) Registration is for this namespace only, do not copy job data.
33 34 35	PMIX_SESSION_INFO_ARRAY "pmix.ssn.arr" (pmix_data_array_t) Provide an array of pmix_info_t containing session-realm information. The PMIX_SESSION_ID attribute is required to be included in the array.
36	<pre>PMIX_JOB_INFO_ARRAY "pmix.job.arr" (pmix_data_array_t)</pre>

Provide an array of <code>pmix_info_t</code> containing job-realm information. The <code>PMIX_SESSION_ID</code> attribute of the <code>session</code> containing the <code>job</code> is required to be included in the array whenever the PMIx server library may host multiple sessions (e.g., when executing with a host RM daemon). As information is registered one job (aka namespace) at a time via the

PMIX_server_register_nspace API, there is no requirement that the array contain either the **PMIX_NSPACE** or **PMIX_JOBID** attributes when used in that context (though either or both of them may be included). At least one of the job identifiers must be provided in all other contexts where the job being referenced is ambiguous.

PMIX_APP_INFO_ARRAY "pmix.app.arr" (pmix_data_array_t)

Provide an array of **pmix_info_t** containing application-realm information. The **PMIX_NSPACE** or **PMIX_JOBID** attributes of the *job* containing the application, plus its **PMIX_APPNUM** attribute, must to be included in the array when the array is *not* included as part of a call to **PMIx_server_register_nspace** - i.e., when the job containing the application is ambiguous. The job identification is otherwise optional.

PMIX_PROC_INFO_ARRAY "pmix.pdata" (pmix_data_array_t)

Provide an array of <code>pmix_info_t</code> containing process-realm information. The <code>PMIX_RANK</code> and <code>PMIX_NSPACE</code> attributes, or the <code>PMIX_PROCID</code> attribute, are required to be included in the array when the array is not included as part of a call to <code>PMIx_server_register_nspace-i.e.</code>, when the job containing the process is ambiguous. All three may be included if desired. When the array is included in some broader structure that identifies the job, then only the <code>PMIX_RANK</code> or the <code>PMIX_PROCID</code> attribute must be included (the others are optional).

PMIX_NODE_INFO_ARRAY "pmix.node.arr" (pmix_data_array_t)

Provide an array of <code>pmix_info_t</code> containing node-realm information. At a minimum, either the <code>PMIX_NODEID</code> or <code>PMIX_HOSTNAME</code> attribute is required to be included in the array, though both may be included.

Host environments are required to provide a wide range of session-, job-, application-, node-, and process-realm information, and may choose to provide a similarly wide range of optional information. The information is broadly separated into categories based on the *data realm* definitions explained in Section 6.1, and retrieved according to the rules detailed in Section 6.2.

Session-realm information may be passed as individual **pmix_info_t** entries, or as part of a **pmix_data_array_t** using the **PMIX_SESSION_INFO_ARRAY** attribute. The list of data referenced in this way shall include:

• PMIX_UNIV_SIZE "pmix.univ.size" (uint32_t)

Maximum number of process that can be simultaneously executing in a session. Note that this attribute is equivalent to the **PMIX_MAX_PROCS** attribute for the *session* realm - it is included in the PMIX Standard for historical reasons.

• PMIX_MAX_PROCS "pmix.max.size" (uint32_t)

Maximum number of processes that can be executed in the specified realm. Typically, this is a constraint imposed by a scheduler or by user settings in a hostfile or other resource description. Defaults to the *job* realm. Must be provided if **PMIX_UNIV_SIZE** is not given. Requires use of the **PMIX_SESSION_INFO** attribute to avoid ambiguity when retrieving it.

3	plus the following optional information:
4 5 6	 PMIX_CLUSTER_ID "pmix.clid" (char*) A string name for the cluster this allocation is on. As this information is not related to the namespace, it is best passed using the PMIx_server_register_resources API.
7 8 9	• PMIX_ALLOCATED_NODELIST "pmix.alist" (char*) Comma-delimited list or regular expression of all nodes in the specified realm regardless of whether or not they currently host processes. Defaults to the <i>job</i> realm.
10 11 12	• PMIX_RM_NAME "pmix.rm.name" (char*) String name of the RM. As this information is not related to the namespace, it is best passed using the PMIx_server_register_resources API.
13 14 15	 PMIX_RM_VERSION "pmix.rm.version" (char*) RM version string. As this information is not related to the namespace, it is best passed using the PMIx_server_register_resources API.
16 17 18	• PMIX_SERVER_HOSTNAME "pmix.srvr.host" (char*) Host where target PMIx server is located. As this information is not related to the namespace, it is best passed using the PMIx_server_register_resources API.
19 20 21	Job-realm information may be passed as individual <code>pmix_info_t</code> entries, or as part of a <code>pmix_data_array_t</code> using the <code>PMIX_JOB_INFO_ARRAY</code> attribute. The list of data referenced in this way shall include:
22 23 24	• PMIX_SERVER_NSPACE "pmix.srv.nspace" (char*) Name of the namespace to use for this PMIx server. Identifies the namespace of the PMIx server itself
25 26	• PMIX_SERVER_RANK "pmix.srv.rank" (pmix_rank_t) Rank of this PMIx server. Identifies the rank of the PMIx server itself.
27 28 29 30	 PMIX_NSPACE "pmix.nspace" (char*) Namespace of the job - may be a numerical value expressed as a string, but is often an alphanumeric string carrying information solely of use to the system. Required to be unique within the scope of the host environment. Identifies the namespace of the job being registered.
31 32 33	• PMIX_JOBID "pmix.jobid" (char*) Job identifier assigned by the scheduler to the specified job - may be identical to the namespace, but is often a numerical value expressed as a string (e.g., "12345.3").
34 35 36 37 38 39	• PMIX_JOB_SIZE "pmix.job.size" (uint32_t) Total number of processes in the specified job across all contained applications. Note that this value can be different from PMIX_MAX_PROCS. For example, users may choose to subdivide an allocation (running several jobs in parallel within it), and dynamic programming models may support adding and removing processes from a running job on-the-fly. In the latter case, PMIx events may be used to notify processes within the job that the job size has changed.

• PMIX_SESSION_ID "pmix.session.id" (uint32_t)

Session identifier assigned by the scheduler.

1

2 3 4 5	Maximum number of processes that can be executed in the specified realm. Typically, this is a constraint imposed by a scheduler or by user settings in a hostfile or other resource description. Defaults to the <i>job</i> realm. Retrieval of this attribute defaults to the job level unless an appropriate specification is given (e.g., PMIX_SESSION_INFO).
6 7 8	• PMIX_NODE_MAP "pmix.nmap" (char*) Regular expression of nodes currently hosting processes in the specified realm - see 16.2.3.2 for an explanation of its generation. Defaults to the <i>job</i> realm.
9 10 11	 PMIX_PROC_MAP "pmix.pmap" (char*) Regular expression describing processes on each node in the specified realm - see 16.2.3.2 for an explanation of its generation. Defaults to the <i>job</i> realm.
12	plus the following optional information:
13 14	• PMIX_NPROC_OFFSET "pmix.offset" (pmix_rank_t) Starting global rank of the specified job.
15 16 17	 PMIX_JOB_NUM_APPS "pmix.job.napps" (uint32_t) Number of applications in the specified job. This is a required attribute if more than one application is included in the job.
18 19 20 21	 PMIX_MAPBY "pmix.mapby" (char*) Process mapping policy - when accessed using PMIx_Get, use the PMIX_RANK_WILDCARD value for the rank to discover the mapping policy used for the provided namespace. Supported values are launcher specific.
22 23 24 25	 PMIX_RANKBY "pmix.rankby" (char*) Process ranking policy - when accessed using PMIx_Get, use the PMIX_RANK_WILDCARD value for the rank to discover the ranking algorithm used for the provided namespace. Supported values are launcher specific.
26 27 28 29	 PMIX_BINDTO "pmix.bindto" (char*) Process binding policy - when accessed using PMIx_Get, use the PMIX_RANK_WILDCARD value for the rank to discover the binding policy used for the provided namespace. Supported values are launcher specific.
30 31	• PMIX_HOSTNAME_KEEP_FQDN "pmix.fqdn" (bool) FQDNs are being retained by the PMIx library.
32 33 34	 PMIX_ANL_MAP "pmix.anlmap" (char*) Process map equivalent to PMIX_PROC_MAP expressed in Argonne National Laboratory's PMI-1/PMI-2 notation. Defaults to the job realm.
35 36	• PMIX_TDIR_RMCLEAN "pmix.tdir.rmclean" (bool) Resource Manager will cleanup assigned temporary directory trees.

• PMIX_MAX_PROCS "pmix.max.size" (uint32_t)

Blob containing crypto key.

• PMIX_CRYPTO_KEY "pmix.sec.key" (pmix_byte_object_t)

37

38

 If more than one application is included in the namespace, then the host environment is also required to supply data consisting of the following items for each application in the job, passed as a pmix_data_array_t using the PMIX APP INFO ARRAY attribute:

• PMIX APPNUM "pmix.appnum" (uint32_t)

The application number within the job in which the specified process is a member. This attribute must appear at the beginning of the array.

• PMIX_APP_SIZE "pmix.app.size" (uint32_t)

Number of processes in the specified application, regardless of their execution state - i.e., this number may include processes that either failed to start or have already terminated.

• PMIX_MAX_PROCS "pmix.max.size" (uint32_t)

Maximum number of processes that can be executed in the specified realm. Typically, this is a constraint imposed by a scheduler or by user settings in a hostfile or other resource description. Defaults to the *job* realm. Requires use of the **PMIX_APP_INFO** attribute to avoid ambiguity when retrieving it.

• PMIX_APPLDR "pmix.aldr" (pmix_rank_t)

Lowest rank in the specified application.

• PMIX_WDIR "pmix.wdir" (char*)

Working directory for spawned processes. This attribute is required for all registrations, but may be provided as an individual **pmix_info_t** entry if only one application is included in the namespace.

• PMIX_APP_ARGV "pmix.app.argv" (char*)

Consolidated argy passed to the spawn command for the given application (e.g., "./myapp arg1 arg2 arg3"). This attribute is required for all registrations, but may be provided as an individual pmix_info_t entry if only one application is included in the namespace.

plus the following optional information:

• PMIX_PSET_NAMES "pmix.pset.nms" (pmix_data_array_t*)

Returns an array of char* string names of the process sets in which the given process is a member.

• PMIX_APP_MAP_TYPE "pmix.apmap.type" (char*)

Type of mapping used to layout the application (e.g., cyclic). This attribute may be provided as an individual pmix info t entry if only one application is included in the namespace.

• PMIX_APP_MAP_REGEX "pmix.apmap.regex" (char*)

Regular expression describing the result of the process mapping. This attribute may be provided as an individual **pmix_info_t** entry if only one application is included in the namespace.

The data may also include attributes provided by the host environment that identify the programming model (as specified by the user) being executed within the application. The PMIx server library may utilize this information to customize the environment to fit that model (e.g., adding environmental variables specified by the corresponding standard for that model):

• PMIX_PROGRAMMING_MODEL "pmix.pgm.model" (char*)

Programming model being initialized (e.g., "MPI" or "OpenMP").

1 2	• PMIX_MODEL_LIBRARY_NAME "pmix.mdl.name" (char*) Programming model implementation ID (e.g., "OpenMPI" or "MPICH").
3 4	• PMIX_MODEL_LIBRARY_VERSION "pmix.mld.vrs" (char*) Programming model version string (e.g., "2.1.1").
5 6 7 8	Node-realm information may be passed as individual <code>pmix_info_t</code> entries if only one node will host processes from the job being registered, or as part of a <code>pmix_data_array_t</code> using the <code>pmix_NODE_INFO_ARRAY</code> attribute when multiple nodes are involved in the job. The list of data referenced in this way shall include:
9 10 11 12 13	 PMIX_NODEID "pmix.nodeid" (uint32_t) Node identifier expressed as the node's index (beginning at zero) in an array of nodes within the active session. The value must be unique and directly correlate to the PMIX_HOSTNAME of the node - i.e., users can interchangeably reference the same location using either the PMIX_HOSTNAME or corresponding PMIX_NODEID.
14 15 16 17 18	 PMIX_HOSTNAME "pmix.hname" (char*) Name of the host, as returned by the gethostname utility or its equivalent. As this information is not related to the namespace, it can be passed using the PMIx_server_register_resources API. However, either it or the PMIX_NODEID must be included in the array to properly identify the node.
19 20 21 22	 PMIX_HOSTNAME_ALIASES "pmix.alias" (char*) Comma-delimited list of names by which the target node is known. As this information is not related to the namespace, it is best passed using the PMIx_server_register_resources API.
23 24 25	• PMIX_LOCAL_SIZE "pmix.local.size" (uint32_t) Number of processes in the specified job or application realm on the caller's node. Defaults to job realm unless the PMIX_APP_INFO and the PMIX_APPNUM qualifiers are given.
26 27 28	 PMIX_NODE_SIZE "pmix.node.size" (uint32_t) Number of processes across all jobs executing upon the node, independent of whether the process has or will use PMIx.
29 30 31	 PMIX_LOCALLDR "pmix.lldr" (pmix_rank_t) Lowest rank within the specified job on the node (defaults to current node in absence of PMIX_HOSTNAME or PMIX_NODEID qualifier).
32 33 34	• PMIX_LOCAL_PEERS "pmix.lpeers" (char*) Comma-delimited list of ranks that are executing on the local node within the specified namespace – shortcut for PMIx_Resolve_peers for the local node.
35 36 37	• PMIX_NODE_OVERSUBSCRIBED "pmix.ndosub" (bool) True if the number of processes from this job on this node exceeds the number of slots allocated to it

plus the following information for the server's own node:

• PMIX_TMPDIR "pmix.tmpdir" (char*)

Full path to the top-level temporary directory assigned to the session.

38

39

8

9

10

11

15

22

29

• PMIX_NSDIR "pmix.nsdir" (char*)

Full path to the temporary directory assigned to the specified job, under PMIX TMPDIR.

• PMIX_LOCAL_PROCS "pmix.lprocs" (pmix_proc_t array)

Array of pmix proc t of all processes executing on the local node – shortcut for PMIx Resolve peers for the local node and a NULL namespace argument. The process identifier is ignored for this attribute.

The data may also include the following optional information for the server's own node:

• PMIX_LOCAL_CPUSETS "pmix.lcpus" (pmix_data_array_t)

A pmix_data_array_t array of string representations of the PU binding bitmaps applied to each local peer on the caller's node upon launch. Each string shall begin with the name of the library that generated it (e.g., "hwloc") followed by a colon and the bitmap string itself. The array shall be in the same order as the processes returned by PMIX_LOCAL_PEERS for that namespace.

• PMIX_AVAIL_PHYS_MEMORY "pmix.pmem" (uint64_t)

Total available physical memory on a node. As this information is not related to the namespace, it can be passed using the PMIx server register resources API.

and the following optional information for other nodes:

• PMIX MAX PROCS "pmix.max.size" (uint32_t)

Maximum number of processes that can be executed in the specified realm. Typically, this is a constraint imposed by a scheduler or by user settings in a hostfile or other resource description. Defaults to the job realm. Requires use of the PMIX NODE INFO attribute to avoid ambiguity when retrieving it.

Process-realm information shall include the following data for each process in the job, passed as a pmix data array t using the PMIX PROC INFO ARRAY attribute:

- PMIX RANK "pmix.rank" (pmix rank t)
 - Process rank within the job, starting from zero.
- PMIX APPNUM "pmix.appnum" (uint32_t)

The application number within the job in which the specified process is a member. This attribute may be omitted if only one application is present in the namespace.

• PMIX_APP_RANK "pmix.apprank" (pmix_rank_t)

Rank of the specified process within its application. This attribute may be omitted if only one application is present in the namespace.

• PMIX_GLOBAL_RANK "pmix.grank" (pmix_rank_t)

Rank of the specified process spanning across all jobs in this session, starting with zero. Note that no ordering of the jobs is implied when computing this value. As jobs can start and end at random times, this is defined as a continually growing number - i.e., it is not dynamically adjusted as individual jobs and processes are started or terminated.

• PMIX_LOCAL_RANK "pmix.lrank" (uint16_t)

Rank of the specified process on its node - refers to the numerical location (starting from zero) of the process on its node when counting only those processes from the same job that share the node, ordered by their overall rank within that job.

• PMIX_NODE_RANK "pmix.nrank" (uint16_t)

Rank of the specified process on its node spanning all jobs- refers to the numerical location (starting from zero) of the process on its node when counting all processes (regardless of job) that share the node, ordered by their overall rank within the job. The value represents a snapshot in time when the specified process was started on its node and is not dynamically adjusted as processes from other jobs are started or terminated on the node.

• PMIX_NODEID "pmix.nodeid" (uint32_t)

Node identifier expressed as the node's index (beginning at zero) in an array of nodes within the active session. The value must be unique and directly correlate to the **PMIX_HOSTNAME** of the node - i.e., users can interchangeably reference the same location using either the **PMIX HOSTNAME** or corresponding **PMIX NODEID**.

• PMIX_REINCARNATION "pmix.reinc" (uint32_t)

Number of times this process has been re-instantiated - i.e, a value of zero indicates that the process has never been restarted. 5

• PMIX_SPAWNED "pmix.spawned" (bool)

true if this process resulted from a call to PMIx_Spawn. Lack of inclusion (i.e., a return status of PMIX ERR NOT FOUND) corresponds to a value of false for this attribute.

plus the following information for processes that are local to the server:

• PMIX_LOCALITY_STRING "pmix.locstr" (char*)

String describing a process's bound location - referenced using the process's rank. The string is prefixed by the implementation that created it (e.g., "hwloc") followed by a colon. The remainder of the string represents the corresponding locality as expressed by the underlying implementation. The entire string must be passed to <code>PMIx_Get_relative_locality</code> for processing. Note that hosts are only required to provide locality strings for local client processes - thus, a call to <code>PMIx_Get</code> for the locality string of a process that returns <code>PMIX_ERR_NOT_FOUND</code> indicates that the process is not executing on the same node.

• PMIX_PROCDIR "pmix.pdir" (char*)

Full path to the subdirectory under **PMIX NSDIR** assigned to the specified process.

• PMIX_PACKAGE_RANK "pmix.pkgrank" (uint16_t)

Rank of the specified process on the *package* where this process resides - refers to the numerical location (starting from zero) of the process on its package when counting only those processes from the same job that share the package, ordered by their overall rank within that job. Note that processes that are not bound to PUs within a single specific package cannot have a package rank.

and the following optional information - note that some of this information can be derived from information already provided by other attributes, but it may be included here for ease of retrieval by users:

• PMIX_HOSTNAME "pmix.hname" (char*)

Name of the host, as returned by the **gethostname** utility or its equivalent.

• PMIX_CPUSET "pmix.cpuset" (char*)

A string representation of the PU binding bitmap applied to the process upon launch. The string shall begin with the name of the library that generated it (e.g., "hwloc") followed by a colon and the bitmap string itself.

The number of local processes for any given namespace is generally fixed at the time of application launch. Calls to **PMIx_Spawn** result in processes launched in their own namespace, not that of their parent. However, it is possible for processes to *migrate* to another node via a call to **PMIx_Job_control_nb**, thus resulting in a change to the number of local processes on both the initial node and the node to which the process moved. It is therefore critical that applications not migrate processes without first ensuring that PMIx-based collective operations are not in progress, and that no such operations be initiated until process migration has completed.

25

26

16.2.3.1 Namespace registration attributes

The following attributes are defined specifically for use with the PMIx_server_register_nspace API: PMIX_REGISTER_NODATA "pmix.reg.nodata" (bool)

Registration is for this namespace only, do not copy job data.

The following attributes are used to assemble information according to its data realm (session, job, application, node, or process as defined in Section 6.1) for registration where ambiguity may exist - see 16.2.3.2 for examples of their use.

PMIX SESSION INFO ARRAY "pmix.ssn.arr" (pmix data array t)

Provide an array of pmix_info_t containing session-realm information. The PMIX_SESSION_ID attribute is required to be included in the array.

PMIX JOB INFO ARRAY "pmix.job.arr" (pmix data_array_t)

Provide an array of pmix info t containing job-realm information. The PMIX SESSION ID attribute of the session containing the job is required to be included in the array whenever the PMIx server library may host multiple sessions (e.g., when executing with a host RM daemon). As information is registered one job (aka namespace) at a time via the

PMIx server register nspace API, there is no requirement that the array contain either the PMIX NSPACE or PMIX JOBID attributes when used in that context (though either or both of them may be included). At least one of the job identifiers must be provided in all other contexts where the job being referenced is ambiguous.

PMIX_APP_INFO_ARRAY "pmix.app.arr" (pmix_data_array_t)

Provide an array of pmix info t containing application-realm information. The PMIX NSPACE or PMIX JOBID attributes of the job containing the application, plus its PMIX APPNUM attribute, must to be included in the array when the array is *not* included as part of a call to

PMIx_server_register_nspace - i.e., when the job containing the application is ambiguous. The job identification is otherwise optional.

PMIX PROC INFO ARRAY "pmix.pdata" (pmix_data_array_t)

Provide an array of pmix info t containing process-realm information. The PMIX RANK and PMIX_NSPACE attributes, or the PMIX_PROCID attribute, are required to be included in the array when the array is not included as part of a call to PMIx server register nspace - i.e., when the job containing the process is ambiguous. All three may be included if desired. When the array is included in some broader structure that identifies the job, then only the PMIX RANK or the **PMIX_PROCID** attribute must be included (the others are optional).

PMIX_NODE_INFO_ARRAY "pmix.node.arr" (pmix_data_array_t)

Provide an array of pmix info t containing node-realm information. At a minimum, either the PMIX_NODEID or PMIX_HOSTNAME attribute is required to be included in the array, though both may be included.

Note that these assemblages can be used hierarchically:

- a PMIX JOB INFO ARRAY might contain multiple PMIX APP INFO ARRAY elements, each describing values for a specific application within the job.
- a PMIX_JOB_INFO_ARRAY could contain a PMIX_NODE_INFO_ARRAY for each node hosting processes from that job, each array describing job-level values for that node.
- a PMIX_SESSION_INFO_ARRAY might contain multiple PMIX_JOB_INFO_ARRAY elements, each describing a job executing within the session. Each job array could, in turn, contain both application and

1 2

3

4

5

6

7

8

9

10

11

12

13

14

15

16

17

18 19

20

21

22

23

24 25

26

27

28

29

30

31

32

33

34

35

36

37

38

39

40

41

42

node arrays, thus providing a complete picture of the active operations within the allocation.

Advice to PMIx library implementers

PMIx implementations must be capable of properly parsing and storing any hierarchical depth of information arrays. The resulting stored values are must to be accessible via both **PMIx_Get** and **PMIx_Query_info_nb** APIs, assuming appropriate directives are provided by the caller.

16.2.3.2 Assembling the registration information

The following description is not intended to represent the actual layout of information in a given PMIx library. Instead, it is describes how information provided in the *info* parameter of the <code>PMIx_server_register_nspace</code> shall be organized for proper processing by a PMIx server library. The ordering of the various information elements is arbitrary - they are presented in a top-down hierarchical form solely for clarity in reading.

Advice to PMIx server hosts

Creating the *info* array of data requires knowing in advance the number of elements required for the array. This can be difficult to compute and somewhat fragile in practice. One method for resolving the problem is to create a linked list of objects, each containing a single <code>pmix_info_t</code> structure. Allocation and manipulation of the list can then be accomplished using existing standard methods. Upon completion, the final *info* array can be allocated based on the number of elements on the list, and then the values in the list object <code>pmix_info_t</code> structures transferred to the corresponding array element utilizing the <code>PMIx_Info_xfer</code> API.

A common building block used in several areas is the construction of a regular expression identifying the nodes involved in that area - e.g., the nodes in a *session* or *job*. PMIx provides several tools to facilitate this operation, beginning by constructing an argv-like array of node names. This array is then passed to the <code>PMIx_generate_regex</code> function to create a regular expression parseable by the PMIx server library, as shown below:

```
4
 5
 6
 7
 8
 9
10
11
12
13
14
15
16
17
18
19
20
21
22
23
24
25
26
27
28
29
30
31
32
33
34
35
```

37

38

1

2

3

```
char **nodes = NULL;
char *nodelist;
char *regex;
size t n;
pmix_status_t rc;
pmix_info_t info;
/* loop over an array of nodes, adding each
 * name to the array */
for (n=0; n < num_nodes; n++) {</pre>
    /* filter the nodes to ignore those not included
     * in the target range (session, job, etc.). In
     * this example, all nodes are accepted */
    PMIX_ARGV_APPEND(&nodes, node[n]->name);
}
/* join into a comma-delimited string */
nodelist = PMIX_ARGV_JOIN(nodes, ',');
/* release the array */
PMIX_ARGV_FREE (nodes);
/* generate regex */
rc = PMIx_generate_regex(nodelist, &regex);
/* release list */
free(nodelist);
/* pass the regex as the value to the PMIX NODE MAP key */
PMIx_Info_load(&info, PMIX_NODE_MAP, regex, PMIX_REGEX);
/* release the regex */
free (regex);
```

Changing the filter criteria allows the construction of node maps for any level of information. A description of the returned regular expression is provided here.

A similar method is used to construct the map of processes on each node from the namespace being registered. This may be done for each information level of interest (e.g., to identify the process map for the entire *job* or for each *application* in the job) by changing the search criteria. An example is shown below for the case of creating the process map for a *job*:

```
1
             char **ndppn;
2
             char rank[30];
3
             char **ppnarray = NULL;
4
             char *ppn;
5
             char *localranks;
6
             char *regex;
7
             size t n, m;
8
             pmix_status_t rc;
9
             pmix_info_t info;
10
11
             /* loop over an array of nodes */
12
             for (n=0; n < num_nodes; n++) {</pre>
13
                 /* for each node, construct an array of ranks on that node */
14
                 ndppn = NULL;
15
                 for (m=0; m < node[n]->num_procs; m++) {
16
                      /* ignore processes that are not part of the target job */
17
                      if (!PMIX_CHECK_NSPACE(targetjob, node[n] -> proc[m].nspace)) {
18
                          continue;
19
20
                      snprintf(rank, 30, "%d", node[n]->proc[m].rank);
21
                      PMIX_ARGV_APPEND(&ndppn, rank);
22
                 }
23
                 /* convert the array into a comma-delimited string of ranks */
24
                 localranks = PMIX_ARGV_JOIN(ndppn, ',');
25
                 /* release the local array */
26
                 PMIX_ARGV_FREE (ndppn);
27
                 /* add this node's contribution to the overall array */
28
                 PMIX_ARGV_APPEND(&ppnarray, localranks);
29
                 /* release the local list */
30
                 free(localranks);
31
             }
32
33
             /* join into a semicolon-delimited string */
34
             ppn = PMIX_ARGV_JOIN(ppnarray, ';');
35
36
             /* release the array */
37
             PMIX_ARGV_FREE (ppnarray);
38
39
             /* generate ppn regex */
40
             rc = PMIx_generate_ppn(ppn, &regex);
41
42
             /* release list */
43
             free (ppn);
44
45
             /* pass the regex as the value to the PMIX_PROC_MAP key */
46
             PMIx_Info_load(&info, PMIX_PROC_MAP, regex, PMIX_REGEX);
```

/* release the regex */
free(regex);

Note that the PMIX_NODE_MAP and PMIX_PROC_MAP attributes are linked in that the order of entries in the process map must match the ordering of nodes in the node map - i.e., there is no provision in the PMIx process map regular expression generator/parser pair supporting an out-of-order node or a node that has no corresponding process map entry (e.g., a node with no processes on it). Armed with these tools, the registration *info* array can be constructed as follows:

• Session-level information includes all session-specific values. In many cases, only two values (PMIX_SESSION_ID and PMIX_UNIV_SIZE) are included in the registration array. Since both of these values are session-specific, they can be specified independently - i.e., in their own pmix_info_t elements of the info array. Alternatively, they can be provided as a pmix_data_array_t array of pmix_info_t using the PMIX_SESSION_INFO_ARRAY attribute and identified by including the PMIX_SESSION_ID attribute in the array - this is required in cases where non-specific attributes (e.g., PMIX_NUM_NODES or PMIX_NODE_MAP) are passed to describe aspects of the session. Note that the node map can include nodes not used by the job being registered as no corresponding process map is specified.

The *info* array at this point might look like (where the labels identify the corresponding attribute - e.g., "Session ID" corresponds to the **PMIX_SESSION_ID** attribute):




Figure 16.1.: Session-level information elements

• Job-level information includes all job-specific values such as PMIX_JOB_SIZE, PMIX_JOB_NUM_APPS, and PMIX_JOBID. Since each invocation of PMIx_server_register_nspace describes a single job, job-specific values can be specified independently - i.e., in their own pmix_info_t elements of the info array. Alternatively, they can be provided as a pmix_data_array_t array of pmix_info_t identified by the PMIX_JOB_INFO_ARRAY attribute - this is required in cases where non-specific attributes (e.g., PMIX_NODE_MAP) are passed to describe aspects of the job. Note that since the invocation only involves a single namespace, there is no need to include the PMIX_NSPACE attribute in the array.

Upon conclusion of this step, the *info* array might look like:

Note that in this example, **PMIX_NUM_NODES** is not required as that information is contained in the **PMIX_NODE_MAP** attribute. Similarly, **PMIX_JOB_SIZE** is not technically required as that information is contained in the **PMIX_PROC_MAP** when combined with the corresponding node map - however, there is no issue with including the job size as a separate entry.




Figure 16.2.: Job-level information elements

The example also illustrates the hierarchical use of the PMIX_NODE_INFO_ARRAY attribute. In this case, we have chosen to pass several job-related values for each node - since those values are non-unique across the job, they must be passed in a node-info container. Note that the choice of what information to pass into the PMIx server library versus what information to derive from other values at time of request is left to the host environment. PMIx implementors in turn may, if they choose, pre-parse registration data to create expanded views (thus enabling faster response to requests at the expense of memory footprint) or to compress views into tighter representations (thus trading minimized footprint for longer response times).

Application-level information includes all application-specific values such as PMIX_APP_SIZE and PMIX_APPLDR. If the job contains only a single application, then the application-specific values can be specified independently - i.e., in their own pmix_info_t elements of the info array - or as a pmix_data_array_t array of pmix_info_t using the PMIX_APP_INFO_ARRAY attribute and identifed by including the PMIX_APPNUM attribute in the array. Use of the array format is must in cases where non-specific attributes (e.g., PMIX_NODE_MAP) are passed to describe aspects of the application.

However, in the case of a job consisting of multiple applications, all application-specific values for each application must be provided using the PMIX_APP_INFO_ARRAY format, each identified by its PMIX_APPNUM value.

Upon conclusion of this step, the *info* array might look like that shown in 16.3, assuming there are two




Figure 16.3.: Application-level information elements

- Process-level information includes an entry for each process in the job being registered, each entry marked with the PMIX PROC INFO ARRAY attribute. The rank of the process must be the first entry in the array - this provides efficiency when storing the data. Upon conclusion of this step, the info array might look like the diagram in 16.4:
- For purposes of this example, node-level information only includes values describing the local node i.e., it does not include information about other nodes in the job or session. In many cases, the values included in this level are unique to it and can be specified independently - i.e., in their own pmix info t elements of the info array. Alternatively, they can be provided as a pmix_data_array_t array of pmix_info_t using the PMIX_NODE_INFO_ARRAY attribute - this is required in cases where non-specific attributes are passed to describe aspects of the node, or where values for multiple nodes are being provided.

The node-level information requires two elements that must be constructed in a manner similar to that used for the node map. The PMIX LOCAL PEERS value is computed based on the processes on the local node, filtered to select those from the job being registered, as shown below using the tools provided by PMIx:

Job

App

App

Proc

Proc

Univ

1

2

3

4

5

6 7

8

9

10

11 12

13

14

15

16

Session

Figure 16.4.: Process-level information elements

```
char **ndppn = NULL;
char rank[30];
char *localranks;
size_t m;
pmix_info_t info;

for (m=0; m < mynode->num_procs; m++) {
    /* ignore processes that are not part of the target job */
    if (!PMIX_CHECK_NSPACE(targetjob,mynode->proc[m].nspace)) {
        continue;
    }
    snprintf(rank, 30, "%d", mynode->proc[m].rank);
    PMIX_ARGV_APPEND(&ndppn, rank);
}
/* convert the array into a comma-delimited string of ranks */
localranks = PMIX_ARGV_JOIN(ndppn, ',');
```

```
/* release the local array */
PMIX_ARGV_FREE(ndppn);

/* pass the string as the value to the PMIX_LOCAL_PEERS key */
PMIx_Info_load(&info, PMIX_LOCAL_PEERS, localranks, PMIX_STRING);

/* release the list */
free(localranks);
```

The PMIX_LOCAL_CPUSETS value is constructed in a similar manner. In the provided example, it is assumed that an Hardware Locality (HWLOC) cpuset representation (a comma-delimited string of processor IDs) of the processors assigned to each process has previously been generated and stored on the process description. Thus, the value can be constructed as shown below:

```
char **ndcpus = NULL;
char *localcpus;
size t m;
pmix_info_t info;
for (m=0; m < mynode->num_procs; m++) {
    /* ignore processes that are not part of the target job */
    if (!PMIX_CHECK_NSPACE(targetjob,mynode->proc[m].nspace)) {
        continue;
    }
    PMIX_ARGV_APPEND(&ndcpus, mynode->proc[m].cpuset);
/* convert the array into a colon-delimited string */
localcpus = PMIX_ARGV_JOIN(ndcpus, ':');
/* release the local array */
PMIX ARGV FREE (ndcpus);
/* pass the string as the value to the PMIX LOCAL CPUSETS key */
PMIx_Info_load(&info, PMIX_LOCAL_CPUSETS, localcpus, PMIX_STRING);
/* release the list */
free(localcpus);
```

Note that for efficiency, these two values can be computed at the same time.

The final *info* array might therefore look like the diagram in 16.5:

16.2.4 PMIx_server_deregister_nspace

Summary

Deregister a namespace.




Figure 16.5.: Final information array

```
Format
 1
2
                 void PMIx_server_deregister_nspace(const pmix_nspace_t nspace,
3
                                                  pmix_op_cbfunc_t cbfunc, void *cbdata);
                 IN
4
                      nspace
5
                       Namespace (string)
6
                 IN
                       cbfunc
7
                       Callback function pmix_op_cbfunc_t. A NULL function reference indicates that the function is to
8
                       be executed as a blocking operation. (function reference)
9
                 IN
                       cbdata
10
                       Data to be passed to the callback function (memory reference)
11
                 Description
12
                 Deregister the specified nspace and purge all objects relating to it, including any client information from that
13
                 namespace. This is intended to support persistent PMIx servers by providing an opportunity for the host RM to
14
                 tell the PMIx server library to release all memory for a completed job. Note that the library must not invoke
```

the callback function prior to returning from the API, and that a **NULL** cbfunc reference indicates that the

function is to be executed as a blocking operation.

15

16.2.5 PMIx_server_register_resources

2 Summary 3 Register non-namespace related information with the local PMIx server library. **Format** ⁴ *PMIx v4.0* 5 pmix_status t 6 PMIx_server_register_resources(pmix_info_t info[], size_t ninfo, 7 pmix_op_cbfunc_t cbfunc, 8 void *cbdata); C 9 info IN 10 Array of info structures (array of handles) 11 12 Number of elements in the *info* array (integer) 13 IN cbfunc 14 Callback function pmix op cbfunc t. A NULL function reference indicates that the function is to 15 be executed as a blocking operation (function reference) 16 IN cbdata 17 Data to be passed to the callback function (memory reference) 18 **Description** 19 Pass information about resources not associated with a given namespace to the PMIx server library for 20 distribution to local client processes. This includes information on fabric devices, GPUs, and other resources. 21 All information provided through this API shall be made available to each job as part of its job-level 22 information. Duplicate information provided with the PMIx server register nspace API shall 23 override any information provided by this function for that namespace, but only for that specific namespace. —Advice to PMIx server hosts— 24 Note that information passed in this manner could also have been included in a call to 25 PMIx_server_register_nspace - e.g., as part of a PMIX_NODE_INFO_ARRAY array. This API is 26 provided as a logical alternative for code clarity, especially where multiple jobs may be supported by a single 27 PMIx server library instance, to avoid multiple registration of static resource information. 28 A **NULL** *cbfunc* reference indicates that the function is to be executed as a blocking operation.

16.2.6 PMIx_server_deregister_resources

Summary

Remove specified non-namespace related information from the local PMIx server library.

29 30

31

1	Format C
2	pmix_status_t
3	PMIx_server_deregister_resources(pmix_info_t info[], size_t ninfo,
4	pmix_op_cbfunc_t cbfunc,
5	void *cbdata);
3	C
6	IN info
7	Array of info structures (array of handles)
8	IN ninfo
9	Number of elements in the <i>info</i> array (integer)
10	IN cbfunc
11	Callback function pmix_op_cbfunc_t. A NULL function reference indicates that the function is to
12	be executed as a blocking operation (function reference)
13	IN cbdata
14	Data to be passed to the callback function (memory reference)
15	Description
16	Remove information about resources not associated with a given namespace from the PMIx server library.
17	Only the <i>key</i> fields of the provided <i>info</i> array shall be used for the operation - the associated values shall be
18	ignored except where they serve as qualifiers to the request. For example, to remove a specific fabric device
19	from a given node, the <i>info</i> array might include a PMIX_NODE_INFO_ARRAY containing the
20	PMIX_NODEID or PMIX_HOSTNAME identifying the node hosting the device, and the
21	PMIX_FABRIC_DEVICE_NAME specifying the device to be removed. Alternatively, the device could be
22	removed using only the PMIX_DEVICE_ID as this is unique across the overall system.
	Advice to PMIx server hosts
23	As information not related to namespaces is considered <i>static</i> , there is no requirement that the host
	environment deregister resources prior to finalizing the PMIx server library. The server library shall properly
24 25	
26 26	cleanup as part of its normal finalize operations. Deregistration of resources is only required, therefore, when the host environment determines that client processes should no longer have access to that information.
_0	the nost environment determines that enem processes should no longer have access to that information.
27	A NULL <i>cbfunc</i> reference indicates that the function is to be executed as a blocking operation.

28 **16.2.7** PMIx_server_register_client

Summary

29

30

Register a client process with the PMIx server library.

32 33 34

31

35 36 37

38

Format

pmix status t

PMIx_server_register_client(const pmix_proc_t *proc, uid_t uid, gid_t gid, void *server object, pmix op cbfunc t cbfunc, void *cbdata);

proc pmix_proc_t structure (handle) IN user id (integer)

IN gid group id (integer)

IN server_object (memory reference)

IN cbfunc

> Callback function pmix_op_cbfunc_t. A NULL function reference indicates that the function is to be executed as a blocking operation (function reference)

IN cbdata

Data to be passed to the callback function (memory reference)

Returns one of the following:

- PMIX SUCCESS, indicating that the request is being processed by the host environment result will be returned in the provided cbfunc. Note that the library must not invoke the callback function prior to returning from the API.
- PMIX_OPERATION_SUCCEEDED, indicating that the request was immediately processed and returned success - the cbfunc will not be called
- a PMIx error constant indicating either an error in the input or that the request was immediately processed and failed - the cbfunc will not be called

Description

Register a client process with the PMIx server library.

The host server can also, if it desires, provide an object it wishes to be returned when a server function is called that relates to a specific process. For example, the host server may have an object that tracks the specific client. Passing the object to the library allows the library to provide that object to the host server during subsequent calls related to that client, such as a pmix server client connected2 fn t function. This allows the host server to access the object without performing a lookup based on the client's namespace and rank.

—Advice to PMIx server hosts—

Host environments are required to execute this operation prior to starting the client process. The expected user ID and group ID of the child process allows the server library to properly authenticate clients as they connect by requiring the two values to match. Accordingly, the detected user and group ID's of the connecting process are not included in the pmix_server_client_connected2_fn_t server module function.

Advice to PMIx library implementers 1 For security purposes, the PMIx server library should check the user and group ID's of a connecting process 2 against those provided for the declared client process identifier via the 3 PMIx server register client prior to completing the connection. 16.2.8 PMIx_server_deregister_client 4 Summary 5 6 Deregister a client and purge all data relating to it. **Format** PMIx v1.0void 8 9 PMIx server deregister client (const pmix proc t *proc, 10 pmix_op_cbfunc_t cbfunc, void *cbdata); C — 11 IN proc 12 pmix proc t structure (handle) IN 13 cbfunc 14 Callback function pmix op cbfunc t. A NULL function reference indicates that the function is to 15 be executed as a blocking operation (function reference) 16 IN cbdata 17 Data to be passed to the callback function (memory reference) 18 Description 19 The PMIx_server_deregister_nspace API will delete all client information for that namespace. The

PMIx server library will automatically perform that operation upon disconnect of all local clients. This API is

therefore intended primarily for use in exception cases, but can be called in non-exception cases if desired.

Note that the library must not invoke the callback function prior to returning from the API.

16.2.9 PMIx_server_setup_fork

Summary

20 21

22

23

24 25

Setup the environment of a child process to be forked by the host.

```
Format
 1
 2
                  pmix status t
 3
                  PMIx_server_setup_fork(const pmix_proc_t *proc,
 4
                                                   char ***env);
                  IN
 5
                       proc
 6
                       pmix_proc_t structure (handle)
 7
                  IN
                       env
 8
                       Environment array (array of strings)
 9
                  Returns PMIX_SUCCESS or a negative value corresponding to a PMIx error constant.
                  Description
10
                  Setup the environment of a child process to be forked by the host so it can correctly interact with the PMIx
11
12
                  server.
13
                  The PMIx client needs some setup information so it can properly connect back to the server. This function will
                  set appropriate environmental variables for this purpose, and will also provide any environmental variables
14
15
                  that were specified in the launch command (e.g., via PMIx_Spawn) plus other values (e.g., variables required
16
                  to properly initialize the client's fabric library).
                                                 Advice to PMIx server hosts—
17
                  Host environments are required to execute this operation prior to starting the client process.
```

16.2.10 PMIx_server_dmodex_request

Summary

Define a function by which the host server can request modex data from the local PMIx server.

18

pmix_status_t pmix_server_dmodex_request(const pmix_proc_t *proc, pmix_dmodex_response_fn_t cbfunc, void *cbdata); C

```
IN proc
    pmix_proc_t structure (handle)
IN cbfunc
    Callback function pmix_dmodex_response_fn_t (function reference)
IN cbdata
    Data to be passed to the callback function (memory reference)
```

Returns one of the following:

- PMIX_SUCCESS, indicating that the request is being processed by the host environment result will be
 returned in the provided *cbfunc*. Note that the library must not invoke the callback function prior to
 returning from the API.
- a PMIx error constant indicating an error in the input the *cbfunc* will not be called

Description

 Define a function by which the host server can request modex data from the local PMIx server. Traditional wireup procedures revolve around the per-process posting of data (e.g., location and endpoint information) via the PMIx_Put and PMIx_Commit functions followed by a PMIx_Fence barrier that globally exchanges the posted information. However, the barrier operation represents a significant time impact at large scale.

PMIx supports an alternative wireup method known as *Direct Modex* that replaces the barrier-based exchange of all process-posted information with on-demand fetch of a peer's data. In place of the barrier operation, data posted by each process is cached on the local PMIx server. When a process requests the information posted by a particular peer, it first checks the local cache to see if the data is already available. If not, then the request is passed to the local PMIx server, which subsequently requests that its RM host request the data from the RM daemon on the node where the specified peer process is located. Upon receiving the request, the RM daemon passes the request into its PMIx server library using the PMIx_server_dmodex_request function, receiving the response in the provided *cbfunc* once the indicated process has posted its information. The RM daemon then returns the data to the requesting daemon, who subsequently passes the data to its PMIx server library for transfer to the requesting client.

Advice to users -

While direct modex allows for faster launch times by eliminating the barrier operation, per-peer retrieval of posted information is less efficient. Optimizations can be implemented - e.g., by returning posted information from all processes on a node upon first request - but in general direct modex remains best suited for sparsely connected applications.

16.2.10.1 Server Direct Modex Response Callback Function

The PMIx server dmodex request callback function.

```
Summary
 1
 2
                 Provide a function by which the local PMIx server library can return connection and other data posted by local
 3
                 application processes to the host resource manager.
 ^{4} PMIx v1.0
 5
                 typedef void (*pmix_dmodex_response_fn_t)(
 6
                                          pmix_status_t status,
 7
                                          char *data, size_t sz,
 8
                                          void *cbdata);
 9
                 IN
                      status
10
                      Returned status of the request (pmix_status_t)
11
                 IN
12
                      Pointer to a data "blob" containing the requested information (handle)
13
                 IN
                      Number of bytes in the data blob (integer)
14
                 IN
15
16
                      Data passed into the initial call to PMIx_server_dmodex_request (memory reference)
17
                 Description
18
                 Define a function to be called by the PMIx server library for return of information posted by a local application
                 process (via PMIx_Put with subsequent PMIx_Commit) in response to a request from the host RM. The
19
20
                 returned data blob is owned by the PMIx server library and will be free'd upon return from the function.
      16.2.11
                    PMIx server setup application
21
                 Summary
22
23
                 Provide a function by which a launcher can request application-specific setup data prior to launch of a job.
24 <sub>PMIx v2.0</sub>
                 Format
25
                 pmix_status_t
26
                PMIx_server_setup_application(const pmix_nspace_t nspace,
27
                                                pmix_info_t info[], size_t ninfo,
28
                                                pmix_setup_application_cbfunc_t cbfunc,
29
                                                void *cbdata);
30
                 IN
                      nspace
31
                      namespace (string)
32
                 IN
33
                      Array of info structures (array of handles)
34
                     ninfo
35
                      Number of elements in the info array (integer)
36
                 IN
37
                      Callback function pmix setup application cbfunc t (function reference)
```

IN 1 cbdata 2 Data to be passed to the *cbfunc* callback function (memory reference) 3 Returns one of the following: 4 • PMIX SUCCESS, indicating that the request is being processed by the host environment - result will be 5 returned in the provided cbfunc. Note that the library must not invoke the callback function prior to 6 returning from the API. 7 • a PMIx error constant indicating either an error in the input - the *cbfunc* will not be called _____ Required Attributes 8 PMIx libraries that support this operation are required to support the following: 9 PMIX_SETUP_APP_ENVARS "pmix.setup.env" (bool) Harvest and include relevant environmental variables. 10 11 PMIX_SETUP_APP_NONENVARS ""pmix.setup.nenv" (bool) Include all relevant data other than environmental variables. 12 13 PMIX SETUP APP ALL "pmix.setup.all" (bool) 14 Include all relevant data. 15 PMIX ALLOC FABRIC "pmix.alloc.net" (array) 16 Array of pmix_info_t describing requested fabric resources. This must include at least: 17 PMIX ALLOC FABRIC ID, PMIX ALLOC FABRIC TYPE, and 18 PMIX ALLOC FABRIC ENDPTS, plus whatever other descriptors are desired. 19 PMIX_ALLOC_FABRIC_ID "pmix.alloc.netid" (char*) 20 The key to be used when accessing this requested fabric allocation. The fabric allocation will be returned/stored as a pmix_data_array_t of pmix_info_t whose first element is composed of 21 22 this key and the allocated resource description. The type of the included value depends upon the fabric 23 support. For example, a TCP allocation might consist of a comma-delimited string of socket ranges 24 such as "32000-32100, 33005, 38123-38146". Additional array entries will consist of any 25 provided resource request directives, along with their assigned values. Examples include: 26 PMIX ALLOC FABRIC TYPE - the type of resources provided; PMIX ALLOC FABRIC PLANE -27 if applicable, what plane the resources were assigned from; PMIX ALLOC FABRIC OOS - the 28 assigned QoS; PMIX ALLOC BANDWIDTH - the allocated bandwidth; 29 PMIX ALLOC FABRIC SEC KEY - a security key for the requested fabric allocation. NOTE: the 30 array contents may differ from those requested, especially if PMIX INFO REQD was not set in the 31 request. 32 PMIX_ALLOC_FABRIC_SEC_KEY "pmix.alloc.nsec" (pmix_byte_object_t) 33 Request that the allocation include a fabric security key for the spawned job. 34 PMIX_ALLOC_FABRIC_TYPE "pmix.alloc.nettype" (char*) Type of desired transport (e.g., "tcp", "udp") being requested in an allocation request. 35 36 PMIX_ALLOC_FABRIC_PLANE "pmix.alloc.netplane" (char*) 37 ID string for the *fabric plane* to be used for the requested allocation. 38 PMIX ALLOC FABRIC ENDPTS "pmix.alloc.endpts" (size_t)

1	Number of endpoints to allocate per <i>process</i> in the job.
2 3	<pre>PMIX_ALLOC_FABRIC_ENDPTS_NODE "pmix.alloc.endpts.nd" (size_t) Number of endpoints to allocate per node for the job.</pre>
4 5 6	PMIX_PROC_MAP "pmix.pmap" (char*) Regular expression describing processes on each node in the specified realm - see 16.2.3.2 for an explanation of its generation. Defaults to the <i>job</i> realm.
7 8 9	PMIX_NODE_MAP "pmix.nmap" (char*) Regular expression of nodes currently hosting processes in the specified realm - see 16.2.3.2 for an explanation of its generation. Defaults to the <i>job</i> realm.
	▼ Optional Attributes
10	PMIx libraries that support this operation may support the following:
11 12	PMIX_ALLOC_BANDWIDTH "pmix.alloc.bw" (float) Fabric bandwidth (in Megabits[base2]/sec) for the job being requested in an allocation request.
13 14	<pre>PMIX_ALLOC_FABRIC_QOS "pmix.alloc.netqos" (char*) Fabric quality of service level for the job being requested in an allocation request.</pre>
15 16 17 18 19	PMIX_SESSION_INFO "pmix.ssn.info" (bool) Return information regarding the session realm of the target process. In this context, indicates that the information provided in the PMIX_NODE_MAP is for the entire session and not just the indicated namespace. Thus, subsequent calls to this API may omit node-level information - e.g., the library may not need to include information on the devices on each node in a subsequent call.
20 21 22 23	The following optional attributes may be provided by the host environment to identify the programming model (as specified by the user) being executed within the application. The PMIx server library may utilize this information to harvest/forward model-specific environmental variables, record the programming model associated with the application, etc.
24 25	• PMIX_PROGRAMMING_MODEL "pmix.pgm.model" (char*) Programming model being initialized (e.g., "MPI" or "OpenMP").
26 27	• PMIX_MODEL_LIBRARY_NAME "pmix.mdl.name" (char*) Programming model implementation ID (e.g., "OpenMPI" or "MPICH").
28 29	• PMIX_MODEL_LIBRARY_VERSION "pmix.mld.vrs" (char*) Programming model version string (e.g., "2.1.1").

Provide a function by which the RM can request application-specific setup data (e.g., environmental variables, fabric configuration and security credentials) from supporting PMIx server library subsystems prior to initiating launch of a job.

This is defined as a non-blocking operation in case contributing subsystems need to perform some potentially time consuming action (e.g., query a remote service) before responding. The returned data must be distributed by the host environment and subsequently delivered to the local PMIx server on each node where application processes will execute, prior to initiating execution of those processes.

Advice to PMIx server hosts-

Host environments are required to execute this operation prior to launching a job. In addition to supported directives, the *info* array must include a description of the *job* using the PMIX_NODE_MAP and PMIX_PROC_MAP attributes.

Note that the function can be called on a per-application basis if the PMIX_PROC_MAP and PMIX_NODE_MAP are provided only for the corresponding application (as opposed to the entire job) each time.

Advice to PMIx library implementers

Support for harvesting of environmental variables and providing of local configuration information by the PMIx implementation is optional.

16.2.11.1 Server Setup Application Callback Function

The PMIx_server_setup_application callback function.

Summary

Provide a function by which the resource manager can receive application-specific environmental variables and other setup data prior to launch of an application.

```
Format
 1
 2
                typedef void (*pmix_setup_application_cbfunc_t)(
 3
                                              pmix_status_t status,
 4
                                              pmix_info_t info[], size_t ninfo,
 5
                                              void *provided cbdata,
 6
                                               pmix op cbfunc t cbfunc, void *cbdata);
 7
                     status
 8
                     returned status of the request (pmix_status_t)
 9
                IN
10
                     Array of info structures (array of handles)
                IN
11
                     Number of elements in the info array (integer)
12
13
                IN
                     provided_cbdata
14
                     Data originally passed to call to PMIx_server_setup_application (memory reference)
15
                IN
                     cbfunc
16
                     pmix_op_cbfunc_t function to be called when processing completed (function reference)
17
                IN
                     cbdata
                     Data to be passed to the cbfunc callback function (memory reference)
18
19
                Description
20
                Define a function to be called by the PMIx server library for return of application-specific setup data in
21
                response to a request from the host RM. The returned info array is owned by the PMIx server library and will
22
                be free'd when the provided cbfunc is called.
                    Server Setup Application Attributes
23
      16.2.11.2
24 PMIx v3.0
                Attributes specifically defined for controlling contents of application setup data.
25
                PMIX_SETUP_APP_ENVARS "pmix.setup.env" (bool)
26
                      Harvest and include relevant environmental variables.
27
                PMIX_SETUP_APP_NONENVARS ""pmix.setup.nenv" (bool)
28
                      Include all relevant data other than environmental variables.
29
                PMIX_SETUP_APP_ALL "pmix.setup.all" (bool)
30
                      Include all relevant data.
     16.2.12
                    PMIx Register attributes
31
                Summary
32
```

Register host environment attribute support for a function.

IN function

String name of function (string)

IN attrs

Array of pmix_regattr_t describing the supported attributes (handle)

IN nattrs

Number of elements in *attrs* (size_t)

Returns **PMIX_SUCCESS** or a negative value corresponding to a PMIx error constant.

Description

The **PMIx_Register_attributes** function is used by the host environment to register with its PMIx server library the attributes it supports for each **pmix_server_module_t** function. The *function* is the string name of the server module function (e.g., "register_events", "validate_credential", or "allocate") whose attributes are being registered. See the **pmix_regattr_t** entry for a description of the *attrs* array elements.

Note that the host environment can also query the library (using the PMIx_Query_info_nb API) for its attribute support both at the server, client, and tool levels once the host has executed PMIx_server_init since the server will internally register those values.

Advice to PMIx server hosts

Host environments are strongly encouraged to register all supported attributes immediately after initializing the library to ensure that user requests are correctly serviced.

Advice to PMIx library implementers

PMIx implementations are *required* to register all internally supported attributes for each API during initialization of the library (i.e., when the process calls their respective PMIx init function). Specifically, the implementation *must not* register supported attributes upon first call to a given API as this would prevent users from discovering supported attributes prior to first use of an API.

It is the implementation's responsibility to associate registered attributes for a given pmix_server_module_t function with their corresponding user-facing API. Supported attributes must be reported to users in terms of their support for user-facing APIs, broken down by the level (see Section 5.4.6) at which the attribute is supported.

Note that attributes can/will be registered on an API for each level. It is *required* that the implementation support user queries for supported attributes on a per-level basis. Duplicate registrations at the *same* level for a function *shall* return an error - however, duplicate registrations at *different* levels *shall* be independently tracked.

16.2.12.1 Attribute registration constants

1

3

4

5 6

15

16

17

18

19

20

21 22

23

24 25

26

27

28

29

30

31

32

33

34

Constants supporting attribute registration.

PMIX_ERR_REPEAT_ATTR_REGISTRATION The attributes for an identical function have already been registered at the specified level (host, server, or client).

16.2.12.2 Attribute registration structure

The **pmix_regattr_t** structure is used to register attribute support for a PMIx function.

```
PMIx v4.0
7
              typedef struct pmix regattr {
8
                  char *name;
9
                  pmix_key_t *string;
10
                  pmix_data_type_t type;
                  pmix_info_t *info;
11
12
                  size_t ninfo;
13
                  char **description;
14
              } pmix_regattr_t;;
```

Note that in this structure:

- the *name* is the actual name of the attribute e.g., "PMIX_MAX_PROCS"
- the string is the literal string value of the attribute e.g., "pmix.max.size" for the PMIX_MAX_PROCS
 attribute
- *type* must be a PMIx data type identifying the type of data associated with this attribute.
- the *info* array contains machine-usable information regarding the range of accepted values. This may include entries for PMIX_MIN_VALUE, PMIX_MAX_VALUE, PMIX_ENUM_VALUE, or a combination of them. For example, an attribute that supports all positive integers might delineate it by including a pmix_info_t with a key of PMIX_MIN_VALUE, type of PMIX_INT, and value of zero. The lack of an entry for PMIX_MAX_VALUE indicates that there is no ceiling to the range of accepted values.
- ninfo indicates the number of elements in the info array
- The *description* field consists of a **NULL**-terminated array of strings describing the attribute, optionally including a human-readable description of the range of accepted values e.g., "ALL POSITIVE INTEGERS", or a comma-delimited list of enum value names. No correlation between the number of entries in the *description* and the number of elements in the *info* array is implied or required.

The attribute *name* and *string* fields must be **NULL**-terminated strings composed of standard alphanumeric values supported by common utilities such as *strcmp*.

Although not strictly required, both PMIx library implementers and host environments are strongly encouraged to provide both human-readable and machine-parsable descriptions of supported attributes when registering them.

16.2.12.3 Attribute registration structure descriptive attributes 1 2 The following attributes relate to the nature of the values being reported in the pmix_regattr_t structures. 3 PMIX_MAX_VALUE "pmix.descr.maxval" (varies) 4 Used in pmix regattr t to describe the maximum valid value for the associated attribute. 5 PMIX MIN VALUE "pmix.descr.minval" (varies) 6 Used in pmix regattr t to describe the minimum valid value for the associated attribute. 7 PMIX ENUM VALUE "pmix.descr.enum" (char*) 8 Used in pmix_regattr_t to describe accepted values for the associated attribute. Numerical values 9 shall be presented in a form convertible to the attribute's declared data type. Named values (i.e., values 10 defined by constant names via a typical C-language enum declaration) must be provided as their 11 numerical equivalent. 16.2.12.4 Attribute registration structure support macros 12 13 The following macros are provided to support the **pmix** regattr t structure. Static initializer for the regattr structure 14 15 (Provisional) 16 Provide a static initializer for the **pmix_regattr_t** fields. PMIx v4.2 17 PMIX REGATTR STATIC INIT Initialize the regattr structure 18 Initialize the pmix regattr t fields 19 PMIx v4.0 20 PMIX REGATTR CONSTRUCT (m) 21 22 Pointer to the structure to be initialized (pointer to pmix_regattr_t) Destruct the regattr structure 23 24 Destruct the pmix_regattr_t fields, releasing all strings. PMIx v4.0 25 PMIX REGATTR DESTRUCT (m) 26 IN 27 Pointer to the structure to be destructed (pointer to pmix regattr t)

```
Create a regattr array
 1
                 Allocate and initialize an array of pmix_regattr_t structures.
 2
                 PMIX_REGATTR_CREATE(m, n)
 3
 4
                 INOUT m
 5
                      Address where the pointer to the array of pmix regattr t structures shall be stored (handle)
 6
 7
                      Number of structures to be allocated (size_t)
 8
                 Free a regattr array
                 Release an array of pmix_regattr_t structures.
 9
   PMIx v4.0
                 PMIX REGATTR FREE (m, n)
10
11
                 INOUT m
12
                      Pointer to the array of pmix_regattr_t structures (handle)
13
                 IN
14
                      Number of structures in the array (size_t)
                 Load a regattr structure
15
16
                 Load values into a pmix_regattr_t structure. The macro can be called multiple times to add as many
17
                 strings as desired to the same structure by passing the same address and a NULL key to the macro. Note that
                 the t type value must be given each time.
18
   PMIx v4.0
19
                 PMIX_REGATTR_LOAD(a, n, k, t, ni, v)
                 IN
20
21
                      Pointer to the structure to be loaded (pointer to pmix proc t)
22
                 IN
23
                      String name of the attribute (string)
24
                 IN
25
                      Key value to be loaded (pmix key t)
26
                 IN
27
                      Type of data associated with the provided key (pmix_data_type_t)
28
                 IN
29
                      Number of pmix_info_t elements to be allocated in info(size_t)
30
                 IN
31
                      One-line description to be loaded (more can be added separately) (string)
```

```
Transfer a regattr to another regattr
 1
 2
                 Non-destructively transfer the contents of a pmix_regattr_t structure to another one.
                 PMIX_REGATTR_XFER(m, n)
 3
 4
                 INOUT m
 5
                      Pointer to the destination pmix_regattr_t structure (handle)
 6
 7
                      Pointer to the source pmix regattr t structure (handle)
      16.2.13
                    PMIx server setup local support
 8
 9
                 Summary
10
                 Provide a function by which the local PMIx server can perform any application-specific operations prior to
11
                 spawning local clients of a given application.
                 Format
12
    PMIx v2.0
13
                 pmix_status_t
                 PMIx_server_setup_local_support(const pmix_nspace_t nspace,
14
15
                                                           pmix info t info[], size t ninfo,
                                                           pmix_op_cbfunc_t cbfunc,
16
17
                                                           void *cbdata);
18
                 IN
                      nspace
19
                      Namespace (string)
20
                      Array of info structures (array of handles)
21
22
                 IN
                      ninfo
23
                      Number of elements in the info array (size t)
24
                      cbfunc
25
                      Callback function pmix op cbfunc t. A NULL function reference indicates that the function is to
                      be executed as a blocking operation (function reference)
26
27
                 IN
                      cbdata
                      Data to be passed to the callback function (memory reference)
28
29
                 Returns one of the following:
30
                 • PMIX SUCCESS, indicating that the request is being processed by the host environment - result will be
31
                   returned in the provided cbfunc. Note that the library must not invoke the callback function prior to
32
                   returning from the API.
33
                 • PMIX_OPERATION_SUCCEEDED, indicating that the request was immediately processed and returned
34
                   success - the cbfunc will not be called
35
                 • a PMIx error constant indicating either an error in the input or that the request was immediately processed
36
                   and failed - the cbfunc will not be called
```

Provide a function by which the local PMIx server can perform any application-specific operations prior to spawning local clients of a given application. For example, a fabric library might need to setup the local driver for "instant on" addressing. The data provided in the *info* array is the data returned to the host RM by the callback function executed as a result of a call to **PMIx** server setup application.

Advice to PMIx server hosts

Host environments are required to execute this operation prior to starting any local application processes from the specified namespace if information was obtained from a call to **PMIx_server_setup_application**.

Host environments must register the *nspace* using **PMIx_server_register_nspace** prior to calling this API to ensure that all namespace-related information required to support this function is available to the library. This eliminates the need to include any of the registration information in the *info* array passed to this API.

16.2.14 PMIx server IOF deliver

Summary

Provide a function by which the host environment can pass forwarded Input/Output (IO) to the PMIx server library for distribution to its clients.

$_{PMIx \ v3.0}$ Format

IN source

Pointer to pmix_proc_t identifying source of the IO (handle)

IN channel

IO channel of the data (pmix iof channel t)

IN bo

Pointer to pmix_byte_object_t containing the payload to be delivered (handle)

IN info

Array of pmix_info_t metadata describing the data (array of handles)

IN ninfo

Number of elements in the *info* array (size_t)

IN cbfunc

Callback function **pmix_op_cbfunc_t**. A **NULL** function reference indicates that the function is to be executed as a blocking operation (function reference)

IN cbdata

Data to be passed to the callback function (memory reference)

Returns one of the following:

1

2

3

5

6

7

8

9 10

11 12

13

15 16

26

27

28

29

30

31 32

- PMIX_SUCCESS, indicating that the request is being processed by the host environment result will be returned in the provided cbfunc. Note that the library must not invoke the callback function prior to returning from the API.
- PMIX_OPERATION_SUCCEEDED, indicating that the request was immediately processed and returned success - the cbfunc will not be called
- a PMIx error constant indicating either an error in the input or that the request was immediately processed and failed - the cbfunc will not be called

Description

Provide a function by which the host environment can pass forwarded IO to the PMIx server library for distribution to its clients. The PMIx server library is responsible for determining which of its clients have actually registered for the provided data and delivering it. The cbfunc callback function will be called once the PMIx server library no longer requires access to the provided data.

16.2.15 PMIx server collect inventory

Summary

Collect inventory of resources on a node.

```
Format
17
    PMIx v3.0
18
              pmix_status_t
              PMIx_server_collect_inventory(const pmix_info_t directives[],
19
20
                                                 size_t ndirs,
                                                pmix_info_cbfunc_t cbfunc,
21
                                                void *cbdata);
22
23
                   directives
24
                   Array of pmix info t directing the request (array of handles)
25
```

Number of elements in the *directives* array (size_t)

IN cbfunc

Callback function to return collected data (pmix_info_cbfunc_t function reference)

IN cbdata

Data to be passed to the callback function (memory reference)

Returns PMIX_SUCCESS or a negative value corresponding to a PMIx error constant. In the event the function returns an error, the cbfunc will not be called.

1 2

3

4

5

6

7

8

9

10

11 12

21

22

23

24 25

26

27

28

29

30

31

32

33

34

Provide a function by which the host environment can request its PMIx server library collect an inventory of local resources. Supported resources depends upon the PMIx implementation, but may include the local node topology and fabric interfaces.

Advice to PMIx server hosts

This is a non-blocking API as it may involve somewhat lengthy operations to obtain the requested information. Inventory collection is expected to be a rare event – at system startup and upon command from a system administrator. Inventory updates are expected to initiate a smaller operation involving only the changed information. For example, replacement of a node would generate an event to notify the scheduler with an inventory update without invoking a global inventory operation.

16.2.16 PMIx_server_deliver_inventory

Summary

Pass collected inventory to the PMIx server library for storage.

```
13 <sub>PMIx v3.0</sub>
14
              pmix status t
15
              PMIx_server_deliver_inventory(const pmix_info_t info[],
                                                size_t ninfo,
16
17
                                                const pmix_info_t directives[],
18
                                                size_t ndirs,
19
                                                pmix_op_cbfunc_t cbfunc,
20
                                                void *cbdata);
                                                   – C
```

IN info

Array of pmix info t containing the inventory (array of handles)

IN ninfo

Number of elements in the *info* array (size_t)

IN directives

Array of **pmix_info_t** directing the request (array of handles)

IN ndirs

Number of elements in the *directives* array (size_t)

IN cbfunc

Callback function **pmix_op_cbfunc_t**. A **NULL** function reference indicates that the function is to be executed as a blocking operation (function reference)

IN cbdata

Data to be passed to the callback function (memory reference)

Returns one of the following:

- PMIX_SUCCESS, indicating that the request is being processed by the host environment result will be
 returned in the provided *cbfunc*. Note that the library must not invoke the callback function prior to
 returning from the API.
- PMIX_OPERATION_SUCCEEDED, indicating that the request was immediately processed and returned success - the cbfunc will not be called
- a PMIx error constant indicating either an error in the input or that the request was immediately processed and failed the *cbfunc* will not be called

Provide a function by which the host environment can pass inventory information obtained from a node (as a result of a call to <code>PMIx_server_collect_inventory</code>) to the PMIx server library for storage. Inventory data is subsequently used by the PMIx server library for allocations in response to <code>PMIx_server_setup_application</code>, and may be available to the library's host via the <code>PMIx_Get</code> API (depending upon PMIx implementation). The <code>cbfunc</code> callback function will be called once the PMIx server

16.2.17 PMIx_server_generate_locality_string

Summary

Generate a PMIx locality string from a given cpuset.

library no longer requires access to the provided data.

PMIx v4.0 Format

pmix_status_t

PMIx_server_generate_locality_string(const pmix_cpuset_t *cpuset, char **locality);

IN cpuset

Pointer to a pmix cpuset t containing the bitmap of assigned PUs (handle)

OUT locality

String representation of the PMIx locality corresponding to the input bitmap (char*)

Returns either **PMIX_SUCCESS** indicating that the returned string contains the locality, or an appropriate PMIx error constant.

Description

Provide a function by which the host environment can generate a PMIx locality string for inclusion in the call to **PMIx_server_register_nspace**. This function shall only be called for local client processes, with the returned locality included in the job-level information (via the **PMIX_LOCALITY_STRING** attribute) provided to local clients. Local clients can use these strings as input to determine the relative locality of their local peers via the **PMIx_Get_relative_locality** API.

The function is required to return a string prefixed by the *source* field of the provided *cpuset* followed by a colon. The remainder of the string shall represent the corresponding locality as expressed by the underlying implementation.


16.2.18 PMIx server generate cpuset string

2 Summary 3 Generate a PMIx string representation of the provided cpuset. 4 *PMIx v4.0* 5 pmix status t 6 PMIx_server_generate_cpuset_string(const pmix_cpuset_t *cpuset, 7 char **cpuset_string); 8 IN cpuset 9 Pointer to a pmix_cpuset_t containing the bitmap of assigned PUs (handle) 10 OUT cpuset_string 11 String representation of the input bitmap (char*) 12 Returns either PMIX SUCCESS indicating that the returned string contains the representation, or an 13 appropriate PMIx error constant. **Description** 14 15 Provide a function by which the host environment can generate a string representation of the cpuset bitmap for inclusion in the call to PMIx_server_register_nspace. This function shall only be called for local 16 17 client processes, with the returned string included in the job-level information (via the PMIX CPUSET 18 attribute) provided to local clients. Local clients can use these strings as input to obtain their PU bindings via 19 the PMIx_Parse_cpuset_string API. 20 The function is required to return a string prefixed by the *source* field of the provided *cpuset* followed by a 21 colon. The remainder of the string shall represent the PUs to which the process is bound as expressed by the 22 underlying implementation. 16.2.18.1 **Cpuset Structure** 23 24 The pmix_cpuset_t structure contains a character string identifying the source of the bitmap (e.g., "hwloc") and a pointer to the corresponding implementation-specific structure (e.g., hwloc cpuset t). 25 PMIx v4.0 26 typedef struct pmix_cpuset { 27 char *source; 28 void *bitmap; 29 } pmix_cpuset_t;

16.2.18.2 Cpuset support macros

The following macros support the **pmix_cpuset_t** structure.

30 31



1 16.2.19 PMIx_server_define_process_set

```
2
                Summary
 3
                Define a PMIx process set.
                Format
 4 PMIx v4.0
 5
                pmix_status_t
                PMIx_server_define_process_set(const pmix_proc_t members[],
 6
 7
                                                        size_t nmembers,
 8
                                                        char *pset_name);
 9
                IN
                     members
10
                      Pointer to an array of pmix proc t containing the identifiers of the processes in the process set
11
12
                IN
                     nmembers
13
                      Number of elements in members (integer)
14
                     pset name
15
                      String name of the process set being defined (char*)
16
                Returns either PMIX_SUCCESS or an appropriate PMIx error constant.
                Description
17
18
                Provide a function by which the host environment can create a process set. The PMIx server shall alert all
19
                local clients of the new process set (including process set name and membership) via the
20
                PMIX PROCESS SET DEFINE event.
                                              Advice to PMIx server hosts—
21
                The host environment is responsible for ensuring:
22
                • consistent knowledge of process set membership across all involved PMIx servers; and
23
                • that process set names do not conflict with system-assigned namespaces within the scope of the set
      16.2.20
                    PMIx server delete process set
24
25
                Summary
26
                Delete a PMIx process set name
27 <sub>PMIx v4.0</sub>
                Format
28
                pmix status t
                PMIx_server_delete_process_set(char *pset_name);
29
30
                IN
                     pset_name
                      String name of the process set being deleted (char*)
31
32
                Returns either PMIX SUCCESS or an appropriate PMIx error constant.
```

Provide a function by which the host environment can delete a process set name. The PMIx server shall alert all local clients of the process set name being deleted via the PMIX_PROCESS_SET_DELETE event. Deletion of the name has no impact on the member processes.

Advice to PMIx server hosts

The host environment is responsible for ensuring consistent knowledge of process set membership across all involved PMIx servers.

16.3 Server Function Pointers

PMIx utilizes a "function-shipping" approach to support for implementing the server-side of the protocol. This method allows RMs to implement the server without being burdened with PMIx internal details. When a request is received from the client, the corresponding server function will be called with the information.

Any functions not supported by the RM can be indicated by a **NULL** for the function pointer. PMIx implementations are required to return a **PMIX_ERR_NOT_SUPPORTED** status to all calls to functions that require host environment support and are not backed by a corresponding server module entry. Host environments may, if they choose, include a function pointer for operations they have not yet implemented and simply return **PMIX_ERR_NOT_SUPPORTED**.

Functions that accept directives (i.e., arrays of <code>pmix_info_t</code> structures) must check any provided directives for those marked as <code>required</code> via the <code>PMIX_INFO_REQD</code> flag. PMIx client and server libraries are required to mark any such directives with the <code>PMIX_INFO_REQD_PROCESSED</code> flag should they have handled the request. Any required directive that has not been marked therefore becomes the responsibility of the host environment. If a required directive that hasn't been processed by a lower level cannot be supported by the host, then the <code>PMIX_ERR_NOT_SUPPORTED</code> error constant must be returned. If the directive can be processed by the host, then the host shall do so and mark the attribute with the <code>PMIX_INFO_REQD_PROCESSED</code> flag.

The host RM will provide the function pointers in a <code>pmix_server_module_t</code> structure passed to <code>PMIx_server_init</code>. The module structure and associated function references are defined in this section.

Advice to PMIx server hosts

For performance purposes, the host server is required to return as quickly as possible from all functions. Execution of the function is thus to be done asynchronously so as to allow the PMIx server support library to handle multiple client requests as quickly and scalably as possible.

All data passed to the host server functions is "owned" by the PMIX server support library and must not be free'd. Data returned by the host server via callback function is owned by the host server, which is free to release it upon return from the callback

16.3.1 pmix_server_module_t Module

Summary

List of function pointers that a PMIx server passes to **PMIx_server_init** during startup.

```
2
 3
 4
 5
 6
 7
 8
 9
10
11
12
13
14
15
16
17
18
19
20
21
22
23
24
```

25

30 31 32

33 34 35

> 36 37

38

```
typedef struct pmix_server_module_4_0_0_t {
    /* v1x interfaces */
    pmix_server_client_connected_fn_t
                                         client_connected;
                                                             // DEPRECATED
                                         client_finalized;
    pmix_server_client_finalized_fn_t
    pmix_server_abort_fn_t
                                         abort;
    pmix_server_fencenb_fn_t
                                         fence nb;
    pmix server dmodex req fn t
                                         direct_modex;
    pmix server publish fn t
                                         publish;
    pmix_server_lookup_fn_t
                                         lookup;
    pmix_server_unpublish_fn_t
                                         unpublish;
    pmix_server_spawn_fn_t
                                         spawn;
    pmix server connect fn t
                                         connect;
    pmix_server_disconnect_fn_t
                                         disconnect;
    pmix_server_register_events_fn_t
                                         register_events;
    pmix server deregister events fn t
                                         deregister_events;
    pmix_server_listener_fn_t
                                         listener;
    /* v2x interfaces */
    pmix_server_notify_event_fn_t
                                         notify_event;
    pmix_server_query_fn_t
                                         query;
    pmix server tool connection fn t
                                         tool_connected;
    pmix server log fn t
                                         log;
    pmix_server_alloc_fn_t
                                         allocate;
    pmix_server_job_control_fn_t
                                         job_control;
    pmix server monitor fn t
                                         monitor;
    /* v3x interfaces */
    pmix_server_get_cred_fn_t
                                         get_credential;
    pmix server validate cred fn t
                                         validate credential;
    pmix_server_iof_fn_t
                                         iof_pull;
    pmix_server_stdin_fn_t
                                         push_stdin;
    /* v4x interfaces */
    pmix_server_grp_fn_t
                                         group;
    pmix_server_fabric_fn_t
                                         fabric;
    pmix_server_client_connected2 fn t client_connected2;
} pmix_server_module_t;
```

Advice to PMIx server hosts

Note that some PMIx implementations *require* the use of C99-style designated initializers to clearly correlate each provided function pointer with the correct member of the <code>pmix_server_module_t</code> structure as the location/ordering of struct members may change over time.

16.3.2 pmix_server_client_connected_fn_t

Summary

Notify the host server that a client connected to this server. This function module entry has been **DEPRECATED** in favor of **pmix server client connected2** fn t.

PMIx v1.0

1

3

4

5

6

7

8

9

10

11

12

13

14 15

16

17

18

19

20

21 22

23

24

25

26

27 28

29

30

31

33

34

35

Format

```
IN proc
```

pmix_proc_t structure (handle)

IN server_object

object reference (memory reference)

IN cbfunc

Callback function **pmix** op **cbfunc t** (function reference)

IN cbdata

Data to be passed to the callback function (memory reference)

Returns one of the following:

- PMIX_SUCCESS, indicating that the request is being processed by the host environment result will be
 returned in the provided *cbfunc*. Note that the host must not invoke the callback function prior to returning
 from the API.
- PMIX_OPERATION_SUCCEEDED, indicating that the request was immediately processed and returned success - the cbfunc will not be called
- a PMIx error constant indicating either an error in the input or that the request was immediately processed and failed - the *cbfunc* will not be called

Description

This function module entry has been DEPRECATED in favor of

pmix_server_client_connected2_fn_t. If both functions are provided, the PMIx library will
ignore this function module entry in favor of its replacement.

16.3.3 pmix_server_client_connected2_fn_t

Summary

Notify the host server that a client connected to this server - this version of the original function definition has been extended to include an array of pmix_info_t, thereby allowing the PMIx server library to pass additional information identifying the client to the host environment.

1

2

13

9

17 18 19

20

21 22 23

242526

272829

30

36 37

38 39 40

rypeder	pmix_status_t	(*pmix_server_ciient_connectedz_in_t)(
		<pre>const pmix_proc_t *proc,</pre>
		<pre>void* server_object,</pre>
		<pre>pmix_info_t info[], size_t ninfo,</pre>
		<pre>pmix_op_cbfunc_t cbfunc,</pre>
		<pre>void *cbdata)</pre>

IN proc pmix_proc_t structure (handle) IN server_object object reference (memory reference) IN info Array of info structures (array of handles) IN ninfo Number of elements in the *info* array (integer) IN Callback function **pmix** op **cbfunc t** (function reference) cbdata IN Data to be passed to the callback function (memory reference)

Returns one of the following:

- PMIX_SUCCESS, indicating that the request is being processed by the host environment result will be
 returned in the provided *cbfunc*. Note that the host must not invoke the callback function prior to returning
 from the API.
- PMIX_OPERATION_SUCCEEDED, indicating that the request was immediately processed and returned success - the cbfunc will not be called
- a PMIx error constant indicating either an error in the input or that the request was immediately processed and failed the *cbfunc* will not be called. The PMIx server library is to immediately terminate the connection.

Description

Notify the host environment that a client has called PMIx_Init. Note that the client will be in a blocked state until the host server executes the callback function, thus allowing the PMIx server support library to release the client. The server_object parameter will be the value of the server_object parameter passed to PMIx_server_register_client by the host server when registering the connecting client. A host server can choose to not be notified when clients connect by setting pmix server client connected2 fn t to NULL.

It is possible that only a subset of the clients in a namespace call **PMIx_Init**. The server's **pmix_server_client_connected2_fn_t** implementation should therefore not depend on being called once per rank in a namespace or delay calling the callback function until all ranks have connected. However, the host may rely on the **pmix_server_client_connected2_fn_t** function module entry being called for a given rank prior to any other function module entries being executed on behalf of that rank.

16.3.4 pmix server client finalized fn t

Summary

Format

Notify the host environment that a client called **PMIx_Finalize**.

PMIx v1.0

```
IN proc
    pmix_proc_t structure (handle)
IN server_object
    object reference (memory reference)
IN cbfunc
    Callback function pmix_op_cbfunc_t (function reference)
IN cbdata
    Data to be passed to the callback function (memory reference)
```

Returns one of the following:

- PMIX_SUCCESS, indicating that the request is being processed by the host environment result will be
 returned in the provided *cbfunc*. Note that the host must not invoke the callback function prior to returning
 from the API.
- PMIX_OPERATION_SUCCEEDED, indicating that the request was immediately processed and returned success - the cbfunc will not be called
- a PMIx error constant indicating either an error in the input or that the request was immediately processed and failed the *cbfunc* will not be called

Description

Notify the host environment that a client called PMIx_Finalize. Note that the client will be in a blocked state until the host server executes the callback function, thus allowing the PMIx server support library to release the client. The server_object parameter will be the value of the server_object parameter passed to PMIx_server_register_client by the host server when registering the connecting client. If provided, an implementation of pmix_server_client_finalized_fn_t is only required to call the callback function designated. A host server can choose to not be notified when clients finalize by setting pmix_server_client_finalized_fn_t to NULL.

Note that the host server is only being informed that the client has called **PMIx_Finalize**. The client might not have exited. If a client exits without calling **PMIx_Finalize**, the server support library will not call the **pmix_server_client_finalized_fn_t** implementation.

-Advice to PMIx server hosts-

This operation is an opportunity for a host server to update the status of the tasks it manages. It is also a convenient and well defined time to release resources used to support that client.

16.3.5 pmix server abort fn t

Summary

Format

2

3

4 5

16

17 18

19 20

21

22

23

24

25

26

27

28

29

30

31

32

33

34

35

Notify the host environment that a local client called **PMIx_Abort**.

```
6 <sub>PMIx v1.0</sub>
7
              typedef pmix_status_t (*pmix_server_abort_fn_t)(
8
                                               const pmix proc t *proc,
9
                                               void *server_object,
10
                                               int status,
11
                                               const char msg[],
12
                                               pmix_proc_t procs[],
13
                                               size_t nprocs,
                                              pmix_op_cbfunc_t cbfunc,
14
15
                                               void *cbdata);
```

IN proc

pmix_proc_t structure identifying the process requesting the abort (handle)

IN server object

object reference (memory reference)

IN status

exit status (integer)

IN

exit status message (string)

procs

Array of pmix_proc_t structures identifying the processes to be terminated (array of handles)

C

IN nprocs

Number of elements in the *procs* array (integer)

cbfunc

Callback function **pmix** op **cbfunc t** (function reference)

cbdata IN

Data to be passed to the callback function (memory reference)

Returns one of the following:

• PMIX_SUCCESS, indicating that the request is being processed by the host environment - result will be returned in the provided cbfunc. Note that the host must not invoke the callback function prior to returning from the API.

- PMIX_OPERATION_SUCCEEDED, indicating that the request was immediately processed and returned success - the cbfunc will not be called
- PMIX_ERR_PARAM_VALUE_NOT_SUPPORTED indicating that the host environment supports this API, but the request includes processes that the host environment cannot abort e.g., if the request is to abort subsets of processes from a namespace, or processes outside of the caller's own namespace, and the host environment does not permit such operations. In this case, none of the specified processes will be terminated the cbfunc will not be called
- PMIX_ERR_NOT_SUPPORTED, indicating that the host environment does not support the request, even though the function entry was provided in the server module the *cbfunc* will not be called
- a PMIx error constant indicating either an error in the input or that the request was immediately processed and failed the *cbfunc* will not be called

A local client called **PMIx_Abort**. Note that the client will be in a blocked state until the host server executes the callback function, thus allowing the PMIx server library to release the client. The array of *procs* indicates which processes are to be terminated. A **NULL** for the *procs* array indicates that all processes in the caller's namespace are to be aborted, including itself - this is the equivalent of passing a **pmix_proc_t** array element containing the caller's namespace and a rank value of **PMIX_RANK_WILDCARD**.

16.3.6 pmix_server_fencenb_fn_t

Summary

At least one client called either PMIx_Fence or PMIx_Fence_nb.

```
PMIx v1.0
```

```
Format
```

C

```
IN procs
```

Array of pmix_proc_t structures identifying operation participants(array of handles)

IN nprocs

Number of elements in the *procs* array (integer)

IN info

Array of info structures (array of handles)

IN ninfo

Number of elements in the *info* array (integer)

IN data

(string)

IN 1 ndata 2 (integer) 3 IN cbfunc 4 Callback function **pmix** modex cbfunc t (function reference) 5 IN cbdata 6 Data to be passed to the callback function (memory reference) 7 Returns one of the following: 8 • PMIX_SUCCESS, indicating that the request is being processed by the host environment - result will be 9 returned in the provided cbfunc. Note that the host must not invoke the callback function prior to returning from the API. 10 11 • PMIX_ERR_NOT_SUPPORTED, indicating that the host environment does not support the request, even though the function entry was provided in the server module - the cbfunc will not be called 12 13 • a PMIx error constant indicating either an error in the input or that the request was immediately processed 14 and failed - the cbfunc will not be called Required Attributes -----______ 15 PMIx libraries are required to pass any provided attributes to the host environment for processing. 16 The following attributes are required to be supported by all host environments: 17 PMIX_COLLECT_DATA "pmix.collect" (bool) 18 Collect all data posted by the participants using **PMIx Put** that has been committed via 19 **PMIx** Commit, making the collection locally available to each participant at the end of the operation. By default, this will include all job-level information that was locally generated by PMIx servers unless 20 excluded using the PMIX_COLLECT_GENERATED_JOB_INFO attribute. 21 22 PMIX_LOCAL_COLLECTIVE_STATUS "pmix.loc.col.st" (pmix_status_t) 23 Status code for local collective operation being reported to the host by the server library. PMIx servers 24 may aggregate the participation by local client processes in a collective operation - e.g., instead of 25 passing individual client calls to PMIx Fence up to the host environment, the server may pass only a 26 single call to the host when all local participants have executed their **PMIx_Fence** call, thereby 27 reducing the burden placed on the host. However, in cases where the operation locally fails (e.g., if a 28 participating client abnormally terminates prior to calling the operation), the server upcall functions to 29 the host do not include a pmix_status_t by which the PMIx server can alert the host to that failure. 30 This attribute resolves that problem by allowing the server to pass the status information regarding the 31 local collective operation. ______ Optional Attributes ----------32 The following attributes are optional for host environments: 33 PMIX_TIMEOUT "pmix.timeout" (int) 34 Time in seconds before the specified operation should time out (zero indicating infinite) and return the

(client, server, and host) simultaneously timing the operation.

PMIX_ERR_TIMEOUT error. Care should be taken to avoid race conditions caused by multiple layers

35

-Advice to PMIx server hosts-

Host environment are required to return **PMIX_ERR_NOT_SUPPORTED** if passed an attributed marked as **PMIX_INFO_REQD** that they do not support, even if support for that attribute is optional.

Description

All local clients in the provided array of *procs* called either **PMIx_Fence** or **PMIx_Fence_nb**. In either case, the host server will be called via a non-blocking function to execute the specified operation once all participating local processes have contributed. All processes in the specified *procs* array are required to participate in the **PMIx_Fence/PMIx_Fence_nb** operation. The callback is to be executed once every daemon hosting at least one participant has called the host server's **pmix_server_fencenb_fn_t** function.

The provided data is to be collectively shared with all PMIx servers involved in the fence operation, and returned in the modex *cbfunc*. A **NULL** data value indicates that the local processes had no data to contribute.

The array of *info* structs is used to pass user-requested options to the server. This can include directives as to the algorithm to be used to execute the fence operation. The directives are optional unless the <code>PMIX_INFO_REQD</code> flag has been set - in such cases, the host RM is required to return an error if the directive cannot be met.

Advice to PMIx library implementers

The PMIx server library is required to aggregate participation by local clients, passing the request to the host environment once all local participants have executed the API.

Advice to PMIx server hosts

The host will receive a single call for each collective operation. It is the responsibility of the host to identify the nodes containing participating processes, execute the collective across all participating nodes, and notify the local PMIx server library upon completion of the global collective. Data received from each node must be simply concatenated to form an aggregated unit, as shown in the following example:

```
uint8_t *blob1, *blob2, *total;
size_t sz_blob1, sz_blob2, sz_total;

sz_total = sz_blob1 + sz_blob2;
total = (uint8_t*)malloc(sz_total);
memcpy(total, blob1, sz_blob1);
memcpy(&total[sz_blob1], blob2, sz_blob2);
```

Note that the ordering of the data blobs does not matter. The host is responsible for free'ing the *data* object passed to it by the PMIx server library.

16.3.6.1 Modex Callback Function

```
2
                Summary
 3
                The pmix_modex_cbfunc_t is used by the pmix_server_fencenb_fn_t and
 4
                pmix_server_dmodex_req_fn_t PMIx server operations to return modex Business Card
 5
                Exchange (BCX) data.
   PMIx v1.0
 6
                typedef void (*pmix_modex_cbfunc_t)
 7
                      (pmix_status_t status,
 8
                      const char *data, size_t ndata,
 9
                      void *cbdata,
10
                      pmix_release_cbfunc_t release_fn,
11
                      void *release_cbdata);
12
                     status
13
                     Status associated with the operation (handle)
14
                IN
                     data
15
                     Data to be passed (pointer)
16
                IN
17
                     size of the data (size_t)
18
                IN
                     cbdata
19
                     Callback data passed to original API call (memory reference)
20
                     release fn
21
                     Callback for releasing data (function pointer)
22
                IN
                     release cbdata
23
                     Pointer to be passed to release_fn (memory reference)
                Description
24
25
                A callback function that is solely used by PMIx servers, and not clients, to return modex BCX data in response
26
                to "fence" and "get" operations. The returned blob contains the data collected from each server participating in
27
                the operation.
     16.3.7
                 pmix server dmodex req fn t
28
29
                Summary
30
                Used by the PMIx server to request its local host contact the PMIx server on the remote node that hosts the
31
                specified process to obtain and return a direct modex blob for that process.
32 <sub>PMIx v1.0</sub>
                Format
33
                typedef pmix_status_t (*pmix_server_dmodex_req_fn_t)(
34
                                                     const pmix proc t *proc,
35
                                                     const pmix_info_t info[],
36
                                                     size t ninfo,
37
                                                     pmix modex cbfunc t cbfunc,
38
                                                     void *cbdata);
```

1	IN proc	
2	<pre>pmix_proc_t structure identifying the process whose data is being requested (handle)</pre>	
3	IN info	
4	Array of info structures (array of handles)	
5	IN ninfo	
6	Number of elements in the <i>info</i> array (integer)	
7 8	IN cbfunc	
9	Callback function <pre>pmix_modex_cbfunc_t</pre> (function reference) IN cbdata	
10	Data to be passed to the callback function (memory reference)	
11	Returns one of the following:	
12 13 14	• PMIX_SUCCESS , indicating that the request is being processed by the host environment - result will be returned in the provided <i>cbfunc</i> . Note that the host must not invoke the callback function prior to returning from the API.	
15 16	• PMIX_ERR_NOT_SUPPORTED, indicating that the host environment does not support the request, even though the function entry was provided in the server module - the <i>cbfunc</i> will not be called	
17 18	• a PMIx error constant indicating either an error in the input or that the request was immediately processed and failed - the <i>cbfunc</i> will not be called	
	▼ Required Attributes	
19	PMIx libraries are required to pass any provided attributes to the host environment for processing.	
20	All host environments are required to support the following attributes:	
21	<pre>PMIX_REQUIRED_KEY "pmix.req.key" (char*)</pre>	
22	Identifies a key that must be included in the requested information. If the specified key is not already	
23	available, then the PMIx servers are required to delay response to the dmodex request until either the	
24	key becomes available or the request times out.	
	▼ Optional Attributes	
25	The following attributes are optional for host environments that support this operation:	
26 27 28 29	PMIX_TIMEOUT "pmix.timeout" (int) Time in seconds before the specified operation should time out (zero indicating infinite) and return the PMIX_ERR_TIMEOUT error. Care should be taken to avoid race conditions caused by multiple layers (client, server, and host) simultaneously timing the operation.	

1

3

4

5

6

7

8

9 10

11

12

13

14

15 16

18

19

20

21

22

23

24

25

26

27

28

29 30

31 32

33 34

35

36 37

17 _{PMIx v1.0}

Used by the PMIx server to request its local host contact the PMIx server on the remote node that hosts the specified proc to obtain and return any information that process posted via calls to PMIx_Put and PMIx_Commit.

The array of *info* structs is used to pass user-requested options to the server. This can include a timeout to preclude an indefinite wait for data that may never become available. The directives are optional unless the *mandatory* flag has been set - in such cases, the host RM is required to return an error if the directive cannot be met.

16.3.7.1 Dmodex attributes

```
PMIX_REQUIRED_KEY "pmix.req.key" (char*)
```

Identifies a key that must be included in the requested information. If the specified key is not already available, then the PMIx servers are required to delay response to the dmodex request until either the key becomes available or the request times out.

16.3.8 pmix_server_publish_fn_t

Summary

Publish data per the PMIx API specification.

```
Format
```

pmix_op_cbfunc_t cbfunc,
void *cbdata);

void *cbdata);

IN proc

pmix proc t structure of the process publishing the data (handle)

IN info

Array of info structures (array of handles)

IN ninfo

Number of elements in the *info* array (integer)

IN cbfunc

Callback function pmix op cbfunc t (function reference)

IN cbdata

Data to be passed to the callback function (memory reference)

Returns one of the following:

PMIX_SUCCESS, indicating that the request is being processed by the host environment - result will be
returned in the provided *cbfunc*. Note that the host must not invoke the callback function prior to returning
from the API.

1 2	• PMIX_OPERATION_SUCCEEDED, indicating that the request was immediately processed and returned success - the cbfunc will not be called			
3 4	• PMIX_ERR_NOT_SUPPORTED, indicating that the host environment does not support the request, even though the function entry was provided in the server module - the <i>cbfunc</i> will not be called			
5 6	• a PMIx error constant indicating either an error in the input or that the request was immediately processed and failed - the <i>cbfunc</i> will not be called			
	▼			
7 8	PMIx libraries are required to pass any provided attributes to the host environment for processing. In addition, the following attributes are required to be included in the passed <i>info</i> array:			
9 10	PMIX_USERID "pmix.euid" (uint32_t) Effective user ID of the connecting process.			
11 12	PMIX_GRPID "pmix.egid" (uint32_t) Effective group ID of the connecting process.			
13				
14	Host environments that implement this entry point are required to support the following attributes:			
15 16 17	<pre>PMIX_RANGE "pmix.range" (pmix_data_range_t) Define constraints on the processes that can access the provided data. Only processes that meet the constraints are allowed to access it.</pre>			
18 19 20	<pre>PMIX_PERSISTENCE "pmix.persist" (pmix_persistence_t) Declare how long the datastore shall retain the provided data. The datastore is to delete the data upon reaching the persistence criterion.</pre>			
	▼ Optional Attributes			
21	The following attributes are optional for host environments that support this operation:			
22 23 24 25	PMIX_TIMEOUT "pmix.timeout" (int) Time in seconds before the specified operation should time out (zero indicating infinite) and return the PMIX_ERR_TIMEOUT error. Care should be taken to avoid race conditions caused by multiple layers (client, server, and host) simultaneously timing the operation.			

Publish data per the PMTx_Publish specification. The callback is to be executed upon completion of the operation. The default data range is left to the host environment, but expected to be

 $\label{pmix_persist} \textbf{PMIX_PERSIST_SESSION} \ \ \text{or their equivalent}.$

These values can be specified by including the respective attributed in the *info* array.

The persistence indicates how long the server should retain the data.

-Advice to PMIx server hosts-

The host environment is not required to guarantee support for any specific range - i.e., the environment does not need to return an error if the data store doesn't support a specified range so long as it is covered by some internally defined range. However, the server must return an error (a) if the key is duplicative within the storage range, and (b) if the server does not allow overwriting of published info by the original publisher - it is left to the discretion of the host environment to allow info-key-based flags to modify this behavior.

The PMIX_USERID and PMIX_GRPID of the publishing process will be provided to support authorization-based access to published information and must be returned on any subsequent lookup request.

16.3.9 pmix_server_lookup_fn_t

Summary

Lookup published data.

```
17_{PMIx v1.0}
```

1

3

4 5

6

7

8

10

11 12

13

14

15 16

18

19 20

21

22

23

24

25

26

27

28

29

30

31

32

33

34 35

36

```
Format
```

typedef pmix status t (*pmix server lookup fn t)(

IN proc

pmix_proc_t structure of the process seeking the data (handle)

IN keys

(array of strings)

IN info

Array of info structures (array of handles)

IN ninfo

Number of elements in the *info* array (integer)

IN cbfunc

Callback function pmix_lookup_cbfunc_t (function reference)

IN cbdata

Data to be passed to the callback function (memory reference)

1	Returns one of the following:			
2 3 4	• PMIX_SUCCESS, indicating that the request is being processed by the host environment - result will be returned in the provided <i>cbfunc</i> . Note that the host must not invoke the callback function prior to returning from the API.			
5 6	• PMIX_OPERATION_SUCCEEDED, indicating that the request was immediately processed and returned <i>success</i> - the <i>cbfunc</i> will not be called			
7 8	• PMIX_ERR_NOT_SUPPORTED, indicating that the host environment does not support the request, even though the function entry was provided in the server module - the <i>cbfunc</i> will not be called			
9 10	• a PMIx error constant indicating either an error in the input or that the request was immediately processed and failed - the <i>cbfunc</i> will not be called			
	▼			
11 12	PMIx libraries are required to pass any provided attributes to the host environment for processing. In addition, the following attributes are required to be included in the passed <i>info</i> array:			
13 14	PMIX_USERID "pmix.euid" (uint32_t) Effective user ID of the connecting process.			
15 16	PMIX_GRPID "pmix.egid" (uint32_t) Effective group ID of the connecting process.			
17				
18	Host environments that implement this entry point are required to support the following attributes:			
19 20 21	<pre>PMIX_RANGE "pmix.range" (pmix_data_range_t) Define constraints on the processes that can access the provided data. Only processes that meet the constraints are allowed to access it.</pre>			
22 23 24	PMIX_WAIT "pmix.wait" (int) Caller requests that the PMIx server wait until at least the specified number of values are found (a value of zero indicates <i>all</i> and is the default).			
	▼ Optional Attributes			
25	The following attributes are optional for host environments that support this operation:			
26 27 28 29	PMIX_TIMEOUT "pmix.timeout" (int) Time in seconds before the specified operation should time out (zero indicating infinite) and return the PMIX_ERR_TIMEOUT error. Care should be taken to avoid race conditions caused by multiple layers (client, server, and host) simultaneously timing the operation.			

1

3

4

5

6

7

8

9

10

11

12

13

14 15

17

18

19

20

21

22

23

35

36

Lookup published data. The host server will be passed a **NULL**-terminated array of string keys identifying the data being requested.

The array of *info* structs is used to pass user-requested options to the server. The default data range is left to the host environment, but expected to be **PMIX_RANGE_SESSION**. This can include a wait flag to indicate that the server should wait for all data to become available before executing the callback function, or should immediately callback with whatever data is available. In addition, a timeout can be specified on the wait to preclude an indefinite wait for data that may never be published.

Advice to PMIx server hosts

The PMIX_USERID and PMIX_GRPID of the requesting process will be provided to support authorization-based access to published information. The host environment is not required to guarantee support for any specific range - i.e., the environment does not need to return an error if the data store doesn't support a specified range so long as it is covered by some internally defined range.

16.3.10 pmix_server_unpublish_fn_t

Summary

Delete data from the data store.

```
16 _{PMIx \ vI.0} Format
```

```
24
                 IN
                       proc
25
                       pmix proc t structure identifying the process making the request (handle)
26
                 IN
                       kevs
27
                       (array of strings)
28
                 IN
                       info
29
                       Array of info structures (array of handles)
                 IN
30
                       ninfo
                       Number of elements in the info array (integer)
31
32
                 IN
                       cbfunc
33
                       Callback function pmix op cbfunc t (function reference)
34
                 IN
                       cbdata
```

Data to be passed to the callback function (memory reference)

Returns one of the following:

1 2 3	• PMIX_SUCCESS, indicating that the request is being processed by the host environment - result will be returned in the provided <i>cbfunc</i> . Note that the host must not invoke the callback function prior to returning from the API.			
4 5	 PMIX_OPERATION_SUCCEEDED, indicating that the request was immediately processed and returned success - the cbfunc will not be called 			
6 7	• PMIX_ERR_NOT_SUPPORTED, indicating that the host environment does not support the request, even though the function entry was provided in the server module - the <i>cbfunc</i> will not be called			
8 9	• a PMIx error constant indicating either an error in the input or that the request was immediately processed and failed - the <i>cbfunc</i> will not be called			
	▼ Required Attributes			
10 11	PMIx libraries are required to pass any provided attributes to the host environment for processing. In addition, the following attributes are required to be included in the passed <i>info</i> array:			
12 13	PMIX_USERID "pmix.euid" (uint32_t) Effective user ID of the connecting process.			
14 15	PMIX_GRPID "pmix.egid" (uint32_t) Effective group ID of the connecting process.			
16				
17	Host environments that implement this entry point are required to support the following attributes:			
18 19 20	PMIX_RANGE "pmix.range" (pmix_data_range_t) Define constraints on the processes that can access the provided data. Only processes that meet the constraints are allowed to access it.			
	▼ Optional Attributes			
21	The following attributes are optional for host environments that support this operation:			
22 23 24 25	PMIX_TIMEOUT "pmix.timeout" (int) Time in seconds before the specified operation should time out (zero indicating infinite) and return the PMIX_ERR_TIMEOUT error. Care should be taken to avoid race conditions caused by multiple layers (client, server, and host) simultaneously timing the operation.			

1

3

4

5

6

7

8

9

10

11 12

14

15

16 17

18

19

20

21

22

23

24

25

26

27

28

29

30

31

32

33

34

35

36

Delete data from the data store. The host server will be passed a **NULL**-terminated array of string keys, plus potential directives such as the data range within which the keys should be deleted. The default data range is left to the host environment, but expected to be **PMIX_RANGE_SESSION**. The callback is to be executed upon completion of the delete procedure.

Advice to PMIx server hosts

The PMIX_USERID and PMIX_GRPID of the requesting process will be provided to support authorization-based access to published information. The host environment is not required to guarantee support for any specific range - i.e., the environment does not need to return an error if the data store doesn't support a specified range so long as it is covered by some internally defined range.

16.3.11 pmix_server_spawn_fn_t

Summary

Spawn a set of applications/processes as per the PMIx_Spawn API.

```
13 _{PMIx \ vI.0} Format
```

C

IN proc

pmix proc t structure of the process making the request (handle)

IN job info

Array of info structures (array of handles)

IN ninfo

Number of elements in the *jobinfo* array (integer)

IN apps

Array of pmix_app_t structures (array of handles)

IN napps

Number of elements in the *apps* array (integer)

IN cbfunc

Callback function **pmix spawn cbfunc t** (function reference)

IN cbdata

Data to be passed to the callback function (memory reference)

Returns one of the following:

	11	
	13	
	15	
1	17	7
2	2021)
2	22	1
	26	
	35	
3	30 31 32)
3	33 34 35	1
٠.	い	,

36

37

38

1

2

3

4

5

6

7

8

9

- PMIX_SUCCESS, indicating that the request is being processed by the host environment result will be
 returned in the provided *cbfunc*. Note that the host must not invoke the callback function prior to returning
 from the API.
- PMIX_OPERATION_SUCCEEDED, indicating that the request was immediately processed and returned success - the cbfunc will not be called
- PMIX_ERR_NOT_SUPPORTED, indicating that the host environment does not support the request, even
 though the function entry was provided in the server module the cbfunc will not be called
- a PMIx error constant indicating either an error in the input or that the request was immediately processed and failed the *cbfunc* will not be called

Required Attributes

PMIx server libraries are required to pass any provided attributes to the host environment for processing. In addition, the following attributes are required to be included in the passed *info* array:

```
PMIX_USERID "pmix.euid" (uint32_t)
```

Effective user ID of the connecting process.

```
PMIX_GRPID "pmix.egid" (uint32_t)
```

Effective group ID of the connecting process.

```
PMIX_SPAWNED "pmix.spawned" (bool)
```

true if this process resulted from a call to **PMIx_Spawn**. Lack of inclusion (i.e., a return status of **PMIX_ERR_NOT_FOUND**) corresponds to a value of **false** for this attribute.

```
PMIX_PARENT_ID "pmix.parent" (pmix_proc_t)
```

Process identifier of the parent process of the specified process - typically used to identify the application process that caused the job containing the specified process to be spawned (e.g., the process that called <code>PMIx_Spawn</code>). This attribute is only provided for a process if it was created by a call to <code>PMIx_Spawn</code> or <code>PMIx_Spawn_nb</code>.

```
PMIX_REQUESTOR_IS_TOOL "pmix.req.tool" (bool)
```

The requesting process is a PMIx tool.

```
PMIX_REQUESTOR_IS_CLIENT "pmix.req.client" (bool)
```

The requesting process is a PMIx client.

Host environments that provide this module entry point are required to pass the **PMIX_SPAWNED** and **PMIX_PARENT_ID** attributes to all PMIx servers launching new child processes so those values can be returned to clients upon connection to the PMIx server. In addition, they are required to support the following attributes when present in either the *job_info* or the *info* array of an element of the *apps* array:

```
PMIX_WDIR "pmix.wdir" (char*)
```

Working directory for spawned processes.

```
PMIX_SET_SESSION_CWD "pmix.ssncwd" (bool)
```

Set the current working directory to the session working directory assigned by the RM - can be assigned to the entire job (by including attribute in the *job_info* array) or on a per-application basis in the *info* array for each **pmix_app_t**.

```
1
               PMIX_PREFIX "pmix.prefix" (char*)
 2
                     Prefix to use for starting spawned processes - i.e., the directory where the executables can be found.
 3
               PMIX_HOST "pmix.host" (char*)
 4
                     Comma-delimited list of hosts to use for spawned processes.
 5
               PMIX HOSTFILE "pmix.hostfile" (char*)
 6
                     Hostfile to use for spawned processes.
               Optional Attributes -----
                ______
 7
               The following attributes are optional for host environments that support this operation:
 8
               PMIX_ADD_HOSTFILE "pmix.addhostfile" (char*)
                     Hostfile containing hosts to add to existing allocation.
 9
10
               PMIX ADD HOST "pmix.addhost" (char*)
11
                     Comma-delimited list of hosts to add to the allocation.
12
               PMIX PRELOAD BIN "pmix.preloadbin" (bool)
                     Preload executables onto nodes prior to executing launch procedure.
13
14
               PMIX PRELOAD FILES "pmix.preloadfiles" (char*)
                     Comma-delimited list of files to pre-position on nodes prior to executing launch procedure.
15
16
               PMIX_PERSONALITY "pmix.pers" (char*)
17
                     Name of personality corresponding to programming model used by application - supported values
18
                     depend upon PMIx implementation.
19
               PMIX DISPLAY MAP "pmix.dispmap" (bool)
20
                     Display process mapping upon spawn.
21
               PMIX_PPR "pmix.ppr" (char*)
22
                     Number of processes to spawn on each identified resource.
23
               PMIX_MAPBY "pmix.mapby" (char*)
24
                     Process mapping policy - when accessed using PMIx_Get, use the PMIX_RANK_WILDCARD value
25
                     for the rank to discover the mapping policy used for the provided namespace. Supported values are
26
                     launcher specific.
27
               PMIX_RANKBY "pmix.rankby" (char*)
28
                     Process ranking policy - when accessed using PMIx_Get, use the PMIX_RANK_WILDCARD value
29
                     for the rank to discover the ranking algorithm used for the provided namespace. Supported values are
30
                     launcher specific.
31
               PMIX_BINDTO "pmix.bindto" (char*)
32
                     Process binding policy - when accessed using PMIx Get, use the PMIX RANK WILDCARD value
33
                     for the rank to discover the binding policy used for the provided namespace. Supported values are
34
                     launcher specific.
35
               PMIX_STDIN_TGT "pmix.stdin" (uint32_t)
36
                     Spawned process rank that is to receive any forwarded stdin.
```

1 PMIX_FWD_STDIN "pmix.fwd.stdin" (pmix_rank_t) 2 The requester intends to push information from its **stdin** to the indicated process. The local spawn 3 agent should, therefore, ensure that the **stdin** channel to that process remains available. A rank of 4 PMIX RANK WILDCARD indicates that all processes in the spawned job are potential recipients. The 5 requester will issue a call to PMIx_IOF_push to initiate the actual forwarding of information to 6 specified targets - this attribute simply requests that the IL retain the ability to forward the information 7 to the designated targets. 8 PMIX_FWD_STDOUT "pmix.fwd.stdout" (bool) 9 Requests that the ability to forward the **stdout** of the spawned processes be maintained. The 10 requester will issue a call to PMIx_IOF_pull to specify the callback function and other options for 11 delivery of the forwarded output. 12 PMIX_FWD_STDERR "pmix.fwd.stderr" (bool) 13 Requests that the ability to forward the **stderr** of the spawned processes be maintained. The 14 requester will issue a call to PMIx IOF pull to specify the callback function and other options for 15 delivery of the forwarded output. 16 PMIX_DEBUGGER_DAEMONS "pmix.debugger" (bool) 17 Included in the pmix info t array of a pmix app t, this attribute declares that the application 18 consists of debugger daemons and shall be governed accordingly. If used as the sole pmix app t in 19 a PMIx_Spawn request, then the PMIX_DEBUG_TARGET attribute must also be provided (in either 20 the job_info or in the info array of the pmix_app_t) to identify the namespace to be debugged so that 21 the launcher can determine where to place the spawned daemons. If neither 22 PMIX DEBUG DAEMONS PER PROC nor PMIX DEBUG DAEMONS PER NODE is specified, then 23 the launcher shall default to a placement policy of one daemon per process in the target job. 24 PMIX TAG OUTPUT "pmix.tagout" (bool) 25 Tag stdout/stderr with the identity of the source process - can be assigned to the entire job (by 26 including attribute in the *job info* array) or on a per-application basis in the *info* array for each 27 pmix_app_t. 28 PMIX_TIMESTAMP_OUTPUT "pmix.tsout" (bool) 29 Timestamp output - can be assigned to the entire job (by including attribute in the job_info array) or on 30 a per-application basis in the *info* array for each pmix_app_t. 31 PMIX_MERGE_STDERR_STDOUT "pmix.mergeerrout" (bool) 32 Merge stdout and stderr streams - can be assigned to the entire job (by including attribute in the 33 job_info array) or on a per-application basis in the info array for each pmix_app_t. 34 PMIX_OUTPUT_TO_FILE "pmix.outfile" (char*) 35 Direct output (both stdout and stderr) into files of form "<filename>.rank" - can be assigned to 36 the entire job (by including attribute in the job info array) or on a per-application basis in the info array 37 for each pmix app t. 38 PMIX_INDEX_ARGV "pmix.indxargv" (bool) 39 Mark the argv with the rank of the process.

PMIX_CPUS_PER_PROC "pmix.cpuperproc" (uint32_t)

1 Number of PUs to assign to each rank - when accessed using **PMIx_Get**, use the 2 PMIX RANK WILDCARD value for the rank to discover the PUs/process assigned to the provided 3 namespace. 4 PMIX NO PROCS ON HEAD "pmix.nolocal" (bool) 5 Do not place processes on the head node. 6 PMIX_NO_OVERSUBSCRIBE "pmix.noover" (bool) 7 Do not oversubscribe the nodes - i.e., do not place more processes than allocated slots on a node. 8 PMIX_REPORT_BINDINGS "pmix.repbind" (bool) 9 Report bindings of the individual processes. 10 PMIX_CPU_LIST "pmix.cpulist" (char*) List of PUs to use for this job - when accessed using PMIx Get, use the PMIX RANK WILDCARD 11 12 value for the rank to discover the PU list used for the provided namespace. 13 PMIX_JOB_RECOVERABLE "pmix.recover" (bool) 14 Application supports recoverable operations. 15 PMIX_JOB_CONTINUOUS "pmix.continuous" (bool) 16 Application is continuous, all failed processes should be immediately restarted. 17 PMIX_MAX_RESTARTS "pmix.maxrestarts" (uint32_t) 18 Maximum number of times to restart a process - when accessed using PMIx_Get, use the PMIX RANK WILDCARD value for the rank to discover the max restarts for the provided namespace. 19 20 PMIX_TIMEOUT "pmix.timeout" (int) 21 Time in seconds before the specified operation should time out (zero indicating infinite) and return the 22 PMIX_ERR_TIMEOUT error. Care should be taken to avoid race conditions caused by multiple layers (client, server, and host) simultaneously timing the operation. 23 24 PMIX_JOB_TIMEOUT "pmix.job.time" (int) 25 Time in seconds before the spawned job should time out and be terminated $(0 \Rightarrow \text{infinite})$, defined as 26 the total runtime of the job (equivalent to the walltime limit of typical batch schedulers). 27 PMIX_SPAWN_TIMEOUT "pmix.sp.time" (int) 28 Time in seconds before spawn operation should time out (0 => infinite). Logically equivalent to passing the PMIX_TIMEOUT attribute to the PMIx_Spawn API, it is provided as a separate attribute 29 30 to distinguish it from the **PMIX JOB TIMEOUT** attribute **Description** 31 32 be MPI or any other programming model. Thus, the host server cannot make any assumptions as to their 33 34

Spawn a set of applications/processes as per the PMIx Spawn API. Note that applications are not required to required support. The callback function is to be executed once all processes have been started. An error in starting any application or process in this request shall cause all applications and processes in the request to be terminated, and an error returned to the originating caller.

Note that a timeout can be specified in the job_info array to indicate that failure to start the requested job within the given time should result in termination to avoid hangs.

35

36 37

16.3.11.1 Server spawn attributes 1 2 PMIX_REQUESTOR_IS_TOOL "pmix.req.tool" (bool) 3 The requesting process is a PMIx tool. PMIX_REQUESTOR_IS_CLIENT "pmix.req.client" (bool) 4 5 The requesting process is a PMIx client. 16.3.12 pmix_server_connect_fn_t 6 7 Summary 8 Record the specified processes as connected. 9 PMIx v1.010 typedef pmix_status_t (*pmix_server_connect_fn_t)(11 const pmix_proc_t procs[], 12 size_t nprocs, 13 const pmix_info_t info[], 14 size t ninfo, 15 pmix_op_cbfunc_t cbfunc, 16 void *cbdata); - c -17 IN procs Array of pmix proc t structures identifying participants (array of handles) 18 19 IN nprocs 20 Number of elements in the *procs* array (integer) 21 IN info 22 Array of info structures (array of handles) 23 IN 24 Number of elements in the *info* array (integer) 25 cbfunc 26 Callback function pmix_op_cbfunc_t (function reference) 27 IN cbdata 28 Data to be passed to the callback function (memory reference) 29 Returns one of the following: 30 • PMIX SUCCESS, indicating that the request is being processed by the host environment - result will be returned in the provided cbfunc. Note that the host must not invoke the callback function prior to returning 31 32 from the API. 33 • PMIX OPERATION SUCCEEDED, indicating that the request was immediately processed and returned success - the cbfunc will not be called 34 • PMIX_ERR_NOT_SUPPORTED, indicating that the host environment does not support the request, even 35 36 though the function entry was provided in the server module - the cbfunc will not be called 37 • a PMIx error constant indicating either an error in the input or that the request was immediately processed 38 and failed - the cbfunc will not be called

1 PMIX_LOCAL_COLLECTIVE_STATUS "pmix.loc.col.st" (pmix_status_t) 2 Status code for local collective operation being reported to the host by the server library. PMIx servers 3 may aggregate the participation by local client processes in a collective operation - e.g., instead of 4 passing individual client calls to **PMIx** Fence up to the host environment, the server may pass only a 5 single call to the host when all local participants have executed their PMIx Fence call, thereby 6 reducing the burden placed on the host. However, in cases where the operation locally fails (e.g., if a 7 participating client abnormally terminates prior to calling the operation), the server upcall functions to 8 the host do not include a pmix status t by which the PMIx server can alert the host to that failure. 9 This attribute resolves that problem by allowing the server to pass the status information regarding the 10 local collective operation. PMIx libraries are required to pass any provided attributes to the host environment for processing. 11 **A**---------- Optional Attributes 12 The following attributes are optional for host environments that support this operation: 13 PMIX_TIMEOUT "pmix.timeout" (int) 14 Time in seconds before the specified operation should time out (zero indicating infinite) and return the PMIX ERR TIMEOUT error. Care should be taken to avoid race conditions caused by multiple layers 15 (client, server, and host) simultaneously timing the operation. 16 ______ **Description** 17 18 Record the processes specified by the procs array as connected as per the PMIx definition. The callback is to 19 be executed once every daemon hosting at least one participant has called the host server's 20 pmix server connect fn t function, and the host environment has completed any supporting 21 operations required to meet the terms of the PMIx definition of *connected* processes. Advice to PMIx library implementers 22 The PMIx server library is required to aggregate participation by local clients, passing the request to the host 23 environment once all local participants have executed the API. Advice to PMIx server hosts 24 The host will receive a single call for each collective operation. It is the responsibility of the host to identify 25 the nodes containing participating processes, execute the collective across all participating nodes, and notify 26 the local PMIx server library upon completion of the global collective. 16.3.13 pmix server disconnect fn t 27

Required Attributes

28 29 Summary

Disconnect a previously connected set of processes.

typedef	pmix_status_t	(*pmix_	server_	_disconnect_	_fn_t)(
			const p	pmix_proc_t	procs[],
			size_t	nprocs,	
			const p	omix_info_t	info[],
			size_t	ninfo,	
]	pmix_op	_cbfunc_t	bfunc,
		•	void *	cbdata);	
A					

IN procs

Array of pmix proc t structures identifying participants (array of handles)

IN nprocs

Number of elements in the *procs* array (integer)

IN info

Array of info structures (array of handles)

IN ninfo

Number of elements in the info array (integer)

IN cbfunc

Callback function pmix_op_cbfunc_t (function reference)

IN cbdata

Data to be passed to the callback function (memory reference)

Returns one of the following:

- PMIX_SUCCESS, indicating that the request is being processed by the host environment result will be returned in the provided *cbfunc*. Note that the host must not invoke the callback function prior to returning from the API.
- PMIX_OPERATION_SUCCEEDED, indicating that the request was immediately processed and returned success the cbfunc will not be called
- PMIX_ERR_NOT_SUPPORTED, indicating that the host environment does not support the request, even though the function entry was provided in the server module the *cbfunc* will not be called
- a PMIx error constant indicating either an error in the input or that the request was immediately processed and failed the *cbfunc* will not be called

Required Attributes

PMIX_LOCAL_COLLECTIVE_STATUS "pmix.loc.col.st" (pmix_status_t)

Status code for local collective operation being reported to the host by the server library. PMIx servers may aggregate the participation by local client processes in a collective operation - e.g., instead of passing individual client calls to <code>PMIx_Fence</code> up to the host environment, the server may pass only a single call to the host when all local participants have executed their <code>PMIx_Fence</code> call, thereby reducing the burden placed on the host. However, in cases where the operation locally fails (e.g., if a participating client abnormally terminates prior to calling the operation), the server upcall functions to the host do not include a <code>pmix_status_t</code> by which the PMIx server can alert the host to that failure.

This attribute resolves that problem by allowing the server to pass the status information regarding the 1 2 local collective operation. 3 PMIx libraries are required to pass any provided attributes to the host environment for processing. **A**-----Optional Attributes The following attributes are optional for host environments that support this operation: 4 5 PMIX_TIMEOUT "pmix.timeout" (int) 6 Time in seconds before the specified operation should time out (zero indicating infinite) and return the 7 PMIX ERR TIMEOUT error. Care should be taken to avoid race conditions caused by multiple layers 8 (client, server, and host) simultaneously timing the operation. ______ 9 Description 10 Disconnect a previously connected set of processes. The callback is to be executed once every daemon hosting 11 at least one participant has called the host server's has called the pmix server disconnect fn t function, and the host environment has completed any required supporting operations. 12 Advice to PMIx library implementers 13 The PMIx server library is required to aggregate participation by local clients, passing the request to the host environment once all local participants have executed the API. 14 -Advice to PMIx server hosts-15 The host will receive a single call for each collective operation. It is the responsibility of the host to identify the nodes containing participating processes, execute the collective across all participating nodes, and notify 16 the local PMIx server library upon completion of the global collective. 17 18 A PMIX ERR INVALID OPERATION error must be returned if the specified set of procs was not previously connected via a call to the pmix server connect fn t function. 19

16.3.14 pmix_server_register_events_fn_t

Summary

Register to receive notifications for the specified events.

20

21

^-----

Description

1

3

4

5

7

9

10

11

12

13

14

15

16

17

Register to receive notifications for the specified status codes. The *info* array included in this API is reserved for possible future directives to further steer notification.

-Advice to PMIx library implementers-

The PMIx server library must track all client registrations for subsequent notification. This module function shall only be called when:

- the PMIx server library has not previously requested notification of that code i.e., the host environment is to be contacted only once a given unique code value

-Advice to PMIx server hosts-

The host environment is required to pass to its PMIx server library all non-environmental events that directly relate to a registered namespace without the PMIx server library explicitly requesting them. Environmental events are to be translated to their nearest PMIx equivalent code as defined in the range between PMIX_EVENT_SYS_BASE and PMIX_EVENT_SYS_OTHER (inclusive).

16.3.15 pmix_server_deregister_events_fn_t

Summary

Deregister to receive notifications for the specified events.

1

2

6

7 8 9

10 11

12 13 14

15 16

17 18

19 20 21

22 23

24

25 26

27 28

29 30 31

32

clbeger	Pmix_scacus_c	(*PMIX_Server_deregrater_events_in_t)(
		<pre>pmix_status_t *codes,</pre>
		size_t ncodes,
		<pre>pmix_op_cbfunc_t cbfunc,</pre>
		<pre>void *cbdata);</pre>
A		

IN codes

Array of pmix_status_t values (array of handles)

Number of elements in the *codes* array (integer)

IN cbfunc

Callback function **pmix** op **cbfunc t** (function reference)

IN cbdata

Data to be passed to the callback function (memory reference)

Returns one of the following:

- PMIX_SUCCESS, indicating that the request is being processed by the host environment result will be returned in the provided cbfunc. Note that the host must not invoke the callback function prior to returning from the API.
- PMIX_OPERATION_SUCCEEDED, indicating that the request was immediately processed and returned success - the cbfunc will not be called
- PMIX_ERR_NOT_SUPPORTED, indicating that the host environment does not support the request, even though the function entry was provided in the server module - the cbfunc will not be called
- a PMIx error constant indicating either an error in the input or that the request was immediately processed and failed - the cbfunc will not be called

Description

Deregister to receive notifications for the specified events to which the PMIx server has previously registered.

Advice to PMIx library implementers—

The PMIx server library must track all client registrations. This module function shall only be called when:

- the library is deregistering environmental codes (i.e., a PMIx codes in the range between PMIX EVENT SYS BASE and PMIX EVENT SYS OTHER, inclusive) or codes that lies outside the defined PMIx range of constants; and
- no client (including the server library itself) remains registered for notifications on any included code i.e., a code should be included in this call only when no registered notifications against it remain.

16.3.16 pmix_server_notify_event_fn_t

2 Summary 3 Notify the specified processes of an event. **Format** 4 *PMIx v2.0* 5 typedef pmix status t (*pmix server notify event fn t) (6 pmix_status_t code, 7 const pmix_proc_t *source, 8 pmix_data_range_t range, 9 pmix_info_t info[], 10 size_t ninfo, 11 pmix_op_cbfunc_t cbfunc, 12 void *cbdata); 13 IN code 14 The pmix_status_t event code being referenced structure (handle) 15 source pmix_proc_t of process that generated the event (handle) 16 17 IN range 18 pmix data range t range over which the event is to be distributed (handle) IN 19 20 Optional array of pmix info t structures containing additional information on the event (array of handles) 21 22 IN ninfo 23 Number of elements in the *info* array (integer) 24 25 Callback function **pmix** op **cbfunc t** (function reference) 26 IN cbdata 27 Data to be passed to the callback function (memory reference) 28 Returns one of the following: 29 • PMIX SUCCESS, indicating that the request is being processed by the host environment - result will be 30 returned in the provided cbfunc. Note that the host must not invoke the callback function prior to returning 31 from the API. 32 • PMIX OPERATION SUCCEEDED, indicating that the request was immediately processed and returned 33 success - the cbfunc will not be called 34 • PMIX ERR NOT SUPPORTED, indicating that the host environment does not support the request, even 35 though the function entry was provided in the server module - the cbfunc will not be called 36 • a PMIx error constant indicating either an error in the input or that the request was immediately processed 37 and failed - the cbfunc will not be called

Required Attributes

PMIx libraries are required to pass any provided attributes to the host environment for processing.

Host environments that provide this module entry point are required to support the following attributes:

```
PMIX_RANGE "pmix.range" (pmix_data_range_t)
```

Define constraints on the processes that can access the provided data. Only processes that meet the constraints are allowed to access it.

Description

Notify the specified processes (described through a combination of *range* and attributes provided in the *info* array) of an event generated either by the PMIx server itself or by one of its local clients. The process generating the event is provided in the *source* parameter, and any further descriptive information is included in the *info* array.

Note that the PMIx server library is not allowed to echo any event given to it by its host via the PMIx_Notify_event API back to the host through the pmix_server_notify_event_fn_t server module function.

Advice to PMIx server hosts

The callback function is to be executed once the host environment no longer requires that the PMIx server library maintain the provided data structures. It does not necessarily indicate that the event has been delivered to any process, nor that the event has been distributed for delivery

16.3.17 pmix_server_listener_fn_t

Summary

Register a socket the host server can monitor for connection requests.

PMIx v1.0

```
Format
```

```
IN incoming_sd (integer)
```

IN cbfunc

Callback function pmix_connection_cbfunc_t (function reference)

IN cbdata (memory reference)

Returns **PMIX_SUCCESS** indicating that the request is accepted, or a negative value corresponding to a PMIx error constant indicating that the request has been rejected.

Description

1

3

4

5

6

7

8 9

10

18

19

20

21

22

23

33

34

Register a socket the host environment can monitor for connection requests, harvest them, and then call the PMIx server library's internal callback function for further processing. A listener thread is essential to efficiently harvesting connection requests from large numbers of local clients such as occur when running on large SMPs. The host server listener is required to call accept on the incoming connection request, and then pass the resulting socket to the provided cbfunc. A **NULL** for this function will cause the internal PMIx server to spawn its own listener thread.

16.3.17.1 PMIx Client Connection Callback Function

Summary

Callback function for incoming connection request from a local client.

```
11 PMIx v1.0 Format

12 typedef void (*pmix_connection_cbfunc_t) (
13 int incoming_sd, void *cbdata);

C

14 IN incoming_sd
(integer)
```

```
16 IN cbdata (memory reference)
```

Description

Callback function for incoming connection requests from local clients - only used by host environments that wish to directly handle socket connection requests.

16.3.18 pmix_server_query_fn_t

Summary

IN

Query information from the resource manager.

```
24 <sub>PMIx v2.0</sub>
              Format
25
              typedef pmix_status_t (*pmix_server_query_fn_t)(
26
                                               pmix_proc_t *proct,
27
                                               pmix_query_t *queries,
                                               size_t nqueries,
28
29
                                               pmix_info_cbfunc_t cbfunc,
30
                                               void *cbdata);
                                                — C —
31
              IN
                  proct
32
                   pmix proc t structure of the requesting process (handle)
```

Array of pmix_query_t structures (array of handles)

1 2 3 4 5 6	IN nqueries Number of elements in the queries array (integer) IN cbfunc Callback function pmix_info_cbfunc_t (function reference) IN cbdata Data to be passed to the callback function (memory reference)		
7	Returns one of the following:		
8 9 10	• PMIX_SUCCESS , indicating that the request is being processed by the host environment - result will be returned in the provided <i>cbfunc</i> . Note that the host must not invoke the callback function prior to returning from the API.		
11 12	 PMIX_OPERATION_SUCCEEDED, indicating that the request was immediately processed and returned success - the cbfunc will not be called 		
13 14	 PMIX_ERR_NOT_SUPPORTED, indicating that the host environment does not support the request, even though the function entry was provided in the server module - the cbfunc will not be called 		
15 16	• a PMIx error constant indicating either an error in the input or that the request was immediately processed and failed - the <i>cbfunc</i> will not be called		
	▼ Required Attributes		
17 18	PMIx libraries are required to pass any provided attributes to the host environment for processing. In addition, the following attributes are required to be included in the passed <i>info</i> array:		
19 20	PMIX_USERID "pmix.euid" (uint32_t) Effective user ID of the connecting process.		
21 22	PMIX_GRPID "pmix.egid" (uint32_t) Effective group ID of the connecting process.		
	▼ Optional Attributes		
23	The following attributes are optional for host environments that support this operation:		
24 25	PMIX_QUERY_NAMESPACES "pmix.qry.ns" (char*) Request a comma-delimited list of active namespaces. NO QUALIFIERS.		
26 27 28	<pre>PMIX_QUERY_JOB_STATUS "pmix.qry.jst" (pmix_status_t) Status of a specified, currently executing job. REQUIRED QUALIFIER: PMIX_NSPACE indicating the namespace whose status is being queried.</pre>		
29 30	PMIX_QUERY_QUEUE_LIST "pmix.qry.qlst" (char*) Request a comma-delimited list of scheduler queues. NO QUALIFIERS.		
31 32 33	PMIX_QUERY_QUEUE_STATUS "pmix.qry.qst" (char*) Returns status of a specified scheduler queue, expressed as a string. OPTIONAL QUALIFIERS: PMIX_ALLOC_QUEUE naming specific queue whose status is being requested.		
34	<pre>PMIX_QUERY_PROC_TABLE "pmix.qry.ptable" (char*)</pre>		

1 2 3	Returns a (pmix_data_array_t) array of pmix_proc_info_t, one entry for each process in the specified namespace, ordered by process job rank. REQUIRED QUALIFIER: pmix_nspace indicating the namespace whose process table is being queried.
4 5 6 7 8 9	PMIX_QUERY_LOCAL_PROC_TABLE "pmix.qry.lptable" (char*) Returns a (pmix_data_array_t) array of pmix_proc_info_t, one entry for each process in the specified namespace executing on the same node as the requester, ordered by process job rank. REQUIRED QUALIFIER: PMIX_NSPACE indicating the namespace whose local process table is being queried. OPTIONAL QUALIFIER: PMIX_HOSTNAME indicating the host whose local process table is being queried. By default, the query assumes that the host upon which the request was made is to be used.
11 12	<pre>PMIX_QUERY_SPAWN_SUPPORT "pmix.qry.spawn" (bool) Return a comma-delimited list of supported spawn attributes. NO QUALIFIERS.</pre>
13 14	<pre>PMIX_QUERY_DEBUG_SUPPORT "pmix.qry.debug" (bool) Return a comma-delimited list of supported debug attributes. NO QUALIFIERS.</pre>
15 16 17 18	<pre>PMIX_QUERY_MEMORY_USAGE "pmix.qry.mem" (bool) Return information on memory usage for the processes indicated in the qualifiers. OPTIONAL QUALIFIERS: PMIX_NSPACE and PMIX_RANK, or PMIX_PROCID of specific process(es) whose memory usage is being requested.</pre>
19 20	PMIX_QUERY_LOCAL_ONLY "pmix.qry.local" (bool) Constrain the query to local information only. NO QUALIFIERS.
21 22	<pre>PMIX_QUERY_REPORT_AVG "pmix.qry.avg" (bool) Report only average values for sampled information. NO QUALIFIERS.</pre>
23 24	PMIX_QUERY_REPORT_MINMAX "pmix.qry.minmax" (bool) Report minimum and maximum values. NO QUALIFIERS.
25 26	<pre>PMIX_QUERY_ALLOC_STATUS "pmix.query.alloc" (char*) String identifier of the allocation whose status is being requested. NO QUALIFIERS.</pre>
27 28 29 30	PMIX_TIME_REMAINING "pmix.time.remaining" (char*) Query number of seconds (uint32_t) remaining in allocation for the specified namespace. OPTIONAL QUALIFIERS: PMIX_NSPACE of the namespace whose info is being requested (defaults to allocation containing the caller).
31 32 33 34	Description Query information from the host environment. The query will include the namespace/rank of the process that is requesting the info, an array of pmix_query_t describing the request, and a callback function/data for the return. Advice to PMIx library implementers

The PMIx server library should not block in this function as the host environment may, depending upon the information being requested, require significant time to respond.

16.3.19 pmix_server_tool_connection_fn_t

```
2
                Summary
 3
                Register that a tool has connected to the server.
                Format
    PMIx v2.0
 5
                typedef void (*pmix_server_tool_connection_fn_t)(
 6
                                                     pmix_info_t info[], size_t ninfo,
 7
                                                     pmix_tool_connection_cbfunc_t cbfunc,
 8
                                                     void *cbdata);
                                                              C -
 9
                     info
                IN
10
                     Array of pmix info t structures (array of handles)
11
12
                     Number of elements in the info array (integer)
13
                     cbfunc
                     Callback function pmix_tool_connection_cbfunc_t (function reference)
14
15
                IN
                     cbdata
16
                     Data to be passed to the callback function (memory reference)
                                                  Required Attributes
17
                PMIx libraries are required to pass the following attributes in the info array:
18
                PMIX_USERID "pmix.euid" (uint32_t)
                      Effective user ID of the connecting process.
19
20
                PMIX_GRPID "pmix.egid" (uint32_t)
21
                      Effective group ID of the connecting process.
22
                PMIX_TOOL_NSPACE "pmix.tool.nspace" (char*)
                      Name of the namespace to use for this tool. This must be included only if the tool already has an
23
24
                      assigned namespace.
25
                PMIX_TOOL_RANK "pmix.tool.rank" (uint32_t)
26
                      Rank of this tool. This must be included only if the tool already has an assigned rank.
27
                PMIX_CREDENTIAL "pmix.cred" (char*)
                      Security credential assigned to the process.
28
```

Optional Attributes

The following attributes are optional for host environments that support this operation:

PMIX_FWD_STDOUT "pmix.fwd.stdout" (bool)

Requests that the ability to forward the **stdout** of the spawned processes be maintained. The requester will issue a call to **PMIx_IOF_pull** to specify the callback function and other options for delivery of the forwarded output.

PMIX_FWD_STDERR "pmix.fwd.stderr" (bool)

Requests that the ability to forward the **stderr** of the spawned processes be maintained. The requester will issue a call to **PMIx_IOF_pull** to specify the callback function and other options for delivery of the forwarded output.

PMIX_FWD_STDIN "pmix.fwd.stdin" (pmix_rank_t)

The requester intends to push information from its **stdin** to the indicated process. The local spawn agent should, therefore, ensure that the **stdin** channel to that process remains available. A rank of **PMIX_RANK_WILDCARD** indicates that all processes in the spawned job are potential recipients. The requester will issue a call to **PMIX_IOF_push** to initiate the actual forwarding of information to specified targets - this attribute simply requests that the IL retain the ability to forward the information to the designated targets.

```
PMIX_VERSION_INFO "pmix.version" (char*)
```

PMIx version of the library being used by the connecting process.

Description

Register that a tool has connected to the server, possibly requesting that the tool be assigned a namespace/rank identifier for further interactions. The <code>pmix_info_t</code> array is used to pass qualifiers for the connection request, including the effective uid and gid of the calling tool for authentication purposes.

If the tool already has an assigned process identifier, then this must be indicated in the *info* array. The host is responsible for checking that the provided namespace does not conflict with any currently known assignments, returning an appropriate error in the callback function if a conflict is found.

The host environment is solely responsible for authenticating and authorizing the connection using whatever means it deems appropriate. If certificates or other authentication information are required, then the tool must provide them. The conclusion of those operations shall be communicated back to the PMIx server library via the callback function.

Approval or rejection of the connection request shall be returned in the *status* parameter of the **pmix_tool_connection_cbfunc_t**. If the connection is refused, the PMIx server library must terminate the connection attempt. The host must not execute the callback function prior to returning from the API.

```
16.3.19.1 Tool connection attributes
 1
 2
               Attributes associated with tool connections.
 3
               PMIX_USERID "pmix.euid" (uint32_t)
 4
                     Effective user ID of the connecting process.
 5
               PMIX GRPID "pmix.egid" (uint32 t)
 6
                     Effective group ID of the connecting process.
 7
               PMIX_VERSION_INFO "pmix.version" (char*)
 8
                     PMIx version of the library being used by the connecting process.
 9
     16.3.19.2 PMIx Tool Connection Callback Function
               Summary
10
11
               Callback function for incoming tool connections.
               Format
12
    PMIx v2.0
13
               typedef void (*pmix_tool_connection_cbfunc_t)(
14
                                        pmix_status_t status,
                                       pmix_proc_t *proc, void *cbdata);
15
                                            ____ C ____
16
               IN
                    status
17
                    pmix status t value (handle)
               IN
18
19
                    pmix proc t structure containing the identifier assigned to the tool (handle)
20
               IN
                    cbdata
21
                    Data to be passed (memory reference)
22
               Description
23
               Callback function for incoming tool connections. The host environment shall provide a namespace/rank
               identifier for the connecting tool.
24
                                          Advice to PMIx server hosts
25
               It is assumed that rank=0 will be the normal assignment, but allow for the future possibility of a parallel set
26
               of tools connecting, and thus each process requiring a unique rank.
```

16.3.20 pmix_server_log_fn_t

Summary

27

28 29

Log data on behalf of a client.

```
Format
 1
 2
               typedef void (*pmix_server_log_fn_t)(
 3
                                        const pmix_proc_t *client,
 4
                                        const pmix_info_t data[], size_t ndata,
 5
                                        const pmix info t directives[], size t ndirs,
 6
                                        pmix op cbfunc t cbfunc, void *cbdata);
                                                        - C
 7
                    client
 8
                    pmix_proc_t structure (handle)
 9
               IN
                    data
10
                    Array of info structures (array of handles)
11
                    Number of elements in the data array (integer)
12
13
               IN
                    directives
14
                    Array of info structures (array of handles)
15
               IN
                    ndirs
16
                    Number of elements in the directives array (integer)
17
               IN
                    cbfunc
                    Callback function pmix op cbfunc t (function reference)
18
               IN
19
                    cbdata
20
                    Data to be passed to the callback function (memory reference)
                  _____
                                                 Required Attributes
               PMIx libraries are required to pass any provided attributes to the host environment for processing. In addition,
21
22
               the following attributes are required to be included in the passed info array:
23
               PMIX USERID "pmix.euid" (uint32 t)
24
                     Effective user ID of the connecting process.
25
               PMIX GRPID "pmix.eqid" (uint32_t)
26
                     Effective group ID of the connecting process.
27
28
               Host environments that provide this module entry point are required to support the following attributes:
29
               PMIX LOG STDERR "pmix.log.stderr" (char*)
30
                     Log string to stderr.
31
               PMIX_LOG_STDOUT "pmix.log.stdout" (char*)
32
                     Log string to stdout.
33
               PMIX_LOG_SYSLOG "pmix.log.syslog" (char*)
34
                     Log data to syslog. Defaults to ERROR priority. Will log to global syslog if available, otherwise to
35
                     local syslog.
                                ______
```

```
Optional Attributes
 1
                The following attributes are optional for host environments that support this operation:
 2
                PMIX LOG MSG "pmix.log.msg" (pmix byte object t)
 3
                      Message blob to be sent somewhere.
 4
                PMIX_LOG_EMAIL "pmix.log.email" (pmix_data_array_t)
 5
                      Log via email based on pmix info t containing directives.
 6
                PMIX_LOG_EMAIL_ADDR "pmix.log.emaddr" (char*)
 7
                      Comma-delimited list of email addresses that are to receive the message.
 8
                PMIX_LOG_EMAIL_SUBJECT "pmix.log.emsub" (char*)
 9
                      Subject line for email.
10
                PMIX_LOG_EMAIL_MSG "pmix.log.emmsg" (char*)
                      Message to be included in email.
11
                Description
12
13
                Log data on behalf of a client. This function is not intended for output of computational results, but rather for
14
                reporting status and error messages. The host must not execute the callback function prior to returning from
15
                the API.
     16.3.21
                   pmix_server_alloc_fn_t
16
17
                Summary
18
                Request allocation operations on behalf of a client.
19
    PMIx v2.0
20
                typedef pmix_status_t (*pmix_server_alloc_fn_t)(
21
                                                    const pmix_proc_t *client,
22
                                                    pmix_alloc_directive_t directive,
23
                                                    const pmix_info_t data[],
24
                                                    size_t ndata,
25
                                                    pmix_info_cbfunc_t cbfunc,
26
                                                    void *cbdata);
                                                          - C
27
                IN
                     client
28
                     pmix proc t structure of process making request (handle)
29
                    directive
30
                     Specific action being requested (pmix_alloc_directive_t)
31
                IN
                     data
32
                     Array of info structures (array of handles)
33
                IN
34
                     Number of elements in the data array (integer)
```

1 2 3 4	 IN cbfunc Callback function pmix_info_cbfunc_t (function reference) IN cbdata Data to be passed to the callback function (memory reference) 		
5	Returns one of the following:		
6 7 8	• PMIX_SUCCESS, indicating that the request is being processed by the host environment - result will be returned in the provided <i>cbfunc</i> . Note that the host must not invoke the callback function prior to returning from the API.		
9 10	 PMIX_OPERATION_SUCCEEDED, indicating that the request was immediately processed and returned success - the cbfunc will not be called 		
11 12	• PMIX_ERR_NOT_SUPPORTED, indicating that the host environment does not support the request, even though the function entry was provided in the server module - the <i>cbfunc</i> will not be called		
13 14	• a PMIx error constant indicating either an error in the input or that the request was immediately processed and failed - the <i>cbfunc</i> will not be called		
	▼ Required Attributes		
15 16	PMIx libraries are required to pass any provided attributes to the host environment for processing. In addition, the following attributes are required to be included in the passed <i>info</i> array:		
17 18	PMIX_USERID "pmix.euid" (uint32_t) Effective user ID of the connecting process.		
19 20 21	PMIX_GRPID "pmix.egid" (uint32_t) Effective group ID of the connecting process.		
22	Host environments that provide this module entry point are required to support the following attributes:		
23 24 25	PMIX_ALLOC_ID "pmix.alloc.id" (char*) A string identifier (provided by the host environment) for the resulting allocation which can later be used to reference the allocated resources in, for example, a call to PMIx_Spawn.		
26 27	<pre>PMIX_ALLOC_NUM_NODES "pmix.alloc.nnodes" (uint64_t) The number of nodes being requested in an allocation request.</pre>		
28 29	PMIX_ALLOC_NUM_CPUS "pmix.alloc.ncpus" (uint64_t) Number of PUs being requested in an allocation request.		
30 31	PMIX_ALLOC_TIME "pmix.alloc.time" (uint32_t) Total session time (in seconds) being requested in an allocation request.		

Optional Attributes The following attributes are optional for host environments that support this operation: 1 2 PMIX ALLOC NODE LIST "pmix.alloc.nlist" (char*) 3 Regular expression of the specific nodes being requested in an allocation request. 4 PMIX_ALLOC_NUM_CPU_LIST "pmix.alloc.ncpulist" (char*) 5 Regular expression of the number of PUs for each node being requested in an allocation request. 6 PMIX_ALLOC_CPU_LIST "pmix.alloc.cpulist" (char*) 7 Regular expression of the specific PUs being requested in an allocation request. 8 PMIX_ALLOC_MEM_SIZE "pmix.alloc.msize" (float) 9 Number of Megabytes[base2] of memory (per process) being requested in an allocation request. 10 PMIX_ALLOC_FABRIC "pmix.alloc.net" (array) Array of pmix_info_t describing requested fabric resources. This must include at least: 11 PMIX ALLOC FABRIC ID, PMIX ALLOC FABRIC TYPE, and 12 13 PMIX_ALLOC_FABRIC_ENDPTS, plus whatever other descriptors are desired. 14 PMIX ALLOC FABRIC ID "pmix.alloc.netid" (char*) 15 The key to be used when accessing this requested fabric allocation. The fabric allocation will be returned/stored as a pmix_data_array_t of pmix_info_t whose first element is composed of 16 17 this key and the allocated resource description. The type of the included value depends upon the fabric 18 support. For example, a TCP allocation might consist of a comma-delimited string of socket ranges 19 such as "32000-32100, 33005, 38123-38146". Additional array entries will consist of any provided resource request directives, along with their assigned values. Examples include: 20 21 PMIX_ALLOC_FABRIC_TYPE - the type of resources provided; PMIX_ALLOC_FABRIC_PLANE -22 if applicable, what plane the resources were assigned from; PMIX_ALLOC_FABRIC_QOS - the 23 assigned QoS; PMIX_ALLOC_BANDWIDTH - the allocated bandwidth; 24 PMIX ALLOC FABRIC SEC KEY - a security key for the requested fabric allocation. NOTE: the 25 array contents may differ from those requested, especially if PMIX INFO REQD was not set in the 26 request. 27 PMIX ALLOC BANDWIDTH "pmix.alloc.bw" (float) 28 Fabric bandwidth (in Megabits[base2]/sec) for the job being requested in an allocation request. 29 PMIX ALLOC FABRIC QOS "pmix.alloc.netgos" (char*)

Fabric quality of service level for the job being requested in an allocation request.

Description

1

3

4

5

6

7

8

9

10

11 12

13

14

15

16 17 Request new allocation or modifications to an existing allocation on behalf of a client. Several broad categories are envisioned, including the ability to:

- Request allocation of additional resources, including memory, bandwidth, and compute for an existing
 allocation. Any additional allocated resources will be considered as part of the current allocation, and thus
 will be released at the same time.
- Request a new allocation of resources. Note that the new allocation will be disjoint from (i.e., not affiliated with) the allocation of the requestor thus the termination of one allocation will not impact the other.
- Extend the reservation on currently allocated resources, subject to scheduling availability and priorities.
- Return no-longer-required resources to the scheduler. This includes the *loan* of resources back to the scheduler with a promise to return them upon subsequent request.

The callback function provides a *status* to indicate whether or not the request was granted, and to provide some information as to the reason for any denial in the **pmix_info_cbfunc_t** array of **pmix_info_t** structures.

16.3.22 pmix_server_job_control_fn_t

Summary

Execute a job control action on behalf of a client.

```
18 <sub>PMIx v2.0</sub>
              Format
19
              typedef pmix_status_t (*pmix_server_job_control_fn_t)(
20
                                               const pmix_proc_t *requestor,
21
                                               const pmix_proc_t targets[],
22
                                               size t ntargets,
23
                                               const pmix_info_t directives[],
24
                                               size_t ndirs,
25
                                               pmix_info_cbfunc_t cbfunc,
26
                                               void *cbdata);
                                                       C
27
                   requestor
28
                   pmix proc t structure of requesting process (handle)
```

```
29
                 IN
                       targets
30
                       Array of proc structures (array of handles)
31
                 IN
                       ntargets
32
                       Number of elements in the targets array (integer)
33
                 IN
                       directives
34
                       Array of info structures (array of handles)
35
                       ndirs
36
                       Number of elements in the info array (integer)
37
                 IN
                       cbfunc
38
                       Callback function pmix info cbfunc t (function reference)
39
                 IN
```

Data to be passed to the callback function (memory reference)

1 Returns one of the following: 2 • PMIX_SUCCESS, indicating that the request is being processed by the host environment - result will be 3 returned in the provided cbfunc. Note that the host must not invoke the callback function prior to returning from the APL 5 PMIX_OPERATION_SUCCEEDED, indicating that the request was immediately processed and returned 6 success - the cbfunc will not be called 7 • PMIX ERR NOT SUPPORTED, indicating that the host environment does not support the request, even though the function entry was provided in the server module - the cbfunc will not be called 8 9 • a PMIx error constant indicating either an error in the input or that the request was immediately processed 10 and failed - the cbfunc will not be called Required Attributes PMIx libraries are required to pass any attributes provided by the client to the host environment for processing. 11 12 In addition, the following attributes are required to be included in the passed *info* array: 13 PMIX_USERID "pmix.euid" (uint32_t) Effective user ID of the connecting process. 14 15 PMIX GRPID "pmix.eqid" (uint32_t) 16 Effective group ID of the connecting process. 17 18 Host environments that provide this module entry point are required to support the following attributes: 19 PMIX_JOB_CTRL_ID "pmix.jctrl.id" (char*) 20 Provide a string identifier for this request. The user can provide an identifier for the requested 21 operation, thus allowing them to later request status of the operation or to terminate it. The host, therefore, shall track it with the request for future reference. 22 23 PMIX_JOB_CTRL_PAUSE "pmix.jctrl.pause" (bool) Pause the specified processes. 24 25 PMIX JOB CTRL RESUME "pmix.jctrl.resume" (bool) Resume ("un-pause") the specified processes. 26 27 PMIX JOB CTRL KILL "pmix.jctrl.kill" (bool) Forcibly terminate the specified processes and cleanup. 28 29 PMIX_JOB_CTRL_SIGNAL "pmix.jctrl.sig" (int) Send given signal to specified processes. 30 31 PMIX_JOB_CTRL_TERMINATE "pmix.jctrl.term" (bool) 32 Politely terminate the specified processes.

Optional Attributes 1 The following attributes are optional for host environments that support this operation: 2 PMIX JOB CTRL CANCEL "pmix.jctrl.cancel" (char*) 3 Cancel the specified request - the provided request ID must match the PMIX_JOB_CTRL_ID 4 provided to a previous call to PMIx_Job_control. An ID of NULL implies cancel all requests from 5 this requestor. 6 PMIX_JOB_CTRL_RESTART "pmix.jctrl.restart" (char*) 7 Restart the specified processes using the given checkpoint ID. 8 PMIX_JOB_CTRL_CHECKPOINT "pmix.jctrl.ckpt" (char*) 9 Checkpoint the specified processes and assign the given ID to it. 10 PMIX JOB CTRL CHECKPOINT EVENT "pmix.jctrl.ckptev" (bool) 11 Use event notification to trigger a process checkpoint. 12 PMIX JOB CTRL CHECKPOINT SIGNAL "pmix.jctrl.ckptsiq" (int) 13 Use the given signal to trigger a process checkpoint. 14 PMIX JOB CTRL CHECKPOINT TIMEOUT "pmix.jctrl.ckptsig" (int) 15 Time in seconds to wait for a checkpoint to complete. 16 PMIX_JOB_CTRL_CHECKPOINT_METHOD "pmix.jctrl.ckmethod" (pmix_data_array_t) 17 Array of pmix info t declaring each method and value supported by this application. 18 PMIX_JOB_CTRL_PROVISION "pmix.jctrl.pvn" (char*) 19 Regular expression identifying nodes that are to be provisioned. 20 PMIX_JOB_CTRL_PROVISION_IMAGE "pmix.jctrl.pvnimg" (char*) 21 Name of the image that is to be provisioned. 22 PMIX_JOB_CTRL_PREEMPTIBLE "pmix.jctrl.preempt" (bool) 23 Indicate that the job can be pre-empted. **Description** 24 25 Execute a job control action on behalf of a client. The targets array identifies the processes to which the 26 requested job control action is to be applied. A **NULL** value can be used to indicate all processes in the caller's 27 namespace. The use of PMIX_RANK_WILDCARD can also be used to indicate that all processes in the given namespace are to be included. 28

The directives are provided as **pmix_info_t** structures in the *directives* array. The callback function provides a *status* to indicate whether or not the request was granted, and to provide some information as to the

reason for any denial in the **pmix_info_cbfunc_t** array of **pmix_info_t** structures.

16.3.23 pmix server monitor fn t

Summary

Request that a client be monitored for activity.

29

30 31

32

33

pmix info t identifying the type of monitor being requested (handle)

IN error
 Status code to use in generating event if alarm triggers (integer)
 IN directives
 Array of info structures (array of handles)
 IN ndirs
 Number of elements in the *info* array (integer)
 IN cbfunc
 Callback function pmix_info_cbfunc_t (function reference)
 IN cbdata
 Data to be passed to the callback function (memory reference)

Returns one of the following:

13

14 15

16

17

18

19 20

21

22

23

24

25

26 27

28

29 30

31

32

33

34

35

- PMIX_SUCCESS, indicating that the request is being processed by the host environment result will be
 returned in the provided *cbfunc*. Note that the host must not invoke the callback function prior to returning
 from the API.
- PMIX_OPERATION_SUCCEEDED, indicating that the request was immediately processed and returned success - the cbfunc will not be called
- PMIX_ERR_NOT_SUPPORTED, indicating that the host environment does not support the request, even though the function entry was provided in the server module the *cbfunc* will not be called
- a PMIx error constant indicating either an error in the input or that the request was immediately processed and failed the *cbfunc* will not be called

This entry point is only called for monitoring requests that are not directly supported by the PMIx server library itself.

	▼ Required Attributes
1 2 3 4	If supported by the PMIx server library, then the library must not pass any supported attributes to the host environment. Any attributes provided by the client that are not directly supported by the server library must be passed to the host environment if it provides this module entry. In addition, the following attributes are required to be included in the passed <i>info</i> array:
5 6	PMIX_USERID "pmix.euid" (uint32_t) Effective user ID of the connecting process.
7 8	PMIX_GRPID "pmix.egid" (uint32_t) Effective group ID of the connecting process.
9	Host environments are not required to support any specific monitoring attributes.
	▼ Optional Attributes
10	The following attributes may be implemented by a host environment.
11 12	<pre>PMIX_MONITOR_ID "pmix.monitor.id" (char*) Provide a string identifier for this request.</pre>
13 14	<pre>PMIX_MONITOR_CANCEL "pmix.monitor.cancel" (char*) Identifier to be canceled (NULL means cancel all monitoring for this process).</pre>
15 16 17 18	PMIX_MONITOR_APP_CONTROL "pmix.monitor.appctrl" (bool) The application desires to control the response to a monitoring event - i.e., the application is requesting that the host environment not take immediate action in response to the event (e.g., terminating the job).
19 20	PMIX_MONITOR_HEARTBEAT "pmix.monitor.mbeat" (void) Register to have the PMIx server monitor the requestor for heartbeats.
21 22	PMIX_MONITOR_HEARTBEAT_TIME "pmix.monitor.btime" (uint32_t) Time in seconds before declaring heartbeat missed.
23 24	PMIX_MONITOR_HEARTBEAT_DROPS "pmix.monitor.bdrop" (uint32_t) Number of heartbeats that can be missed before generating the event.
25 26	<pre>PMIX_MONITOR_FILE "pmix.monitor.fmon" (char*) Register to monitor file for signs of life.</pre>
27 28	<pre>PMIX_MONITOR_FILE_SIZE "pmix.monitor.fsize" (bool)</pre>
29 30	<pre>PMIX_MONITOR_FILE_ACCESS "pmix.monitor.faccess" (char*)</pre>
31 32	<pre>PMIX_MONITOR_FILE_MODIFY "pmix.monitor.fmod" (char*)</pre>
33 34	<pre>PMIX_MONITOR_FILE_CHECK_TIME "pmix.monitor.ftime" (uint32_t) Time in seconds between checking the file.</pre>

```
1
                PMIX_MONITOR_FILE_DROPS "pmix.monitor.fdrop" (uint32_t)
 2
                       Number of file checks that can be missed before generating the event.
                Description
 3
                Request that a client be monitored for activity.
 4
      16.3.24
                    pmix_server_get_cred_fn_t
 5
                Summary
 6
 7
                Request a credential from the host environment.
    PMIx v3.0
 9
                typedef pmix_status_t (*pmix_server_get_cred_fn_t)(
10
                                                      const pmix_proc_t *proc,
                                                      const pmix_info_t directives[],
11
12
                                                      size t ndirs,
13
                                                      pmix_credential_cbfunc_t cbfunc,
14
                                                      void *cbdata);
15
                     proc
16
                      pmix_proc_t structure of requesting process (handle)
17
                     directives
18
                      Array of info structures (array of handles)
19
                IN
20
                      Number of elements in the info array (integer)
                      cbfunc
21
                IN
22
                      Callback function to return the credential (pmix_credential_cbfunc_t function reference)
23
                IN
                      cbdata
24
                      Data to be passed to the callback function (memory reference)
25
                • PMIX_SUCCESS, indicating that the request is being processed by the host environment - result will be
26
                   returned in the provided cbfunc
27
                • PMIX ERR_NOT_SUPPORTED, indicating that the host environment does not support the request, even
28
                   though the function entry was provided in the server module - the cbfunc will not be called
29

    a PMIx error constant indicating either an error in the input or that the request was immediately processed

30
                   and failed - the cbfunc will not be called
```

Required Attributes 1 If the PMIx library does not itself provide the requested credential, then it is required to pass any attributes 2 provided by the client to the host environment for processing. In addition, it must include the following 3 attributes in the passed *info* array: 4 PMIX_USERID "pmix.euid" (uint32_t) 5 Effective user ID of the connecting process. 6 PMIX_GRPID "pmix.egid" (uint32_t) 7 Effective group ID of the connecting process. ______ Optional Attributes 8 The following attributes are optional for host environments that support this operation: 9 PMIX_CRED_TYPE "pmix.sec.ctype" (char*) 10 When passed in PMIx Get credential, a prioritized, comma-delimited list of desired credential 11 types for use in environments where multiple authentication mechanisms may be available. When 12 returned in a callback function, a string identifier of the credential type. 13 PMIX_TIMEOUT "pmix.timeout" (int) 14 Time in seconds before the specified operation should time out (zero indicating infinite) and return the 15 PMIX ERR TIMEOUT error. Care should be taken to avoid race conditions caused by multiple layers (client, server, and host) simultaneously timing the operation. 16 Description 17 Request a credential from the host environment. 18

16.3.24.1 Credential callback function

Summary

Callback function to return a requested security credential

19 20

Format 1 2 typedef void (*pmix_credential_cbfunc_t)(3 pmix_status_t status, 4 pmix_byte_object_t *credential, 5 pmix_info_t info[], size_t ninfo, 6 void *cbdata); 7 IN status 8 pmix_status_t value (handle) 9 IN credential 10 pmix byte object t structure containing the security credential (handle) IN 12 Array of provided by the system to pass any additional information about the credential - e.g., the identity of the issuing agent. (handle) 13 14 IN ninfo 15 Number of elements in *info* (size_t) IN 16 Object passed in original request (memory reference) 17 **Description** 18 19 Define a callback function to return a requested security credential. Information provided by the issuing agent 20 can subsequently be used by the application for a variety of purposes. Examples include: 21 • checking identified authorizations to determine what requests/operations are feasible as a means to steering 22 workflows 23 • compare the credential type to that of the local SMS for compatibility 24 The credential is opaque and therefore understandable only by a service compatible with the issuer. The info array is owned by the PMIx library and is not to be released or altered by the receiving party. 25

16.3.25 pmix server validate cred fn t

Summary

26

27

28

Request validation of a credential.

1 2 Host environments are not required to support any specific attributes. **A**-----**-**Optional Attributes 3 The following attributes are optional for host environments that support this operation: 4 PMIX_TIMEOUT "pmix.timeout" (int) 5 Time in seconds before the specified operation should time out (zero indicating infinite) and return the 6 PMIX ERR TIMEOUT error. Care should be taken to avoid race conditions caused by multiple layers 7 (client, server, and host) simultaneously timing the operation. Description 8 9 Request validation of a credential obtained from the host environment via a prior call to the pmix_server_get_cred_fn_t module entry. 10 Credential validation callback function 16.3.26 11 Summarv 12 13 Callback function for security credential validation. 14 Format PMIx v3.0 15 typedef void (*pmix_validation_cbfunc_t)(16 pmix_status_t status, 17 pmix info t info[], size t ninfo, 18 void *cbdata); IN 19 status 20 pmix_status_t value (handle) IN 21 22 Array of pmix info t provided by the system to pass any additional information about the authentication - e.g., the effective userid and group id of the certificate holder, and any related 23 authorizations (handle) 24 IN ninfo 25 Number of elements in *info* (size_t) 26 27 IN 28 Object passed in original request (memory reference) 29 The returned status shall be one of the following: 30 • PMIX_SUCCESS, indicating that the request was processed and returned success (i.e., the credential was 31 both valid and any information it contained was successfully processed). Details of the result will be 32 returned in the info array 33 • a PMIx error constant indicating either an error in the parsing of the credential or that the request was 34 refused

Description

1 2

3

4 5

6

7

8

9 10

19

20

21 22

23 24

25

26

27

28 29

30

31 32

33

34

35

36

Define a validation callback function to indicate if a provided credential is valid, and any corresponding information regarding authorizations and other security matters.

Advice to users —

The precise contents of the array will depend on the host environment and its associated security system. At the minimum, it is expected (but not required) that the array will contain entries for the PMIX_USERID and **PMIX** GRPID of the client described in the credential. The *info* array is owned by the PMIx library and is not to be released or altered by the receiving party.

16.3.27 pmix server iof fn t

Summarv

Format

Request the specified IO channels be forwarded from the given array of processes.

```
11 PMIx v3.0
12
             typedef pmix_status_t (*pmix_server_iof_fn_t)(
13
                                       const pmix_proc_t procs[],
14
                                       size_t nprocs,
15
                                       const pmix_info_t directives[],
16
                                       size t ndirs,
                                       pmix iof channel t channels,
17
18
                                       pmix_op_cbfunc_t cbfunc, void *cbdata);
```

IN procs

Array pmix_proc_t identifiers whose IO is being requested (handle)

IN

Number of elements in *procs* (size t)

directives

Array of pmix_info_t structures further defining the request (array of handles)

IN ndirs

Number of elements in the *info* array (integer)

channels IN

Bitmask identifying the channels to be forwarded (pmix iof channel t)

IN cbfunc

Callback function pmix_op_cbfunc_t (function reference)

IN cbdata

Data to be passed to the callback function (memory reference)

Returns one of the following:

• PMIX_SUCCESS, indicating that the request is being processed by the host environment - result will be returned in the provided cbfunc. Note that the library must not invoke the callback function prior to returning from the API.

1 2	 PMIX_OPERATION_SUCCEEDED, indicating that the request was immediately processed and returned success - the cbfunc will not be called
3 4	• PMIX_ERR_NOT_SUPPORTED, indicating that the host environment does not support the request, even though the function entry was provided in the server module - the <i>cbfunc</i> will not be called
5 6	• a PMIx error constant indicating either an error in the input or that the request was immediately processed and failed - the <i>cbfunc</i> will not be called
	▼
7	The following attributes are required to be included in the passed <i>info</i> array:
8 9	PMIX_USERID "pmix.euid" (uint32_t) Effective user ID of the connecting process.
10 11	PMIX_GRPID "pmix.egid" (uint32_t) Effective group ID of the connecting process.
12	
13	Host environments that provide this module entry point are required to support the following attributes:
14 15 16	PMIX_IOF_CACHE_SIZE "pmix.iof.csize" (uint32_t) The requested size of the PMIx server cache in bytes for each specified channel. By default, the server is allowed (but not required) to drop all bytes received beyond the max size.
17 18	PMIX_IOF_DROP_OLDEST "pmix.iof.old" (bool) In an overflow situation, the PMIx server is to drop the oldest bytes to make room in the cache.
19 20 21	PMIX_IOF_DROP_NEWEST "pmix.iof.new" (bool) In an overflow situation, the PMIx server is to drop any new bytes received until room becomes available in the cache (default).
	▼ Optional Attributes
22	The following attributes may be supported by a host environment.
23 24 25 26 27 28	PMIX_IOF_BUFFERING_SIZE "pmix.iof.bsize" (uint32_t) Requests that IO on the specified channel(s) be aggregated in the PMIx tool library until the specified number of bytes is collected to avoid being called every time a block of IO arrives. The PMIx tool library will execute the callback and reset the collection counter whenever the specified number of bytes becomes available. Any remaining buffered data will be <i>flushed</i> to the callback upon a call to deregister the respective channel.
29 30 31	PMIX_IOF_BUFFERING_TIME "pmix.iof.btime" (uint32_t) Max time in seconds to buffer IO before delivering it. Used in conjunction with buffering size, this prevents IO from being held indefinitely while waiting for another payload to arrive.

Description 1 2 Request the specified IO channels be forwarded from the given array of processes. An error shall be returned 3 in the callback function if the requested service from any of the requested processes cannot be provided. Advice to PMIx library implementers The forwarding of stdin is a *push* process - processes cannot request that it be *pulled* from some other source. 4 5 Requests including the PMIX_FWD_STDIN_CHANNEL channel will return a PMIX ERR NOT SUPPORTED error. 6 16.3.27.1 **IOF** delivery function 7 Summary 8 9 Callback function for delivering forwarded IO to a process. 10 _{PMIx v3.0} Format 11 typedef void (*pmix_iof_cbfunc_t)(12 size_t iofhdlr, pmix_iof_channel_t channel, 13 pmix proc t *source, pmix byte object t *payload, pmix_info_t info[], size_t ninfo); 14 15 IN iofhdlr 16 Registration number of the handler being invoked (size_t) 17 IN channel bitmask identifying the channel the data arrived on (pmix iof channel t) 18 19 IN source 20 Pointer to a pmix proc t identifying the namespace/rank of the process that generated the data 21 (char*) 22 payload IN Pointer to a pmix_byte_object_t that describes the character array containing the data. 23 24 IN 25 Array of pmix info t provided by the source containing metadata about the payload. This could include PMIX_IOF_COMPLETE (handle) 26 27 IN ninfo 28 Number of elements in *info* (size_t) 29 **Description** 30 Define a callback function for delivering forwarded IO to a process. This function will be called whenever data 31 becomes available, or a specified buffering size and/or time has been met. Advice to users — 32 Multiple strings may be included in a given payload, and the payload may not be NULL terminated. The user

is responsible for releasing the payload memory. The info array is owned by the PMIx library and is not to be

released or altered by the receiving party.

33

16.3.28 pmix server stdin fn t

Summary

Pass standard input data to the host environment for transmission to specified recipients.

PMIx v3.0

1 2

3

5

6

7

8

9

10

11

12

15

16

17

18

19 20

21

22

23

24 25

26

27

28 29

30

31

32

33

34

35

36 37

38

```
Format
```

```
typedef pmix_status_t (*pmix_server_stdin_fn_t)(
                           const pmix_proc_t *source,
                           const pmix_proc_t targets[],
                           size_t ntargets,
                           const pmix_info_t directives[],
                           size_t ndirs,
                           const pmix_byte_object_t *bo,
                           pmix_op_cbfunc_t cbfunc, void *cbdata);
```

```
IN
13
                      source
14
                      pmix_proc_t structure of source process (handle)
```

targets

Array of **pmix proc t** target identifiers (handle)

ntargets IN

Number of elements in the *targets* array (integer)

directives

Array of info structures (array of handles)

IN ndirs

Number of elements in the *info* array (integer)

IN

Pointer to pmix_byte_object_t containing the payload (handle)

IN cbfunc

Callback function **pmix** op **cbfunc t** (function reference)

IN cbdata

Data to be passed to the callback function (memory reference)

Returns one of the following:

- PMIX_SUCCESS, indicating that the request is being processed by the host environment result will be returned in the provided cbfunc. Note that the library must not invoke the callback function prior to returning from the API.
- PMIX OPERATION SUCCEEDED, indicating that the request was immediately processed and returned success - the cbfunc will not be called
- PMIX ERR NOT SUPPORTED, indicating that the host environment does not support the request, even though the function entry was provided in the server module - the cbfunc will not be called
- a PMIx error constant indicating either an error in the input or that the request was immediately processed and failed - the cbfunc will not be called

```
Required Attributes
 1
                The following attributes are required to be included in the passed info array:
 2
                PMIX_USERID "pmix.euid" (uint32_t)
 3
                      Effective user ID of the connecting process.
 4
                PMIX GRPID "pmix.eqid" (uint32_t)
 5
                      Effective group ID of the connecting process.
                Description
 6
 7
                Passes stdin to the host environment for transmission to specified recipients. The host environment is
 8
                responsible for forwarding the data to all locations that host the specified targets and delivering the payload to
 9
                the PMIx server library connected to those clients.
     16.3.29
                   pmix server grp fn t
10
                Summary
11
12
                Request group operations (construct, destruct, etc.) on behalf of a set of processes.
13 <sub>PMIx v4.0</sub>
14
                typedef pmix_status_t (*pmix_server_grp_fn_t)(
15
                                                pmix_group_operation_t op,
16
                                                 char grp[],
17
                                                 const pmix_proc_t procs[],
18
                                                 size_t nprocs,
19
                                                 const pmix_info_t directives[],
20
                                                 size_t ndirs,
21
                                                pmix_info_cbfunc_t cbfunc,
22
                                                 void *cbdata);
                                                     23
                IN
24
                    pmix group operation t value indicating operation the host is requested to perform (integer)
25
                IN
26
                    Character string identifying the group (string)
27
                IN
                    procs
                    Array of pmix proc t identifiers of participants (handle)
28
29
                IN
30
                    Number of elements in the procs array (integer)
31
                    directives
32
                    Array of info structures (array of handles)
33
                IN
                    ndirs
34
                    Number of elements in the info array (integer)
35
                IN
                    cbfunc
36
                    Callback function pmix info cbfunc t (function reference)
```

IN cbdata

Data to be passed to the callback function (memory reference)

Returns one of the following:

- PMIX_SUCCESS, indicating that the request is being processed by the host environment result will be returned in the provided *cbfunc*. Note that the library must not invoke the callback function prior to returning from the API.
- PMIX_OPERATION_SUCCEEDED, indicating that the request was immediately processed and returned success - the cbfunc will not be called
- PMIX_ERR_NOT_SUPPORTED, indicating that the host environment does not support the request, even though the function entry was provided in the server module the *cbfunc* will not be called
- a PMIx error constant indicating either an error in the input or that the request was immediately processed and failed the *cbfunc* will not be called

Required Attributes

The following attributes are required to be supported by a host environment.

PMIX_LOCAL_COLLECTIVE_STATUS "pmix.loc.col.st" (pmix_status_t)

Status code for local collective operation being reported to the host by the server library. PMIx servers may aggregate the participation by local client processes in a collective operation - e.g., instead of passing individual client calls to <code>PMIx_Fence</code> up to the host environment, the server may pass only a single call to the host when all local participants have executed their <code>PMIx_Fence</code> call, thereby reducing the burden placed on the host. However, in cases where the operation locally fails (e.g., if a participating client abnormally terminates prior to calling the operation), the server upcall functions to the host do not include a <code>pmix_status_t</code> by which the PMIx server can alert the host to that failure. This attribute resolves that problem by allowing the server to pass the status information regarding the local collective operation.

Optional Attributes -----

▲------

The following attributes may be supported by a host environment.

```
PMIX_GROUP_ASSIGN_CONTEXT_ID "pmix.grp.actxid" (bool)
```

Requests that the RM assign a new context identifier to the newly created group. The identifier is an unsigned, <code>size_t</code> value that the RM guarantees to be unique across the range specified in the request. Thus, the value serves as a means of identifying the group within that range. If no range is specified, then the request defaults to <code>PMIX_RANGE_SESSION</code>.

```
PMIX_GROUP_LOCAL_ONLY "pmix.grp.lcl" (bool)
```

Group operation only involves local processes. PMIx implementations are *required* to automatically scan an array of group members for local vs remote processes - if only local processes are detected, the implementation need not execute a global collective for the operation unless a context ID has been requested from the host environment. This can result in significant time savings. This attribute can be used to optimize the operation by indicating whether or not only local processes are represented, thus allowing the implementation to bypass the scan.

PMIX_GROUP_ENDPT_DATA "pmix.grp.endpt" (pmix_byte_object_t)

1 Data collected during group construction to ensure communication between group members is 2 supported upon completion of the operation. 3 PMIX_GROUP_OPTIONAL "pmix.grp.opt" (bool) 4 Participation is optional - do not return an error if any of the specified processes terminate without 5 having joined. The default is false. 6 PMIX_RANGE "pmix.range" (pmix_data_range_t) 7 Define constraints on the processes that can access the provided data. Only processes that meet the constraints are allowed to access it. 8 9 The following attributes may be included in the host's response: 10 PMIX_GROUP_ID "pmix.grp.id" (char*) 11 User-provided group identifier - as the group identifier may be used in PMIx operations, the user is required to ensure that the provided ID is unique within the scope of the host environment (e.g., by 12 including some user-specific or application-specific prefix or suffix to the string). 13 14 PMIX_GROUP_MEMBERSHIP "pmix.grp.mbrs" (pmix_data_array_t*) 15 Array pmix_proc_t identifiers identifying the members of the specified group. 16 PMIX GROUP CONTEXT ID "pmix.grp.ctxid" (size_t) 17 Context identifier assigned to the group by the host RM. 18 PMIX_GROUP_ENDPT_DATA "pmix.grp.endpt" (pmix_byte_object_t) 19 Data collected during group construction to ensure communication between group members is supported upon completion of the operation. 20 **Description** 21 22 Perform the specified operation across the identified processes, plus any special actions included in the 23 directives. Return the result of any special action requests in the callback function when the operation is 24 completed. Actions may include a request (PMIX_GROUP_ASSIGN_CONTEXT_ID) that the host assign a 25 unique numerical (size t) ID to this group - if given, the PMIX RANGE attribute will specify the range across 26 which the ID must be unique (default to PMIX RANGE SESSION). 16.3.29.1 **Group Operation Constants** 27 28 *PMIx v4.0* The pmix_group_operation_t structure is a uint8_t value for specifying group operations. All values were originally defined in version 4 of the standard unless otherwise marked. 29 30 PMIX GROUP CONSTRUCT Construct a group composed of the specified processes - used by a PMIx 31 server library to direct host operation. 32 PMIX_GROUP_DESTRUCT Destruct the specified group - used by a PMIx server library to direct host

16.3.30 pmix_server_fabric_fn_t

Summary

operation.

Request fabric-related operations (e.g., information on a fabric) on behalf of a tool or other process.

33

34 35

ID string of a fabric plane (e.g., CIDR for Ethernet). When used as a modifier in a request for information, specifies the plane whose information is to be returned. When used directly as a key in a request, returns a <code>pmix_data_array_t</code> of string identifiers for all fabric planes in the overall system.

Description

Perform the specified operation. Return the result of any requests in the callback function when the operation is completed. Operations may, for example, include a request for fabric information. See pmix_fabric_t for a list of expected information to be included in the response. Note that requests for device index are to be returned in the callback function's array of pmix_info_t using the PMIX_FABRIC_DEVICE_INDEX attribute.

CHAPTER 17

Tools and Debuggers

The term *tool* widely refers to programs executed by the user or system administrator on a command line. Tools frequently interact with either the SMS, user applications, or both to perform administrative and support functions. For example, a debugger tool might be used to remotely control the processes of a parallel application, monitoring their behavior on a step-by-step basis. Historically, such tools were custom-written for each specific host environment due to the customized and/or proprietary nature of the environment's interfaces.

The advent of PMIx offers the possibility for creating portable tools capable of interacting with multiple RMs without modification. Possible use-cases include:

- querying the status of scheduling queues and estimated allocation time for various resource options
- job submission and allocation requests
- querying job status for executing applications
- launching, monitoring, and debugging applications

Enabling these capabilities requires some extensions to the PMIx Standard (both in terms of APIs and attributes), and utilization of client-side APIs for more tool-oriented purposes.

This chapter defines specific APIs related to tools, provides tool developers with an overview of the support provided by PMIx, and serves to guide RM vendors regarding roles and responsibilities of RMs to support tools. As the number of tool-specific APIs and attributes is fairly small, the bulk of the chapter serves to provide a "theory of operation" for tools and debuggers. Description of the APIs themselves is therefore deferred to the Section 17.5 later in the chapter.

17.1 Connection Mechanisms

The key to supporting tools lies in providing mechanisms by which a tool can connect to a PMIx server. Application processes are able to connect because their local RM daemon provides them with the necessary contact information upon execution. A command-line tool, however, isn't spawned by an RM daemon, and therefore lacks the information required for rendezvous with a PMIx server.

Once a tool has started, it initializes PMIx as a tool (via PMIx_tool_init) if its access is restricted to PMIx-based informational services such as PMIx_Query_info. However, if the tool intends to start jobs, then it must include the PMIX_LAUNCHER attribute to inform the library of that intent so that the library can initialize and provide access to the corresponding support.

Support for tools requires that the PMIx server be initialized with an appropriate attribute indicating that tool connections are to be allowed. Separate attributes are provided to "fine-tune" this permission by allowing the environment to independently enable (or disable) connections from tools executing on nodes other than the one hosting the server itself. The PMIx server library shall provide an opportunity for the host environment to

authenticate and approve each connection request from a specific tool by calling the pmix_server_tool_connection_fn_t "hook" provided in the server module for that purpose.
Servers in environments that do not provide this "hook" shall automatically reject all tool connection requests.

Tools can connect to any local or remote PMIx server provided they are either explicitly given the required connection information, or are able to discover it via one of several defined rendezvous protocols. Connection discovery centers around the existence of *rendezvous files* containing the necessary connection information, as illustrated in Fig. 17.1.




Figure 17.1.: Tool rendezvous files

The contents of each rendezvous file are specific to a given PMIx implementation, but should at least contain the namespace and rank of the server along with its connection URI. Note that tools linked to one PMIx implementation are therefore unlikely to successfully connect to PMIx server libraries from another implementation.

The top of the directory tree is defined by either the PMIX_SYSTEM_TMPDIR attribute (if given) or the TMPDIR environmental variable. PMIx servers that are designated as system servers by including the PMIX_SERVER_SYSTEM_SUPPORT attribute when calling PMIx_server_init will create a rendezvous file in this top-level directory. The filename will be of the form pmix.sys.hostname, where hostname is the string returned by the gethostname system call. Note that only one PMIx server on a node can be designated as the system server.

Non-system PMIx servers will create a set of three rendezvous files in the directory defined by either the **PMIX_SERVER_TMPDIR** attribute or the **TMPDIR** environmental variable:

- pmix.host.tool.nspace where host is the string returned by the gethostname system call and nspace is the namespace of the server.
- pmix.host.tool.pid where host is the string returned by the gethostname system call and pid is the PID of
 the server.
- pmix.host.tool where host is the string returned by the gethostname system call. Note that servers which
 are not given a namespace-specific PMIX_SERVER_TMPDIR attribute may not generate this file due to
 conflicts should multiple servers be present on the node.

 The files are identical and may be implemented as symlinks to a single instance. The individual file names are composed so as to aid the search process should a tool wish to connect to a server identified by its namespace or PID.

Servers will additionally provide a rendezvous file in any given location if the path (either absolute or relative) and filename is specified either during PMIx_server_init using the

PMIX_LAUNCHER_RENDEZVOUS_FILE attribute, or by the PMIX_LAUNCHER_RNDZ_FILE environmental variable prior to executing the process containing the server. This latter mechanism may be the preferred mechanism for tools such as debuggers that need to fork/exec a launcher (e.g., "mpiexec") and then rendezvous with it. This is described in more detail in Section 17.2.2.

Rendezvous file ownerships are set to the UID and GID of the server that created them, with permissions set according to the desires of the implementation and/or system administrator policy. All connection attempts are first governed by read access privileges to the target rendezvous file - thus, the combination of permissions, UID, and GID of the rendezvous files act as a first-level of security for tool access.

A tool may connect to as many servers at one time as the implementation supports, but is limited to designating only one such connection as its *primary* server. This is done to avoid confusion when the tool calls an API as to which server should service the request. The first server the tool connects to is automatically designated as the *primary* server.

Tools are allowed to change their primary server at any time via the PMIx_tool_set_server API, and to connect/disconnect from a server as many times as desired. Note that standing requests (e.g., event registrations) with the current primary server may be lost and/or may not be transferred when transitioning to another primary server - PMIx implementors are not required to maintain or transfer state across tool-server connections.

Tool process identifiers are assigned by one of the following methods:

- If PMIX TOOL NSPACE is given, then the namespace of the tool will be assigned that value.
 - If PMIX TOOL RANK is also given, then the rank of the tool will be assigned that value.
 - If **PMIX_TOOL_RANK** is not given, then the rank will be set to a default value of zero.
- If a process ID is not provided and the tool connects to a server, then one will be assigned by the host environment upon connection to that server.
- If a process ID is not provided and the tool does not connect to a server (e.g., if
 PMIX_TOOL_DO_NOT_CONNECT is given), then the tool shall self-assign a unique identifier. This is
 often done using some combination involving hostname and PID.

Tool process identifiers remain constant across servers. Thus, it is critical that a system-wide unique namespace be provided if the tool itself sets the identifier, and that host environments provide a system-wide unique identifier in the case where the identifier is set by the server upon connection. The host environment is required to reject any connection request that fails to meet this criterion.

For simplicity, the following descriptions will refer to the:

- PMIX_SYSTEM_TMPDIR as the directory specified by either the PMIX_SYSTEM_TMPDIR attribute (if given) or the TMPDIR environmental variable.
- PMIX_SERVER_TMPDIR as the directory specified by either the PMIX_SERVER_TMPDIR attribute or the TMPDIR environmental variable.

17.1.1 Rendezvousing with a local server

Connection to a local PMIx server is pursued according to the following precedence chain based on attributes contained in the call to the PMIx_tool_init or PMIx_tool_attach_to_server APIs. Servers to which the tool already holds a connection will be ignored. Except where noted, the PMIx library will return an error if the specified file cannot be found, the caller lacks permissions to read it, or the server specified within the file does not respond to or accept the connection — the library will not proceed to check for other connection options as the user specified a particular one to use.

Note that the PMIx implementation may choose to introduce a "delayed connection" protocol between steps in the precedence chain - i.e., the library may cycle several times, checking for creation of the rendezvous file each time after a delay of some period of time, thereby allowing the tool to wait for the server to create the rendezvous file before either returning an error or continuing to the next step in the chain.

- If PMIX_TOOL_ATTACHMENT_FILE is given, then the tool will attempt to read the specified file and
 connect to the server based on the information contained within it. The format of the attachment file is
 identical to the rendezvous files described in earlier in this section. An error will be returned if the specified
 file cannot be found.
- If PMIX_SERVER_URI or PMIX_TCP_URI is given, then connection will be attempted to the server at
 the specified URI. Note that it is an error for both of these attributes to be specified. PMIX_SERVER_URI
 is the preferred method as it is more generalized PMIX_TCP_URI is provided for those cases where the
 user specifically wants to use a TCP transport for the connection and wants to error out if one isn't available
 or cannot be used.
- If PMIX_SERVER_PIDINFO was provided, then the tool will search for a rendezvous file created by a
 PMIx server of the given PID in the PMIX_SERVER_TMPDIR directory. An error will be returned if a
 matching rendezvous file cannot be found.
- If PMIX_SERVER_NSPACE is given, then the tool will search for a rendezvous file created by a PMIx server of the given namespace in the PMIX_SERVER_TMPDIR directory. An error will be returned if a matching rendezvous file cannot be found.
- If PMIX_CONNECT_TO_SYSTEM is given, then the tool will search for a system-level rendezvous file
 created by a PMIx server in the PMIX_SYSTEM_TMPDIR directory. An error will be returned if a
 matching rendezvous file cannot be found.
- If PMIX_CONNECT_SYSTEM_FIRST is given, then the tool will look for a system-level rendezvous file
 created by a PMIx server in the PMIX_SYSTEM_TMPDIR directory. If found, then the tool will attempt to
 connect to it. In this case, no error will be returned if the rendezvous file is not found or connection is
 refused the PMIx library will silently continue to the next option.
- By default, the tool will search the directory tree under the PMIX_SERVER_TMPDIR directory for
 rendezvous files of PMIx servers, attempting to connect to each it finds until one accepts the connection. If
 no rendezvous files are found, or all contacted servers refuse connection, then the PMIx library will return
 an error. No "delayed connection" protocols may be utilized at this point.

Note that there can be multiple local servers - one from the system plus others from launchers and active jobs. The PMIx tool connection search method is not guaranteed to pick a particular server unless directed to do so. Tools can obtain a list of servers available on their local node using the PMIx_Query_info APIs with the PMIX_QUERY_AVAIL_SERVERS key.

17.1.2 Connecting to a remote server

Connecting to remote servers is complicated due to the lack of access to the previously-described rendezvous files. Two methods are required to be supported, both based on the caller having explicit knowledge of either connection information or a path to a local file that contains such information:

- If PMIX_TOOL_ATTACHMENT_FILE is given, then the tool will attempt to read the specified file and
 connect to the server based on the information contained within it. The format of the attachment file is
 identical to the rendezvous files described in earlier in this section.
- If PMIX_SERVER_URI or PMIX_TCP_URI is given, then connection will be attempted to the server at
 the specified URI. Note that it is an error for both of these attributes to be specified. PMIX_SERVER_URI
 is the preferred method as it is more generalized PMIX_TCP_URI is provided for those cases where the
 user specifically wants to use the TCP transport for the connection and wants to error out if it isn't available
 or cannot be used.

Additional methods may be provided by particular PMIx implementations. For example, the tool may use *ssh* to launch a *probe* process onto the remote node so that the probe can search the **PMIX_SYSTEM_TMPDIR** and **PMIX_SERVER_TMPDIR** directories for rendezvous files, relaying the discovered information back to the requesting tool. If sufficient information is found to allow for remote connection, then the tool can use it to establish the connection. Note that this method is not required to be supported - it is provided here as an example and left to the discretion of PMIx implementors.

17.1.3 Attaching to running jobs

When attaching to a running job, the tool must connect to a PMIx server that is associated with that job - e.g., a server residing in the host environment's local daemon that spawned one or more of the job's processes, or the server residing in the launcher that is overseeing the job. Identifying an appropriate server can sometimes prove challenging, particularly in an environment where multiple job launchers may be in operation, possibly under control of the same user.

In cases where the user has only the one job of interest in operation on the local node (e.g., when engaged in an interactive session on the node from which the launcher was executed), the normal rendezvous file discovery method can often be used to successfully connect to the target job, even in the presence of jobs executed by other users. The permissions and security authorizations can, in many cases, reliably ensure that only the one connection can be made. However, this is not guaranteed in all cases.

The most common method, therefore, for attaching to a running job is to specify either the PID of the job's launcher or the namespace of the launcher's job (note that the launcher's namespace frequently differs from the namespace of the job it has launched). Unless the application processes themselves act as PMIx servers, connection must be to the servers in the daemons that oversee the application. This is typically either daemons specifically started by the job's launcher process, or daemons belonging to the host environment, that are responsible for starting the application's processes and oversee their execution.

Identifying the correct PID or namespace can be accomplished in a variety of ways, including:

- Using typical OS or host environment tools to obtain a listing of active jobs and perusing those to find the
 target launcher.
 - Using a PMIx-based tool attached to a system-level server to query the active jobs and their command lines, thereby identifying the application of interest and its associated launcher.
 - Manually recording the PID of the launcher upon starting the job.

Once the namespace and/or PID of the target server has been identified, either of the previous methods can be used to connect to it.

17.1.4 Tool initialization attributes

The following attributes are passed to the **PMIx tool init** API for use when initializing the PMIx library.

```
PMIX_TOOL_NSPACE "pmix.tool.nspace" (char*)
```

Name of the namespace to use for this tool.

PMIX_TOOL_RANK "pmix.tool.rank" (uint32_t)

Rank of this tool.

PMIX_LAUNCHER "pmix.tool.launcher" (bool)

Tool is a launcher and needs to create rendezvous files.

17.1.5 Tool initialization environmental variables

The following environmental variables are used during **PMIx_tool_init** and **PMIx_server_init** to control various rendezvous-related operations when the process is started manually (e.g., on a command line) or by a fork/exec-like operation.

PMIX LAUNCHER RNDZ URI

The spawned tool is to be connected back to the spawning tool using the given URI so that the spawning tool can provide directives (e.g., a PMIx_Spawn command) to it.

PMIX LAUNCHER RNDZ FILE

If the specified file does not exist, this variable contains the absolute path of the file where the spawned tool is to store its connection information so that the spawning tool can connect to it. If the file does exist, it contains the information specifying the server to which the spawned tool is to connect.

PMIX KEEPALIVE PIPE

An integer **read**-end of a POSIX pipe that the tool should monitor for closure, thereby indicating that the parent tool has terminated. Used. for example, when a tool fork/exec's an intermediate launcher that should self-terminate if the originating tool exits.

Note that these environmental variables should be cleared from the environment after use and prior to forking child processes to avoid potentially unexpected behavior by the child processes.

17.1.6 Tool connection attributes

These attributes are defined to assist PMIx-enabled tools to connect with a PMIx server by passing them into either the PMIx_tool_init or the PMIx_tool_attach_to_server APIs - thus, they are not typically accessed via the PMIx_Get API.

```
PMIX_SERVER_PIDINFO "pmix.srvr.pidinfo" (pid_t)
```

3

4 5

6

7

8 9

10

11

12

13 14

15

16 17

18

19

20

21

22

23

24

25 26

27

28

29

30

31

32

33 34

35

36

1	PID of the target PMIx server for a tool.	
2	PMIX_CONNECT_TO_SYSTEM "pmix.cnct.sys" (bool)	
3	The requester requires that a connection be made only to a local, system-level PMIx server.	
4	PMIX_CONNECT_SYSTEM_FIRST "pmix.cnct.sys.first" (bool)	
5	Preferentially, look for a system-level PMIx server first.	
6	PMIX_SERVER_URI "pmix.srvr.uri" (char*)	
7	URI of the PMIx server to be contacted.	
8	<pre>PMIX_SERVER_HOSTNAME "pmix.srvr.host" (char*)</pre>	
9	Host where target PMIx server is located.	
10	PMIX_CONNECT_MAX_RETRIES "pmix.tool.mretries" (uint32_t)	
11	Maximum number of times to try to connect to PMIx server - the default value is implementation	
12	specific.	
13	PMIX_CONNECT_RETRY_DELAY "pmix.tool.retry" (uint32_t)	
14	Time in seconds between connection attempts to a PMIx server - the default value is implementation	
15	specific.	
16	PMIX_TOOL_DO_NOT_CONNECT "pmix.tool.nocon" (bool)	
17	The tool wants to use internal PMIx support, but does not want to connect to a PMIx server.	
18	<pre>PMIX_TOOL_CONNECT_OPTIONAL "pmix.tool.conopt" (bool)</pre>	
19	The tool shall connect to a server if available, but otherwise continue to operate unconnected.	
20	<pre>PMIX_TOOL_ATTACHMENT_FILE "pmix.tool.attach" (char*)</pre>	
21	Pathname of file containing connection information to be used for attaching to a specific server.	
22	<pre>PMIX_LAUNCHER_RENDEZVOUS_FILE "pmix.tool.lncrnd" (char*)</pre>	
23	Pathname of file where the launcher is to store its connection information so that the spawning tool car	
24	connect to it.	
25	PMIX_PRIMARY_SERVER "pmix.pri.srvr" (bool)	
26	The server to which the tool is connecting shall be designated the <i>primary</i> server once connection has	
27	been accomplished.	
28	PMIX_WAIT_FOR_CONNECTION "pmix.wait.conn" (bool)	
29	Wait until the specified process has connected to the requesting tool or server, or the operation times	
30	out (if the PMIX_TIMEOUT directive is included in the request).	

17.2 Launching Applications with Tools

Tool-directed launches require that the tool include the **PMIX_LAUNCHER** attribute when calling **PMIx tool init**. Two launch modes are supported:

- *Direct launch* where the tool itself is directly responsible for launching all processes, including debugger daemons, using either the RM or daemons launched by the tool i.e., there is no *intermediate launcher* (IL) such as *mpiexec*. The case where the tool is self-contained (i.e., uses its own daemons without interacting with an external entity such as the RM) lies outside the scope of this Standard; and
- *Indirect launch* where all processes are started via an IL such as *mpiexec* and the tool itself is not directly involved in launching application processes or debugger daemons. Note that the IL may utilize the RM to launch processes and/or daemons under the tool's direction.

Either of these methods can be executed interactively or by a batch script. Note that not all host environments may support the direct launch method.

17.2.1 Direct launch

In the direct-launch use-case (Fig. 17.2), the tool itself performs the role of the launcher. Once invoked, the tool connects to an appropriate PMIx server - e.g., a system-level server hosted by the RM. The tool is responsible for assembling the description of the application to be launched (e.g., by parsing its command line) into a spawn request containing an array of <code>pmix_app_t</code> applications and <code>pmix_info_t</code> job-level information. An allocation of resources may or may not have been made in advance – if not, then the spawn request must include allocation request information.




Figure 17.2.: Direct Launch

In addition to the attributes described in **PMIx_Spawn**, the tool may optionally wish to include the following tool-specific attributes in the *job_info* argument to that API (the debugger-related attributes are discussed in more detail in Section 17.4):

• PMIX_FWD_STDIN "pmix.fwd.stdin" (pmix_rank_t)

The requester intends to push information from its **stdin** to the indicated process. The local spawn agent should, therefore, ensure that the **stdin** channel to that process remains available. A rank of **PMIX_RANK_WILDCARD** indicates that all processes in the spawned job are potential recipients. The requester will issue a call to **PMIX_IOF_push** to initiate the actual forwarding of information to specified targets - this attribute simply requests that the IL retain the ability to forward the information to the designated targets.

• PMIX_FWD_STDOUT "pmix.fwd.stdout" (bool)

Requests that the ability to forward the **stdout** of the spawned processes be maintained. The requester will issue a call to **PMIx_IOF_pull** to specify the callback function and other options for delivery of the forwarded output.

• PMIX_FWD_STDERR "pmix.fwd.stderr" (bool)

 Requests that the ability to forward the **stderr** of the spawned processes be maintained. The requester will issue a call to **PMIx_IOF_pull** to specify the callback function and other options for delivery of the forwarded output.

• PMIX_FWD_STDDIAG "pmix.fwd.stddiag" (bool)

Requests that the ability to forward the diagnostic channel (if it exists) of the spawned processes be maintained. The requester will issue a call to **PMIx_IOF_pull** to specify the callback function and other options for delivery of the forwarded output.

- PMIX_IOF_CACHE_SIZE "pmix.iof.csize" (uint32_t)
 - The requested size of the PMIx server cache in bytes for each specified channel. By default, the server is allowed (but not required) to drop all bytes received beyond the max size.
- PMIX_IOF_DROP_OLDEST "pmix.iof.old" (bool)

In an overflow situation, the PMIx server is to drop the oldest bytes to make room in the cache.

• PMIX_IOF_DROP_NEWEST "pmix.iof.new" (bool)

In an overflow situation, the PMIx server is to drop any new bytes received until room becomes available in the cache (default).

• PMIX IOF BUFFERING SIZE "pmix.iof.bsize" (uint32_t)

Requests that IO on the specified channel(s) be aggregated in the PMIx tool library until the specified number of bytes is collected to avoid being called every time a block of IO arrives. The PMIx tool library will execute the callback and reset the collection counter whenever the specified number of bytes becomes available. Any remaining buffered data will be *flushed* to the callback upon a call to deregister the respective channel.

- PMIX_IOF_BUFFERING_TIME "pmix.iof.btime" (uint32_t)
 - Max time in seconds to buffer IO before delivering it. Used in conjunction with buffering size, this prevents IO from being held indefinitely while waiting for another payload to arrive.
- PMIX_IOF_OUTPUT_RAW "pmix.iof.raw" (bool)
 - Do not buffer output to be written as complete lines output characters as the stream delivers them
- PMIX_IOF_TAG_OUTPUT "pmix.iof.tag" (bool)
 - Requests that output be prefixed with the nspace, rank of the source and a string identifying the channel (**stdout**, **stderr**, etc.).
- PMIX IOF TIMESTAMP OUTPUT "pmix.iof.ts" (bool)
 - Requests that output be marked with the time at which the data was received by the tool note that this will differ from the time at which the data was collected from the source.
- PMIX_IOF_XML_OUTPUT "pmix.iof.xml" (bool)
 - Requests that output be formatted in XML.
- PMIX IOF RANK OUTPUT "pmix.iof.rank" (bool)
 - Tag output with the rank it came from
- PMIX_IOF_OUTPUT_TO_FILE "pmix.iof.file" (char*)

Direct application output into files of form "<filename>.<nspace>.<rank>.stdout" (for **stdout**) and "<filename>.<nspace>.<rank>.stderr" (for **stderr**). If **PMIX_IOF_MERGE_STDERR_STDOUT** was given, then only the **stdout** file will be created and both streams will be written into it.

• PMIX IOF OUTPUT TO DIRECTORY "pmix.iof.dir" (char*)

Direct application output into files of form "<directory>/<nspace>/rank.<rank>/stdout" (for stdout) and "<directory>/<nspace>/rank.<rank>/stderr" (for stderr). If PMIX_IOF_MERGE_STDERR_STDOUT was given, then only the stdout file will be created and both streams will be written into it.

• PMIX_IOF_FILE_PATTERN "pmix.iof.fpt" (bool)

Specified output file is to be treated as a pattern and not automatically annotated by nspace, rank, or other parameters. The pattern can use **%n** for the namespace, and **%r** for the rank wherever those quantities are to be placed. The resulting filename will be appended with ".stdout" for the **stdout** stream and ".stderr" for the **stderr** stream. If **PMIX_IOF_MERGE_STDERR_STDOUT** was given, then only the **stdout** file will be created and both streams will be written into it.

- PMIX_IOF_FILE_ONLY "pmix.iof.fonly" (bool)
 - Output only into designated files do not also output a copy to the console's stdout/stderr
- PMIX_IOF_MERGE_STDERR_STDOUT "pmix.iof.mrg" (bool)

Merge stdout and stderr streams from application procs

• PMIX NOHUP "pmix.nohup" (bool)

Any processes started on behalf of the calling tool (or the specified namespace, if such specification is included in the list of attributes) should continue after the tool disconnects from its server.

• PMIX_NOTIFY_JOB_EVENTS "pmix.note.jev" (bool)

Requests that the launcher generate the PMIX_EVENT_JOB_START,

PMIX_LAUNCH_COMPLETE, and PMIX_EVENT_JOB_END events. Each event is to include at least the namespace of the corresponding job and a PMIX_EVENT_TIMESTAMP indicating the time the event occurred. Note that the requester must register for these individual events, or capture and process them by registering a default event handler instead of individual handlers and then process the events based on the returned status code. Another common method is to register one event handler for all job-related events, with a separate handler for non-job events - see PMIx_Register_event_handler for details.

• PMIX_NOTIFY_COMPLETION "pmix.notecomp" (bool)

Requests that the launcher generate the PMIX_EVENT_JOB_END event for normal or abnormal termination of the spawned job. The event shall include the returned status code (PMIX_JOB_TERM_STATUS) for the corresponding job; the identity (PMIX_PROCID) and exit status (PMIX_EXIT_CODE) of the first failed process, if applicable; and a PMIX_EVENT_TIMESTAMP indicating the time the termination occurred. Note that the requester must register for the event or capture and process it within a default event handler.

- PMIX_LOG_JOB_EVENTS "pmix.log.jev" (bool)
 - Requests that the launcher log the PMIX_EVENT_JOB_START, PMIX_LAUNCH_COMPLETE, and PMIX_EVENT_JOB_END events using PMIx_Log, subject to the logging attributes of Section 12.4.3.
- PMIX LOG COMPLETION "pmix.logcomp" (bool)

Requests that the launcher log the PMIX_EVENT_JOB_END event for normal or abnormal termination of the spawned job using PMIx_Log, subject to the logging attributes of Section 12.4.3. The event shall include the returned status code (PMIX_JOB_TERM_STATUS) for the corresponding job; the identity (PMIX_PROCID) and exit status (PMIX_EXIT_CODE) of the first failed process, if applicable; and a PMIX_EVENT_TIMESTAMP indicating the time the termination occurred.

• PMIX DEBUG STOP ON EXEC "pmix.dbg.exec" (bool)

Included in either the <code>pmix_info_t</code> array in a <code>pmix_app_t</code> description (if the directive applies only to that application) or in the <code>job_info</code> array if it applies to all applications in the given spawn request. Indicates that the application is being spawned under a debugger, and that the local launch agent is to pause the resulting application processes on first instruction for debugger attach. The launcher (RM or IL) is to generate the <code>PMIX_LAUNCH_COMPLETE</code> event when all processes are stopped at the exec point.

• PMIX_DEBUG_STOP_IN_INIT "pmix.dbg.init" (bool)

Included in either the <code>pmix_info_t</code> array in a <code>pmix_app_t</code> description (if the directive applies only to that application) or in the <code>job_info</code> array if it applies to all applications in the given spawn request. Indicates that the specified application is being spawned under a debugger. The PMIx client library in each resulting application process shall notify its PMIx server that it is pausing and then pause during <code>PMIx_Init</code> of the spawned processes until either released by debugger modification of an appropriate variable or receipt of the <code>PMIX_DEBUGGER_RELEASE</code> event. The launcher (RM or IL) is responsible for generating the <code>PMIX_READY_FOR_DEBUG</code> event (stipulating a breakpoint of pmix-init) when all processes have reached the pause point.

• PMIX_DEBUG_STOP_IN_APP "pmix.dbg.notify" (varies)

Direct specified ranks to stop at application-specific point and notify they are ready-to-debug. The attribute's value can be any of three data types:

- bool true indicating all ranks
- pmix_rank_t the rank of one proc, or PMIX_RANK_WILDCARD for all
- a pmix_data_array_t if an array of individual processes are specified

The resulting application processes are to notify their server (by generating the <code>PMIX_READY_FOR_DEBUG</code> event) when they reach some application-determined location - the event shall include the <code>PMIX_BREAKPOINT</code> attribute indicating where the application has stopped. The application shall pause at that point until released by debugger modification of an appropriate variable. The launcher (RM or IL) is responsible for generating the <code>PMIX_READY_FOR_DEBUG</code> event when all processes have indicated they are at the pause point.

Advice to users —

The PMIX_IOF_FILE_ONLY indicates output is directed to files and no copy is sent back to the application. For example, this can be combined with PMIX_IOF_OUTPUT_TO_FILE or PMIX_IOF_OUTPUT_TO_DIRECTORY to only output to files.

The tool then calls the **PMIx_Spawn** API so that the PMIx library can communicate the spawn request to the server.

Upon receipt, the PMIx server library passes the spawn request to its host RM daemon for processing via the <code>pmix_server_spawn_fn_t</code> server module function. If this callback was not provided, then the PMIx server library will return the <code>PMIX_ERR_NOT_SUPPORTED</code> error status.

If an allocation must be made, then the host environment is responsible for communicating the request to its associated scheduler. Once resources are available, the host environment initiates the launch process to start the job. The host environment must parse the spawn request for relevant directives, returning an error if any required directive cannot be supported. Optional directives may be ignored if they cannot be supported.

Any error while executing the spawn request must be returned by **PMIx_Spawn** to the requester. Once the spawn request has succeeded in starting the specified processes, the request will return **PMIX_SUCCESS** back to the requester along with the namespace of the started job. Upon termination of the spawned job, the host environment must generate a **PMIX_EVENT_JOB_END** event for normal or abnormal termination if requested to do so. The event shall include:

- the returned status code (PMIX JOB TERM STATUS) for the corresponding job;
- the identity (PMIX_PROCID) and exit status (PMIX_EXIT_CODE) of the first failed process, if applicable;
- a PMIX_EVENT_TIMESTAMP indicating the time the termination occurred; plus
- any other info provided by the host environment.

17.2.2 Indirect launch

In the indirect launch use-case, the application processes are started via an intermediate launcher (e.g., *mpiexec*) that is itself started by the tool (see Fig 17.3). Thus, at a high level, this is a two-stage launch procedure to start the application: the tool (henceforth referred to as the *initiator*) starts the IL, which then starts the applications. In practice, additional steps may be involved if, for example, the IL starts its own daemons to shepherd the application processes.

A key aspect of this operational mode is the avoidance of any requirement that the initiator parse and/or understand the command line of the IL. Instead, the indirect launch procedure supports either of two methods: one where the initiator assumes responsibility for parsing its command line to obtain the application as well as the IL and its options, and another where the initiator defers the command line parsing to the IL. Both of these methods are described in the following sections.

17.2.2.1 Initiator-based command line parsing

This method utilizes a first call to the PMIx_Spawn API to start the IL itself, and then uses a second call to PMIx_Spawn to request that the IL spawn the actual job. The burden of analyzing the initial command line to separately identify the IL's command line from the application itself falls upon the initiator. An example is provided below:

```
$ initiator --launcher "mpiexec --verbose" -n 3 ./app <appoptions>
```

The initiator spawns the IL using the same procedure for launching an application - it begins by assembling the description of the IL into a spawn request containing an array of <code>pmix_app_t</code> and <code>pmix_info_t</code> job-level information. Note that this step does not include any information regarding the application itself - only the launcher is included. In addition, the initiator must include the rendezvous URI in the environment so the IL knows how to connect back to it.

An allocation of resources for the IL itself may or may not be required – if it is, then the allocation must be made in advance or the spawn request must include allocation request information.




Figure 17.3.: Indirect launch procedure

The initiator may optionally wish to include the following tool-specific attributes in the *job_info* argument to **PMI***_Spawn - note that these attributes refer only to the behavior of the IL itself and not the eventual job to be launched:

- PMIX FWD STDIN "pmix.fwd.stdin" (pmix rank t)
 - The requester intends to push information from its **stdin** to the indicated process. The local spawn agent should, therefore, ensure that the **stdin** channel to that process remains available. A rank of **PMIX_RANK_WILDCARD** indicates that all processes in the spawned job are potential recipients. The requester will issue a call to **PMIx_IOF_push** to initiate the actual forwarding of information to specified targets this attribute simply requests that the IL retain the ability to forward the information to the designated targets.
- PMIX_FWD_STDOUT "pmix.fwd.stdout" (bool)
 Requests that the ability to forward the stdout of the spawned processes be maintained. The requester will issue a call to PMIx_IOF_pull to specify the callback function and other options for delivery of the forwarded output.
- PMIX_FWD_STDERR "pmix.fwd.stderr" (bool)
 Requests that the ability to forward the stderr of the spawned processes be maintained. The requester will issue a call to PMIx_IOF_pull to specify the callback function and other options for delivery of the forwarded output.
- PMIX_FWD_STDDIAG "pmix.fwd.stddiag" (bool)

 Requests that the ability to forward the diagnostic channel (if it exists) of the spawned processes be maintained. The requester will issue a call to **PMIx_IOF_pull** to specify the callback function and other options for delivery of the forwarded output.

• PMIX_IOF_CACHE_SIZE "pmix.iof.csize" (uint32_t)

The requested size of the PMIx server cache in bytes for each specified channel. By default, the server is allowed (but not required) to drop all bytes received beyond the max size.

• PMIX_IOF_DROP_OLDEST "pmix.iof.old" (bool)

In an overflow situation, the PMIx server is to drop the oldest bytes to make room in the cache.

• PMIX IOF DROP NEWEST "pmix.iof.new" (bool)

In an overflow situation, the PMIx server is to drop any new bytes received until room becomes available in the cache (default).

• PMIX_IOF_BUFFERING_SIZE "pmix.iof.bsize" (uint32_t)

Requests that IO on the specified channel(s) be aggregated in the PMIx tool library until the specified number of bytes is collected to avoid being called every time a block of IO arrives. The PMIx tool library will execute the callback and reset the collection counter whenever the specified number of bytes becomes available. Any remaining buffered data will be *flushed* to the callback upon a call to deregister the respective channel.

• PMIX_IOF_BUFFERING_TIME "pmix.iof.btime" (uint32_t)

Max time in seconds to buffer IO before delivering it. Used in conjunction with buffering size, this prevents IO from being held indefinitely while waiting for another payload to arrive.

• PMIX_IOF_TAG_OUTPUT "pmix.iof.tag" (bool)

Requests that output be prefixed with the nspace, rank of the source and a string identifying the channel (stdout, stderr, etc.).

• PMIX_IOF_TIMESTAMP_OUTPUT "pmix.iof.ts" (bool)

Requests that output be marked with the time at which the data was received by the tool - note that this will differ from the time at which the data was collected from the source.

• PMIX_IOF_XML_OUTPUT "pmix.iof.xml" (bool)

Requests that output be formatted in XML.

• PMIX_NOHUP "pmix.nohup" (bool)

Any processes started on behalf of the calling tool (or the specified namespace, if such specification is included in the list of attributes) should continue after the tool disconnects from its server.

• PMIX_LAUNCHER_DAEMON "pmix.lnch.dmn" (char*)

Path to executable that is to be used as the backend daemon for the launcher. This replaces the launcher's own daemon with the specified executable. Note that the user is therefore responsible for ensuring compatibility of the specified executable and the host launcher.

• PMIX_FORKEXEC_AGENT "pmix.frkex.agnt" (char*)

Path to executable that the launcher's backend daemons are to fork/exec in place of the actual application processes. The fork/exec agent shall connect back (as a PMIx tool) to the launcher's

daemon to receive its spawn instructions, and is responsible for starting the actual application process it replaced. See Section 17.4.3 for details.

• PMIX_EXEC_AGENT "pmix.exec.agnt" (char*)

Path to executable that the launcher's backend daemons are to fork/exec in place of the actual application processes. The launcher's daemon shall pass the full command line of the application on the command line of the exec agent, which shall not connect back to the launcher's daemon. The exec agent is responsible for exec'ing the specified application process in its own place. See Section 17.4.3 for details.

• PMIX_DEBUG_STOP_IN_INIT "pmix.dbg.init" (bool)

Included in either the <code>pmix_info_t</code> array in a <code>pmix_app_t</code> description (if the directive applies only to that application) or in the <code>job_info</code> array if it applies to all applications in the given spawn request. Indicates that the specified application is being spawned under a debugger. The PMIx client library in each resulting application process shall notify its PMIx server that it is pausing and then pause during <code>PMIx_Init</code> of the spawned processes until either released by debugger modification of an appropriate variable or receipt of the <code>PMIX_DEBUGGER_RELEASE</code> event. The launcher (RM or IL) is responsible for generating the <code>PMIX_READY_FOR_DEBUG</code> event (stipulating a breakpoint of pmix-init) when all processes have reached the pause point. In this context, the initiator is directing the IL to stop in <code>PMIx_tool_init</code>. This gives the initiator a chance to connect to the IL and register for events prior to the IL launching the application job.

and the following optional variables in the environment of the IL:

 PMIX_KEEPALIVE_PIPE - an integer read-end of a POSIX pipe that the IL should monitor for closure, thereby indicating that the initiator has terminated.

The initiator then calls the **PMIx_Spawn** API so that the PMIx library can either communicate the spawn request to a server (if connected to one), or locally spawn the IL itself if not connected to a server and the PMIx implementation includes self-spawn support. **PMIx_Spawn** shall return an error if neither of these conditions is met.

When initialized by the IL, the **PMIx_tool_init** function must perform two operations:

- check for the presence of the PMIX_KEEPALIVE_PIPE environmental variable if provided, then the library shall monitor the pipe for closure, providing a PMIX_EVENT_JOB_END event when the pipe closes (thereby indicating the termination of the initiator). The IL should register for this event after completing PMIx_tool_init the initiator's namespace can be obtained via a call to PMIx_Get with the PMIX_PARENT_ID key. Note that this feature will only be available if the spawned IL is local to the initiator.
- check for the PMIX_LAUNCHER_RNDZ_URI environmental parameter if found, the library shall connect
 back to the initiator using the PMIx_tool_attach_to_server API, retaining its current server as its
 primary server.

Once the IL completes PMIx_tool_init, it must register for the PMIX_EVENT_JOB_END termination event and then idle until receiving that event - either directly from the initiator, or from the PMIx library upon detecting closure of the keepalive pipe. The IL idles in the intervening time as it is solely acting as a relay (if connected to a server that is performing the actual application launch) or as a PMIx server responding to spawn requests.

6 7

8 9

10

11 12

13

14

15

16

17

18

19

20

21 22

23

24 25

26

27

28

29

30 31

32

33

34

35

36 37

1

Upon return from the PMIx_Spawn API, the initiator should set the spawned IL as its primary server using the PMIx tool set server API with the nspace returned by PMIx Spawn and any valid rank (a rank of zero would ordinarily be used as only one IL process is typically started). It is advisable to set a connection timeout value when calling this function. The initiator can then proceed to spawn the actual application according to the procedure described in Section 17.2.1.

17.2.2.2 IL-based command line parsing

In the case where the initiator cannot parse its command line, it must defer that parsing to the IL. A common example is provided below:

```
$ initiator mpiexec --verbose -n 3 ./app <appoptions>
```

For this situation, the initiator proceeds as above with only one notable exception: instead of calling PMIx_Spawn twice (once to start the IL and again to start the actual application), the initiator only calls that API one time:

- The app parameter passed to the spawn request contains only one pmix_app_t that contains the entire command line, including both launcher and application(s).
- The launcher executable must be in the app.cmd field and in app.argv[0], with the rest of the command line appended to the app.argv array.
- Any job-level directives for the IL itself (e.g., PMIX FORKEXEC AGENT or PMIX FWD STDOUT) are included in the *job_info* parameter of the call to **PMIx_Spawn**.
- The job-level directives must include both the PMIX SPAWN TOOL attribute indicating that the initiator is spawning a tool, and the PMIX_DEBUG_STOP_IN_INIT attribute directing the IL to stop during the call to PMIx tool init. The latter directive allows the initiator to connect to the IL prior to launch of the application.
- The PMIX_LAUNCHER_RNDZ_URI and PMIX_KEEPALIVE_PIPE environmental variables are provided to the launcher in its environment via the app.env field.
- The IL must use PMIx Get with the PMIX LAUNCH DIRECTIVES key to obtain any initiator-provided directives (e.g., PMIX DEBUG STOP IN INIT or PMIX DEBUG STOP ON EXEC) aimed at the application(s) it will spawn.

Upon return from **PMIx** Spawn, the initiator must:

- use the PMIx_tool_set_server API to set the spawned IL as its primary server
- register with that server to receive the PMIX_LAUNCH_COMPLETE event. This allows the initiator to know when the IL has completed launch of the application
- release the IL from its "hold" in PMIx_tool_init by issuing the PMIX_DEBUGGER_RELEASE event, specifying the IL as the custom range. Upon receipt of the event, the IL is free to parse its command line, apply any provided directives, and execute the application.

Upon receipt of the PMIX_LAUNCH_COMPLETE event, the initiator should register to receive notification of completion of the returned namespace of the application. Receipt of the PMIX_EVENT_JOB_END event provides a signal that the initiator may itself terminate.

17.2.3 Tool spawn-related attributes

 Tools are free to utilize the spawn attributes available to applications (see 11.2.4) when constructing a spawn request, but can also utilize the following attributes that are specific to tool-based spawn operations:

PMIX_FWD_STDIN "pmix.fwd.stdin" (pmix_rank_t)

The requester intends to push information from its **stdin** to the indicated process. The local spawn agent should, therefore, ensure that the **stdin** channel to that process remains available. A rank of **PMIX_RANK_WILDCARD** indicates that all processes in the spawned job are potential recipients. The requester will issue a call to **PMIX_IOF_push** to initiate the actual forwarding of information to specified targets - this attribute simply requests that the IL retain the ability to forward the information to the designated targets.

PMIX_FWD_STDOUT "pmix.fwd.stdout" (bool)

Requests that the ability to forward the **stdout** of the spawned processes be maintained. The requester will issue a call to **PMIx_IOF_pull** to specify the callback function and other options for delivery of the forwarded output.

PMIX_FWD_STDERR "pmix.fwd.stderr" (bool)

Requests that the ability to forward the **stderr** of the spawned processes be maintained. The requester will issue a call to **PMIx_IOF_pull** to specify the callback function and other options for delivery of the forwarded output.

PMIX_FWD_STDDIAG "pmix.fwd.stddiag" (bool)

Requests that the ability to forward the diagnostic channel (if it exists) of the spawned processes be maintained. The requester will issue a call to **PMIx_IOF_pull** to specify the callback function and other options for delivery of the forwarded output.

PMIX_NOHUP "pmix.nohup" (bool)

Any processes started on behalf of the calling tool (or the specified namespace, if such specification is included in the list of attributes) should continue after the tool disconnects from its server.

PMIX LAUNCHER DAEMON "pmix.lnch.dmn" (char*)

Path to executable that is to be used as the backend daemon for the launcher. This replaces the launcher's own daemon with the specified executable. Note that the user is therefore responsible for ensuring compatibility of the specified executable and the host launcher.

PMIX FORKEXEC AGENT "pmix.frkex.agnt" (char*)

Path to executable that the launcher's backend daemons are to fork/exec in place of the actual application processes. The fork/exec agent shall connect back (as a PMIx tool) to the launcher's daemon to receive its spawn instructions, and is responsible for starting the actual application process it replaced. See Section 17.4.3 for details.

PMIX_EXEC_AGENT "pmix.exec.agnt" (char*)

Path to executable that the launcher's backend daemons are to fork/exec in place of the actual application processes. The launcher's daemon shall pass the full command line of the application on the command line of the exec agent, which shall not connect back to the launcher's daemon. The exec agent is responsible for exec'ing the specified application process in its own place. See Section 17.4.3 for details.

PMIX_LAUNCH_DIRECTIVES "pmix.lnch.dirs" (pmix_data_array_t*)

Array of **pmix_info_t** containing directives for the launcher - a convenience attribute for retrieving all directives with a single call to **PMIx_Get**.

17.2.4 Tool rendezvous-related events

The following constants refer to events relating to rendezvous of a tool and launcher during spawn of the IL.

PMIX_LAUNCHER_READY An application launcher (e.g., *mpiexec*) shall generate this event to signal a tool that started it that the launcher is ready to receive directives/commands (e.g., **PMIx_Spawn**). This is only used when the initiator is able to parse the command line itself, or the launcher is started as a persistent Distributed Virtual Machine (DVM).

17.3 IO Forwarding

Underlying the operation of many tools is a common need to forward **stdin** from the tool to targeted processes, and to return **stdout/stderr** from those processes to the tool (e.g., for display on the user's console). Historically, each tool developer was responsible for creating their own IO forwarding subsystem. However, the introduction of PMIx as a standard mechanism for interacting between applications and the host environment has made it possible to relieve tool developers of this burden.

This section defines functions by which tools can request forwarding of input/output to/from other processes and serves as a design guide to:

- provide tool developers with an overview of the expected behavior of the PMIx IO forwarding support;
- guide RM vendors regarding roles and responsibilities expected of the RM to support IO forwarding; and
- provide insight into the thinking of the PMIx community behind the definition of the PMIx IO forwarding APIs.

Note that the forwarding of IO via PMIx requires that both the host environment and the tool support PMIx, but does not impose any similar requirements on the application itself.

The responsibility of the host environment in forwarding of IO falls into the following areas:

- Capturing output from specified processes.
- Forwarding that output to the host of the PMIx server library that requested it.
- Delivering that payload to the PMIx server library via the PMIx_server_IOF_deliver API for final dispatch to the requesting tool.

It is the responsibility of the PMIx library to buffer, format, and deliver the payload to the requesting client. This may require caching of output until a forwarding registration is received, as governed by the corresponding IO forwarding attributes of Section 17.3.5 that are supported by the implementation.

17.3.1 Forwarding stdout/stderr

At an appropriate point in its operation (usually during startup), a tool will utilize the **PMIx_tool_init** function to connect to a PMIx server. The PMIx server can be hosted by an RM daemon or could be embedded in a library-provided starter program such as *mpiexec* - in terms of IO forwarding, the operations remain the same either way. For purposes of this discussion, we will assume the server is in an RM daemon and that the application processes are directly launched by the RM, as shown in Fig 17.4.

Once the tool has connected to the target server, it can request that processes be spawned on its behalf or that output from a specified set of existing processes in a given executing application be forwarded to it. Requests to spawn processes should include the PMIX_FWD_STDIN, PMIX_FWD_STDOUT, and/or PMIX_FWD_STDERR attributes if the tool intends to request that the corresponding streams be forwarded at some point during execution.

2

15

16

10 11



23




Figure 17.4.: Forwarding stdout/stderr

Note that requests to capture output from existing processes via the PMIx_IOF_pull API, and/or to forward input to specified processes via the PMIx IOF push API, can only succeed if the required attributes to retain that ability were passed when the corresponding job was spawned. The host is required to return an error for all such requests in cases where this condition is not met.

Two modes are supported when requesting that the host forward standard output/error via the PMIx_IOF_pull API - these can be controlled by including one of the following attributes in the info array passed to that function:

- PMIX_IOF_COPY "pmix.iof.cpy" (bool) Requests that the host environment deliver a copy of the specified output stream(s) to the tool, letting the stream(s) continue to also be delivered to the default location. This allows the tool to tap into the output stream(s) without redirecting it from its current final destination.
- PMIX_IOF_REDIRECT "pmix.iof.redir" (bool)

Requests that the host environment intercept the specified output stream(s) and deliver it to the requesting tool instead of its current final destination. This might be used, for example, during a debugging procedure to avoid injection of debugger-related output into the application's results file. The original output stream(s) destination is restored upon termination of the tool. This is the default mode of operation.

When requesting to forward stdout/stderr, the tool can specify several formatting options to be used on the resulting output stream. These include:

- PMIX_IOF_TAG_OUTPUT "pmix.iof.tag" (bool) Requests that output be prefixed with the nspace, rank of the source and a string identifying the channel (stdout, stderr, etc.).
- PMIX_IOF_TIMESTAMP_OUTPUT "pmix.iof.ts" (bool)

- PMIX_IOF_XML_OUTPUT "pmix.iof.xml" (bool)
 Requests that output be formatted in XML.
- PMIX_IOF_RANK_OUTPUT "pmix.iof.rank" (bool)

 Tag output with the rank it came from
- PMIX_IOF_OUTPUT_TO_FILE "pmix.iof.file" (char*)
 Direct application output into files of form "<filename>.<nspace>.<rank>.stdout" (for stdout) and "<filename>.<nspace>.<rank>.stderr" (for stderr). If PMIX_IOF_MERGE_STDERR_STDOUT was given, then only the stdout file will be created and both streams will be written into it.
- PMIX_IOF_OUTPUT_TO_DIRECTORY "pmix.iof.dir" (char*)
 Direct application output into files of form "<directory>/<nspace>/rank.<rank>/stdout" (for stdout) and "<directory>/<nspace>/rank.<rank>/stderr" (for stderr). If
 PMIX_IOF_MERGE_STDERR_STDOUT was given, then only the stdout file will be created and both streams will be written into it.
- PMIX_IOF_FILE_PATTERN "pmix.iof.fpt" (bool)

 Specified output file is to be treated as a pattern and not automatically annotated by nspace, rank, or other parameters. The pattern can use %n for the namespace, and %r for the rank wherever those quantities are to be placed. The resulting filename will be appended with ".stdout" for the stdout stream and ".stderr" for the stderr stream. If PMIX_IOF_MERGE_STDERR_STDOUT was given, then only the stdout file will be created and both streams will be written into it.
- PMIX_IOF_FILE_ONLY "pmix.iof.fonly" (bool)
 Output only into designated files do not also output a copy to the console's stdout/stderr
- PMIX_IOF_MERGE_STDERR_STDOUT "pmix.iof.mrg" (bool)

 Merge stdout and stderr streams from application procs

The PMIx client in the tool is responsible for formatting the output stream. Note that output from multiple processes will often be interleaved due to variations in arrival time - ordering of output is not guaranteed across processes and/or nodes.

17.3.2 Forwarding stdin

A tool is not necessarily a child of the RM as it may have been started directly from the command line. Thus, provision must be made for the tool to collect its **stdin** and pass it to the host RM (via the PMIx server) for forwarding. Two methods of support for forwarding of **stdin** are defined:

• internal collection by the PMIx tool library itself. This is requested via the PMIX_IOF_PUSH_STDIN attribute in the PMIx_IOF_push call. When this mode is selected, the tool library begins collecting all stdin data and internally passing it to the local server for distribution to the specified target processes. All collected data is sent to the same targets until stdin is closed, or a subsequent call to PMIx_IOF_push is made that includes the PMIX_IOF_COMPLETE attribute indicating that forwarding of stdin is to be terminated.




Figure 17.5.: Forwarding stdin

external collection directly by the tool. It is assumed that the tool will provide its own code/mechanism for collecting its stdin as the tool developers may choose to insert some filtering and/or editing of the stream prior to forwarding it. In addition, the tool can directly control the targets for the data on a per-call basis – i.e., each call to PMIx_IOF_push can specify its own set of target recipients for that particular blob of data. Thus, this method provides maximum flexibility, but requires that the tool developer provide their own code to capture stdin.

Note that it is the responsibility of the RM to forward data to the host where the target process(es) are executing, and for the host daemon on that node to deliver the data to the **stdin** of target process(es). The PMIx server on the remote node is not involved in this process. Systems that do not support forwarding of **stdin** shall return **PMIX_ERR_NOT_SUPPORTED** in response to a forwarding request.

Advice to users

Scalable forwarding of **stdin** represents a significant challenge. Most environments will at least handle a *send-to-1* model whereby **stdin** is forwarded to a single identified process, and occasionally an additional *send-to-all* model where **stdin** is forwarded to all processes in the application. Users are advised to check their host environment for available support as the distribution method lies outside the scope of PMIx.

Stdin buffering by the RM and/or PMIx library can be problematic. If any targeted recipient is slow reading data (or decides never to read data), then the data must be buffered in some intermediate daemon or the PMIx tool library itself. Thus, piping a large amount of data into **stdin** can result in a very large memory footprint in the system management stack or the tool. Best practices, therefore, typically focus on reading of input files by application processes as opposed to forwarding of **stdin**.

17.3.3 IO Forwarding Channels

2	The pmix_iof_channel_t structure is a uint16_t type that defines a set of bit-mask flags for
3	specifying IO forwarding channels. These can be bitwise OR'd together to reference multiple channels.

```
4
             PMIX FWD NO CHANNELS
                                       Forward no channels.
5
             PMIX FWD STDIN CHANNEL
                                          Forward stdin.
6
             PMIX FWD STDOUT CHANNEL
                                           Forward stdout.
7
             PMIX FWD STDERR CHANNEL
                                           Forward stderr.
8
```

PMIX FWD STDDIAG CHANNEL Forward **stddiag**, if available.

PMIX FWD ALL CHANNELS Forward all available channels.

17.3.4 IO Forwarding constants

```
11
                  PMIX ERR IOF FAILURE
                                                  An IO forwarding operation failed - the affected channel will be included in
12
                       the notification.
```

PMIX_ERR_IOF_COMPLETE IO forwarding of the standard input for this process has completed - i.e., the stdin file descriptor has closed.

17.3.5 IO Forwarding attributes

The following attributes are used to control IO forwarding behavior at the request of tools. Use of the attributes is optional - any option not provided will revert to some implementation-specific value.

```
PMIX_IOF_LOCAL_OUTPUT "pmix.iof.local" (bool) (Provisional)
```

Write output streams to local stdout/err

PMIX IOF MERGE STDERR STDOUT "pmix.iof.mrg" (bool) (Provisional)

Merge stdout and stderr streams from application procs

```
PMIX_IOF_CACHE_SIZE "pmix.iof.csize" (uint32 t)
```

The requested size of the PMIx server cache in bytes for each specified channel. By default, the server is allowed (but not required) to drop all bytes received beyond the max size.

```
PMIX_IOF_DROP_OLDEST "pmix.iof.old" (bool)
```

In an overflow situation, the PMIx server is to drop the oldest bytes to make room in the cache.

```
PMIX_IOF_DROP_NEWEST "pmix.iof.new" (bool)
```

In an overflow situation, the PMIx server is to drop any new bytes received until room becomes available in the cache (default).

```
PMIX_IOF_BUFFERING_SIZE "pmix.iof.bsize" (uint32_t)
```

Requests that IO on the specified channel(s) be aggregated in the PMIx tool library until the specified number of bytes is collected to avoid being called every time a block of IO arrives. The PMIx tool library will execute the callback and reset the collection counter whenever the specified number of bytes becomes available. Any remaining buffered data will be *flushed* to the callback upon a call to deregister the respective channel.

```
PMIX IOF BUFFERING TIME "pmix.iof.btime" (uint32 t)
```

Max time in seconds to buffer IO before delivering it. Used in conjunction with buffering size, this prevents IO from being held indefinitely while waiting for another payload to arrive.

```
PMIX_IOF_OUTPUT_RAW "pmix.iof.raw" (bool) (Provisional)
```

Do not buffer output to be written as complete lines - output characters as the stream delivers them

9

10

13

14

15 16

17

18

19

20

21

22

23

24

25

26

27

28

29

30

31 32

33

34

35

36

37

38

39

PMIX_IOF_COMPLETE "pmix.iof.cmp" (bool)

Indicates that the specified IO channel has been closed by the source.

PMIX_IOF_TAG_OUTPUT "pmix.iof.tag" (bool)

Requests that output be prefixed with the nspace, rank of the source and a string identifying the channel (stdout, stderr, etc.).

PMIX_IOF_TIMESTAMP_OUTPUT "pmix.iof.ts" (bool)

Requests that output be marked with the time at which the data was received by the tool - note that this will differ from the time at which the data was collected from the source.

PMIX_IOF_RANK_OUTPUT "pmix.iof.rank" (bool) (Provisional)

Tag output with the rank it came from

PMIX_IOF_XML_OUTPUT "pmix.iof.xml" (bool)

Requests that output be formatted in XML.

PMIX_IOF_PUSH_STDIN "pmix.iof.stdin" (bool)

Requests that the PMIx library collect the **stdin** of the requester and forward it to the processes specified in the **PMIx_IOF_push** call. All collected data is sent to the same targets until **stdin** is closed, or a subsequent call to **PMIx_IOF_push** is made that includes the **PMIX_IOF_COMPLETE** attribute indicating that forwarding of **stdin** is to be terminated.

PMIX_IOF_COPY "pmix.iof.cpy" (bool)

Requests that the host environment deliver a copy of the specified output stream(s) to the tool, letting the stream(s) continue to also be delivered to the default location. This allows the tool to tap into the output stream(s) without redirecting it from its current final destination.

PMIX_IOF_REDIRECT "pmix.iof.redir" (bool)

Requests that the host environment intercept the specified output stream(s) and deliver it to the requesting tool instead of its current final destination. This might be used, for example, during a debugging procedure to avoid injection of debugger-related output into the application's results file. The original output stream(s) destination is restored upon termination of the tool.

PMIX IOF OUTPUT_TO_FILE "pmix.iof.file" (char*) (Provisional)

Direct application output into files of form "<filename>.<nspace>.<rank>.stdout" (for stdout) and "<filename>.<nspace>.<rank>.stderr" (for stderr). If PMIX_IOF_MERGE_STDERR_STDOUT was given, then only the stdout file will be created and both streams will be written into it.

PMIX_IOF_OUTPUT_TO_DIRECTORY "pmix.iof.dir" (char*) (Provisional)

Direct application output into files of form "<directory>/<nspace>/rank.<rank>/stdout" (for **stdout**) and "<directory>/<nspace>/rank.<rank>/stderr" (for **stderr**). If

PMIX_IOF_MERGE_STDERR_STDOUT was given, then only the **stdout** file will be created and both streams will be written into it.

PMIX_IOF_FILE_PATTERN "pmix.iof.fpt" (bool) (Provisional)

Specified output file is to be treated as a pattern and not automatically annotated by nspace, rank, or other parameters. The pattern can use **%n** for the namespace, and **%r** for the rank wherever those quantities are to be placed. The resulting filename will be appended with ".stdout" for the **stdout** stream and ".stderr" for the **stderr** stream. If **PMIX_IOF_MERGE_STDERR_STDOUT** was given, then only the **stdout** file will be created and both streams will be written into it.

PMIX_IOF_FILE_ONLY "pmix.iof.fonly" (bool) (Provisional)

Output only into designated files - do not also output a copy to the console's stdout/stderr

17.4 Debugger Support

Debuggers are a class of tool that merits special consideration due to their particular requirements for access to job-related information and control over process execution. The primary advantage of using PMIx for these purposes lies in the resulting portability of the debugger as it can be used with any system and/or programming model that supports PMIx. In addition to the general tool support described above, debugger support includes:

- Co-location, co-spawn, and communication wireup of debugger daemons for scalable launch. This includes providing debugger daemons with endpoint connection information across the daemons themselves.
- Identification of the job that is to be debugged. This includes automatically providing debugger daemons with the job-level information for their target job.

Debuggers can also utilize the options in the **PMIx_Spawn** API to exercise a degree of control over spawned jobs for debugging purposes. For example, a debugger can utilize the environmental parameter attributes of Section 11.2.4 to request **LD_PRELOAD** of a memory interceptor library prior to spawning an application process, or interject a custom fork/exec agent to shepherd the application process.

A key element of the debugging process is the ability of the debugger to require that processes *pause* at some well-defined point, thereby providing the debugger with an opportunity to attach and control execution. The actual implementation of the *pause* lies outside the scope of PMIx - it typically requires either the launcher or the application itself to implement the necessary operations. However, PMIx does provide several standard attributes by which the debugger can specify the desired attach point:

• PMIX_DEBUG_STOP_ON_EXEC "pmix.dbg.exec" (bool)

Included in either the <code>pmix_info_t</code> array in a <code>pmix_app_t</code> description (if the directive applies only to that application) or in the <code>job_info</code> array if it applies to all applications in the given spawn request. Indicates that the application is being spawned under a debugger, and that the local launch agent is to pause the resulting application processes on first instruction for debugger attach. The launcher (RM or IL) is to generate the <code>PMIX_LAUNCH_COMPLETE</code> event when all processes are stopped at the exec point. Launchers that cannot support this operation shall return an error from the <code>PMIx_Spawn</code> API if this behavior is requested.

• PMIX_DEBUG_STOP_IN_INIT "pmix.dbg.init" (bool)

Included in either the <code>pmix_info_t</code> array in a <code>pmix_app_t</code> description (if the directive applies only to that application) or in the <code>job_info</code> array if it applies to all applications in the given spawn request. Indicates that the specified application is being spawned under a debugger. The PMIx client library in each resulting application process shall notify its PMIx server that it is pausing and then pause during <code>PMIx_Init</code> of the spawned processes until either released by debugger modification of an appropriate variable or receipt of the <code>PMIX_DEBUGGER_RELEASE</code> event. The launcher (RM or IL) is responsible for generating the <code>PMIX_READY_FOR_DEBUG</code> event (stipulating a breakpoint of pmix-init) when all processes have reached the pause point. PMIx implementations that do not support this operation shall return an error from <code>PMIx_Init</code> if this behavior is requested.

Launchers that cannot support this operation shall return an error from the <code>PMIx_Spawn</code> API if this behavior is requested.

• PMIX_DEBUG_STOP_IN_APP "pmix.dbg.notify" (varies)

Direct specified ranks to stop at application-specific point and notify they are ready-to-debug. The attribute's value can be any of three data types:

- bool - true indicating all ranks

 - pmix_rank_t - the rank of one proc, or PMIX_RANK_WILDCARD for all

- a pmix data array t if an array of individual processes are specified

The resulting application processes are to notify their server (by generating the <code>PMIX_READY_FOR_DEBUG</code> event) when they reach some application-determined location - the event shall include the <code>PMIX_BREAKPOINT</code> attribute indicating where the application has stopped. The application shall pause at that point until released by debugger modification of an appropriate variable. The launcher (RM or IL) is responsible for generating the <code>PMIX_READY_FOR_DEBUG</code> event when all processes have indicated they are at the pause point. Launchers that cannot support this operation shall return an error from the <code>PMIx_Spawn</code> API if this behavior is requested.

Note that there is no mechanism by which the PMIx library or the launcher can verify that an application will recognize and support the PMIX_DEBUG_STOP_IN_APP request. Debuggers utilizing this attachment method must, therefore, be prepared to deal with the case where the application fails to recognize and/or honor the request.

If the PMIx implementation and/or the host environment support it, debuggers can utilize the PMIx_Query_info API to determine which features are available via the PMIX_QUERY_ATTRIBUTE_SUPPORT attribute.

- PMIX_DEBUG_STOP_IN_INIT by checking PMIX_CLIENT_ATTRIBUTES for the PMIx_Init API.
- PMIX_DEBUG_STOP_ON_EXEC by checking PMIX_HOST_ATTRIBUTES for the PMIx_Spawn API.

The target namespace or process (as given by the debugger in the spawn request) shall be provided to each daemon in its job-level information via the PMIX_DEBUG_TARGET attribute. Debugger daemons are responsible for self-determining their specific target process(es), and can then utilize the PMIx_Query_info API to obtain information about them (see Fig 17.6) - e.g., to obtain the PIDs of the local processes to which they need to attach. PMIx provides the pmix_proc_info_t structure for organizing information about a process' PID, location, and state. Debuggers may request information on a given job at two levels:

- PMIX_QUERY_PROC_TABLE "pmix.qry.ptable" (char*)
 Returns a (pmix_data_array_t) array of pmix_proc_info_t, one entry for each process in the specified namespace, ordered by process job rank. REQUIRED QUALIFIER: PMIX_NSPACE indicating the namespace whose process table is being queried.
- PMIX_QUERY_LOCAL_PROC_TABLE "pmix.qry.lptable" (char*)
 Returns a (pmix_data_array_t) array of pmix_proc_info_t, one entry for each process in the specified namespace executing on the same node as the requester, ordered by process job rank.
 REQUIRED QUALIFIER: PMIX_NSPACE indicating the namespace whose local process table is being queried. OPTIONAL QUALIFIER: PMIX_HOSTNAME indicating the host whose local process table is being queried. By default, the query assumes that the host upon which the request was made is to be used.

Note that the information provided in the returned proctable represents a snapshot in time. Any process, regardless of role (tool, client, debugger, etc.) can obtain the proctable of a given namespace so long as it has the system-determined authorizations to do so. The list of namespaces available via a given server can be obtained using the PMIx_Query_info API with the PMIX_QUERY_NAMESPACES key.

Debugger daemons can be started in two ways - either at the same time the application is spawned, or separately at a later time.




Figure 17.6.: Obtaining proctables

17.4.1 Co-Location of Debugger Daemons

Debugging operations typically require the use of daemons that are located on the same node as the processes they are attempting to debug. The debugger can, of course, specify its own mapping method when issuing its spawn request or utilize its own internal launcher to place the daemons. However, when attaching to a running job, PMIx provides debuggers with a simplified method for requesting that the launcher associated with the job co-locate the required daemons. Debuggers can request co-location of their daemons by adding the following attributes to the PMIx_Spawn used to spawn them:

- PMIX DEBUGGER DAEMONS indicating that the launcher is being asked to spawn debugger daemons.
- PMIX_DEBUG_TARGET indicating the job or process that is to be debugged. This allows the launcher to
 identify the processes to be debugged and their location. Note that the debugger job shall be assigned its
 own namespace (different from that of the job it is being spawned to debug) and each daemon will be
 assigned a unique rank within that namespace.
- PMIX_DEBUG_DAEMONS_PER_PROC specifies the number of debugger daemons to be co-located per target process.
- PMIX_DEBUG_DAEMONS_PER_NODE specifies the number of debugger daemons to be co-located per node where at least one target process is executing.

Debugger daemons spawned in this manner shall be provided with the typical PMIx information for their own job plus the target they are to debug via the PMIX_DEBUG_TARGET attribute. The debugger daemons spawned on a given node are responsible for self-determining their specific target process(es) - e.g., by referencing their own PMIX_LOCAL_RANK in the daemon debugger job versus the corresponding PMIX_LOCAL_RANK of the target processes on the node. Note that the debugger will be attaching to the application processes at some arbitrary point in the application's execution unless some method for pausing the application (e.g., by providing a PMIx directive at time of launch, or via a tool using the PMIx_Job_control API to direct that the process be paused) has been employed.

Advice to users

Note that the tool calling **PMIx_Spawn** to request the launch of the debugger daemons is *not* included in the resulting job - i.e., the debugger daemons do not inherit the namespace of the tool. Thus, collective operations and notifications that target the debugger daemon job will not include the tool unless the namespace/rank of the tool is explicitly included.

17.4.2 Co-Spawn of Debugger Daemons

In the case where a job is being spawned under the control of a debugger, PMIx provides a shortcut method for spawning the debugger's daemons in parallel with the job. This requires that the debugger be specified as one of the <code>pmix_app_t</code> in the same spawn command used to start the job. The debugger application must include at least the <code>PMIX_DEBUGGER_DAEMONS</code> attribute identifying itself as a debugger, and may utilize either a mapping option to direct daemon placement, or one of the <code>PMIX_DEBUG_DAEMONS_PER_PROC</code> or <code>PMIX_DEBUG_DAEMONS_PER_NODE</code> directives.

The launcher must not include information regarding the debugger daemons in the job-level info provided to the rest of the <code>pmix_app_ts</code>, nor in any calculated rank values (e.g., <code>PMIX_NODE_RANK</code> or <code>PMIX_LOCAL_RANK</code>) in those applications. The debugger job is to be assigned its own namespace and each debugger daemon shall receive a unique rank - i.e., the debugger application is to be treated as a completely separate PMIx job that is simply being started in parallel with the user's applications. The launcher is free to implement the launch as a single operation for both the applications and debugger daemons (preferred), or may stage the launches as required. The launcher shall not return from the <code>PMIx_Spawn</code> command until all included applications and the debugger daemons have been started.

Attributes that apply to both the debugger daemons and the application processes can be specified in the *job_info* array passed into the **PMIx_Spawn** API. Attributes that either (a) apply solely to the debugger daemons or to one of the applications included in the spawn request, or (b) have values that differ from those provided in the *job_info* array, should be specified in the *info* array in the corresponding **pmix_app_t**. Note that PMIx job *pause* attributes (e.g., **PMIX_DEBUG_STOP_IN_INIT**) do not apply to applications (defined in **pmix_app_t**) where the **PMIX_DEBUGGER_DAEMONS** attribute is set to **true**.

Debugger daemons spawned in this manner shall be provided with the typical PMIx information for their own job plus the target they are to debug via the PMIX_DEBUG_TARGET attribute. The debugger daemons spawned on a given node are responsible for self-determining their specific target process(es) - e.g., by referencing their own PMIX_LOCAL_RANK in the daemon debugger job versus the corresponding PMIX_LOCAL_RANK of the target processes on the node.

— Advice to users ·

Note that the tool calling PMIx_Spawn to request the launch of the debugger daemons is *not* included in the resulting job - i.e., the debugger daemons do not inherit the namespace of the tool. Thus, collective operations and notifications that target the debugger daemon job will not include the tool unless the namespace/rank of the tool is explicitly included.

The PMIx_Spawn API only supports the return of a single namespace resulting from the spawn request. In the case where the debugger job is co-spawned with the application, the spawn function shall return the namespace of the application and not the debugger job. Tools requiring access to the namespace of the debugger job must query the launcher for the spawned namespaces to find the one belonging to the debugger job.

17.4.3 Debugger Agents

Individual debuggers may, depending upon implementation, require varying degrees of control over each application process when it is started beyond those available via directives to **PMIx_Spawn**. PMIx offers two mechanisms to help provide a means of meeting these needs.

The PMIX_FORKEXEC_AGENT attribute allows the debugger to specify an intermediate process (the Fork/Exec Agent (FEA)) for spawning the actual application process (see Fig. 17.7a), thereby interposing the debugger daemon between the application process and the launcher's daemon. Instead of spawning the application process, the launcher will spawn the FEA, which will connect back to the PMIx server as a tool to obtain the spawn description of the application process it is to spawn. The PMIx server in the launcher's daemon shall not register the fork/exec agent as a local client process, nor shall the launcher include the agent in any of the job-level values (e.g., PMIX_RANK within the job or PMIX_LOCAL_RANK on the node) provided to the application process. The launcher shall treat the collection of FEAs as a debugger job equivalent to the co-spawn use-case described in Section 17.4.2.




Figure 17.7.: Intermediate agents

In contrast, the PMIX_EXEC_AGENT attribute (Fig. 17.7b) allows the debugger to specify an agent that will perform some preparatory actions and then exec the eventual application process to replace itself. In this scenario, the exec agent is provided with the application process' command line as arguments on its command line (e.g., "./agent appargv[0] appargv[1]") and does not connect back to the host's PMIx server. It is the responsibility of the exec agent to properly separate its own command line arguments (if any) from the application description.

17.4.4 Tracking the job lifecycle

There are a wide range of events a debugger can register to receive, but three are specifically defined for tracking a job's progress:

- PMIX_EVENT_JOB_START indicates when the first process in the job has been spawned.
- PMIX LAUNCH COMPLETE indicates when the last process in the job has been spawned.

• PMIX_EVENT_JOB_END indicates that all processes have terminated.

Each event is required to contain at least the namespace of the corresponding job and a
PMIX_EVENT_TIMESTAMP indicating the time the event occurred. In addition, the

PMIX_EVENT_JOB_END event shall contain the returned status code (PMIX_JOB_TERM_STATUS) for the corresponding job, plus the identity (PMIX_PROCID) and exit status (PMIX_EXIT_CODE) of the first failed process, if applicable. Generation of these events by the launcher can be requested by including the
PMIX_NOTIFY_JOB_EVENTS attributes in the spawn request. Note that these events can be logged via the
PMIX_Log API by including the PMIX_LOG_JOB_EVENTS attribute - this can be done either in
conjunction with generated events, or in place of them.

Alternatively, if the debugger or tool solely wants to be alerted to job termination, then including the **PMIX_NOTIFY_COMPLETION** attribute in the spawn request would suffice. This attribute directs the launcher to provide just the **PMIX_EVENT_JOB_END** event. Note that this event can be logged via the **PMIX_LOG_API** by including the **PMIX_LOG_COMPLETION** attribute - this can be done either in conjunction with the generated event, or in place of it.

— Advice to users -

The PMIx server is required to cache events in order to avoid race conditions - e.g., when a tool is trying to register for the PMIX_EVENT_JOB_END event from a very short-lived job. Accordingly, registering for job-related events can result in receiving events relating to jobs other than the one of interest.

Users are therefore advised to specify the job whose events are of interest by including the **PMIX_EVENT_AFFECTED_PROC** or **PMIX_EVENT_AFFECTED_PROCS** attribute in the *info* array passed to the **PMIX_Register_event_handler** API.

17.4.4.1 Job lifecycle events

PMIX_EVENT_JOB_START The first process in the job has been spawned - includes

PMIX_EVENT_TIMESTAMP as well as the PMIX_JOBID and/or PMIX_NSPACE of the job.

PMIX_LAUNCH_COMPLETE All processes in the job have been spawned - includes

PMIX_EVENT_TIMESTAMP as well as the PMIX_JOBID and/or PMIX_NSPACE of the job.

PMIX_EVENT_JOB_END All processes in the job have terminated - includes
PMIX_EVENT_TIMESTAMP when the last process terminated as well as the PMIX_JOBID and/or PMIX_NSPACE of the job.

PMIX_EVENT_SESSION_START The allocation has been instantiated and is ready for use - includes **PMIX_EVENT_TIMESTAMP** as well as the **PMIX_SESSION_ID** of the allocation. This event is issued after any system-controlled prologue has completed, but before any user-specified actions are taken.

PMIX_EVENT_SESSION_END The allocation has terminated - includes PMIX_EVENT_TIMESTAMP as well as the PMIX_SESSION_ID of the allocation. This event is issued after any user-specified actions have completed, but before any system-controlled epilogue is performed.

The following events relate to processes within a job:

PMIX_EVENT_PROC_TERMINATED The specified process(es) terminated - normal or abnormal termination will be indicated by the PMIX_PROC_TERM_STATUS in the info array of the notification. Note that a request for individual process events can generate a significant event volume from large-scale jobs.

1 PMIX_ERR_PROC_TERM_WO_SYNC Process terminated without calling PMIx_Finalize, or was a 2 member of an assemblage formed via PMIx Connect and terminated or called PMIx Finalize 3 without first calling PMIx_Disconnect (or its non-blocking form) from that assemblage. 4 The following constants may be included via the PMIX JOB TERM STATUS attributed in the *info* array in 5 the PMIX_EVENT_JOB_END event notification to provide more detailed information regarding the reason for 6 job abnormal termination: 7 PMIX ERR JOB CANCELED The job was canceled by the host environment. 8 One or more processes in the job called abort, causing the job to be PMIX ERR JOB ABORTED 9 terminated. 10 PMIX_ERR_JOB_KILLED_BY_CMD The job was killed by user command. 11 PMIX_ERR_JOB_ABORTED_BY_SIG The job was aborted due to receipt of an error signal (e.g., SIGKILL). 12 13 PMIX ERR JOB TERM WO SYNC The job was terminated due to at least one process terminating 14 without calling PMIx Finalize, or was a member of an assemblage formed via PMIx Connect 15 and terminated or called PMIx_Finalize without first calling PMIx_Disconnect (or its 16 non-blocking form) from that assemblage. 17 PMIX ERR JOB SENSOR BOUND EXCEEDED The job was terminated due to one or more processes 18 exceeding a specified sensor limit. 19 PMIX ERR JOB NON ZERO TERM The job was terminated due to one or more processes exiting with 20 a non-zero status.

17.4.4.2 Job lifecycle attributes

rate.

PMIX ERR JOB ABORTED BY SYS EVENT

PMIX_JOB_TERM_STATUS "pmix.job.term.status" (pmix_status_t)

Status returned by job upon its termination. The status will be communicated as part of a PMIx event payload provided by the host environment upon termination of a job. Note that generation of the PMIX_EVENT_JOB_END event is optional and host environments may choose to provide it only upon request.

The job was aborted due to receipt of a system event.

PMIX_PROC_TERM_STATUS "pmix.proc.term.status" (pmix_status_t)

Status returned by a process upon its termination. The status will be communicated as part of a PMIx event payload provided by the host environment upon termination of a process. Note that generation of the PMIX_EVENT_PROC_TERMINATED event is optional and host environments may choose to provide it only upon request.

17.4.5 Debugger-related constants

The following constants are used in events used to coordinate applications and the debuggers attaching to them.

PMIX_READY_FOR_DEBUG Event indicating a job (or specified set of processes) is ready for debug - includes identification of the target processes as well as the **PMIX_BREAKPOINT** indicating where the target is waiting

PMIX DEBUGGER RELEASE Release a tool that is paused during PMIx tool init.

21

22 23

24

25

26

27 28

29

30

31

32

33

34 35

36 37

38

39

40

17.4.6 Debugger attributes 1

2

3

4

5

6

7

8

9

10

11 12

13

14

15

16

17

18 19

20

21

22

26

27

28

29

30

31

32

33

34

35

36

37

38

39

40

41

42

43

44

45

46

47

Attributes used to assist debuggers - these are values that can either be passed to the PMIx Spawn APIs or accessed by a debugger itself using the PMIx Get API with the PMIX RANK WILDCARD rank.

PMIX DEBUG STOP ON EXEC "pmix.dbg.exec" (bool)

Included in either the pmix info t array in a pmix app t description (if the directive applies only to that application) or in the job_info array if it applies to all applications in the given spawn request. Indicates that the application is being spawned under a debugger, and that the local launch agent is to pause the resulting application processes on first instruction for debugger attach. The launcher (RM or IL) is to generate the PMIX_LAUNCH_COMPLETE event when all processes are stopped at the exec point.

PMIX DEBUG STOP IN INIT "pmix.dbg.init" (bool)

Included in either the pmix info t array in a pmix app t description (if the directive applies only to that application) or in the *job_info* array if it applies to all applications in the given spawn request. Indicates that the specified application is being spawned under a debugger. The PMIx client library in each resulting application process shall notify its PMIx server that it is pausing and then pause during PMIx_Init of the spawned processes until either released by debugger modification of an appropriate variable or receipt of the PMIX_DEBUGGER_RELEASE event. The launcher (RM or IL) is responsible for generating the PMIX READY FOR DEBUG event (stipulating a breakpoint of pmix-init) when all processes have reached the pause point.

PMIX DEBUG STOP IN APP "pmix.dbq.notify" (varies)

Direct specified ranks to stop at application-specific point and notify they are ready-to-debug. The attribute's value can be any of three data types:

- bool true indicating all ranks

 pmix_rank_t the rank of one proc, or PMIX_RANK_WILDCARD for all
 a pmix_data_array_t if an array of individual processes are specified

The resulting application processes are to notify their server (by generating the

PMIX_READY_FOR_DEBUG event) when they reach some application-determined location - the event shall include the **PMIX BREAKPOINT** attribute indicating where the application has stopped. The application shall pause at that point until released by debugger modification of an appropriate variable. The launcher (RM or IL) is responsible for generating the PMIX READY FOR DEBUG event when all processes have indicated they are at the pause point.

PMIX_BREAKPOINT "pmix.brkpnt" (char*)

String ID of the breakpoint where the process(es) is(are) waiting.

PMIX DEBUG TARGET "pmix.dbg.tgt" (pmix proc t*)

Identifier of process(es) to be debugged - a rank of PMIX RANK WILDCARD indicates that all processes in the specified namespace are to be included.

PMIX_DEBUGGER_DAEMONS "pmix.debugger" (bool)

Included in the pmix info t array of a pmix app t, this attribute declares that the application consists of debugger daemons and shall be governed accordingly. If used as the sole pmix_app_t in a PMIx_Spawn request, then the PMIX_DEBUG_TARGET attribute must also be provided (in either the job_info or in the info array of the pmix_app_t) to identify the namespace to be debugged so that the launcher can determine where to place the spawned daemons. If neither

PMIX DEBUG DAEMONS PER PROC nor PMIX DEBUG DAEMONS PER NODE is specified, then the launcher shall default to a placement policy of one daemon per process in the target job.

PMIX_COSPAWN_APP "pmix.cospawn" (bool)

Designated application is to be spawned as a disconnected job - i.e., the launcher shall not include the application in any of the job-level values (e.g., PMIX_RANK within the job) provided to any other

application process generated by the same spawn request. Typically used to cospawn debugger daemons alongside an application.

PMIX_DEBUG_DAEMONS_PER_PROC "pmix.dbg.dpproc" (uint16_t)

Number of debugger daemons to be spawned per application process. The launcher is to pass the identifier of the namespace to be debugged by including the <code>PMIX_DEBUG_TARGET</code> attribute in the daemon's job-level information. The debugger daemons spawned on a given node are responsible for self-determining their specific target process(es) - e.g., by referencing their own <code>PMIX_LOCAL_RANK</code> in the daemon debugger job versus the corresponding <code>PMIX_LOCAL_RANK</code> of the target processes on the node.

PMIX_DEBUG_DAEMONS_PER_NODE "pmix.dbg.dpnd" (uint16_t)

Number of debugger daemons to be spawned on each node where the target job is executing. The launcher is to pass the identifier of the namespace to be debugged by including the
PMIX_DEBUG_TARGET attribute in the daemon's job-level information. The debugger daemons spawned on a given node are responsible for self-determining their specific target process(es) - e.g., by referencing their own PMIX_LOCAL_RANK in the daemon debugger job versus the corresponding
PMIX_LOCAL_RANK of the target processes on the node.

PMIX_QUERY_PROC_TABLE "pmix.qry.ptable" (char*)

Returns a (pmix_data_array_t) array of pmix_proc_info_t, one entry for each process in the specified namespace, ordered by process job rank. REQUIRED QUALIFIER: PMIX_NSPACE indicating the namespace whose process table is being queried.

PMIX_QUERY_LOCAL_PROC_TABLE "pmix.qry.lptable" (char*)

Returns a (pmix_data_array_t) array of pmix_proc_info_t, one entry for each process in the specified namespace executing on the same node as the requester, ordered by process job rank. REQUIRED QUALIFIER: PMIX_NSPACE indicating the namespace whose local process table is being queried. OPTIONAL QUALIFIER: PMIX_HOSTNAME indicating the host whose local process table is being queried. By default, the query assumes that the host upon which the request was made is to be used.

17.5 Tool-Specific APIs

PMIx-based tools automatically have access to all PMIx client functions. Tools designated as a *launcher* or a *server* will also have access to all PMIx server functions. There are, however, an additional set of functions (described in this section) that are specific to a PMIx tool. Access to those functions require use of the tool initialization routine.

17.5.1 PMIx_tool_init

Summary

Initialize the PMIx library for operating as a tool, optionally connecting to a specified PMIx server.

```
Format

pmix_status_t

PMIx_tool_init(pmix_proc_t *proc,

pmix_info_t info[], size_t ninfo);
```

	C		
1 2	INOUT proc		
3	<pre>pmix_proc_t structure (handle) IN info</pre>		
4	Array of pmix_info_t structures (array of handles)		
5	IN ninfo		
6	Number of elements in the <i>info</i> array (size_t)		
7	Returns PMIX_SUCCESS or a negative value corresponding to a PMIx error constant.		
	▼ Required Attributes		
8	The following attributes are required to be supported by all PMIx libraries:		
9 10	<pre>PMIX_TOOL_NSPACE "pmix.tool.nspace" (char*) Name of the namespace to use for this tool.</pre>		
11 12	<pre>PMIX_TOOL_RANK "pmix.tool.rank" (uint32_t)</pre>		
13 14	<pre>PMIX_TOOL_DO_NOT_CONNECT "pmix.tool.nocon" (bool)</pre> The tool wants to use internal PMIx support, but does not want to connect to a PMIx server.		
15 16	<pre>PMIX_TOOL_ATTACHMENT_FILE "pmix.tool.attach" (char*) Pathname of file containing connection information to be used for attaching to a specific server.</pre>		
17 18	<pre>PMIX_SERVER_URI "pmix.srvr.uri" (char*) URI of the PMIx server to be contacted.</pre>		
19 20 21	<pre>PMIX_TCP_URI "pmix.tcp.uri" (char*) The URI of the PMIx server to connect to, or a file name containing it in the form of file:<name containing="" file="" it="" of="">.</name></pre>		
22 23	PMIX_SERVER_PIDINFO "pmix.srvr.pidinfo" (pid_t) PID of the target PMIx server for a tool.		
24 25	PMIX_SERVER_NSPACE "pmix.srv.nspace" (char*) Name of the namespace to use for this PMIx server.		
26 27	PMIX_CONNECT_TO_SYSTEM "pmix.cnct.sys" (bool) The requester requires that a connection be made only to a local, system-level PMIx server.		
28 29	<pre>PMIX_CONNECT_SYSTEM_FIRST "pmix.cnct.sys.first" (bool) Preferentially, look for a system-level PMIx server first.</pre>		

 Optional Attributes

The following attributes are optional for implementers of PMIx libraries: 1 2 PMIX CONNECT RETRY DELAY "pmix.tool.retry" (uint32 t) 3 Time in seconds between connection attempts to a PMIx server - the default value is implementation 4 specific. 5 PMIX CONNECT MAX RETRIES "pmix.tool.mretries" (uint32 t) 6 Maximum number of times to try to connect to PMIx server - the default value is implementation 7 specific. 8 PMIX_SOCKET_MODE "pmix.sockmode" (uint32_t) 9 POSIX mode_t (9 bits valid). If the library supports socket connections, this attribute may be 10 supported for setting the socket mode. 11 PMIX_TCP_REPORT_URI "pmix.tcp.repuri" (char*) 12 If provided, directs that the TCP URI be reported and indicates the desired method of reporting: '-' for stdout, '+' for stderr, or filename. If the library supports TCP socket connections, this attribute 13 may be supported for reporting the URI. 14 15 PMIX_TCP_IF_INCLUDE "pmix.tcp.ifinclude" (char*) 16 Comma-delimited list of devices and/or CIDR notation to include when establishing the TCP 17 connection. If the library supports TCP socket connections, this attribute may be supported for specifying the interfaces to be used. 18 19 PMIX_TCP_IF_EXCLUDE "pmix.tcp.ifexclude" (char*) 20 Comma-delimited list of devices and/or CIDR notation to exclude when establishing the TCP 21 connection. If the library supports TCP socket connections, this attribute may be supported for 22 specifying the interfaces that are *not* to be used. 23 PMIX_TCP_IPV4_PORT "pmix.tcp.ipv4" (int) 24 The IPv4 port to be used.. If the library supports IPV4 connections, this attribute may be supported 25 for specifying the port to be used. 26 PMIX TCP IPV6 PORT "pmix.tcp.ipv6" (int) 27 The IPv6 port to be used. If the library supports IPV6 connections, this attribute may be supported for specifying the port to be used. 28 29 PMIX_TCP_DISABLE_IPV4 "pmix.tcp.disipv4" (bool) Set to true to disable IPv4 family of addresses. If the library supports IPV4 connections, this 30 31 attribute may be supported for disabling it. 32 PMIX_TCP_DISABLE_IPV6 "pmix.tcp.disipv6" (bool) 33 Set to **true** to disable IPv6 family of addresses. If the library supports IPV6 connections, this attribute may be supported for disabling it. 34 PMIX_EXTERNAL_PROGRESS "pmix.evext" (bool) 35 The host shall progress the PMIx library via calls to PMIx_Progress 36

37

PMIX_EVENT_BASE "pmix.evbase" (void*)

Pointer to an **event_base** to use in place of the internal progress thread. All PMIx library events are to be assigned to the provided event base. The event base *must* be compatible with the event library used by the PMIx implementation - e.g., either both the host and PMIx library must use libevent, or both must use libev. Cross-matches are unlikely to work and should be avoided - it is the responsibility of the host to ensure that the PMIx implementation supports (and was built with) the appropriate event library.

PMIX_IOF_LOCAL_OUTPUT "pmix.iof.local" (bool)

Write output streams to local stdout/err

Description

 Initialize the PMIx tool, returning the process identifier assigned to this tool in the provided **pmix_proc_t** struct. The *info* array is used to pass user requests pertaining to the initialization and subsequent operations. Passing a **NULL** value for the array pointer is supported if no directives are desired.

If called with the PMIX_TOOL_DO_NOT_CONNECT attribute, the PMIx tool library will fully initialize but not attempt to connect to a PMIx server. The tool can connect to a server at a later point in time, if desired, by calling the PMIx_tool_attach_to_server function. If provided, the proc structure will be set to a zero-length namespace and a rank of PMIX_RANK_UNDEF unless the PMIX_TOOL_NSPACE and PMIX_TOOL_RANK attributes are included in the info array.

In all other cases, the PMIx tool library will automatically attempt to connect to a PMIx server according to the precedence chain described in Section 17.1. If successful, the function will return PMIX_SUCCESS and will fill the process structure (if provided) with the assigned namespace and rank of the tool. The server to which the tool connects will be designated its *primary* server. Note that each connection attempt in the above precedence chain will retry (with delay between each retry) a number of times according to the values of the corresponding attributes.

Note that the PMIx tool library is referenced counted, and so multiple calls to PMIx_tool_init are allowed. If the tool is not connected to any server when this API is called, then the tool will attempt to connect to a server unless the PMIX TOOL DO NOT CONNECT is included in the call to API.

17.5.2 PMIx_tool_finalize

Summary

Finalize the PMIx tool library.

PMIx v2.0 Format

C

pmix_status_t
PMIx_tool_finalize(void);

Returns **PMIX_SUCCESS** or a negative value corresponding to a PMIx error constant.

Description

Finalize the PMIx tool library, closing all existing connections to servers. An error code will be returned if, for some reason, a connection cannot be cleanly terminated — in such cases, the connection is dropped. Upon detecting loss of the connection, the PMIx server shall cleanup all associated records of the tool.

17.5.3 PMIx_tool_disconnect

```
2
                 Summary
 3
                 Disconnect the PMIx tool from the specified server connection while leaving the tool library initialized.
 4 PMIx v4.0
 5
                 pmix status t
 6
                 PMIx_tool_disconnect(const pmix_proc_t *server);
 7
                 IN
                      server
 8
                      pmix proc t structure (handle)
 9
                 Returns PMIX_SUCCESS or a negative value corresponding to a PMIx error constant.
                 Description
10
11
                 Close the current connection to the specified server, if one has been made, while leaving the PMIx library
12
                 initialized. An error code will be returned if, for some reason, the connection cannot be cleanly terminated - in
                 this case, the connection is dropped. In either case, the library will remain initialized. Upon detecting loss of
13
                 the connection, the PMIx server shall cleanup all associated records of the tool.
14
15
                 Note that if the server being disconnected is the current primary server, then all operations requiring support
16
                 from a server will return the PMIX_ERR_UNREACH error until the tool either designates an existing
17
                 connection to be the primary server or, if no other connections exist, the tool establishes a connection to a
18
                 PMIx server.
      17.5.4
                   PMIx tool attach to server
19
                 Summary
20
21
                 Establish a connection to a PMIx server.
                 Format
22 <sub>PMIx v4.0</sub>
23
                 pmix status t
24
                 PMIx_tool_attach_to_server(pmix_proc_t *proc,
25
                                                     pmix_proc_t *server,
26
                                                     pmix_info_t info[],
27
                                                     size t ninfo);
                                                    —— C —
                 INOUT proc
28
                      Pointer to pmix_proc_t structure (handle)
29
                 INOUT server
30
                      Pointer to pmix_proc_t structure (handle)
31
                 IN
32
33
                      Array of pmix info t structures (array of handles)
                 IN
                      ninfo
34
35
                      Number of elements in the info array (size_t)
36
                 Returns PMIX_SUCCESS or a negative value corresponding to a PMIx error constant.
```

Required Attributes

The following attributes are required to be supported by all PMIx libraries:

```
PMIX_TOOL_ATTACHMENT_FILE "pmix.tool.attach" (char*)
```

Pathname of file containing connection information to be used for attaching to a specific server.

```
PMIX_SERVER_URI "pmix.srvr.uri" (char*)
```

URI of the PMIx server to be contacted.

```
PMIX_TCP_URI "pmix.tcp.uri" (char*)
```

The URI of the PMIx server to connect to, or a file name containing it in the form of **file:<name** of **file containing it>**.

```
PMIX_SERVER_PIDINFO "pmix.srvr.pidinfo" (pid_t)
```

PID of the target PMIx server for a tool.

```
PMIX_SERVER_NSPACE "pmix.srv.nspace" (char*)
```

Name of the namespace to use for this PMIx server.

```
PMIX_CONNECT_TO_SYSTEM "pmix.cnct.sys" (bool)
```

The requester requires that a connection be made only to a local, system-level PMIx server.

```
PMIX_CONNECT_SYSTEM_FIRST "pmix.cnct.sys.first" (bool)
```

Preferentially, look for a system-level PMIx server first.

```
PMIX_PRIMARY_SERVER "pmix.pri.srvr" (bool)
```

The server to which the tool is connecting shall be designated the *primary* server once connection has been accomplished.

Description

1

3

4

5

6

7

8

9

10

11

12 13

14

15

16

17

18

19

20

21 22

23

24

25

26

27

28

29

30

31

32

33

34

Establish a connection to a server. This function can be called at any time by a PMIx tool to create a new connection to a server. If a specific server is given and the tool is already attached to it, then the API shall return PMIX_SUCCESS without taking any further action. In all other cases, the tool will attempt to discover a server using the method described in Section 17.1, ignoring all candidates to which it is already connected. The PMIX_ERR_UNREACH error shall be returned if no new connection is made.

The process identifier assigned to this tool is returned in the provided *proc* structure. Passing a value of **NULL** for the *proc* parameter is allowed if the user wishes solely to connect to a PMIx server and does not require return of the identifier at that time.

The process identifier of the server to which the tool attached is returned in the *server* structure. Passing a value of **NULL** for the *proc* parameter is allowed if the user wishes solely to connect to a PMIx server and does not require return of the identifier at that time.

Note that the **PMIX_PRIMARY_SERVER** attribute must be included in the *info* array if the server being connected to is to become the primary server, or a call to **PMIx_tool_set_server** must be provided immediately after the call to this function.

Advice to PMIx library implementers

When a tool connects to a server that is under a different namespace manager (e.g., host RM) from the prior server, the namespace in the identifier of the tool must remain unique in the new universe. If the namespace of the tool fails to meet this criteria in the new universe, then the new namespace manager is required to return an error and the connection attempt must fail.

— Advice to users —

Some PMIx implementations may not support connecting to a server that is not under the same namespace manager (e.g., host RM) as the server to which the tool is currently connected.

17.5.5 PMIx_tool_get_servers

Summary

Get an array containing the **pmix_proc_t** process identifiers of all servers to which the tool is currently connected.

11 $_{PMIx \ v4.0}$ Format

1

2

3

5

6

7

8

10

12

13

14

16

17

18

19 20

21 22

23

25

pmix_status_t

PMIx_tool_get_servers(pmix_proc_t *servers[], size_t *nservers);

OUT servers

Address where the pointer to an array of **pmix proc** t structures shall be returned (handle)

INOUT nservers

Address where the number of elements in *servers* shall be returned (handle)

Returns **PMIX SUCCESS** or a negative value corresponding to a PMIx error constant.

Description

Return an array containing the pmix_proc_t process identifiers of all servers to which the tool is currently connected. The process identifier of the current primary server shall be the first entry in the array, with the remaining entries in order of attachment from earliest to most recent.

17.5.6 PMIx tool set server

24 Summary

Designate a server as the tool's *primary* server.

```
Format
 1
 2
                pmix status t
 3
                PMIx_tool_set_server(const pmix_proc_t *server,
 4
                                           pmix_info_t info[], size_t ninfo);
                                                   ____ C ____
 5
                IN
                     server
 6
                     pmix proc t structure (handle)
 7
                IN
                     info
 8
                     Array of pmix info t structures (array of handles)
 9
                IN
                     ninfo
10
                     Number of elements in the info array (size_t)
11
                Returns PMIX_SUCCESS or a negative value corresponding to a PMIx error constant.

→ - - - - - Required Attributes

12
                The following attributes are required to be supported by all PMIx libraries:
                PMIX_WAIT_FOR_CONNECTION "pmix.wait.conn" (bool)
13
14
                      Wait until the specified process has connected to the requesting tool or server, or the operation times
                      out (if the PMIX_TIMEOUT directive is included in the request).
15
16
                PMIX_TIMEOUT "pmix.timeout" (int)
17
                      Time in seconds before the specified operation should time out (zero indicating infinite) and return the
                      PMIX_ERR_TIMEOUT error. Care should be taken to avoid race conditions caused by multiple layers
18
19
                      (client, server, and host) simultaneously timing the operation.
                Description
20
21
                Designate the specified server to be the tool's primary server for all subsequent API calls.
     17.5.7
                 PMIx_IOF_pull
22
23
                Summary
```

Register to receive output forwarded from a set of remote processes.

1	Format C		
2 3 4 5 6 7 8	<pre>pmix_status_t PMIx_IOF_pull(const pmix_proc_t procs[], size_t nprocs,</pre>		
9 10	IN procs Array of proc structures identifying desired source processes (array of handles)		
11 12	IN nprocs Number of elements in the <i>procs</i> array (integer)		
13 14 15	IN directives Array of pmix_info_t structures (array of handles) IN ndirs		
16 17 18	Number of elements in the <i>directives</i> array (integer) IN channel Bitmask of IO channels included in the request (pmix_iof_channel_t)		
19 20 21 22 23	 IN cbfunc Callback function for delivering relevant output (pmix_iof_cbfunc_t function reference) IN regcbfunc Function to be called when registration is completed (pmix_hdlr_reg_cbfunc_t function reference) 		
24 25	IN regcbdata Data to be passed to the regcbfunc callback function (memory reference)		
26 27	Returns PMIX_SUCCESS or a negative value corresponding to a PMIx error constant. In the event the function returns an error, the <i>regcbfunc</i> will <i>not</i> be called.		
	▼ Required Attributes		
28	The following attributes are required for PMIx libraries that support IO forwarding:		
29 30 31	PMIX_IOF_CACHE_SIZE "pmix.iof.csize" (uint32_t) The requested size of the PMIx server cache in bytes for each specified channel. By default, the server is allowed (but not required) to drop all bytes received beyond the max size.		
32 33	PMIX_IOF_DROP_OLDEST "pmix.iof.old" (bool) In an overflow situation, the PMIx server is to drop the oldest bytes to make room in the cache.		
34 35 36	PMIX_IOF_DROP_NEWEST "pmix.iof.new" (bool) In an overflow situation, the PMIx server is to drop any new bytes received until room becomes available in the cache (default).		

Optional Attributes

The following attributes are optional for PMIx libraries that support IO forwarding:

PMIX_IOF_BUFFERING_SIZE "pmix.iof.bsize" (uint32_t)

Requests that IO on the specified channel(s) be aggregated in the PMIx tool library until the specified number of bytes is collected to avoid being called every time a block of IO arrives. The PMIx tool library will execute the callback and reset the collection counter whenever the specified number of bytes becomes available. Any remaining buffered data will be *flushed* to the callback upon a call to deregister the respective channel.

PMIX_IOF_BUFFERING_TIME "pmix.iof.btime" (uint32_t)

Max time in seconds to buffer IO before delivering it. Used in conjunction with buffering size, this prevents IO from being held indefinitely while waiting for another payload to arrive.

PMIX_IOF_TAG_OUTPUT "pmix.iof.tag" (bool)

Requests that output be prefixed with the nspace, rank of the source and a string identifying the channel (stdout, stderr, etc.).

PMIX IOF TIMESTAMP OUTPUT "pmix.iof.ts" (bool)

Requests that output be marked with the time at which the data was received by the tool - note that this will differ from the time at which the data was collected from the source.

PMIX_IOF_XML_OUTPUT "pmix.iof.xml" (bool)

Requests that output be formatted in XML.

Description

1 2

3

4

5

6

7

8

9

10 11

12

13

14

15

16 17

18

19 20

21

22

23

24

25 26

27

Register to receive output forwarded from a set of remote processes.

—— Advice to users —

Providing a **NULL** function pointer for the *cbfunc* parameter will cause output for the indicated channels to be written to their corresponding **stdout/stderr** file descriptors. Use of **PMIX_RANK_WILDCARD** to specify all processes in a given namespace is supported but should be used carefully due to bandwidth and memory footprint considerations.

17.5.8 PMIx_IOF_deregister

Summary

Deregister from output forwarded from a set of remote processes.

1	Format C				
2	pmix_status_t				
3	PMIx_IOF_deregister(size_t iofhdlr,				
4 5	<pre>const pmix_info_t directives[], size_t ndirs, pmix_op_cbfunc_t cbfunc, void *cbdata);</pre>				
5	pmix_op_ebiume_t ebiume, void *ebdata),				
6	IN iofhdlr				
7	Registration number returned from the pmix_hdlr_reg_cbfunc_t callback from the call to				
8	PMIx_IOF_pull(size_t)				
9	IN directives				
10	Array of pmix_info_t structures (array of handles)				
11	IN ndirs				
12	Number of elements in the <i>directives</i> array (integer)				
13	IN cbfunc				
14	Callback function to be called when deregistration has been completed. (function reference)				
15	IN cbdata				
16	Data to be passed to the <i>cbfunc</i> callback function (memory reference)				
17	Returns one of the following:				
18 19 20	• PMIX_SUCCESS , indicating that the request is being processed by the host environment - result will be returned in the provided <i>cbfunc</i> . Note that the library <i>must not</i> invoke the callback function prior to returning from the API.				
21 22	 PMIX_OPERATION_SUCCEEDED, indicating that the request was immediately processed and returned success - the cbfunc will not be called 				
23 24	• a PMIx error constant indicating either an error in the input or that the request was immediately processed and failed - the <i>cbfunc</i> will <i>not</i> be called				
25 26	Description Deregister from output forwarded from a set of remote processes.				
	Advice to PMIx library implementers				
27 28	Any currently buffered IO should be flushed upon receipt of a deregistration request. All received IO after receipt of the request shall be discarded.				

17.5.9 PMIx_IOF_push

Summary

Push data collected locally (typically from **stdin** or a file) to **stdin** of the target recipients.

29

30

1	Format C			
2 3 4 5 6	<pre>pmix_status_t PMIx_IOF_push(const pmix_proc_t targets[], size_t ntargets,</pre>			
7 8 9 10 11 12 13 14 15 16 17 18 19 20 21 22 23	IN targets Array of proc structures identifying desired target processes (array of handles) IN ntargets Number of elements in the targets array (integer) IN bo Pointer to pmix_byte_object_t containing the payload to be delivered (handle) IN directives Array of pmix_info_t structures (array of handles) IN ndirs Number of elements in the directives array (integer) IN directives Array of pmix_info_t structures (array of handles) IN cbdata Description of the called when operation has been completed. (pmix_op_cbfunc_t function reference) IN cbdata Description of the process of the complete of th			
24	Data to be passed to the <i>cbfunc</i> callback function (memory reference) Returns one of the following:			
25 26 27 28	 PMIX_SUCCESS, indicating that the request is being processed by the host environment - result will be returned in the provided <i>cbfunc</i>. Note that the library <i>must not</i> invoke the callback function prior to returning from the API. PMIX_OPERATION_SUCCEEDED, indicating that the request was immediately processed and returned 			
29	success - the cbfunc will not be called.			
30 31	 a PMIx error constant indicating either an error in the input or that the request was immediately processed and failed - the <i>cbfunc</i> will <i>not</i> be called. Required Attributes 			
32	The following attributes are required for PMIx libraries that support IO forwarding:			
33 34 35	<pre>PMIX_IOF_CACHE_SIZE "pmix.iof.csize" (uint32_t) The requested size of the PMIx server cache in bytes for each specified channel. By default, the server is allowed (but not required) to drop all bytes received beyond the max size.</pre>			
36 37	PMIX_IOF_DROP_OLDEST "pmix.iof.old" (bool) In an overflow situation, the PMIx server is to drop the oldest bytes to make room in the cache.			
38	<pre>PMIX_IOF_DROP_NEWEST "pmix.iof.new" (bool)</pre>			

1 In an overflow situation, the PMIx server is to drop any new bytes received until room becomes 2 available in the cache (default). ----- Optional Attributes 3 The following attributes are optional for PMIx libraries that support IO forwarding: 4 PMIX IOF BUFFERING SIZE "pmix.iof.bsize" (uint32_t) 5 Requests that IO on the specified channel(s) be aggregated in the PMIx tool library until the specified 6 number of bytes is collected to avoid being called every time a block of IO arrives. The PMIx tool 7 library will execute the callback and reset the collection counter whenever the specified number of 8 bytes becomes available. Any remaining buffered data will be flushed to the callback upon a call to 9 deregister the respective channel. 10 PMIX_IOF_BUFFERING_TIME "pmix.iof.btime" (uint32_t) 11 Max time in seconds to buffer IO before delivering it. Used in conjunction with buffering size, this 12 prevents IO from being held indefinitely while waiting for another payload to arrive. 13 PMIX_IOF_PUSH_STDIN "pmix.iof.stdin" (bool) 14 Requests that the PMIx library collect the **stdin** of the requester and forward it to the processes 15 specified in the PMIx_IOF_push call. All collected data is sent to the same targets until stdin is 16 closed, or a subsequent call to PMIx IOF push is made that includes the PMIX IOF COMPLETE 17 attribute indicating that forwarding of **stdin** is to be terminated. **Description** 18 Called either to: 19 20 • push data collected by the caller themselves (typically from **stdin** or a file) to **stdin** of the target 21 recipients; 22 • request that the PMIx library automatically collect and push the **stdin** of the caller to the target recipients; 23 24 • indicate that automatic collection and transmittal of **stdin** is to stop Advice to users – 25 Execution of the cbfunc callback function serves as notice that the PMIx library no longer requires the caller to 26 maintain the bo data object - it does not indicate delivery of the payload to the targets. Use of 27 PMIX_RANK_WILDCARD to specify all processes in a given namespace is supported but should be used 28 carefully due to bandwidth and memory footprint considerations.

CHAPTER 18

Storage Support Definitions (Provisional)

Distributed and parallel computing systems are increasingly embracing storage hierarchies to meet the diverse data management needs of applications and other systems software in a cost-effective manner. These hierarchies provide access to a number of distinct storage layers, with each potentially composed of different storage hardware (e.g., HDD, SSD, tape, PMEM), deployed at different locations (e.g., on-node, on-switch, on-site, WAN), and designed using different storage paradigms (e.g., file-based, object-based). Each of these systems offers unique performance and usage characteristics that storage system users should carefully consider to ensure the most efficient use of storage resources.

PMIx enables users to better understand storage hierarchies by defining attributes that formalize storage system characteristics, state, and other parameters. These attributes can be queried by applications, I/O libraries and middleware, and workflow systems to discover available storage resources and to inform on which resources are most suitable for different I/O workload requirements.

18.1 Storage support constants (Provisional)

The <code>pmix_storage_medium_t</code> (*Provisional*) is a <code>uint64_t</code> type that defines a set of bit-mask flags for specifying different types of storage mediums. These can be bitwise OR'd together to accommodate storage systems that mix storage medium types.

PMIX_STORAGE_MEDIUM_UNKNOWN (*Provisional*) The storage medium type is unknown.

PMIX STORAGE MEDIUM TAPE (*Provisional*) The storage system uses tape media.

PMIX_STORAGE_MEDIUM_HDD (Provisional)
The storage system uses HDDs with traditional SAS, SATA interfaces.

PMIX_STORAGE_MEDIUM_SSD (*Provisional*) The storage system uses SSDs with traditional SAS, SATA interfaces.

PMIX_STORAGE_MEDIUM_NVME (*Provisional*) The storage system uses SSDs with NVMe interface.

PMIX_STORAGE_MEDIUM_PMEM (*Provisional*) The storage system uses persistent memory.

PMIX_STORAGE_MEDIUM_RAM (*Provisional*) The storage system is volatile (e.g., tmpfs).

Advice to PMIx library implementers

PMIx implementations should maintain the same ordering for bit-mask values for <code>pmix_storage_medium_t</code> struct as provided in this standard, since these constants are ordered to provide semantic information that may be of use to PMIx users. Namely, <code>pmix_storage_medium_t</code> constants are ordered in terms of increasing medium bandwidth.

It is further recommended that implementations should try to allocate empty bits in the mask so that they can be extended to account for new constant definitions corresponding to new storage mediums.

36

37

PMIX_STORAGE_ACCESS_RDWR (Provisional)

operations.

Provide information on storage system read and write

18.2 Storage support attributes (Provisional)

	following attributes may be returned in response to queries (e.g., PMIx_Get or PMIx_Query_i.e. by processes or tools.
DMT	<pre>STORAGE_ID "pmix.strg.id" (char*) (Provisional)</pre>
_ 1111	An identifier for the storage system (e.g., lustre-fs1, daos-oss1, home-fs)
DMT	<pre>K_STORAGE_PATH "pmix.strg.path" (char*) (Provisional)</pre>
EMIZ	Mount point path for the storage system (valid only for file-based storage systems)
DMTS	<pre>C_STORAGE_TYPE "pmix.strg.type" (char*) (Provisional)</pre>
EMIZ	Type of storage system (i.e., "lustre", "gpfs", "daos", "ext4")
DMTS	STORAGE VERSION "pmix.strq.ver" (char*) (Provisional)
PMIX	Version string for the storage system
DMTS	
PMT2	K_STORAGE_MEDIUM "pmix.strg.medium" (pmix_storage_medium_t) (Provision_t) Three of storage mediums williged by the storage system (e.g., SSDs, HDDs, torage)
	Types of storage mediums utilized by the storage system (e.g., SSDs, HDDs, tape)
	K_STORAGE_ACCESSIBILITY
"pn	nix.strg.access" (pmix_storage_accessibility_t) (Provisional)
	Accessibility level of the storage system (e.g., within same node, within same session)
	<pre>K_STORAGE_PERSISTENCE "pmix.strg.persist" (pmix_storage_persistence)</pre>
(Prov	r <mark>isional)</mark>
	Persistence level of the storage system (e.g., sratch storage or achive storage)
PMIX	<pre>C_QUERY_STORAGE_LIST "pmix.strg.list" (char*) (Provisional)</pre>
	Comma-delimited list of storage identifiers (i.e., PMIX_STORAGE_ID types) for available stor
	systems
PMIX	<pre>C_STORAGE_CAPACITY_LIMIT "pmix.strg.caplim" (double) (Provisional)</pre>
	Overall limit on capacity (in bytes) for the storage system
PMIX	<pre>\(\text{STORAGE_CAPACITY_USED "pmix.strg.capuse" (double) (\(\text{Provisional} \) \)</pre>
	Overall used capacity (in bytes) for the storage system
PMIX	<pre>C_STORAGE_OBJECT_LIMIT "pmix.strg.objlim" (uint64_t) (Provisional)</pre>
	Overall limit on number of objects (e.g., inodes) for the storage system
PMI	<pre>K_STORAGE_OBJECTS_USED "pmix.strg.objuse" (uint64_t) (Provisional)</pre>
	Overall used number of objects (e.g., inodes) for the storage system
KIMG	<pre>K_STORAGE_MINIMAL_XFER_SIZE "pmix.strg.minxfer" (double) (Provisional)</pre>
	Minimal transfer size (in bytes) for the storage system - this is the storage system's atomic unit
	transfer (e.g., block size)
PMIX	<pre>\(\sum_STORAGE_SUGGESTED_XFER_SIZE "pmix.strg.sxfer" (double) (Provisional)</pre>
	Suggested transfer size (in bytes) for the storage system
PMIX	<pre>K_STORAGE_BW_MAX "pmix.strg.bwmax" (double) (Provisional)</pre>
	Maximum bandwidth (in bytes/sec) for storage system - provided as the theoretical maximum o
	maximum observed bandwidth value
рмтх	<pre>K_STORAGE_BW_CUR "pmix.strg.bwcur" (double) (Provisional)</pre>
	Observed bandwidth (in bytes/sec) for storage system - provided as a recently observed bandwidth
	value, with the exact measurement interval depending on the storage system and/or PMIx librar
	implementation
DMTY	STORAGE IOPS MAX "pmix.strg.iopsmax" (double) (Provisional)
	Maximum IOPS (in I/O operations per second) for storage system - provided as the theoretical
	maximum or the maximum observed IOPS value

1	PMIX_STORAGE_IOPS_CUR "p
2	Observed IOPS (in I/O opera
3	IOPS value, with the exact m
4	implementation
5	PMIX_STORAGE_ACCESS_TYPE
6	(Provisional)
7	Qualifier describing the type
8	PMIX_STORAGE_BW_CUR,
0	DMIN GMODACH GUGGHG

MIX_STORAGE_IOPS_CUR "pmix.strg.iopscur" (double) (Provisional)

Observed IOPS (in I/O operations per second) for storage system - provided as a recently observed IOPS value, with the exact measurement interval depending on the storage system and/or PMIx library implementation

PMIX_STORAGE_ACCESS_TYPE "pmix.strg.atype" (pmix_storage_access_type_t)
(Provisional)

Qualifier describing the type of storage access to return information for (e.g., for qualifying PMIX_STORAGE_BW_CUR, PMIX_STORAGE_IOPS_CUR, or PMIX_STORAGE_SUGGESTED_XFER_SIZE attributes)

APPENDIX A

Python Bindings

While the PMIx Standard is defined in terms of C-based APIs, there is no intent to limit the use of PMIx to that specific language. Support for other languages is captured in the Standard by describing their equivalent syntax for the PMIx APIs and native forms for the PMIx datatypes. This Appendix specifically deals with Python interfaces, beginning with a review of the PMIx datatypes. Support is restricted to Python 3 and above - i.e., the Python bindings do not support Python 2.

Note: the PMIx APIs have been loosely collected into three Python classes based on their PMIx "class" (i.e., client, server, and tool). All processes have access to a basic set of the APIs, and therefore those have been included in the "client" class. Servers can utilize any of those functions plus a set focused on operations not commonly executed by an application process. Finally, tools can also act as servers but have their own initialization function.

A.1 Design Considerations

Several issues arose during design of the Python bindings:

A.1.1 Error Codes vs Python Exceptions

The C programming language reports errors through the return of the corresponding integer status codes. PMIx has defined a range of negative values for this purpose. However, Python has the option of raising *exceptions* that effectively operate as interrupts that can be trapped if the program appropriately tests for them. The PMIx Python bindings opted to follow the C-based standard and return PMIx status codes in lieu of raising exceptions as this method was considered more consistent for those working in both domains.

A.1.2 Representation of Structured Data

PMIx utilizes a number of C-language structures to efficiently bundle related information. For example, the PMIx process identifier is represented as a struct containing a character array for the namespace and a 32-bit unsigned integer for the process rank. There are several options for translating such objects to Python – e.g., the PMIx process identifier could be represented as a two-element tuple (nspace, rank) or as a dictionary 'nspace': name, 'rank': 0. Exploration found no discernible benefit to either representation, nor was any clearly identifiable rationale developed that would lead a user to expect one versus the other for a given PMIx data type. Consistency in the translation (i.e., exclusively using tuple or dictionary) appeared to be the most important criterion. Hence, the decision was made to express all complex datatypes as Python dictionaries.

A.2 Datatype Definitions

PMIx defines a number of datatypes comprised of fixed-size character arrays, restricted range integers (e.g., uint32_t), and structures. Each datatype is represented by a named unsigned 16-bit integer (uint16_t) constant. Users are advised to use the named PMIx constants for indicating datatypes instead of integer values to ensure compatibility with future PMIx versions.

With only a few exceptions, the C-based PMIx datatypes defined in Chapter 3 on page 12 directly translate to Python. However, Python lacks the size-specific value definitions of C (e.g., uint8_t) and thus some care must be taken to protect against overflow/underflow situations when moving between the languages. Python bindings that accept values including PMIx datatypes shall therefore have the datatype and associated value checked for compatibility with their PMIx-defined equivalents, returning an error if:

- datatypes not defined by PMIx are encountered
- provided values fall outside the range of the C-equivalent definition e.g., if a value identified as
 PMIX_UINT8 lies outside the uint8_trange

Note that explicit labeling of PMIx data type, even when Python itself doesn't care, is often required for the Python bindings to know how to properly interpret and label the provided value when passing it to the PMIx library.

Table A.1 lists the correspondence between data types in the two languages.

ΑP
P
PI
[T]
Z
DIX
Ĕ.
\times
~
≻
P
\prec
TY
Η
$\overline{}$
\simeq
4
В
BIN
4
U
Ž
\Box
S

Table A.1.: C-to-Python Datatype Correspondence

C-Definition	PMIx Name	Python Definition	Notes
bool	PMIX_BOOL	boolean	
byte	PMIX_BYTE	A single element byte array (i.e., a byte array of length one)	
char*	PMIX_STRING	string	
size_t	PMIX_SIZE	integer	
pid_t	PMIX_PID	integer	value shall be limited to the uint32_t range
<pre>int, int8_t, int16_t, int32_t, int64_t</pre>	PMIX_INT, PMIX_INT8, PMIX_INT16, PMIX_INT32, PMIX_INT64	integer	value shall be limited to its corresponding range
uint, uint8_t, uint16_t, uint32_t, uint64_t	PMIX_UINT, PMIX_UINT8, PMIX_UINT16, PMIX_UINT32, PMIX_UINT64	integer	value shall be limited to its corresponding range
float, double	PMIX_FLOAT, PMIX_DOUBLE	float	value shall be limited to its corresponding range
struct timeval	PMIX_TIMEVAL	{'sec': sec, 'usec': microsec}	each field is an integer value
time_t	PMIX_TIME	integer	limited to positive values
pmix_data_type_t	PMIX_DATA_TYPE	integer	value shall be limited to the uint16_t range
pmix_status_t	PMIX_STATUS	integer	
pmix_key_t	N/A	string	The string's length shall be limited to one less than the size of the <code>pmix_key_t</code> array (to reserve space for the terminating <code>NULL</code>)
pmix_nspace_t	N/A	string	The string's length shall be limited to one less than the size of the <code>pmix_nspace_t</code> array (to reserve space for the terminating <code>NULL</code>)

Table A.1.: C-to-Python Datatype Correspondence

C-Definition	PMIx Name	Python Definition	Notes
pmix_rank_t	PMIX_PROC_RANK	integer	value shall be limited to the uint32_t range excepting the reserved values near UINT32_MAX
pmix_proc_t	PMIX_PROC	{'nspace': nspace, 'rank': rank}	nspace is a Python string and rank is an integer value. The nspace string's length shall be limited to one less than the size of the pmix_nspace_t array (to reserve space for the terminating NULL), and the rank value shall conform to the constraints associated with pmix_rank_t
pmix_byte_object_t	PMIX_BYTE_OBJECT	{'bytes': bytes, 'size': size}	bytes is a Python byte array and size is the integer number of bytes in that array.
pmix_persistence_t	PMIX_PERSISTENCE	integer	value shall be limited to the uint8_t range
pmix_scope_t	PMIX_SCOPE	integer	value shall be limited to the uint8_t range
pmix_data_range_t	PMIX_RANGE	integer	value shall be limited to the uint8_t range
pmix_proc_state_t	PMIX_PROC_STATE	integer	value shall be limited to the uint8_t range
pmix_proc_info_t	PMIX_PROC_INFO	{'proc': {'nspace': nspace, 'rank': rank}, 'hostname': hostname, 'executable': executable, 'pid': pid, 'exitcode': exitcode, 'state': state}	proc is a Python proc dictionary; hostname and executable are Python strings; and pid, exitcode, and state are Python integers

Python Definition C-Definition PMIx Name Notes *type* is the PMIx type of object in the array PMIX DATA ARRAY pmix data array t {'type': type, 'array': and array is a Python list containing the array } individual array elements. Note that array can consist of any PMIx types, including (for example) a Python **info** object that itself contains an array value list of integer values (defined in Section PMIX INFO DIRECTIVES pmix_info_directives_t list 3.2.10) value shall be limited to the uint8 t PMIX ALLOC DIRECTIVE pmix alloc directive t integer list of integer values (defined in Section PMIX_IOF_CHANNEL pmix iof channel t list 17.3.3) envar and value are Python strings, and {'envar': envar, PMIX ENVAR pmix_envar_t separator a single-character Python string 'value': value. 'separator': separator} type is the PMIx datatype of value, and PMIX VALUE pmix value t {'value': value, value is the associated value expressed 'val type': type} in the appropriate Python form for the specified datatype kev is a Python string **key**, flags is an PMIX INFO {'key': key, 'flags': pmix info t info directives value, type is flags, value': value, the PMIx datatype of *value*, and *value* 'val_type': type} is the associated value expressed in the appropriate Python form for the specified datatype *proc* is a Python **proc** dictionary; PMIX PDATA pmix pdata t {'proc': {'nspace': key is a Python string **key**; type is the nspace, 'rank': rank}, PMIx datatype of *value*; and *value* is 'key': key, 'value': the associated value expressed in the value, 'val_type': type} appropriate Python form for the specified datatype

Table A.1.: C-to-Python Datatype Correspondence

-		on Datatype Correspondenc	
C-Definition	PMIx Name	Python Definition	Notes
pmix_app_t	PMIX_APP	{'cmd': cmd, 'argv': [argv], 'env': [env], 'maxprocs': maxprocs, 'info': [info]}	cmd is a Python string; argv and env are Python lists containing Python strings; maxprocs is an integer; and info is a Python list of info values
pmix_query_t	PMIX_QUERY	{'keys': [keys], 'qualifiers': [info]}	keys is a Python list of Python strings, and qualifiers is a Python list of info values
pmix_regattr_t	PMIX_REGATTR	{'name': name, 'key': key, 'type': type, 'info': [info], 'description': [desc]}	name and string are Python strings; type is the PMIx datatype for the attribute's value; info is a Python list of info values; and description is a list of Python strings describing the attribute
pmix_job_state_t	PMIX_JOB_STATE	integer	value shall be limited to the uint8_t range
pmix_link_state_t	PMIX_LINK_STATE	integer	value shall be limited to the uint8_t range
pmix_cpuset_t	PMIX_PROC_CPUSET	{'source': source, 'cpus': bitmap}	source is a string name of the library that created the cpuset; and cpus is a list of string ranges identifying the PUs to which the process is bound (e.g., [1, 3-5, 7])
pmix_locality_t	PMIX_LOCTYPE	list	list of integer values (defined in Section 11.4.2.3) describing the relative locality of the specified local process
pmix_fabric_t	N/A	{'name': name, 'index': idx, 'info': [info]}	name is the string name assigned to the fabric; index is the integer ID assigned to the fabric; info is a list of info describing the fabric
pmix_endpoint_t	PMIX_ENDPOINT	{'uuid': uuid, 'osname': osname, endpt': endpt}	uuid is the string system-unique identifier assigned to the device; osname is the operating system name assigned to the device; endpt is a byteobject containing the endpoint information

C-Definition	PMIx Name	Python Definition	Notes
pmix_device_distance_t	PMIX_DEVICE_DIST	{'uuid': uuid, 'osname': osname, mindist': mindist, 'maxdist': maxdist}	uuid is the string system-unique identifier assigned to the device; osname is the operating system name assigned to the device; and mindist and maxdist are Python integers
pmix_coord_t	PMIX_COORD	{'view': view, 'coord': [coords]}	view is the pmix_coord_view_t of the coordinate; and coord is a list of integer coordinates, one for each dimension of the fabric
pmix_geometry_t	PMIX_GEOMETRY	{'fabric': idx, 'uuid': uuid, 'osname': osname, coordinates': [coords]}	fabric is the Python integer index of the fabric; uuid is the string system-unique identifier assigned to the device; osname is the operating system name assigned to the device; and coordinates is a list of coord containing the coordinates for the device across all views
pmix_device_type_t	PMIX_DEVTYPE	list	list of integer values (defined in Section 11.4.8)
pmix_bind_envelope_t	N/A	integer	one of the values defined in Section 11.4.4.1

Table A.1.: C-to-Python Datatype Correspondence

A.2.1 Example

Converting a C-based program to its Python equivalent requires translation of the relevant datatypes as well as use of the appropriate API form. An example small program may help illustrate the changes. Consider the following C-based program snippet:

```
#include <pmix.h>
...

pmix_info_t info[2];

PMIx_Info_load(&info[0], PMIX_PROGRAMMING_MODEL, "TEST", PMIX_STRING)

PMIx_Info_load(&info[1], PMIX_MODEL_LIBRARY_NAME, "PMIX", PMIX_STRING)

rc = PMIx_Init(&myproc, info, 2);

PMIX_INFO_DESTRUCT(&info[0]); // free the copied string

PMIX_INFO_DESTRUCT(&info[1]); // free the copied string
```

Moving to the Python version requires that the <code>pmix_info_t</code> be translated to the Python <code>info</code> equivalent, and that the returned information be captured in the return parameters as opposed to a pointer parameter in the function call, as shown below:

Python

Note the use of the **PMIX_STRING** identifier to ensure the Python bindings interpret the provided string value as a PMIx "string" and not an array of bytes.

A.3 Callback Function Definitions

A.3.1 IOF Delivery Function

Summary

Callback function for delivering forwarded IO to a process

I		LOI	Python —			
2		def	iofcbfunc(iofhdlr:integer, channel:bitarray, source:dict, payload:dict, info:list) Python			
4		IN	iofhdlr			
5			Registration number of the handler being invoked (integer)			
6		IN	Channel Dithon about a 1.16 hit hitemany identifying the channel the date arrived on (hitemany)			
7 8		IN	Python channel 16-bit bitarray identifying the channel the data arrived on (bitarray) source			
9		114	Python proc identifying the namespace/rank of the process that generated the data (dict)			
10		IN	payload			
11			Python byteobject containing the data (dict)			
12		IN	info			
13 14			List of Python info provided by the source containing metadata about the payload. This could include PMIX_IOF_COMPLETE (list)			
15		Retu	rns: nothing			
16		See	pmix_iof_cbfunc_t for details			
17	A.3.2	Event Handler				
18 19		Summary Callback function for event handlers				
20	PMIx v4.0	Format Python				
21		def	evhandler(evhdlr:integer, status:integer,			
22			source:dict, info:list, results:list)			
			Python			
23		IN	iofhdlr			
24			Registration number of the handler being invoked (integer)			
25		IN	status			
26			Status associated with the operation (integer)			
27		IN	source			
28			Python proc identifying the namespace/rank of the process that generated the event (dict)			
29		IN	info			
30			List of Python info provided by the source containing metadata about the event (list)			
31 32		IN	results List of Duthon in 60 containing the appropriate results of all raise other days (list)			
32			List of Python info containing the aggregated results of all prior evhandlers (list)			
33		Returns:				
34		• rc - Status returned by the event handler's operation (integer)				
35		• results - List of Python info containing results from this event handler's operation on the event (list)				
36		See	pmix_notification_fn_t for details			

A.3.3 Server Module Functions 1 2 The following definitions represent functions that may be provided to the PMIx server library at time of 3 initialization for servicing of client requests. Module functions that are not provided default to returning "not 4 supported" to the caller. A.3.3.1 Client Connected 5 6 Summary 7 Notify the host server that a client connected to this server. 8 _{PMIx v4.0} ——— Python ————— 9 def clientconnected2(proc:dict is not None, info:list) _____ Python _____ 10 IN 11 Python **proc** identifying the namespace/rank of the process that connected (dict) 12 IN info 13 list of Python **info** containing information about the process (list) 14 Returns: • rc - PMIX_SUCCESS or a PMIx error code indicating the connection should be rejected (integer) 15 16 See pmix_server_client_connected2_fn_t for details A.3.3.2 Client Finalized 17 18 Summary 19 Notify the host environment that a client called **PMIx_Finalize**. 20 _{PMIx v4.0} Python — 21 def clientfinalized(proc:dict is not None): Python — 22 IN 23 Python proc identifying the namespace/rank of the process that finalized (dict) 24 Returns: nothing 25 See pmix server client finalized fn t for details

A.3.3.3 Client Aborted

27 Summary

Notify the host environment that a local client called **PMIx Abort**.

26

1		For	mat	Python
2		def	clientaborted(args:dict is no	Python —
3 4		IN	args Python dictionary containing:	
5			• 'caller': Python proc identifying the n	amespace/rank of the process calling abort (dict)
6			• 'status': PMIx status to be returned on e	exit (integer)
7			• 'msg': Optional string message to be pr	inted (string)
8 9			• 'targets': Optional list of Python proc (list)	identifying the namespace/rank of the processes to be aborted
0		Retu	rns:	
11		• <i>rc</i>	- PMIX_SUCCESS or a PMIx error code in	adicating the operation failed (integer)
12		See r	omix_server_abort_fn_t for details	
13	A.3.3.4	Fe	ence	
14 15			nmary ast one client called either PMIx_Fence o	rPMIx_Fence_nb
6 PMIx v4.0 Format		mat	Python —	
17		def	fence(args:dict is not None)	Python
18 19		IN	args Python dictionary containing:	
20			• 'procs': List of Python proc identifyin	g the namespace/rank of the participating processes (list)
21			• 'directives': Optional list of Python int	containing directives controlling the operation (list)
22			• 'data': Optional Python bytearray of dat	a to be circulated during fence operation (bytearray)
23		Retu	rns:	
24		• <i>rc</i>	- PMIX_SUCCESS or a PMIx error code in	adicating the operation failed (integer)
25		 da 	tta - Python bytearray containing the aggreg	ated data from all participants (bytearray)
26		See r	omix_server_fencenb_fn_t for deta	ils
27	A.3.3.5	Di	rect Modex	
28 29 30		Used	nmary by the PMIx server to request its local host fied proc to obtain and return a direct mode	contact the PMIx server on the remote node that hosts the x blob for that proc.

1	Format Python —
2	<pre>def dmodex(args:dict is not None)</pre>
_	Python —
3 4	IN args Python dictionary containing:
5	• 'proc': Python proc of process whose data is being requested (dict)
6	• 'directives': Optional list of Python info containing directives controlling the operation (list)
7	Returns:
8	• <i>rc</i> - PMIX_SUCCESS or a PMIx error code indicating the operation failed (integer)
9	• data - Python bytearray containing the data for the specified process (bytearray)
10	See pmix_server_dmodex_req_fn_t for details
11 A.3.3.6	6 Publish
12 13	Summary Publish data per the PMIx API specification.
14 _{PMIx v4.0}	Format Python —
15	def publish(args:dict is not None) Python
16 17	IN args Python dictionary containing:
18	• 'proc': Python proc dictionary of process publishing the data (dict)
19	• 'directives': List of Python info containing data and directives (list)
20	Returns:
21	• rc - PMIX_SUCCESS or a PMIx error code indicating the operation failed (integer)
22	See pmix_server_publish_fn_t for details
23 A.3.3.7	' Lookup
24 25	Summary Lookup published data.

1		Format	Python —
2		def lookup(args:dict is not None)
		_	Python —
3 4		IN args Python dictionary containing:	
5		• 'proc': Python proc of process seeking	g the data (dict)
6		• 'keys': List of Python strings (list)	
7		• 'directives': Optional list of Python in	fo containing directives (list)
8		Returns:	
9		• <i>rc</i> - PMIX_SUCCESS or a PMIx error code i	ndicating the operation failed (integer)
10		• pdata - List of pdata containing the returne	d results (list)
11		See pmix_server_lookup_fn_t for detail	s
12	A.3.3.8	Unpublish	
13 14		Summary Delete data from the data store.	
15	PMIx v4.0	Format	Python —
16		def unpublish(args:dict is not N	one) Python
17 18		IN args Python dictionary containing:	
19		• 'proc': Python proc of process unpub	lishing data (dict)
20		• 'keys': List of Python strings (list)	
21		• 'directives': Optional list of Python in	fo containing directives (list)
22		Returns:	
23		• <i>rc</i> - PMIX_SUCCESS or a PMIx error code i	ndicating the operation failed (integer)
24		See pmix_server_unpublish_fn_t for o	letails
25	A.3.3.9	Spawn	
26 27		Summary Spawn a set of applications/processes as per the	PMIx_Spawn API.

1	Format Python —
2	def spawn(args:dict is not None) Python
3 4	IN args Python dictionary containing:
5	• 'proc': Python proc of process making the request (dict)
6	• 'jobinfo': Optional list of Python info job-level directives and information (list)
7	• 'apps': List of Python app describing applications to be spawned (list)
8	Returns:
9	• rc - PMIX_SUCCESS or a PMIx error code indicating the operation failed (integer)
10	• nspace - Python string containing namespace of the spawned job (str)
11	See pmix_server_spawn_fn_t for details
12 A.3.3.1 0	Connect
13 14	Summary Record the specified processes as <i>connected</i> .
15 _{PMIx v4.0}	Format Python
16	def connect(args:dict is not None) Python
17 18	IN args Python dictionary containing:
19	• 'procs': List of Python proc identifying the namespace/rank of the participating processes (list)
20	• 'directives': Optional list of Python info containing directives controlling the operation (list)
21	Returns:
22	• rc - PMIX_SUCCESS or a PMIx error code indicating the operation failed (integer)
23	See pmix_server_connect_fn_t for details
24 A.3.3.1 1	Disconnect
25 26	Summary Disconnect a previously connected set of processes.

1		For	mat	– Python ————————————————————————————————————	_
2			disconnect(args:dict is not	None)	•
3 4		IN	args Python dictionary containing:		
5			• 'procs': List of Python proc identifying	ring the namespace/rank of the participating processes (list)	
6			• 'directives': Optional list of Python in	nfo containing directives controlling the operation (list)	
7		Retur	rns:		
8		• <i>rc</i>	- PMIX_SUCCESS or a PMIx error code	e indicating the operation failed (integer)	
9		See r	omix_server_disconnect_fn_t fo	or details	
10	A.3.3.12	2 F	Register Events		
11 12			nmary ster to receive notifications for the specifie	ed events.	
13	PMIx v4.0	For	mat	– Python –	_
14			register_events(args:dict is		•
15 16		IN	args Python dictionary containing:		
17			• 'codes': List of Python integers (list)		
18			• 'directives': Optional list of Python in	nfo containing directives controlling the operation (list)	
19		Retur	ms:		
20		• <i>rc</i>	- PMIX_SUCCESS or a PMIx error code	e indicating the operation failed (integer)	
21		See r	omix_server_register_events_f	fn_t for details	
22	A.3.3.13	3 D	Peregister Events		
23 24		Sun	nmary gister to receive notifications for the specif	ified events.	

1	Format Python —
2	def deregister_events(args:dict is not None) Python
3 4	IN args Python dictionary containing:
5	• 'codes': List of Python integers (list)
6	Returns:
7	• rc - PMIX_SUCCESS or a PMIx error code indicating the operation failed (integer)
8	See pmix_server_deregister_events_fn_t for details
9 A.3.3. 1	14 Notify Event
10 11	Summary Notify the specified range of processes of an event.
12 _{PMIx v4.0}	Format Python —
13	def notify_event(args:dict is not None) Python
14 15	IN args Python dictionary containing:
16	• 'code': Python integer pmix_status_t (integer)
17	• 'source': Python proc of process that generated the event (dict)
18	• 'range': Python range in which the event is to be reported (integer)
19	• 'directives': Optional list of Python info directives (list)
20	Returns:
21	• rc - PMIX_SUCCESS or a PMIx error code indicating the operation failed (integer)
22	See pmix_server_notify_event_fn_t for details
23 A.3.3. 1	15 Query
24 25	Summary Ouery information from the resource manager

1		Format	- Python —
2		def query(args:dict is not None)	- Python —
3 4		IN args Python dictionary containing:	
5		• 'source': Python proc of requesting p	process (dict)
6		• 'queries': List of Python query direc	tives (list)
7		Returns:	
8		\bullet rc - PMIX_SUCCESS or a PMIx error code	indicating the operation failed (integer)
9		• <i>info</i> - List of Python info containing the re	turned results (list)
10		See pmix_server_query_fn_t for detail.	S
11	A.3.3.10	6 Tool Connected	
12 13		Summary Register that a tool has connected to the server.	
14	PMIx v4.0	Format	- Python —
15		<pre>def tool_connected(args:dict is</pre>	not None) - Python —
16 17		IN args Python dictionary containing:	
18		• 'directives': Optional list of Python in	nfo info on the connecting tool (list)
19		Returns:	
20		• <i>rc</i> - PMIX_SUCCESS or a PMIx error code	indicating the operation failed (integer)
21		• proc - Python proc containing the assigned	namespace:rank for the tool (dict)
22		See pmix_server_tool_connection_f	En_t for details
23	A.3.3.1	7 Log	
24 25		Summary Log data on behalf of a client.	

1	Python —
2	def log(args:dict is not None)
	Python —
3 4	IN args Python dictionary containing:
5	• 'source': Python proc of requesting process (dict)
6	• 'data': Optional list of Python info containing data to be logged (list)
7	• 'directives': Optional list of Python info containing directives (list)
8	Returns:
9	• rc - PMIX_SUCCESS or a PMIx error code indicating the operation failed (integer)
10	See pmix_server_log_fn_t for details.
11 A.3.3.	18 Allocate Resources
12 13	Summary Request allocation operations on behalf of a client.
14 <i>PMIx v4.0</i>	Format Python —
15	def allocate(args:dict is not None) Python
16 17	IN args Python dictionary containing:
18	• 'source': Python proc of requesting process (dict)
19	• 'action': Python allocdir specifying requested action (integer)
20	• 'directives': Optional list of Python info containing directives (list)
21	Returns:
22	• rc - PMIX_SUCCESS or a PMIx error code indicating the operation failed (integer)
23	• refarginfo - List of Python info containing results of requested operation (list)
24	See <pre>pmix_server_alloc_fn_t</pre> for details.
25 A.3.3.	19 Job Control
26 27	Summary Execute a job control action on behalf of a client.

1		Format	- Python
2		<pre>def job_control(args:dict is no</pre>	t None) - Python -
3		IN args Python dictionary containing:	
5		• 'source': Python proc of requesting p	process (dict)
6		• 'targets': List of Python proc specify	ring target processes (list)
7		• 'directives': Optional list of Python in	nfo containing directives (list)
8		Returns:	
9		• rc - PMIX_SUCCESS or a PMIx error code	indicating the operation failed (integer)
0		See pmix_server_job_control_fn_t	for details.
11	A.3.3.20	0 Monitor	
12		Summary Request that a client be monitored for activity.	
14	PMIx v4.0	Format	- Python -
15		def monitor(args:dict is not No	
16 17		IN args Python dictionary containing:	
8		• 'source': Python proc of requesting p	process (dict)
19		• 'monitor': Python info attribute indi	icating the type of monitor being requested (dict)
20 21		 'error': Status code to be used when g monitor has been triggered. 	generating an event notification (integer) alerting that the
22		• 'directives': Optional list of Python in	nfo containing directives (list)
23		Returns:	
24		• rc - PMIX_SUCCESS or a PMIx error code	indicating the operation failed (integer)
25		See pmix_server_monitor_fn_t for de	tails.
26	A.3.3.2	1 Get Credential	
27 28		Summary Request a credential from the host environment	t.

Python def get_credential(args:dict is not None) Python Python	
3 IN args 4 Python dictionary containing:	
• 'source': Python proc of requesting process (dict)	
• 'directives': Optional list of Python info containing	directives (list)
7 Returns:	
8 • rc - PMIX_SUCCESS or a PMIx error code indicating the o	operation failed (integer)
• cred - Python byteobject containing returned credential	ıl (dict)
• info - List of Python info containing any additional info a	bout the credential (list)
See pmix_server_get_cred_fn_t for details.	
2 A.3.3.22 Validate Credential	
Summary Request validation of a credential	
Format Python	
def validate_credential(args:dict is not be represented by the position of the	None)
7 IN args 18 Python dictionary containing:	
• 'source': Python proc of requesting process (dict)	
• 'credential': Python byteobject containing credential	ntial (dict)
• 'directives': Optional list of Python info containing	directives (list)
Returns:	
• rc - PMIX_SUCCESS or a PMIx error code indicating the c	operation failed (integer)
• info - List of Python info containing any additional info fr	rom the credential (list)
See pmix_server_validate_cred_fn_t for details.	
26 A.3.3.23 IO Forward	
Summary Request the specified IO channels be forwarded from the given	n array of processes.

1		Format Python —	
2		def iof_pull(args:dict is not None) Python	
3		IN args Python dictionary containing:	
5		• 'sources': List of Python proc of processes whose IO is being requested (list)	
6		• 'channels': Bitmask of Python channel identifying IO channels to be forwarded	(integer)
7		• 'directives': Optional list of Python info containing directives (list)	
8		Returns:	
9		\bullet rc - PMIX_SUCCESS or a PMIx error code indicating the operation failed (integer)	
10		See pmix_server_iof_fn_t for details.	
11	A.3.3.2	l IO Push	
12 13		Summary Pass standard input data to the host environment for transmission to specified recipients.	
14	PMIx v4.0	Format Python —	—
15		<pre>def iof_push(args:dict is not None)</pre>	
16 17		IN args Python dictionary containing:	
18		• 'source': Python proc of process whose input is being forwarded (dict)	
19		• 'payload': Python byteobject containing input bytes (dict)	
20		• 'targets': List of proc of processes that are to receive the payload (list)	
21		• 'directives': Optional list of Python info containing directives (list)	
22		Returns:	
23		• rc - PMIX_SUCCESS or a PMIx error code indicating the operation failed (integer)	
24		See pmix_server_stdin_fn_t for details.	
25	A.3.3.2	Group Operations	
26 27		Summary Request group operations (construct, destruct, etc.) on behalf of a set of processes.	

1	Format Python
2	def group(args:dict is not None) Python
3 4	IN args Python dictionary containing:
5	• 'op': Operation host is to perform on the specified group (integer)
6	• 'group': String identifier of target group (str)
7	• 'procs': List of Python proc of participating processes (dict)
8	• 'directives': Optional list of Python info containing directives (list)
9	Returns:
10	• rc - PMIX_SUCCESS or a PMIx error code indicating the operation failed (integer)
11	• refarginfo - List of Python info containing results of requested operation (list)
12	See pmix_server_grp_fn_t for details.
13 A.3.3.2 6	6 Fabric Operations
14 15	Summary Request fabric-related operations (e.g., information on a fabric) on behalf of a tool or other process.
16 _{PMIx v4.0}	Format Python
17	def fabric(args:dict is not None) Python
18 19	IN args Python dictionary containing:
20	• 'source': Python proc of requesting process (dict)
21	• 'index': Identifier of the fabric being operated upon (integer)
22	• 'op': Operation host is to perform on the specified fabric (integer)
23	• 'directives': Optional list of Python info containing directives (list)
24	Returns:
25	• rc - PMIX_SUCCESS or a PMIx error code indicating the operation failed (integer)
26	• refarginfo - List of Python info containing results of requested operation (list)
27	See pmix_server_fabric_fn_t for details.

A.4 PMIxClient 1 2 The client Python class is by far the richest in terms of APIs as it houses all the APIs that an application might 3 utilize. Due to the datatype translation requirements of the C-Python interface, only the blocking form of each 4 API is supported – providing a Python callback function directly to the C interface underlying the bindings 5 was not a supportable option. A.4.1 Client.init 6 7 Summary 8 Initialize the PMIx client library after obtaining a new PMIxClient object. Python PMIx v4.0 10 rc, proc = myclient.init(info:list) Python info 11 12 List of Python **info** dictionaries (list) 13 Returns: 14 • rc - PMIX_SUCCESS or a negative value corresponding to a PMIx error constant (integer) • proc - a Python proc dictionary (dict) 15 See PMIx Init for description of all relevant attributes and behaviors. 16 Client.initialized A.4.2 17 Format 18 Python PMIx v4.0 19 rc = myclient.initialized() Python — 20 Returns: 21 • rc - a value of 1 (true) will be returned if the PMIx library has been initialized, and 0 (false) otherwise 22 (integer) 23 See PMIx_Initialized for description of all relevant attributes and behaviors. A.4.3 Client.get version 24 25 Format ———— Python ————— PMIx v4.0 26 vers = myclient.get_version() Python — 27 Returns:

See PMIx_Get_version for description of all relevant attributes and behaviors.

• vers - Python string containing the version of the PMIx library (e.g., "3.1.4") (integer)

28

A.4.4 Client.finalize

```
2
              Summary
              Finalize the PMIx client library.
 3
                       Python —
              Format
 4 PMIx v4.0
 5
              rc = myclient.finalize(info:list)
                                                   Python —
                  info
 6
              IN
 7
                   List of Python info dictionaries (list)
 8
              Returns:
 9
              • rc - PMIX SUCCESS or a negative value corresponding to a PMIx error constant (integer)
10
              See PMIx_Finalize for description of all relevant attributes and behaviors.
     A.4.5 Client.abort
11
              Summary
12
13
              Request that the provided list of processes be aborted.
14 PMIx v4.0
                                          ——— Python ——————
15
              rc = myclient.abort(status:integer, msg:str, targets:list)
                                                 - Python ———
16
              IN
                   status
17
                   PMIx status to be returned on exit (integer)
18
                   String message to be printed (string)
19
20
              IN
                  targets
21
                   List of Python proc dictionaries (list)
22
              Returns:
              • rc - PMIX_SUCCESS or a negative value corresponding to a PMIx error constant (integer)
23
24
              See PMIx_Abort for description of all relevant attributes and behaviors.
     A.4.6 Client.store internal
25
              Summary
26
27
              Store some data locally for retrieval by other areas of the process
```

```
Format
 1
                                   ______ Python ______
               rc = myclient.store_internal(proc:dict, key:str, value:dict)
 2
                                                       Python -
 3
               IN
                   proc
 4
                    Python proc dictionary of the process being referenced (dict)
 5
 6
                    String key of the data (string)
 7
               IN
                    value
 8
                    Python value dictionary (dict)
 9
               Returns:
10
               • rc - PMIX SUCCESS or a negative value corresponding to a PMIx error constant (integer)
11
               See PMIx Store internal for details.
     A.4.7 Client.put
12
13
               Summary
14
               Push a key/value pair into the client's namespace.
15
               Format
                                                     - Python -----
    PMIx v4.0
16
               rc = myclient.put(scope:integer, key:str, value:dict)
                                                       Python -
17
                    scope
                    Scope of the data being posted (integer)
18
19
               IN
                    String key of the data (string)
20
21
                    value
22
                    Python value dictionary (dict)
23
               Returns:
               • rc - PMIX_SUCCESS or a negative value corresponding to a PMIx error constant (integer)
24
25
               See PMIx_Put for description of all relevant attributes and behaviors.
     A.4.8 Client.commit
26
               Summary
27
28
               Push all previously PMIxClient.put values to the local PMIx server.
```

1		Format Python —
2		rc = myclient.commit() Python
3		Returns:
4		• rc - PMIX_SUCCESS or a negative value corresponding to a PMIx error constant (integer)
5		See PMIx_Commit for description of all relevant attributes and behaviors.
6	A.4.9	Client.fence
7 8		Summary Execute a blocking barrier across the processes identified in the specified list.
9 _P	PMIx v4.0	Format Python —
10		rc = myclient.fence(peers:list, directives:list) Python
11		IN peers
12 13		List of Python proc dictionaries (list) IN directives
14		List of Python info dictionaries (list)
15		Returns:
16		• rc - PMIX_SUCCESS or a negative value corresponding to a PMIx error constant (integer)
17		See PMIx_Fence for description of all relevant attributes and behaviors.
18	A.4.10	Client.get
19		Summary
20		Retrieve a key/value pair.
21 _P	PMIx v4.0	Format

```
_____ Python _____
1
              rc, val = myclient.get(proc:dict, key:str, directives:list)
              Python —
2
              IN
                 proc
 3
                  Python proc whose data is being requested (dict)
4
 5
                  Python string key of the data to be returned (str)
6
              IN
                  directives
                  List of Python info dictionaries (list)
8
              Returns:
9
              • rc - PMIX SUCCESS or a negative value corresponding to a PMIx error constant (integer)
              • val - Python value containing the returned data (dict)
10
              See PMIx Get for description of all relevant attributes and behaviors.
11
    A.4.11
               Client.publish
12
13
              Summary
14
              Publish data for later access via PMIx_Lookup.
              Format
15
                             Python —
   PMIx v4.0
              rc = myclient.publish(directives:list)
16
              Python -
17
                 directives
                  List of Python info dictionaries containing data to be published and directives (list)
18
19
              Returns:
              • rc - PMIX_SUCCESS or a negative value corresponding to a PMIx error constant (integer)
20
              See PMIx_Publish for description of all relevant attributes and behaviors.
21
    A.4.12 Client.lookup
22
23
              Summary
24
              Lookup information published by this or another process with PMIx Publish.
```

```
Format
 1
                                 ______ Python _____
               rc,info = myclient.lookup(pdata:list, directives:list)
 2
                                                      Python
3
               IN
                   pdata
                    List of Python pdata dictionaries identifying data to be retrieved (list)
 4
 5
                    directives
6
                    List of Python info dictionaries (list)
 7
               Returns:
8
               • rc - PMIX_SUCCESS or a negative value corresponding to a PMIx error constant (integer)
9
               • info - Python list of info containing the returned data (list)
10
               See PMIx_Lookup for description of all relevant attributes and behaviors.
     A.4.13 Client.unpublish
11
               Summary
12
13
               Delete data published by this process with PMIx Publish.
               Format
14 PMIx v4.0
                                      ———— Python —————
15
               rc = myclient.unpublish(keys:list, directives:list)
                                                      Python
16
               IN
                   keys
17
                    List of Python string keys identifying data to be deleted (list)
18
                    directives
19
                    List of Python info dictionaries (list)
20
               Returns:
21
               • rc - PMIX SUCCESS or a negative value corresponding to a PMIx error constant (integer)
22
               See PMIx_Unpublish for description of all relevant attributes and behaviors.
     A.4.14 Client.spawn
23
24
               Summary
25
               Spawn a new job.
```

```
Format
1
                                    ______ Python ______
 2
              rc,nspace = myclient.spawn(jobinfo:list, apps:list)
                                                    Pvthon -
3
              IN
                   iobinfo
                   List of Python info dictionaries (list)
 4
 5
              IN
6
                   List of Python app dictionaries (list)
 7
              Returns:
8
              • rc - PMIX_SUCCESS or a negative value corresponding to a PMIx error constant (integer)
9
              • nspace - Python nspace of the new job (dict)
10
              See PMIx_Spawn for description of all relevant attributes and behaviors.
     A.4.15 Client.connect
11
              Summary
12
13
              Connect namespaces.
              Format
                                     _____ Python _____
    PMIx v4.0
15
              rc = myclient.connect(peers:list, directives:list)
                                                     Python ———
16
              IN
                   peers
17
                   List of Python proc dictionaries (list)
18
                   directives
19
                   List of Python info dictionaries (list)
20
              Returns:
21
              • rc - PMIX SUCCESS or a negative value corresponding to a PMIx error constant (integer)
22
              See PMIx_Connect for description of all relevant attributes and behaviors.
     A.4.16 Client.disconnect
23
24
              Summary
25
              Disconnect namespaces.
```

```
Format
                                 Python —
 1
 2
               rc = myclient.disconnect(peers:list, directives:list)

    Pvthon

 3
               IN
                   peers
                   List of Python proc dictionaries (list)
 4
 5
                   directives
 6
                    List of Python info dictionaries (list)
               Returns:
 8
               • rc - PMIX_SUCCESS or a negative value corresponding to a PMIx error constant (integer)
 9
               See PMIx_Disconnect for description of all relevant attributes and behaviors.
     A.4.17
                 Client.resolve peers
10
               Summary
11
12
               Return list of processes within the specified nspace on the given node.
13 <sub>PMIx v4.0</sub>
               Format
                                      ______ Python ______
14
               rc,procs = myclient.resolve_peers(node:str, nspace:str)
                                ———— Python
15
               IN
                   node
16
                    Name of node whose processes are being requested (str)
17
                    Python nspace whose processes are to be returned (str)
18
19
               Returns:
20
               • rc - PMIX_SUCCESS or a negative value corresponding to a PMIx error constant (integer)
21
               • procs - List of Python proc dictionaries (list)
22
               See PMIx_Resolve_peers for description of all relevant attributes and behaviors.
     A.4.18 Client.resolve nodes
23
24
               Summary
25
               Return list of nodes hosting processes within the specified nspace.
```

1		Format	Python
2		rc,nodes = myclient.resolve_nodes	Python —
3 4		IN nspace Python nspace (str)	
5		Returns:	
6		• rc - PMIX_SUCCESS or a negative value corn	responding to a PMIx error constant (integer)
7		• nodes - List of Python string node names (list)	
8		See PMIx_Resolve_nodes for description of	f all relevant attributes and behaviors.
9	A .4.19	Client.query	
10 11		Summary Query information about the system in general.	
12	PMIx v4.0	Format	Python —
13		rc,info = myclient.query(queries:	Python —
14 15		IN queries List of Python query dictionaries (list)	
16		Returns:	
17		• rc - PMIX_SUCCESS or a negative value corn	responding to a PMIx error constant (integer)
18		• <i>info</i> - List of Python info containing results	of the query (list)
19		See PMIx_Query_info for description of all	relevant attributes and behaviors.
20	A.4.20	Client.log	
21 22		Summary Log data to a central data service/store.	

```
Format
 1
                                ______ Python ______
 2
               rc = myclient.log(data:list, directives:list)
                                                    Pvthon -
 3
               IN
                  data
 4
                    List of Python info (list)
 5
                   directives
                    Optional list of Python info (list)
 6
               Returns:
 8
               • rc - PMIX_SUCCESS or a negative value corresponding to a PMIx error constant (integer)
 9
               See PMIx_Log for description of all relevant attributes and behaviors.
     A.4.21
                 Client.allocation request
10
               Summary
11
12
               Request an allocation operation from the host resource manager.
13 <sub>PMIx v4.0</sub>
               Format
                                     Python —
14
               rc,info = myclient.allocation_request(request:integer, directives:list)
                                                    - Pvthon -
15
               IN
                   request
16
                    Python allocdir specifying requested operation (integer)
17
                   directives
                    List of Python info describing request (list)
18
19
               Returns:
20
               • rc - PMIX_SUCCESS or a negative value corresponding to a PMIx error constant (integer)
21
               • info - List of Python info containing results of the request (list)
               See PMIx_Allocation_request for description of all relevant attributes and behaviors.
22
     A.4.22 Client.job ctrl
23
24
               Summary
25
               Request a job control action.
```

1		Format Python
2		rc,info = myclient.job_ctrl(targets:list, directives:list) Python
3 4 5 6		<pre>IN targets List of Python proc specifying targets of requested operation (integer) IN directives List of Python info describing operation to be performed (list)</pre>
7		Returns:
8		• rc - PMIX_SUCCESS or a negative value corresponding to a PMIx error constant (integer)
9		• info - List of Python info containing results of the request (list)
10		See PMIx_Job_control for description of all relevant attributes and behaviors.
11	A.4.23	Client.monitor
12 13		Summary Request that something be monitored.
14	PMIx v4.0	Format Python
15		<pre>rc,info = myclient.monitor(monitor:dict, error_code:integer, directives:list)</pre>
16 17		<pre>IN monitor Python info specifying specifying the type of monitor being requested (dict)</pre>
18 19 20		IN error_code Status code to be used when generating an event notification alerting that the monitor has been triggered (integer)
21 22		IN directives List of Python info describing request (list)
23		Returns:
24		• rc - PMIX_SUCCESS or a negative value corresponding to a PMIx error constant (integer)
25		• info - List of Python info containing results of the request (list)
26		See PMIx_Process_monitor for description of all relevant attributes and behaviors.
27	A.4.24	Client.get_credential
28 29		Summary Request a credential from the PMIx server/SMS.

```
Format
 1
                                 ______ Python _____
 2
               rc,cred = myclient.get_credential(directives:list)
                                                      Python
 3
               IN
                   directives
                    Optional list of Python info describing request (list)
 5
               Returns:
 6
               • rc - PMIX_SUCCESS or a negative value corresponding to a PMIx error constant (integer)
 7
               • cred - Python byteobject containing returned credential (dict)
 8
               See PMIx Get credential for description of all relevant attributes and behaviors.
     A.4.25
               Client.validate_credential
 9
               Summary
10
               Request validation of a credential by the PMIx server/SMS.
11
               Format
12 <sub>PMIx v4.0</sub>
                                                      Python —
13
               rc,info = myclient.validate_credential(cred:dict, directives:list)
                                                      Python ——
               IN
14
                    cred
15
                    Python byteobject containing credential (dict)
16
               IN
                    directives
17
                    Optional list of Python info describing request (list)
18
               Returns:
               • rc - PMIX_SUCCESS or a negative value corresponding to a PMIx error constant (integer)
19
20
               • info - List of Python info containing additional results of the request (list)
21
               See PMIx Validate credential for description of all relevant attributes and behaviors.
     A.4.26 Client.group_construct
22
               Summary
23
```

Construct a new group composed of the specified processes and identified with the provided group identifier.

460

1		Format Python —
2 3		rc,info = myclient.construct_group(grp:string,
4 5 6 7 8 9		IN grp Python string identifier for the group (str) IN members List of Python proc dictionaries identifying group members (list) IN directives Optional list of Python info describing request (list)
10		Returns:
11 12		 rc - PMIX_SUCCESS or a negative value corresponding to a PMIx error constant (integer) info - List of Python info containing results of the request (list)
13		See PMIx_Group_construct for description of all relevant attributes and behaviors.
14	A.4.27	Client.group_invite
15 16		Summary Explicitly invite specified processes to join a group.
17	PMIx v4.0	Format Python
17 18 19	PMIx v4.0	<pre>Format</pre>
18	PMIx v4.0	rc,info = myclient.group_invite(grp:string,
18 19 20 21 22 23 24	PMIx v4.0	rc, info = myclient.group_invite(grp:string,
18 19 20 21 22 23 24 25	PMIx v4.0	rc, info = myclient.group_invite(grp:string,
18 19 20 21 22 23 24 25 26	PMIx v4.0	rc, info = myclient.group_invite(grp:string,
18 19 20 21 22 23 24 25 26 27	PMIx v4.0	rc, info = myclient.group_invite(grp:string,
18 19 20 21 22 23 24 25 26 27	PMIx v4.0	rc, info = myclient.group_invite(grp:string,

```
Format
 1
                              ______ Pvthon _____
 2
              rc,info = myclient.group_join(grp:string,
 3
                                          leader:dict, opt:integer,
 4
                                          directives:list)
                                           ——— Python ————
 5
              IN
 6
                   Python string identifier for the group (str)
 7
                   leader
 8
                   Python proc dictionary identifying process leading the group (dict)
 9
              IN
                   One of the pmix_group_opt_t values indicating decline/accept (integer)
10
              IN
11
                   directives
                   Optional list of Python info describing request (list)
12
13
              Returns:
14
              • rc - PMIX SUCCESS or a negative value corresponding to a PMIx error constant (integer)
15
              • info - List of Python info containing results of the request (list)
16
              See PMIx_Group_join for description of all relevant attributes and behaviors.
     A.4.29 Client.group leave
17
              Summary
18
19
              Leave a PMIx Group.
20_{\ PMIx\ v4.0}
              Format
                                       Python —
21
              rc = myclient.group_leave(grp:string, directives:list)
                                                    Python ———
22
              IN
                   grp
23
                   Python string identifier for the group (str)
24
                   directives
                   Optional list of Python info describing request (list)
25
26
              Returns:
27
              • rc - PMIX_SUCCESS or a negative value corresponding to a PMIx error constant (integer)
28
              See PMIx Group leave for description of all relevant attributes and behaviors.
     A.4.30 Client.group destruct
29
30
              Summary
31
              Destruct a PMIx Group.
```

```
Format
                                   _____ Python _____
 1
               rc = myclient.group_destruct(grp:string, directives:list)
 2
                                                      Pvthon -
3
               IN
 4
                    Python string identifier for the group (str)
 5
                   directives
6
                    Optional list of Python info describing request (list)
 7
               Returns:
 8
               • rc - PMIX SUCCESS or a negative value corresponding to a PMIx error constant (integer)
 9
               See PMIx Group destruct for description of all relevant attributes and behaviors.
     A.4.31
                 Client.register event handler
10
               Summary
11
12
               Register an event handler to report events.
               Format
13
                                             ——— Python ——————
    PMIx v4.0
14
               rc,id = myclient.register_event_handler(codes:list,
15
                                           directives:list, cbfunc)
                                                       Python -
16
               IN
                    codes
                    List of Python integer status codes that should be reported to this handler (llist)
17
18
                    directives
19
                    Optional list of Python info describing request (list)
20
               IN
21
                    Python evhandler to be called when event is received (func)
22
               Returns:
23
               • rc - PMIX_SUCCESS or a negative value corresponding to a PMIx error constant (integer)
24
               • id - PMIx reference identifier for handler (integer)
25
               See PMIx Register event handler for description of all relevant attributes and behaviors.
     A.4.32
                 Client.deregister event handler
26
27
               Summary
28
               Deregister an event handler.
```

1		Format Python —
2		myclient.deregister_event_handler(id:integer) Python
3 4		IN id PMIx reference identifier for handler (integer)
5		Returns: None
6		See PMIx_Deregister_event_handler for description of all relevant attributes and behaviors.
7	A.4.33	B Client.notify_event
8 9		Summary Report an event for notification via any registered handler.
10 _P	MIx v4.0	Format Python
11 12		<pre>rc = myclient.notify_event(status:integer, source:dict,</pre>
13 14 15 16 17 18 19 20		IN status PMIx status code indicating the event being reported (integer) IN source Python proc of the process that generated the event (dict) IN range Python range in which the event is to be reported (integer) IN directives Optional list of Python info dictionaries describing the event (list)
21		Returns:
22		• rc - PMIX_SUCCESS or a negative value corresponding to a PMIx error constant (integer)
23		See PMIx_Notify_event for description of all relevant attributes and behaviors.
24	A.4.34	Client.fabric_register
25		Summary
26		Designation for access to fehric related information, including communication acceptances

Register for access to fabric-related information, including communication cost matrix.

1		Format Python —
2		rc,idx,fabricinfo = myclient.fabric_register(directives:list) Python
3 4		IN directives Optional list of Python info containing directives (list)
5		Returns:
6		• rc - PMIX_SUCCESS or a negative value corresponding to a PMIx error constant (integer)
7		• <i>idx</i> - Index of the registered fabric (integer)
8		• fabricinfo - List of Python info containing fabric info (list)
9		See PMIx_Fabric_register for details.
10	A.4.35	Client.fabric_update
11 12		Summary Update fabric-related information, including communication cost matrix.
13	PMIx v4.0	Format Python —
14		rc,fabricinfo = myclient.fabric_update(idx:integer) Python
15 16		IN idx Index of the registered fabric (list)
17		Returns:
18		• rc - PMIX_SUCCESS or a negative value corresponding to a PMIx error constant (integer)
19		• fabricinfo - List of Python info containing updated fabric info (list)
20		See PMIx_Fabric_update for details.
21	A.4.36	Client.fabric_deregister
22 23		Summary Deregister fabric.

```
Format
 1
                          Python —
 2
             rc = myclient.fabric_deregister(idx:integer)
                                                 Python ——
 3
             IN
                  idx
 4
                  Index of the registered fabric (list)
 5
             Returns:
 6
             • rc - PMIX SUCCESS or a negative value corresponding to a PMIx error constant (integer)
 7
             See PMIx Fabric deregister for details.
     A.4.37 Client.load topology
 8
             Summary
 9
10
             Load the local hardware topology into the PMIx library.
             Format
11 <sub>PMIx v4.0</sub>
                        Python —
             rc = myclient.load_topology()
12
                    13
             Returns:
14
             • rc - PMIX SUCCESS or a negative value corresponding to a PMIx error constant (integer)
15
             See PMIx_Load_topology for details - note that the topology loaded into the PMIx library may be utilized
             by PMIx and other libraries, but is not directly accessible by Python.
16
     A.4.38 Client.get relative locality
17
18
             Summary
19
             Get the relative locality of two local processes.
20 _{PMIx\ v4.0}
             Format
                                   Python —
21
             rc,locality = myclient.get_relative_locality(loc1:str, loc2:str)
                                                 Python —
22
             IN
                  loc1
23
                  Locality string of a process (str)
24
             IN
25
                  Locality string of a process (str)
             Returns:
26
27
             • rc - PMIX_SUCCESS or a negative value corresponding to a PMIx error constant (integer)
28
             • locality - locality list containing the relative locality of the two processes (list)
29
             See PMIx Get relative locality for details.
```

A.4.39 Client.get_cpuset 1 2 Summary 3 Get the PU binding bitmap of the current process. Format ______ Python _____ PMIx v4.0 5 rc,cpuset = myclient.get_cpuset(ref:integer) Python IN 6 ref 7 **bindenv** binding envelope to be used (integer) 8 Returns: 9 • rc - PMIX SUCCESS or a negative value corresponding to a PMIx error constant (integer) 10 • cpuset - cpuset containing the source and bitmap of the cpuset (dict) See PMIx Get cpuset for details. 11 A.4.40 Client.parse cpuset string 12 13 Summary 14 Parse the PU binding bitmap from its string representation. 15 PMIx v4.0 — Python —— 16 rc,cpuset = myclient.parse_cpuset_string(cpuset:string) Python — 17 IN cpuset 18 String returned by **PMIxServer.generate_cpuset_string** (string) 19 Returns: 20 • rc - PMIX_SUCCESS or a negative value corresponding to a PMIx error constant (integer) 21 • cpuset - cpuset containing the source and bitmap of the cpuset (dict) 22 See PMIx_Parse_cpuset_string for details. A.4.41 Client.compute distances 23

Compute distances from specified process location to local devices.

Summary

```
Format
 1
                                      Python —
                rc,distances = myclient.compute_distances(cpuset:dict, info:list)
 2
                                                        Pvthon
 3
                IN
                     cpuset
 4
                     cpuset describing the location of the process (dict)
 5
 6
                     List of info dictionaries describing the devices whose distance is to be computed (list)
                Returns:
 8
                • rc - PMIX_SUCCESS or a negative value corresponding to a PMIx error constant (integer)
 9
                • distances - List of devdist structures containing the distances from the caller to the specified devices (list)
10
                See PMIx_Compute_distances for details. Note that distances can only be computed against the local
11
                topology.
     A.4.42 Client.error string
12
13
                Summary
                Pretty-print string representation of pmix_status_t.
14
15 <sub>PMIx v4.0</sub>
                                                       Python -
16
                rep = myclient.error_string(status:integer)
                                                         Python
17
                IN
                     status
18
                     PMIx status code (integer)
19
                Returns:
20
                • rep - String representation of the provided status code (str)
21
                See PMIx Error string for further details.
                 Client.proc state string
     A.4.43
22
                Summary
23
24
                Pretty-print string representation of pmix_proc_state_t.
```

1		Format	Python —
2		rep = myclient.proc_state_string	(state:integer) Python
3		IN state PMIx process state code (integer)	
5		Returns:	
6		• rep - String representation of the provided pro	cess state (str)
7		See PMIx_Proc_state_string for further	details.
8	A.4.44	Client.scope_string	
9 10		Summary Pretty-print string representation of pmix_scop	pe_t.
11	PMIx v4.0	Format	Python —
12		rep = myclient.scope_string(scope	Python —
13 14		IN scope PMIx scope value (integer)	
15		Returns:	
16		• <i>rep</i> - String representation of the provided sco	pe (str)
17		See PMIx_Scope_string for further details	
18	A.4.45	Client.persistence_string	
19 20		Summary Pretty-print string representation of pmix_pers	sistence_t.
21	PMIx v4.0	Format	Python
22		rep = myclient.persistence_string	g(persistence:integer) Python
23 24		IN persistence PMIx persistence value (integer)	
25		Returns:	
26		• rep - String representation of the provided per	sistence (str)
27		See PMIx_Persistence_string for furthe	r details.

A.4.46 Client.data_range_string

```
Summary
 2
 3
              Pretty-print string representation of pmix_data_range_t.
 <sup>4</sup> PMIx v4.0
              Format
                            ______ Python _____
              rep = myclient.data_range_string(range:integer)
 5
                                                    Python
              IN
 6
                   range
 7
                   PMIx data range value (integer)
 8
              Returns:
 9
              • rep - String representation of the provided data range (str)
10
              See PMIx_Data_range_string for further details.
     A.4.47
                Client.info directives string
11
              Summary
12
13
              Pretty-print string representation of pmix info directives t.
14 <sub>PMIx v4.0</sub>
                                                 — Pvthon ————
15
              rep = myclient.info_directives_string(directives:bitarray)
                                                    Python —
16
                   directives
17
                   PMIx info directives value (bitarray)
18
              Returns:
19
              • rep - String representation of the provided info directives (str)
20
              See PMIx_Info_directives_string for further details.
     A.4.48
                Client.data type string
21
22
              Summary
```

23

Pretty-print string representation of pmix_data_type_t.

```
Format
 1
                              Python —
 2
             rep = myclient.data_type_string(dtype:integer)
                                                 Python -
             IN
3
                  dtype
                  PMIx datatype value (integer)
 5
             Returns:
 6
             • rep - String representation of the provided datatype (str)
 7
             See PMIx_Data_type_string for further details.
               Client.alloc directive string
    A.4.49
9
             Summary
             Pretty-print string representation of pmix_alloc_directive_t.
10
11
             Format
   PMIx v4.0
                                                 Python -
12
             rep = myclient.alloc_directive_string(adir:integer)
                                               – Python ——
13
                  adir
14
                  PMIx allocation directive value (integer)
15
             Returns:
16
             • rep - String representation of the provided allocation directive (str)
17
             See PMIx_Alloc_directive_string for further details.
    A.4.50
               Client.iof channel string
18
             Summary
19
20
             Pretty-print string representation of pmix_iof_channel_t.
             Format
21
                                       ——— Python —————
   PMIx v4.0
             rep = myclient.iof_channel_string(channel:bitarray)
22
                   Python —
23
             IN
                  channel
24
                  PMIx IOF channel value (bitarray)
25
             Returns:
26
             • rep - String representation of the provided IOF channel (str)
             See PMIx IOF channel string for further details.
27
```

A.4.51 Client.job_state_string

1

```
Summary
 2
 3
              Pretty-print string representation of pmix_job_state_t.
 4 PMIx v4.0
              Format
                             Python —
              rep = myclient.job_state_string(state:integer)
 5
                                                    Python -
              IN
 6
                   state
 7
                   PMIx job state value (integer)
 8
              Returns:
 9
              • rep - String representation of the provided job state (str)
              See PMIx_Job_state_string for further details.
10
     A.4.52 Client.get attribute string
11
              Summary
12
13
              Pretty-print string representation of a PMIx attribute.
              Format
14 <sub>PMIx v4.0</sub>
                                                   Pvthon —
15
              rep = myclient.get_attribute_string(attribute:str)
                                                 – Python –
16
                   attribute
17
                   PMIx attribute name (string)
18
              Returns:
19
              • rep - String representation of the provided attribute (str)
              See PMIx_Get_attribute_string for further details.
20
     A.4.53 Client.get attribute name
21
22
              Summary
```

23

Pretty-print name of a PMIx attribute corresponding to the provided string.

```
Format
 1
                                _____ Python _____
 2
              rep = myclient.get_attribute_name(attribute:str)
                                                   Python -
              IN
3
                  attributestring
                  Attribute string (string)
 5
              Returns:
 6
              • rep - Attribute name corresponding to the provided string (str)
 7
              See PMIx Get attribute name for further details.
     A.4.54 Client.link state string
8
9
              Summary
10
              Pretty-print string representation of pmix_link_state_t.
              Format
11
    PMIx v4.0
                                                   Python -
12
              rep = myclient.link_state_string(state:integer)
                                                   Python —
13
                  state
14
                  PMIx link state value (integer)
15
              Returns:
16
              • rep - String representation of the provided link state (str)
17
              See PMIx_Link_state_string for further details.
     A.4.55
                Client.device type string
18
              Summary
19
20
              Pretty-print string representation of pmix_device_type_t.
              Format
21
                                        ——— Python —————
    PMIx v4.0
22
              rep = myclient.device_type_string(type:bitarray)
                         ------ Python -
23
              IN
                  type
24
                  PMIx device type value (bitarray)
25
              Returns:
26
              • rep - String representation of the provided device type (str)
27
              See PMIx Device type string for further details.
```

1 A.4.56 Client.progress

Summary 2 3 Progress the PMIx library. ⁴ *PMIx v4.0* **Format** Python myclient.progress() 5 — Python — See PMIx_Progress for further details. 6 A.5 PMIxServer 7 The server Python class inherits the Python "client" class as its parent. Thus, it includes all client functions in 8 addition to the ones defined in this section. 9 A.5.1 Server.init 10 11 Summary 12 Initialize the PMIx server library after obtaining a new PMIxServer object. 13 _{PMIx v4.0} **Format** ——— Python ———— 14 rc = myserver.init(directives:list, map:dict) — Python — 15 directives

List of Python **info** dictionaries (list)

17 **IN** ma

18

19

21

22

23

25

Python dictionary key-function pairs that map **server module** callback functions to provided implementations (see **pmix_server_module_t**) (dict)

20 Returns:

• rc - PMIX SUCCESS or a negative value corresponding to a PMIx error constant (integer)

See PMIx_server_init for description of all relevant attributes and behaviors.

A.5.2 Server.finalize

24 Summary

Finalize the PMIx server library.

1		Format Python
2		rc = myserver.finalize() Python
3		Returns:
4		• rc - PMIX_SUCCESS or a negative value corresponding to a PMIx error constant (integer)
5		See PMIx_server_finalize for details.
6	A.5.3	Server.generate_regex
7 8		Summary Generate a regular expression representation of the input strings.
9	PMIx v4.0	Format Python —
10		rc,regex = myserver.generate_regex(input:list) Python
11 12		IN input List of Python strings (e.g., node names) (list)
13		Returns:
14		• rc - PMIX_SUCCESS or a negative value corresponding to a PMIx error constant (integer)
15		• regex - Python bytearray containing regular expression representation of the input list (bytearray)
16		See PMIx_generate_regex for details.
17	A.5.4	Server.generate_ppn
18 19		Summary Generate a regular expression representation of the input strings.
20	PMIx v4.0	Format Python
21		rc,regex = myserver.generate_ppn(input:list) Python
22 23 24		IN input List of Python strings, each string consisting of a comma-delimited list of ranks on each node, with the strings being in the same order as the node names provided to "generate_regex" (list)
25		Returns:
26		• rc - PMIX_SUCCESS or a negative value corresponding to a PMIx error constant (integer)
27		• regex - Python bytearray containing regular expression representation of the input list (bytearray)
28		See PMIx_generate_ppn for details.

2 Summary 3 Generate a PMIx locality string from a given cpuset. **Format** 4 *PMIx v4.0* Python — 5 rc,locality = myserver.generate_locality_string(cpuset:dict) ———— Python IN 6 cset 7 cpuset containing the bitmap of assigned PUs (dict) 8 Returns: 9 • rc - PMIX SUCCESS or a negative value corresponding to a PMIx error constant (integer) 10 • locality - String representation of the PMIx locality corresponding to the input bitmap (string) 11 See PMIx_server_generate_locality_string for details. A.5.6 Server.generate cpuset string 12 13 Summary 14 Generate a PMIx string representation of the provided cpuset. 15 _{PMIx v4.0} Format Python 16 rc,cpustr = myserver.generate_cpuset_string(cpuset:dict) Python —— 17 IN 18 **cpuset** containing the bitmap of assigned PUs (dict) 19 Returns: 20 • rc - PMIX_SUCCESS or a negative value corresponding to a PMIx error constant (integer) 21 • *cpustr* - String representation of the input bitmap (string) 22 See PMIx_server_generate_cpuset_string for details. A.5.7 Server.register nspace 23 Summary 24 25 Setup the data about a particular namespace.

1

A.5.5 Server.generate locality string

1		Python —
2 3 4		<pre>rc = myserver.register_nspace(nspace:str,</pre>
5 6 7 8 9		IN nspace Python string containing the namespace (str) IN nlocalprocs Number of local processes (integer) IN directives List of Python info dictionaries (list)
11		Returns:
12		• rc - PMIX_SUCCESS or a negative value corresponding to a PMIx error constant (integer)
13	4.50	See PMIx_server_register_nspace for description of all relevant attributes and behaviors.
14	A.5.8	Server.deregister_nspace
15 16		Summary Deregister a namespace.
17	PMIx v4.0	Format Python —
18 19		myserver.deregister_nspace(nspace:str) Python IN nspace
20		Python string containing the namespace (str)
21 22		Returns: None See PMIx_server_deregister_nspace for details.
23	A.5.9	Server.register resources
24 25		Summary Register non-namespace related information with the local PMIx library
26	PMIx v4.0	Format Python
27		myserver.register_resources(directives:list) Python
28 29		IN directives List of Python info dictionaries (list)
30		Returns: None
31		See PMIx_server_register_resources for details.

A.5.10 Server.deregister_resources

2	Summary Remove non-namespace related information from the local PMIx library
4 <i>PMIx v4.0</i>	Format Python
5	myserver.deregister_resources(directives:list) Python
6 7	IN directives List of Python info dictionaries (list)
8	Returns: None
9	See PMIx_server_deregister_resources for details.
10 A.5.11	Server.register_client
11 12	Summary Register a client process with the PMIx server library.
13 _{PMIx v4.0}	Format Python —
14	<pre>rc = myserver.register_client(proc:dict, uid:integer, gid:integer)</pre>
15	IN proc
16 17	Python proc dictionary identifying the client process (dict) IN uid
18	Linux uid value for user executing client process (integer)
19 20	IN gid Linux gid value for user executing client process (integer)
21	Returns:
22	• rc - PMIX_SUCCESS or a negative value corresponding to a PMIx error constant (integer)
23	See PMIx_server_register_client for details.
24 A.5.12	Server.deregister_client
25 26	Summary Deregister a client process and purge all data relating to it.

1		Format Python —
2		myserver.deregister_client(proc:dict)
		T ython
3 4		Python proc dictionary identifying the client process (dict)
5		Returns: None
6		See PMIx_server_deregister_client for details.
7	A.5.13	Server.setup_fork
8 9		Summary Setup the environment of a child process that is to be forked by the host.
10	PMIx v4.0	Format Python
11		<pre>rc = myserver.setup_fork(proc:dict, envin:dict)</pre>
12 13 14 15		IN proc Python proc dictionary identifying the client process (dict) INOUT envin Python dictionary containing the environment to be passed to the client (dict)
16		Returns:
17		• rc - PMIX_SUCCESS or a negative value corresponding to a PMIx error constant (integer)
18		See PMIx_server_setup_fork for details.
19	A.5.14	Server.dmodex_request
20 21		Summary Function by which the host server can request modex data from the local PMIx server.
22	PMIx v4.0	Format Python
23		rc,data = myserver.dmodex_request(proc:dict) Python
24 25		IN proc Python proc dictionary identifying the process whose data is requested (dict)
26		Returns:
27		• rc - PMIX_SUCCESS or a negative value corresponding to a PMIx error constant (integer)
28		• data - Python byteobject containing the returned data (dict)
29		See PMIx_server_dmodex_request for details.

A.5.15 Server.setup_application

2 3	Summary Function by which the resource manager can request application-specific setup data prior to launch of a <i>job</i> .
4 <i>PMIx v4.0</i>	Format Python —
5	<pre>rc,info = myserver.setup_application(nspace:str, directives:list)</pre>
6 7 8 9	 IN nspace Namespace whose setup information is being requested (str) IN directives Python list of info directives
10	Returns:
11	• rc - PMIX_SUCCESS or a negative value corresponding to a PMIx error constant (integer)
12	• <i>info</i> - Python list of info dictionaries containing the returned data (list)
13	See PMIx_server_setup_application for details.
14 A.5.16	Server.register_attributes
15 16	Summary Register host environment attribute support for a function.
17 _{PMIx v4.0}	Format Python
18	rc = myserver.register_attributes(function:str, attrs:list) Python
19 20 21 22	<pre>IN function Name of the function (str) IN attrs Python list of regattr describing the supported attributes</pre>
23	Returns:
24	• rc - PMIX_SUCCESS or a negative value corresponding to a PMIx error constant (integer)
25	See PMIx_Register_attributes for details.
26 A.5.17	Server.setup_local_support
27	Summary
28 29	Function by which the local PMIx server can perform any application-specific operations prior to spawning local clients of a given application.

```
Format
 1
                                   ______ Python ______
 2
               rc = myserver.setup_local_support(nspace:str, info:list)
                                                       Pvthon
 3
               IN
                    nspace
 4
                    Namespace whose setup information is being requested (str)
 5
 6
                    Python list of info containing the setup data (list)
 7
               Returns:
 8
               • rc - PMIX SUCCESS or a negative value corresponding to a PMIx error constant (integer)
 9
               See PMIx_server_setup_local_support for details.
     A.5.18 Server.iof deliver
10
               Summary
11
12
               Function by which the host environment can pass forwarded IO to the PMIx server library for distribution to
13
               its clients.
               Format
14
    PMIx v4.0
                                                  — Pvthon ———
15
               rc = myserver.iof_deliver(source:dict, channel:integer,
16
                                              data:dict, directives:list)
                                                  — Pvthon ———
17
               IN
                    source
18
                    Python proc dictionary identifying the process who generated the data (dict)
19
20
                    Python channel bitmask identifying IO channel of the provided data (integer)
21
               IN
22
                    Python byteobject containing the data (dict)
23
                    directives
                    Python list of info containing directives (list)
24
25
               Returns:
26
               • rc - PMIX_SUCCESS or a negative value corresponding to a PMIx error constant (integer)
27
               See PMIx_server_IOF_deliver for details.
     A.5.19
                 Server.collect inventory
28
               Summary
29
30
               Collect inventory of resources on a node.
```

```
Format
 1
                                 ______ Python _____
 2
               rc,info = myserver.collect_inventory(directives:list)
                                                      Python
               IN
 3
                   directives
                    Optional Python list of info containing directives (list)
 5
               Returns:
 6
               • rc - PMIX_SUCCESS or a negative value corresponding to a PMIx error constant (integer)
 7
               • info - Python list of info containing the returned data (list)
 8
               See PMIx server collect inventory for details.
     A.5.20
                 Server.deliver_inventory
 9
               Summary
10
               Pass collected inventory to the PMIx server library for storage.
11
               Format
12 <sub>PMIx v4.0</sub>
                                                      Python —
13
               rc = myserver.deliver_inventory(info:list, directives:list)
                                                      Python –
14
15
                    - Python list of info dictionaries containing the inventory data (list)
16
               IN
                    directives
17
                    Python list of info dictionaries containing directives (list)
18
               Returns:
               • rc - PMIX_SUCCESS or a negative value corresponding to a PMIx error constant (integer)
19
20
               See PMIx_server_deliver_inventory for details.
     A.5.21
                 Server.define process set
21
22
               Summary
23
               Add members to a PMIx process set.
```

```
Format
1
                               ______ Python ______
 2
              rc = myserver.define_process_set(members:list, name:str)
                                                   Python
3
              IN
                  members
4
                  - List of Python proc dictionaries identifying the processes to be added to the process set (list)
 5
6
                  - Name of the process set (str)
 7
              Returns:
              • rc - PMIX_SUCCESS or a negative value corresponding to a PMIx error constant (integer)
8
9
              See PMIx_server_define_process_set for details.
                Server.delete_process_set
     A.5.22
10
              Summary
11
12
              Delete a PMIx process set.
              Format
                                         ——— Python —————
13
   PMIx v4.0
14
              rc = myserver.delete_process_set(name:str)
                                                   Python —
15
              IN
                  - Name of the process set (str)
16
17
              Returns:
18
              • rc - PMIX_SUCCESS or a negative value corresponding to a PMIx error constant (integer)
19
              See PMIx server delete process set for details.
     A.5.23
               Server.register resources
20
21
              Summary
22
              Register non-namespace related information with the local PMIx server library.
23
              Format
                                        ——— Python —————
   PMIx v4.0
24
              rc = myserver.register_resources(info:list)
                                                 Python —
25
              IN
                  info
                  - List of Python info dictionaries list)
26
27
              Returns:
28
              • rc - PMIX_SUCCESS or a negative value corresponding to a PMIx error constant (integer)
29
              See PMIx_server_register_resources for details.
```

A.5.24 Server.deregister_resources

2 Summary 3 Deregister non-namespace related information with the local PMIx server library. **Format** 4 *PMIx v4.0* Pvthon — 5 rc = myserver.deregister_resources(info:list) Python IN info 6 7 - List of Python info dictionaries list) 8 Returns: 9 • rc - PMIX SUCCESS or a negative value corresponding to a PMIx error constant (integer) 10 See PMIx_server_deregister_resources for details. A.6 PMIxTool 11 12 The tool Python class inherits the Python "server" class as its parent. Thus, it includes all client and server 13 functions in addition to the ones defined in this section. Tool.init A.6.1 14 Summary 15 16 Initialize the PMIx tool library after obtaining a new PMIxTool object. 17 *PMIx v4.0* ——— Python ————— 18 rc,proc = mytool.init(info:list) Python _____ 19 IN info 20 List of Python info directives (list) 21 Returns: 22 • rc - PMIX_SUCCESS or a negative value corresponding to a PMIx error constant (integer) 23 • proc - a Python proc (dict) 24 See PMIx_tool_init for description of all relevant attributes and behaviors. A.6.2 Tool.finalize 25 26 Summary 27 Finalize the PMIx tool library, closing the connection to the server.

```
Format
 1
                          Python —
 2
             rc = mytool.finalize()
                                             — Python —
 3
             Returns:
 4
             • rc - PMIX_SUCCESS or a negative value corresponding to a PMIx error constant (integer)
 5
             See PMIx_tool_finalize for description of all relevant attributes and behaviors.
    A.6.3 Tool.disconnect
6
             Summary
8
             Disconnect the PMIx tool from the specified server connection while leaving the tool library initialized.
             Format
                                       _____ Python ______
   PMIx v4.0
10
             rc = mytool.disconnect(server:dict)
                                     11
             IN
                  server
12
                  Process identifier of server from which the tool is to be disconnected (proc)
13
             Returns:
14
             • rc - PMIX_SUCCESS or a negative value corresponding to a PMIx error constant (integer)
15
             See PMIx tool disconnect for details.
    A.6.4 Tool.attach_to_server
16
17
             Summary
18
             Establish a connection to a PMIx server.
19
             Format
                        ______ Python _____
   PMIx v4.0
20
             rc,proc,server = mytool.connect_to_server(info:list)
                              ----- Python -----
21
             IN
22
                  List of Python info dictionaries (list)
23
             Returns:
24
             • rc - PMIX_SUCCESS or a negative value corresponding to a PMIx error constant (integer)
25
             • proc - a Python proc containing the tool's identifier (dict)
26
             • server - a Python proc containing the identifier of the server to which the tool attached (dict)
27
             See PMIx tool attach to server for details.
```

A.6.5 Tool.get_servers

2 Summary 3 Get a list conta

Get a list containing the proc process identifiers of all servers to which the tool is currently connected.

4 PMIx v4.0 Format

1

5

8

9

10

11

13

15

16

17

18

19

21 22

23

rc, servers = mytool.get_servers()

- Python -

6 Returns:

- rc PMIX_SUCCESS or a negative value corresponding to a PMIx error constant (integer)
- servers a list of Python proc containing the identifiers of the servers to which the tool is currently attached (dict)
 - See PMIx_tool_get_servers for details.

A.6.6 Tool.set_server

12 Summary

Designate a server as the tool's *primary* server.

14 $_{PMIx v4.0}$ Format

——— Python —————

IN proc

Python **proc** containing the identifier of the servers to which the tool is to attach (list)

IN info

List of Python **info** dictionaries (list)

20 Returns:

• rc - PMIX_SUCCESS or a negative value corresponding to a PMIx error constant (integer)

See PMIx_tool_set_server for details.

A.6.7 Tool.iof pull

24 **Summary** 25 Register to rec

Register to receive output forwarded from a remote process.

1		Format Python —
2 3		<pre>rc,id = mytool.iof_pull(sources:list, channel:integer,</pre>
		Python —
4 5 6 7 8 9		IN sources List of Python proc dictionaries of processes whose IO is being requested (list) IN channel Python channel bitmask identifying IO channels to be forwarded (integer) IN directives List of Python info dictionaries describing request (list) IN cbfunc
11		Python iofcbfunc to receive IO payloads (func)
12		Returns:
13		• rc - PMIX_SUCCESS or a negative value corresponding to a PMIx error constant (integer)
14		• <i>id</i> - PMIx reference identifier for request (integer)
15		See PMIx_IOF_pull for description of all relevant attributes and behaviors.
16	A.6.8	Tool.iof_deregister
17 18		Summary Deregister from output forwarded from a remote process.
19	PMIx v4.0	Format Python —
20		<pre>rc = mytool.iof_deregister(id:integer, directives:list)</pre>
21 22 23 24		IN id PMIx reference identifier returned by pull request (list) IN directives List of Python info dictionaries describing request (list)
25		Returns:
26		• rc - PMIX_SUCCESS or a negative value corresponding to a PMIx error constant (integer)
27		See PMIx_IOF_deregister for description of all relevant attributes and behaviors.
28	A.6.9	Tool.iof_push
29 30		Summary Push data collected locally (typically from stdin) to stdin of target recipients.

```
Format
                                      ———— Python —————
 1
 2
               rc = mytool.iof_push(targets:list, data:dict, directives:list)
                                                     - Pvthon –
3
               IN
                    sources
 4
                    List of Python proc of target processes (list)
 5
6
                    Python byteobject containing data to be delivered (dict)
 7
                    directives
8
                    Optional list of Python info describing request (list)
9
               Returns:
10
               • rc - PMIX SUCCESS or a negative value corresponding to a PMIx error constant (integer)
11
               See PMIx_IOF_push for description of all relevant attributes and behaviors.
```

A.7 Example Usage

12

13

15

16

17

18

19

20 21

22

23

24

25 26

27

28 29

30 31

32

33

34

35

36

The following examples are provided to illustrate the use of the Python bindings.

A.7.1 Python Client

The following example contains a client program that illustrates a fairly common usage pattern. The program instantiates and initializes the PMIxClient class, posts some data that is to be shared across all processes in the job, executes a "fence" that circulates the data, and then retrieves a value posted by one of its peers. Note that the example has been formatted to fit the document layout.

```
------Python -
from pmix import *
def main():
    # Instantiate a client object
    myclient = PMIxClient()
   print("Testing PMIx ", myclient.get_version())
    # Initialize the PMIx client library, declaring the programming model
    # as "TEST" and the library name as "PMIX", just for the example
   info = ['key':PMIX_PROGRAMMING_MODEL,
             'value': 'TEST', 'val_type': PMIX_STRING,
            'key': PMIX MODEL LIBRARY NAME,
             'value':'PMIX', 'val_type':PMIX_STRING]
    rc,myname = myclient.init(info)
    if PMIX_SUCCESS != rc:
       print("FAILED TO INIT WITH ERROR", myclient.error_string(rc))
       exit(1)
```

```
1
                 # try posting a value
2
                 rc = myclient.put(PMIX_GLOBAL, "mykey",
3
                                    'value':1, 'val_type':PMIX_INT32)
4
                 if PMIX_SUCCESS != rc:
5
                     print("PMIx_Put FAILED WITH ERROR", myclient.error_string(rc))
6
                     # cleanly finalize
7
                     myclient.finalize()
8
                     exit(1)
9
10
                 # commit it
11
                 rc = myclient.commit()
12
                 if PMIX_SUCCESS != rc:
                     print("PMIx_Commit FAILED WITH ERROR",
13
14
                            myclient.error_string(rc))
15
                     # cleanly finalize
16
                     myclient.finalize()
17
                     exit(1)
18
19
                 # execute fence across all processes in my job
20
                 procs = []
21
                 info = []
22
                 rc = myclient.fence(procs, info)
23
                 if PMIX_SUCCESS != rc:
24
                     print("PMIx_Fence FAILED WITH ERROR", myclient.error_string(rc))
25
                     # cleanly finalize
26
                     myclient.finalize()
27
                     exit(1)
28
29
                 # Get a value from a peer
30
                 if 0 != myname['rank']:
31
                     info = []
32
                     rc, get_val = myclient.get('nspace':"testnspace", 'rank': 0,
33
                                                  "mykey", info)
34
                     if PMIX SUCCESS != rc:
35
                          print ("PMIx_Commit_FAILED_WITH_ERROR",
36
                                myclient.error_string(rc))
37
                          # cleanly finalize
38
                          myclient.finalize()
39
                          exit(1)
40
                     print("Get value returned: ", get_val)
41
                 # test a fence that should return not_supported because
42
43
                 # we pass a required attribute that the server is known
44
                 # not to support
45
                 procs = []
46
                 info = ['key': 'ARBIT', 'flags': PMIX_INFO_REQD,
47
                           'value':10, 'val_type':PMIX_INT]
```

```
1
                 rc = myclient.fence(procs, info)
2
                 if PMIX_SUCCESS == rc:
 3
                      print("PMIx Fence SUCCEEDED BUT SHOULD HAVE FAILED")
4
                      # cleanly finalize
5
                      myclient.finalize()
6
                      exit(1)
7
8
                 # Publish something
9
                 info = ['key': 'ARBITRARY', 'value':10, 'val_type':PMIX_INT]
10
                 rc = myclient.publish(info)
11
                 if PMIX_SUCCESS != rc:
12
                      print ("PMIx_Publish FAILED WITH ERROR",
13
                            myclient.error_string(rc))
14
                      # cleanly finalize
15
                      myclient.finalize()
16
                      exit(1)
17
18
                 # finalize
19
                 info = []
20
                 myclient.finalize(info)
21
                 print("Client finalize complete")
22
23
             # Python main program entry point
24
             if __name__ == '__main__':
25
                 main()
                                                Python -
```

A.7.2 Python Server

The following example contains a minimum-level server host program that instantiates and initializes the PMIxServer class. The program illustrates passing several server module functions to the bindings and includes code to setup and spawn a simple client application, waiting until the spawned client terminates before finalizing and exiting itself. Note that the example has been formatted to fit the document layout.

Python

```
31
             from pmix import *
32
             import signal, time
33
             import os
             import select
34
35
             import subprocess
36
37
             def clientconnected(proc:tuple is not None):
38
                 print("CLIENT CONNECTED", proc)
39
                 return PMIX_OPERATION_SUCCEEDED
40
41
             def clientfinalized(proc:tuple is not None):
42
                 print("CLIENT FINALIZED", proc)
```

26 27

28

29

```
1
                 return PMIX_OPERATION_SUCCEEDED
2
3
             def clientfence(procs:list, directives:list, data:bytearray):
4
                 # check directives
5
                 if directives is not None:
6
                     for d in directives:
7
                          # these are each an info dict
8
                          if "pmix" not in d['key']:
9
                              # we do not support such directives - see if
10
                              # it is required
11
                              try:
12
                                  if d['flags'] & PMIX_INFO_REQD:
13
                                      # return an error
14
                                      return PMIX_ERR_NOT_SUPPORTED
15
                              except:
16
                                  #it can be ignored
17
                                  pass
18
                 return PMIX_OPERATION_SUCCEEDED
19
20
             def main():
21
                 try:
22
                     myserver = PMIxServer()
23
                 except:
24
                     print("FAILED TO CREATE SERVER")
25
                     exit(1)
26
                 print("Testing server version ", myserver.get_version())
27
28
                 args = ['key':PMIX_SERVER_SCHEDULER,
29
                           'value':'T', 'val_type':PMIX_BOOL]
30
                 map = 'clientconnected': clientconnected,
31
                         'clientfinalized': clientfinalized,
32
                         'fencenb': clientfence
33
                 my_result = myserver.init(args, map)
34
35
                 # get our environment as a base
36
                 env = os.environ.copy()
37
38
                 # register an nspace for the client app
                  (rc, regex) = myserver.generate_regex("test000, test001, test002")
39
40
                  (rc, ppn) = myserver.generate_ppn("0")
41
                 kvals = ['key':PMIX_NODE_MAP,
42
                            'value':regex, 'val_type':PMIX_STRING,
43
                           'key':PMIX_PROC_MAP,
44
                            'value':ppn, 'val_type':PMIX_STRING,
45
                           'key':PMIX_UNIV_SIZE,
46
                            'value':1, 'val_type':PMIX_UINT32,
47
                           'key':PMIX_JOB_SIZE,
```

```
'value':1, 'val_type':PMIX_UINT32]
1
2
                 rc = foo.register_nspace("testnspace", 1, kvals)
3
                 print("RegNspace ", rc)
4
5
                 # register a client
6
                 uid = os.getuid()
7
                 gid = os.getgid()
8
                 rc = myserver.register_client('nspace':"testnspace", 'rank':0,
9
                                                uid, gid)
10
                 print("RegClient ", rc)
11
                 # setup the fork
12
                 rc = myserver.setup_fork('nspace':"testnspace", 'rank':0, env)
13
                 print("SetupFrk", rc)
14
15
                 # setup the client argv
16
                 args = ["./client.py"]
17
                 # open a subprocess with stdout and stderr
18
                 # as distinct pipes so we can capture their
19
                 # output as the process runs
20
                 p = subprocess.Popen(args, env=env,
21
                      stdout=subprocess.PIPE, stderr=subprocess.PIPE)
22
                 # define storage to catch the output
23
                 stdout = []
24
                 stderr = []
25
                 # loop until the pipes close
26
                 while True:
27
                     reads = [p.stdout.fileno(), p.stderr.fileno()]
28
                     ret = select.select(reads, [], [])
29
30
                     stdout_done = True
31
                     stderr done = True
32
33
                     for fd in ret[0]:
34
                          # if the data
35
                          if fd == p.stdout.fileno():
36
                              read = p.stdout.readline()
37
                              if read:
38
                                  read = read.decode('utf-8').rstrip()
39
                                  print('stdout: ' + read)
40
                                  stdout_done = False
41
                         elif fd == p.stderr.fileno():
42
                              read = p.stderr.readline()
43
                              if read:
44
                                  read = read.decode('utf-8').rstrip()
45
                                  print('stderr: ' + read)
46
                                  stderr_done = False
47
```

```
1
2
3
4
5
6
7
```

——— Python —

APPENDIX B

2

3

18

19

20

21

22

23 24

25

26

Revision History

B.1 Version 1.0: June 12, 2015

The PMIx version 1.0 ad hoc standard was defined in a set of header files as part of the v1.0.0 release of the OpenPMIx library prior to the creation of the formal PMIx 2.0 standard. Below are a summary listing of the interfaces defined in the 1.0 headers.

Client APIs

```
5
6
                - PMIx_Init, PMIx_Initialized, PMIx_Abort, PMIx_Finalize
 7
                - PMIx Put, PMIx Commit,
8
                - PMIx Fence, PMIx Fence nb
9
                - PMIx Get, PMIx Get nb
10
                - PMIx_Publish, PMIx_Publish_nb
11
                - PMIx_Lookup, PMIx_Lookup_nb
12
                - PMIx_Unpublish, PMIx_Unpublish_nb
13
                - PMIx_Spawn, PMIx_Spawn_nb
14
                - PMIx Connect, PMIx Connect nb
15
                - PMIx Disconnect, PMIx Disconnect nb
16
                - PMIx Resolve nodes, PMIx Resolve peers
17
```

Server APIs

```
- PMIx server init, PMIx server finalize
- PMIx_generate_regex, PMIx_generate_ppn
- PMIx_server_register_nspace, PMIx_server_deregister_nspace
- PMIx_server_register_client, PMIx_server_deregister_client
- PMIx_server_setup_fork, PMIx_server_dmodex_request
```

• Common APIs

```
- PMIx Get version, PMIx Store internal, PMIx Error string
- PMIx_Register_errhandler, PMIx_Deregister_errhandler, PMIx_Notify_error
```

The **PMIx_Init** API was subsequently modified in the v1.1.0 release of that library.

B.2 Version 2.0: Sept. 2018

2 The following APIs were introduced in v2.0 of the PMIx Standard: Client APIs 4 - PMIx Query info nb, PMIx Log nb 5 - PMIx_Allocation_request_nb, PMIx_Job_control_nb, 6 PMIx Process monitor nb, PMIx Heartbeat 7 Server APIs 8 - PMIx server setup application, PMIx server setup local support 9 Tool APIs 10 - PMIx_tool_init, PMIx_tool_finalize 11 Common APIs 12 - PMIx_Register_event_handler, PMIx_Deregister_event_handler 13 - PMIx_Notify_event 14 - PMIx_Proc_state_string, PMIx_Scope_string 15 - PMIx Persistence string, PMIx Data range string 16 - PMIx Info directives string, PMIx Data type string 17 - PMIx Alloc directive string 18 - PMIx_Data_pack, PMIx_Data_unpack, PMIx_Data_copy 19 - PMIx_Data_print, PMIx_Data_copy_payload Removed/Modified APIs B.2.1 The PMIx Init API was modified in v2.0 of the standard from its ad hoc v1.0 signature to include passing

20

21 22 of a pmix info t array for flexibility and "future-proofing" of the API. In addition, the 23 PMIx_Notify_error, PMIx_Register_errhandler, and PMIx_Deregister_errhandler 24 APIs were replaced. This pre-dated official adoption of PMIx as a Standard.

B.2.2 Deprecated constants

The following constants were deprecated in v2.0:

27 PMIX MODEX 28 PMIX_INFO_ARRAY

B.2.3 Deprecated attributes

1

23 24

25

26

27

28

29

30

31

32

33

34

35 36

37

38 39

40

41

The following attributes were deprecated in v2.0: 3 PMIX_ERROR_NAME "pmix.errname" (pmix_status_t) 4 Specific error to be notified 5 PMIX ERROR GROUP COMM "pmix.errgroup.comm" (bool) 6 Set true to get comm errors notification 7 PMIX_ERROR_GROUP_ABORT "pmix.errgroup.abort" (bool) 8 Set true to get abort errors notification 9 PMIX_ERROR_GROUP_MIGRATE "pmix.errgroup.migrate" (bool) 10 Set true to get migrate errors notification 11 PMIX_ERROR_GROUP_RESOURCE "pmix.errgroup.resource" (bool) 12 Set true to get resource errors notification 13 PMIX_ERROR_GROUP_SPAWN "pmix.errgroup.spawn" (bool) 14 Set true to get spawn errors notification 15 PMIX ERROR GROUP NODE "pmix.errgroup.node" (bool) 16 Set true to get node status notification PMIX_ERROR_GROUP_LOCAL "pmix.errgroup.local" (bool) 17 18 Set true to get local errors notification 19 PMIX_ERROR_GROUP_GENERAL "pmix.errgroup.gen" (bool) 20 Set true to get notified of generic errors 21 PMIX ERROR HANDLER ID "pmix.errhandler.id" (int) 22 Errhandler reference id of notification being reported

B.3 Version 2.1: Dec. 2018

The v2.1 update includes clarifications and corrections from the v2.0 document, plus addition of examples:

- Clarify description of **PMIx_Connect** and **PMIx_Disconnect** APIs.
- Explain that values for the PMIX COLLECTIVE ALGO are environment-dependent
- Identify the namespace/rank values required for retrieving attribute-associated information using the PMIx Get API
- Provide definitions for session, job, application, and other terms used throughout the document
- Clarify definitions of PMIX_UNIV_SIZE versus PMIX_JOB_SIZE
- Clarify server module function return values
- Provide examples of the use of **PMIx_Get** for retrieval of information
- Clarify the use of PMIx_Get versus PMIx_Query_info_nb
- Clarify return values for non-blocking APIs and emphasize that callback functions must not be invoked prior to return from the API
- Provide detailed example for construction of the PMIx_server_register_nspace input information array
- Define information levels (e.g., *session* vs *job*) and associated attributes for both storing and retrieving values
- Clarify roles of PMIx server library and host environment for collective operations
- Clarify definition of PMIX UNIV SIZE

B.4 Version 2.2: Jan 2019

- 2 The v2.2 update includes the following clarifications and corrections from the v2.1 document:
 - Direct modex upcall function (pmix_server_dmodex_req_fn_t) cannot complete atomically as the API cannot return the requested information except via the provided callback function
 - Add missing pmix_data_array_t definition and support macros
 - Add a rule divider between implementer and host environment required attributes for clarity
 - Add PMIX_QUERY_QUALIFIERS_CREATE macro to simplify creation of pmix_query_t qualifiers
 - Add PMIX APP INFO CREATE macro to simplify creation of pmix app t directives
 - Add flag and PMIX_INFO_IS_END macro for marking and detecting the end of a pmix_info_t array
 - Clarify the allowed hierarchical nesting of the PMIX_SESSION_INFO_ARRAY,
 PMIX_JOB_INFO_ARRAY, and associated attributes

B.5 Version 3.0: Dec. 2018

- The following APIs were introduced in v3.0 of the PMIx Standard:
- 14 Client APIs

3

4

5

6

7

8

9

10

11

12

13

15

16

17

18

19

20

23

24

25

26

27

28

29

- PMIx_Log, PMIx_Job_control
 - PMIx_Allocation_request, PMIx_Process_monitor
 - PMIx_Get_credential, PMIx_Validate_credential
- Server APIs
 - PMIx server IOF deliver
 - PMIx server collect inventory, PMIx server deliver inventory
- Tool APIs
- 22 PMIx IOF pull, PMIx IOF push, PMIx IOF deregister
 - PMIx_tool_connect_to_server
 - Common APIs
 - PMIx_IOF_channel_string
 - The document added a chapter on security credentials, a new section for IO forwarding to the Process Management chapter, and a few blocking forms of previously-existing non-blocking APIs. Attributes supporting the new APIs were introduced, as well as additional attributes for a few existing functions.

B.5.1 Removed constants

- The following constants were removed in v3.0:
- 31 PMIX MODEX
- 32 PMIX INFO ARRAY

B.5.2 Deprecated attributes

1

5 6

7

8

9

10

11 12

13

14

15

16 17

18

19

20

21

22

23

24

25

26

27

28

29

30

31

32

33

34 35

36

37

38

39

```
3 PMIX_COLLECTIVE_ALGO_REQD "pmix.calreqd" (bool)
4 If true, indicates that the requested choice of algorithm is mandatory.
```

The following attributes were deprecated in v3.0:

B.5.3 Removed attributes

```
The following attributes were removed in v3.0:
```

```
PMIX_ERROR_NAME "pmix.errname" (pmix_status_t)
      Specific error to be notified
PMIX ERROR GROUP COMM "pmix.errgroup.comm" (bool)
      Set true to get comm errors notification
PMIX_ERROR_GROUP_ABORT "pmix.errgroup.abort" (bool)
      Set true to get abort errors notification
PMIX_ERROR_GROUP_MIGRATE "pmix.errgroup.migrate" (bool)
      Set true to get migrate errors notification
PMIX ERROR_GROUP_RESOURCE "pmix.errgroup.resource" (bool)
      Set true to get resource errors notification
PMIX ERROR GROUP SPAWN "pmix.errgroup.spawn" (bool)
      Set true to get spawn errors notification
PMIX ERROR GROUP NODE "pmix.errgroup.node" (bool)
      Set true to get node status notification
PMIX_ERROR_GROUP_LOCAL "pmix.errgroup.local" (bool)
      Set true to get local errors notification
PMIX ERROR GROUP GENERAL "pmix.errgroup.gen" (bool)
      Set true to get notified of generic errors
```

B.6 Version 3.1: Jan. 2019

The v3.1 update includes clarifications and corrections from the v3.0 document:

PMIX ERROR HANDLER ID "pmix.errhandler.id" (int)

Errhandler reference id of notification being reported

- Direct modex upcall function (pmix_server_dmodex_req_fn_t) cannot complete atomically as the API cannot return the requested information except via the provided callback function
- Fix typo in name of **PMIX_FWD_STDDIAG** attribute
- Correctly identify the information retrieval and storage attributes as "new" to v3 of the standard
- Add missing pmix_data_array_t definition and support macros
- Add a rule divider between implementer and host environment required attributes for clarity
- Add PMIX QUERY QUALIFIERS CREATE macro to simplify creation of pmix query t qualifiers
- Add PMIX APP INFO CREATE macro to simplify creation of pmix app t directives
- Add new attributes to specify the level of information being requested where ambiguity may exist (see 6.1)
- Add new attributes to assemble information by its level for storage where ambiguity may exist (see 16.2.3.1)
- Add flag and PMIX_INFO_IS_END macro for marking and detecting the end of a pmix_info_t array

- Clarify that PMIX_NUM_SLOTS is duplicative of (a) PMIX_UNIV_SIZE when used at the session level and (b) PMIX_MAX_PROCS when used at the job and application levels, but leave it in for backward compatibility.
 - Clarify difference between PMIX_JOB_SIZE and PMIX_MAX_PROCS
 - Clarify that PMIx_server_setup_application must be called per-*job* instead of per-*application* as the name implies. Unfortunately, this is a historical artifact. Note that both PMIX_NODE_MAP and PMIX_PROC_MAP must be included as input in the *info* array provided to that function. Further descriptive explanation of the "instant on" procedure will be provided in the next version of the PMIx Standard.
 - Clarify how the PMIx server expects data passed to the host by pmix_server_fencenb_fn_t should be aggregated across nodes, and provide a code snippet example

B.7 Version 3.2: Oct. 2020

4

5

6

7

8

9

10

12

13

14

15 16

17

18

19

20

21

22

23

25

The v3.2 update includes clarifications and corrections from the v3.1 document:

- Correct an error in the PMIx_Allocation_request function signature, and clarify the allocation ID attributes
- Rename the PMIX_ALLOC_ID attribute to PMIX_ALLOC_REQ_ID to clarify that this is a string the user
 provides as a means to identify their request to query status
- Add a new PMIX_ALLOC_ID attribute that contains the identifier (provided by the host environment) for the resulting allocation which can later be used to reference the allocated resources in, for example, a call to PMIx_Spawn
- Update the PMIx_generate_regex and PMIx_generate_ppn descriptions to clarify that the output
 from these generator functions may not be a NULL-terminated string, but instead could be a byte array of
 arbitrary binary content.
- Add a new **PMIX_REGEX** constant that represents a regular expression data type.

24 B.7.1 Deprecated constants

The following constants were deprecated in v3.2:

```
26
                                                     Data value not found
               PMIX ERR DATA VALUE NOT FOUND
27
               PMIX ERR HANDSHAKE FAILED
                                                Connection handshake failed
28
               PMIX ERR IN ERRNO
                                       Error defined in errno
29
               PMIX ERR INVALID ARG
                                          Invalid argument
30
               PMIX ERR INVALID ARGS
                                            Invalid arguments
31
               PMIX_ERR_INVALID_KEY
                                          Invalid key
32
               PMIX ERR INVALID KEY LENGTH
                                                   Invalid key length
33
                                               Invalid key/value pair
               PMIX ERR INVALID KEYVALP
34
                                              Invalid argument length
               PMIX ERR INVALID LENGTH
35
               PMIX ERR INVALID NAMESPACE
                                                  Invalid namespace
36
               PMIX_ERR_INVALID_NUM_ARGS
                                                Invalid number of arguments
37
                                                   Invalid number parsed
               PMIX ERR INVALID NUM PARSED
38
               PMIX ERR INVALID SIZE
                                            Invalid size
39
               PMIX ERR INVALID VAL
                                          Invalid value
```

1	PMIX_ERR_INVALID_VAL_LENGTH Invalid value length
2	PMIX_ERR_NOT_IMPLEMENTED Not implemented
3	PMIX_ERR_PACK_MISMATCH Pack mismatch
4	PMIX_ERR_PROC_ENTRY_NOT_FOUND Process not found
5	PMIX_ERR_PROC_REQUESTED_ABORT Process is already requested to abort
6	PMIX_ERR_READY_FOR_HANDSHAKE Ready for handshake
7	PMIX_ERR_SERVER_FAILED_REQUEST Failed to connect to the server
8	PMIX_ERR_SERVER_NOT_AVAIL Server is not available
9	PMIX_ERR_SILENT Silent error
10	PMIX_GDS_ACTION_COMPLETE The Global Data Storage (GDS) action has completed
11	PMIX_NOTIFY_ALLOC_COMPLETE Notify that a requested allocation operation is complete - the result
12	of the request will be included in the <i>info</i> array

B.7.2 Deprecated attributes

```
The following attributes were deprecated in v3.2:
```

```
PMIX_ARCH "pmix.arch" (uint32_t)
Architecture flag.
```

PMIX_COLLECTIVE_ALGO "pmix.calgo" (char*)

Comma-delimited list of algorithms to use for the collective operation. PMIx does not impose any requirements on a host environment's collective algorithms. Thus, the acceptable values for this attribute will be environment-dependent - users are encouraged to check their host environment for supported values.

```
PMIX_DSTPATH "pmix.dstpath" (char*)
```

Path to shared memory data storage (dstore) files. Deprecated from Standard as being implementation specific.

```
PMIX_HWLOC_HOLE_KIND "pmix.hwlocholek" (char*)
```

Kind of VM "hole" HWLOC should use for shared memory

```
PMIX_HWLOC_SHARE_TOPO "pmix.hwlocsh" (bool)
```

Share the HWLOC topology via shared memory

PMIX HWLOC SHMEM ADDR "pmix.hwlocaddr" (size_t)

Address of the HWLOC shared memory segment.

PMIX_HWLOC_SHMEM_FILE "pmix.hwlocfile" (char*)

Path to the HWLOC shared memory file.

PMIX_HWLOC_SHMEM_SIZE "pmix.hwlocsize" (size_t)

Size of the HWLOC shared memory segment.

PMIX HWLOC XML V1 "pmix.hwlocxml1" (char*)

XML representation of local topology using HWLOC's v1.x format.

PMIX_HWLOC_XML_V2 "pmix.hwlocxml2" (char*)

XML representation of local topology using HWLOC's v2.x format.

PMIX_LOCAL_TOPO "pmix.ltopo" (char*)

XML representation of local node topology.

PMIX_MAPPER "pmix.mapper" (char*)

13 14

15

16 17

18

19

20

21

22

23

24

25

26

27

28

29

30

31 32

33

34 35

36

37

38

39 40

```
1
                      Mapping mechanism to use for placing spawned processes - when accessed using PMIx_Get, use the
 2
                      PMIX RANK WILDCARD value for the rank to discover the mapping mechanism used for the
 3
                      provided namespace.
 4
                PMIX MAP_BLOB "pmix.mblob" (pmix_byte_object_t)
 5
                      Packed blob of process location.
 6
                PMIX_NON_PMI "pmix.nonpmi" (bool)
 7
                      Spawned processes will not call PMIx_Init.
 8
                PMIX_PROC_BLOB "pmix.pblob" (pmix_byte_object_t)
 9
                      Packed blob of process data.
10
                PMIX_PROC_URI "pmix.puri" (char*)
11
                      URI containing contact information for the specified process.
                PMIX TOPOLOGY_FILE "pmix.topo.file" (char*)
12
13
                      Full path to file containing XML topology description
14
                PMIX_TOPOLOGY_SIGNATURE "pmix.toposig" (char*)
15
                      Topology signature string.
16
                PMIX_TOPOLOGY_XML "pmix.topo.xml" (char*)
17
                      XML-based description of topology
```

B.8 Version 4.0: Dec. 2020

18

19

20

21

22

23

24

25

26

27

28

29

30

31

32

33

34

35

36

37

38

39

40

41

NOTE: The PMIx Standard document has undergone significant reorganization in an effort to become more user-friendly. Highlights include:

- Moving all added, deprecated, and removed items to this revision log section to make them more visible
- Co-locating constants and attribute definitions with the primary API that uses them citations and hyperlinks are retained elsewhere
- Splitting the Key-Value Management chapter into separate chapters on the use of reserved keys, non-reserved keys, and non-process-related key-value data exchange
- Creating a new chapter on synchronization and data access methods
- Removing references to specific implementations of PMIx and to implementation-specific features and/or behaviors

In addition to the reorganization, the following changes were introduced in v4.0 of the PMIx Standard:

- Clarified that the PMIx_Fence_nb operation can immediately return PMIX_OPERATION_SUCCEEDED
 in lieu of passing the request to a PMIx server if only the calling process is involved in the operation
- Added the PMIx_Register_attributes API by which a host environment can register the attributes it supports for each server-to-host operation
- Added the ability to query supported attributes from the PMIx tool, client and server libraries, as well as the
 host environment via the new pmix_regattr_t structure. Both human-readable and machine-parsable
 output is supported. New attributes to support this operation include:
 - PMIX_CLIENT_ATTRIBUTES, PMIX_SERVER_ATTRIBUTES, PMIX_TOOL_ATTRIBUTES, and
 PMIX_HOST_ATTRIBUTES to identify which library supports the attribute; and
 - PMIX_MAX_VALUE, PMIX_MIN_VALUE, and PMIX_ENUM_VALUE to provide machine-parsable description of accepted values
- Add PMIX APP WILDCARD to reference all applications within a given job

1

15

20 21 22

23

24 25

26 27 28

29 30 31

32 33

34 35

36

37 38

39

40

41 42 • Fix signature of blocking APIs PMIx_Allocation_request, PMIx_Job_control, PMIx Process monitor, PMIx Get credential, and PMIx Validate credential to allow return of results

• Update description to provide an option for blocking behavior of the PMIx Register event handler, PMIx Deregister event handler, PMIx_Notify_event, PMIx_IOF_pull, PMIx_IOF_deregister, and PMIx_IOF_push APIs. The need for blocking forms of these functions was not initially anticipated but has emerged over time. For these functions, the return value is sufficient to provide the caller with information otherwise returned via callback. Thus, use of a NULL value as the callback function parameter was deemed a minimal disruption method for providing the desired capability

- Added a chapter on fabric support that includes new APIs, datatypes, and attributes
- Added a chapter on process sets and groups that includes new APIs and attributes
- Added APIs and a new datatypes to support generation and parsing of PMIx locality and cpuset strings
- Added a new chapter on tools that provides deeper explanation on their operation and collecting all tool-relevant definitions into one location. Also introduced two new APIs and removed restriction that limited tools to being connected to only one server at a time.
- Extended behavior of **PMIx_server_init** to scalably expose the topology description to the local clients. This includes creating any required shared memory backing stores and/or XML representations, plus ensuring that all necessary key-value pairs for clients to access the description are included in the job-level information provided to each client.
- Added a new API by which the host can manually progress the PMIx library in lieu of the library's own progress thread. s

The above changes included introduction of the following APIs and data types:

Client APIs

```
- PMIx_Group_construct, PMIx_Group_construct_nb
 - PMIx_Group_destruct, PMIx_Group_destruct_nb
 - PMIx_Group_invite, PMIx_Group_invite_nb
 - PMIx Group join, PMIx Group join nb
 - PMIx Group leave, PMIx Group leave nb
 - PMIx Get relative locality, PMIx Load topology
 - PMIx Parse cpuset string, PMIx Get cpuset
 - PMIx_Link_state_string, PMIx_Job_state_string
 - PMIx_Device_type_string
 - PMIx_Fabric_register, PMIx_Fabric_register_nb
 - PMIx Fabric update, PMIx Fabric update nb
 - PMIx Fabric deregister, PMIx Fabric deregister nb
 - PMIx_Compute_distances, PMIx_Compute_distances_nb
 - PMIx Get attribute string, PMIx Get attribute name
 - PMIx Progress

    Server APIs
```

- - PMIx_server_generate_locality_string
 - PMIx Register attributes

```
1
               - PMIx_server_define_process_set, PMIx_server_delete_process_set
2
               - pmix_server_grp_fn_t, pmix_server_fabric_fn_t
 3
               - pmix_server_client_connected2_fn_t
4
               - PMIx_server_generate_cpuset_string
 5
               - PMIx server register resources, PMIx server deregister resources
             • Tool APIs
6
 7
               - PMIx tool disconnect
8
               - PMIx tool set server
9
               - PMIx tool attach to server
10
               - PMIx_tool_get_servers
             • Data types
11
12
               - pmix_regattr_t
13
               - pmix_cpuset_t
14
               - pmix_topology_t
15
               - pmix_locality_t
16
               - pmix bind envelope t
17
               - pmix_group_opt_t
18
               - pmix_group_operation_t
19
               - pmix_fabric_t
20
               - pmix_device_distance_t
21
               - pmix_coord_t
22
               - pmix_coord_view_t
23
               - pmix_geometry_t
24
               - pmix link state t
25
               - pmix job state t
26
               - pmix_device_type_t
27

    Callback functions

28
               - pmix_device_dist_cbfunc_t
    B.8.1 Added Constants
29
```

General error constants PMIX_ERR_EXISTS_OUTSIDE_SCOPE

PMIX_ERR_PARAM_VALUE_NOT_SUPPORTED

PMIX_ERR_EMPTY

30

31

32

33

1	Data type constants
2	PMIX_COORD
3	PMIX REGATTR
4	PMIX REGEX
5	PMIX JOB STATE
6	PMIX LINK STATE
7	PMIX PROC CPUSET
8	PMIX GEOMETRY
9	PMIX DEVICE DIST
10	PMIX ENDPOINT
11	PMIX TOPO
12	PMIX DEVTYPE
13	PMIX LOCTYPE
14	PMIX DATA TYPE MAX
15	PMIX COMPRESSED BYTE OBJECT
16	
17	Info directives
18	PMIX_INFO_REQD_PROCESSED
19	
20	Convey constants
20	Server constants
21	PMIX_ERR_REPEAT_ATTR_REGISTRATION
22	
23	Job-Mgmt constants
-0 24	PMIX ERR CONFLICTING CLEANUP DIRECTIVES
- · 25	11111_1111_00111110_01111101_5111110111111
26	Publish constants
27	PMIX_ERR_DUPLICATE_KEY
28	
20	Tool constants
29	Tool constants
30	PMIX_LAUNCHER_READY
31	PMIX_ERR_IOF_FAILURE
32	PMIX_ERR_IOF_COMPLETE
33	PMIX_EVENT_JOB_START
34	PMIX_LAUNCH_COMPLETE
35	PMIX_EVENT_JOB_END
36 37	PMIX_EVENT_SESSION_START
-	PMIX_EVENT_SESSION_END
38 20	PMIX_ERR_PROC_TERM_WO_SYNC
39 40	PMIX_ERR_JOB_CANCELED
40 41	PMIX_ERR_JOB_ABORTED
+ 1	
40	PMIX_ERR_JOB_KILLED_BY_CMD
42 43	PMIX_ERR_JOB_RILLED_BI_CMD PMIX_ERR_JOB_ABORTED_BY_SIG PMIX_ERR_JOB_TERM_WO_SYNC

1	PMIX ERR JOB SENSOR BOUND EXCEEDED
2	PMIX ERR JOB NON ZERO TERM
3	PMIX ERR JOB ABORTED BY SYS EVENT
4	PMIX DEBUG WAITING FOR NOTIFY
5	PMIX DEBUGGER RELEASE
6	
-	
7	Fabric constants
8	PMIX_FABRIC_UPDATE_PENDING
9	PMIX_FABRIC_UPDATED
10	PMIX_FABRIC_UPDATE_ENDPOINTS
11	PMIX_COORD_VIEW_UNDEF
12	PMIX_COORD_LOGICAL_VIEW
13	PMIX_COORD_PHYSICAL_VIEW
14	PMIX_LINK_STATE_UNKNOWN
15	PMIX_LINK_DOWN
16	PMIX_LINK_UP
17	PMIX_FABRIC_REQUEST_INFO
18	PMIX_FABRIC_UPDATE_INFO
19	
20	Sets-Groups constants
20 21	PMIX PROCESS SET DEFINE
22	PMIX_PROCESS_SET_DEFINE PMIX PROCESS SET DELETE
23	PMIX_FROCESS_SEI_DELETE PMIX_GROUP_INVITED
23 24	PMIX_GROUP_LEFT
2 4 25	PMIX_GROUP_LEFT PMIX GROUP MEMBER FAILED
26 26	PMIX_GROUP_NEMBER_FAILED PMIX GROUP INVITE ACCEPTED
27	PMIX_GROUP_INVITE_ACCEPTED PMIX GROUP INVITE DECLINED
28	PMIX GROUP INVITE FAILED
29	PMIX GROUP MEMBERSHIP UPDATE
30	PMIX GROUP CONSTRUCT ABORT
31	PMIX GROUP CONSTRUCT COMPLETE
32	PMIX GROUP LEADER FAILED
33	PMIX GROUP LEADER SELECTED
34	PMIX GROUP CONTEXT ID ASSIGNED
35	TMTM_GROOT_GONTENT_ID_NGGTGNED
36	Process-Mgmt constants
37	PMIX_ERR_JOB_ALLOC_FAILED
38	PMIX_ERR_JOB_APP_NOT_EXECUTABLE
39	PMIX_ERR_JOB_NO_EXE_SPECIFIED
40	PMIX_ERR_JOB_FAILED_TO_MAP
41	PMIX_ERR_JOB_FAILED_TO_LAUNCH
42	PMIX_LOCALITY_UNKNOWN
43	PMIX_LOCALITY_NONLOCAL
44	PMIX_LOCALITY_SHARE_HWTHREAD
45	PMIX_LOCALITY_SHARE_CORE

```
1
             PMIX_LOCALITY_SHARE_L1CACHE
2
             PMIX LOCALITY SHARE L2CACHE
3
             PMIX LOCALITY SHARE L3CACHE
4
             PMIX LOCALITY SHARE PACKAGE
5
             PMIX LOCALITY SHARE NUMA
6
             PMIX LOCALITY SHARE NODE
7
             Events
8
9
             PMIX EVENT SYS BASE
10
             PMIX_EVENT_NODE_DOWN
11
             PMIX_EVENT_NODE_OFFLINE
```

B.8.2 Added Attributes

Sync-Access attributes

PMIX EVENT SYS OTHER

```
PMIX_COLLECT_GENERATED_JOB_INFO "pmix.collect.gen" (bool)
```

Collect all job-level information (i.e., reserved keys) that was locally generated by PMIx servers. Some job-level information (e.g., distance between processes and fabric devices) is best determined on a distributed basis as it primarily pertains to local processes. Should remote processes need to access the information, it can either be obtained collectively using the PMIx_Fence operation with this directive, or can be retrieved one peer at a time using PMIx_Get without first having performed the job-wide collection.

```
PMIX_ALL_CLONES_PARTICIPATE "pmix.clone.part" (bool)
```

All *clones* of the calling process must participate in the collective operation.

```
PMIX_GET_POINTER_VALUES "pmix.get.pntrs" (bool)
```

Request that any pointers in the returned value point directly to values in the key-value store. The user *must not* release any returned data pointers.

```
PMIX_GET_STATIC_VALUES "pmix.get.static" (bool)
```

Request that the data be returned in the provided storage location. The caller is responsible for destructing the **pmix_value_t** using the **PMIX_VALUE_DESTRUCT** macro when done.

```
PMIX GET REFRESH CACHE "pmix.get.refresh" (bool)
```

When retrieving data for a remote process, refresh the existing local data cache for the process in case new values have been put and committed by the process since the last refresh. Local process information is assumed to be automatically updated upon posting by the process. A **NULL** key will cause all values associated with the process to be refreshed - otherwise, only the indicated key will be updated. A process rank of **PMIX_RANK_WILDCARD** can be used to update job-related information in dynamic environments. The user is responsible for subsequently updating refreshed values they may have cached in their own local memory.

```
PMIX QUERY_RESULTS "pmix.gry.res" (pmix_data_array_t)
```

1 2 3 4 5 6	Contains an array of query results for a given <code>pmix_query_t</code> passed to the <code>PMIx_Query_info</code> APIs. If qualifiers were included in the query, then the first element of the array shall be the <code>PMIX_QUERY_QUALIFIERS</code> attribute containing those qualifiers. Each of the remaining elements of the array is a <code>pmix_info_t</code> containing the query key and the corresponding value returned by the query. This attribute is solely for reporting purposes and cannot be used in <code>PMIx_Get</code> or other query operations.
7 8 9	PMIX_QUERY_QUALIFIERS "pmix.qry.quals" (pmix_data_array_t) Contains an array of qualifiers that were included in the query that produced the provided results. This attribute is solely for reporting purposes and cannot be used in PMIx_Get or other query operations.
0 1	<pre>PMIX_QUERY_SUPPORTED_KEYS "pmix.qry.keys" (char*) Returns comma-delimited list of keys supported by the query function. NO QUALIFIERS.</pre>
2 3 4	<pre>PMIX_QUERY_SUPPORTED_QUALIFIERS "pmix.qry.quals" (char*) Return comma-delimited list of qualifiers supported by a query on the provided key, instead of actually performing the query on the key. NO QUALIFIERS.</pre>
5 6 7 8	PMIX_QUERY_NAMESPACE_INFO "pmix.qry.nsinfo" (pmix_data_array_t*) Return an array of active namespace information - each element will itself contain an array including the namespace plus the command line of the application executing within it. OPTIONAL QUALIFIERS: PMIX_NSPACE of specific namespace whose info is being requested.
9 20 21 22	PMIX_QUERY_ATTRIBUTE_SUPPORT "pmix.qry.attrs" (bool) Query list of supported attributes for specified APIs. REQUIRED QUALIFIERS: one or more of PMIX_CLIENT_FUNCTIONS, PMIX_SERVER_FUNCTIONS, PMIX_TOOL_FUNCTIONS, and PMIX_HOST_FUNCTIONS.
23 24 25	PMIX_QUERY_AVAIL_SERVERS "pmix.qry.asrvrs" (pmix_data_array_t*) Return an array of pmix_info_t, each element itself containing a PMIX_SERVER_INFO_ARRAY entry holding all available data for a server on this node to which the caller might be able to connect.
26 27 28	<pre>PMIX_SERVER_INFO_ARRAY "pmix.srv.arr" (pmix_data_array_t) Array of pmix_info_t about a given server, starting with its PMIX_NSPACE and including at least one of the rendezvous-required pieces of information.</pre>
9 80	PMIX_CLIENT_FUNCTIONS "pmix.client.fns" (bool) Request a list of functions supported by the PMIx client library.
31 32	PMIX_CLIENT_ATTRIBUTES "pmix.client.attrs" (bool) Request attributes supported by the PMIx client library.
3 34	PMIX_SERVER_FUNCTIONS "pmix.srvr.fns" (bool) Request a list of functions supported by the PMIx server library.
35 36	PMIX_SERVER_ATTRIBUTES "pmix.srvr.attrs" (bool) Request attributes supported by the PMIx server library.
37 88	PMIX_HOST_FUNCTIONS "pmix.srvr.fns" (bool) Request a list of functions supported by the host environment.
9	PMIX_HOST_ATTRIBUTES "pmix.host.attrs" (bool)

1 Request attributes supported by the host environment. 2 PMIX_TOOL_FUNCTIONS "pmix.tool.fns" (bool) 3 Request a list of functions supported by the PMIx tool library. 4 PMIX TOOL ATTRIBUTES "pmix.setup.env" (bool) 5 Request attributes supported by the PMIx tool library functions. Server attributes 6 PMIX_TOPOLOGY2 "pmix.topo2" (pmix_topology_t) 7 8 Provide a pointer to an implementation-specific description of the local node topology. 9 PMIX SERVER SHARE TOPOLOGY "pmix.srvr.share" (bool) 10 The PMIx server is to share its copy of the local node topology (whether given to it or self-discovered) 11 with any clients. 12 PMIX SERVER_SESSION_SUPPORT "pmix.srvr.sess" (bool) 13 The host RM wants to declare itself as being the local session server for PMIx connection requests. 14 PMIX_SERVER_START_TIME "pmix.srvr.strtime" (char*) 15 Time when the server started - i.e., when the server created it's rendezvous file (given in ctime string 16 format). 17 PMIX_SERVER_SCHEDULER "pmix.srv.sched" (bool) 18 Server is supporting system scheduler and desires access to appropriate WLM-supporting features. 19 Indicates that the library is to be initialized for scheduler support. 20 PMIX_JOB_INFO_ARRAY "pmix.job.arr" (pmix_data_array_t) 21 Provide an array of pmix info t containing job-realm information. The PMIX SESSION ID 22 attribute of the session containing the job is required to be included in the array whenever the PMIx 23 server library may host multiple sessions (e.g., when executing with a host RM daemon). As 24 information is registered one job (aka namespace) at a time via the 25 PMIx_server_register_nspace API, there is no requirement that the array contain either the 26 PMIX NSPACE or PMIX JOBID attributes when used in that context (though either or both of them 27 may be included). At least one of the job identifiers must be provided in all other contexts where the 28 job being referenced is ambiguous. 29 PMIX_APP_INFO_ARRAY "pmix.app.arr" (pmix_data_array_t) 30 Provide an array of pmix info t containing application-realm information. The PMIX NSPACE 31 or PMIX JOBID attributes of the job containing the application, plus its PMIX APPNUM attribute, 32 must to be included in the array when the array is *not* included as part of a call to 33 **PMIx_server_register_nspace** - i.e., when the job containing the application is ambiguous. The job identification is otherwise optional. 34 35 PMIX_PROC_INFO_ARRAY "pmix.pdata" (pmix_data_array_t) 36 Provide an array of pmix info t containing process-realm information. The PMIX RANK and 37 PMIX NSPACE attributes, or the PMIX PROCID attribute, are required to be included in the array when the array is not included as part of a call to PMIx_server_register_nspace - i.e., when 38 39 the job containing the process is ambiguous. All three may be included if desired. When the array is 40 included in some broader structure that identifies the job, then only the PMIX_RANK or the 41 **PMIX PROCID** attribute must be included (the others are optional).

1 2 3 4	<pre>PMIX_NODE_INFO_ARRAY "pmix.node.arr" (pmix_data_array_t) Provide an array of pmix_info_t containing node-realm information. At a minimum, either the PMIX_NODEID or PMIX_HOSTNAME attribute is required to be included in the array, though both may be included.</pre>
5 6	PMIX_MAX_VALUE "pmix.descr.maxval" (varies) Used in pmix_regattr_t to describe the maximum valid value for the associated attribute.
7 8	PMIX_MIN_VALUE "pmix.descr.minval" (varies) Used in pmix_regattr_t to describe the minimum valid value for the associated attribute.
9 0 1 2 3	PMIX_ENUM_VALUE "pmix.descr.enum" (char*) Used in pmix_regattr_t to describe accepted values for the associated attribute. Numerical values shall be presented in a form convertible to the attribute's declared data type. Named values (i.e., values defined by constant names via a typical C-language enum declaration) must be provided as their numerical equivalent.
4 5 6	PMIX_HOMOGENEOUS_SYSTEM "pmix.homo" (bool) The nodes comprising the session are homogeneous - i.e., they each contain the same number of identical packages, fabric interfaces, GPUs, and other devices.
7 8 9 20	PMIX_REQUIRED_KEY "pmix.req.key" (char*) Identifies a key that must be included in the requested information. If the specified key is not already available, then the PMIx servers are required to delay response to the dmodex request until either the key becomes available or the request times out.
21 22 23 24	Job-Mgmt attributes PMIX_ALLOC_ID "pmix.alloc.id" (char*) A string identifier (provided by the host environment) for the resulting allocation which can later be used to reference the allocated resources in, for example, a call to PMIx_Spawn.
25 26 27	<pre>PMIX_ALLOC_QUEUE "pmix.alloc.queue" (char*) Name of the WLM queue to which the allocation request is to be directed, or the queue being referenced in a query.</pre>
28 29 30 31	Publish attributes PMIX_ACCESS_PERMISSIONS "pmix.aperms" (pmix_data_array_t) Define access permissions for the published data. The value shall contain an array of pmix_info_t structs containing the specified permissions.
3 3	<pre>PMIX_ACCESS_USERIDS "pmix.auids" (pmix_data_array_t) Array of effective UIDs that are allowed to access the published data.</pre>
34 35	PMIX_ACCESS_GRPIDS "pmix.agids" (pmix_data_array_t) Array of effective GIDs that are allowed to access the published data.

Reserved keys 1 2 PMIX NUM ALLOCATED NODES "pmix.num.anodes" (uint32_t) 3 Number of nodes in the specified realm regardless of whether or not they currently host processes. 4 Defaults to the *job* realm. 5 PMIX_NUM_NODES "pmix.num.nodes" (uint32_t) 6 Number of nodes currently hosting processes in the specified realm. Defaults to the *job* realm. 7 PMIX_CMD_LINE "pmix.cmd.line" (char*) 8 Command line used to execute the specified job (e.g., "mpirun -n 2 -map-by foo ./myapp: -n 4 9 ./myapp2"). If the job was created by a call to PMIx Spawn, the string is an inorder concatenation of 10 the values of **PMIX APP ARGV** for each application in the job using the character ':' as a separator. 11 PMIX APP_ARGV "pmix.app.argv" (char*) 12 Consolidated argy passed to the spawn command for the given application (e.g., "./myapp arg1 arg2 arg3"). 13 14 PMIX_PACKAGE_RANK "pmix.pkgrank" (uint16_t) 15 Rank of the specified process on the package where this process resides - refers to the numerical location (starting from zero) of the process on its package when counting only those processes from the 16 17 same job that share the package, ordered by their overall rank within that job. Note that processes that are not bound to PUs within a single specific package cannot have a package rank. 18 19 PMIX REINCARNATION "pmix.reinc" (uint32 t) 20 Number of times this process has been re-instantiated - i.e, a value of zero indicates that the process 21 has never been restarted. 5 22 PMIX HOSTNAME ALIASES "pmix.alias" (char*) 23 Comma-delimited list of names by which the target node is known. 24 PMIX HOSTNAME KEEP FQDN "pmix.fqdn" (bool) FQDNs are being retained by the PMIx library. 25 26 PMIX_CPUSET_BITMAP "pmix.bitmap" (pmix_cpuset_t*) 27 Bitmap applied to the process upon launch. 28 PMIX_EXTERNAL_PROGRESS "pmix.evext" (bool) 29 The host shall progress the PMIx library via calls to PMIx_Progress 30 PMIX_NODE_MAP_RAW "pmix.nmap.raw" (char*) 31 Comma-delimited list of nodes containing procs within the specified realm. Defaults to the *job* realm. 32 PMIX PROC MAP RAW "pmix.pmap.raw" (char*) 33 Semi-colon delimited list of strings, each string containing a comma-delimited list of ranks on the 34 corresponding node within the specified realm. Defaults to the *job* realm. 35 Tool attributes PMIX_TOOL_CONNECT_OPTIONAL "pmix.tool.conopt" (bool) 36 37 The tool shall connect to a server if available, but otherwise continue to operate unconnected. 38 PMIX_TOOL_ATTACHMENT_FILE "pmix.tool.attach" (char*) 39 Pathname of file containing connection information to be used for attaching to a specific server.

1 PMIX_LAUNCHER_RENDEZVOUS_FILE "pmix.tool.lncrnd" (char*)

Pathname of file where the launcher is to store its connection information so that the spawning tool can connect to it.

PMIX_PRIMARY_SERVER "pmix.pri.srvr" (bool)

The server to which the tool is connecting shall be designated the *primary* server once connection has been accomplished.

PMIX_NOHUP "pmix.nohup" (bool)

Any processes started on behalf of the calling tool (or the specified namespace, if such specification is included in the list of attributes) should continue after the tool disconnects from its server.

PMIX_LAUNCHER_DAEMON "pmix.lnch.dmn" (char*)

Path to executable that is to be used as the backend daemon for the launcher. This replaces the launcher's own daemon with the specified executable. Note that the user is therefore responsible for ensuring compatibility of the specified executable and the host launcher.

PMIX_FORKEXEC_AGENT "pmix.frkex.agnt" (char*)

Path to executable that the launcher's backend daemons are to fork/exec in place of the actual application processes. The fork/exec agent shall connect back (as a PMIx tool) to the launcher's daemon to receive its spawn instructions, and is responsible for starting the actual application process it replaced. See Section 17.4.3 for details.

PMIX_EXEC_AGENT "pmix.exec.agnt" (char*)

Path to executable that the launcher's backend daemons are to fork/exec in place of the actual application processes. The launcher's daemon shall pass the full command line of the application on the command line of the exec agent, which shall not connect back to the launcher's daemon. The exec agent is responsible for exec'ing the specified application process in its own place. See Section 17.4.3 for details.

PMIX_IOF_PUSH_STDIN "pmix.iof.stdin" (bool)

Requests that the PMIx library collect the **stdin** of the requester and forward it to the processes specified in the **PMIx_IOF_push** call. All collected data is sent to the same targets until **stdin** is closed, or a subsequent call to **PMIx_IOF_push** is made that includes the **PMIX_IOF_COMPLETE** attribute indicating that forwarding of **stdin** is to be terminated.

PMIX_IOF_COPY "pmix.iof.cpy" (bool)

Requests that the host environment deliver a copy of the specified output stream(s) to the tool, letting the stream(s) continue to also be delivered to the default location. This allows the tool to tap into the output stream(s) without redirecting it from its current final destination.

PMIX IOF REDIRECT "pmix.iof.redir" (bool)

Requests that the host environment intercept the specified output stream(s) and deliver it to the requesting tool instead of its current final destination. This might be used, for example, during a debugging procedure to avoid injection of debugger-related output into the application's results file. The original output stream(s) destination is restored upon termination of the tool.

PMIX_DEBUG_TARGET "pmix.dbg.tgt" (pmix_proc_t*)

Identifier of process(es) to be debugged - a rank of **PMIX_RANK_WILDCARD** indicates that all processes in the specified namespace are to be included.

1 PMIX_DEBUG_DAEMONS_PER_PROC "pmix.dbg.dpproc" (uint16_t) 2 Number of debugger daemons to be spawned per application process. The launcher is to pass the 3 identifier of the namespace to be debugged by including the PMIX DEBUG TARGET attribute in the 4 daemon's job-level information. The debugger daemons spawned on a given node are responsible for 5 self-determining their specific target process(es) - e.g., by referencing their own PMIX_LOCAL_RANK 6 in the daemon debugger job versus the corresponding PMIX_LOCAL_RANK of the target processes on 7 the node. 8 PMIX_DEBUG_DAEMONS_PER_NODE "pmix.dbg.dpnd" (uint16_t) 9 Number of debugger daemons to be spawned on each node where the target job is executing. The 10 launcher is to pass the identifier of the namespace to be debugged by including the 11 PMIX DEBUG TARGET attribute in the daemon's job-level information. The debugger daemons 12 spawned on a given node are responsible for self-determining their specific target process(es) - e.g., by 13 referencing their own PMIX_LOCAL_RANK in the daemon debugger job versus the corresponding 14 **PMIX LOCAL RANK** of the target processes on the node. 15 PMIX_WAIT_FOR_CONNECTION "pmix.wait.conn" (bool) 16 Wait until the specified process has connected to the requesting tool or server, or the operation times 17 out (if the **PMIX_TIMEOUT** directive is included in the request). 18 PMIX_LAUNCH_DIRECTIVES "pmix.lnch.dirs" (pmix_data_array_t*) Array of pmix_info_t containing directives for the launcher - a convenience attribute for retrieving 19 20 all directives with a single call to PMIx_Get. Fabric attributes 21 22 PMIX SERVER SCHEDULER "pmix.srv.sched" (bool) 23 Server is supporting system scheduler and desires access to appropriate WLM-supporting features. 24 Indicates that the library is to be initialized for scheduler support. 25 PMIX_FABRIC_COST_MATRIX "pmix.fab.cm" (pointer) 26 Pointer to a two-dimensional square array of point-to-point relative communication costs expressed as 27 uint16_t values. 28 PMIX_FABRIC_GROUPS "pmix.fab.grps" (string) 29 A string delineating the group membership of nodes in the overall system, where each fabric group 30 consists of the group number followed by a colon and a comma-delimited list of nodes in that group, 31 with the groups delimited by semi-colons (e.g., 0:node000, node002, node004, node006; 32 1:node001, node003, node005, node007) 33 PMIX FABRIC VENDOR "pmix.fab.vndr" (string) Name of the vendor (e.g., Amazon, Mellanox, HPE, Intel) for the specified fabric. 34 35 PMIX FABRIC IDENTIFIER "pmix.fab.id" (string) 36 An identifier for the specified fabric (e.g., MgmtEthernet, Slingshot-11, OmniPath-1). 37 PMIX_FABRIC_INDEX "pmix.fab.idx" (size_t) 38 The index of the fabric as returned in **pmix fabric t**. 39 PMIX FABRIC NUM DEVICES "pmix.fab.nverts" (size t) 40 Total number of fabric devices in the overall system - corresponds to the number of rows or columns in

41

the cost matrix.

1 2

PMIX_FABRIC_COORDINATES "pmix.fab.coords" (pmix_data_array_t)

3 4 5

6

8

7

9 10 11

> 12 13 14

20 21 22

19

23

32 33 34

35

40 41

42 43 Array of pmix geometry t fabric coordinates for devices on the specified node. The array will contain the coordinates of all devices on the node, including values for all supported coordinate views. The information for devices on the local node shall be provided if the node is not specified in the request.

PMIX_FABRIC_DIMS "pmix.fab.dims" (uint32_t)

Number of dimensions in the specified fabric plane/view. If no plane is specified in a request, then the dimensions of all planes in the overall system will be returned as a pmix_data_array_t containing an array of uint32_t values. Default is to provide dimensions in logical view.

PMIX_FABRIC_ENDPT "pmix.fab.endpt" (pmix_data_array_t)

Fabric endpoints for a specified process. As multiple endpoints may be assigned to a given process (e.g., in the case where multiple devices are associated with a package to which the process is bound), the returned values will be provided in a pmix_data_array_t of pmix_endpoint_t elements.

PMIX_FABRIC_SHAPE "pmix.fab.shape" (pmix_data_array_t*)

The size of each dimension in the specified fabric plane/view, returned in a pmix_data_array_t containing an array of uint32 t values. The size is defined as the number of elements present in that dimension - e.g., the number of devices in one dimension of a physical view of a fabric plane. If no plane is specified, then the shape of each plane in the overall system will be returned in a pmix_data_array_t array where each element is itself a two-element array containing the PMIX_FABRIC_PLANE followed by that plane's fabric shape. Default is to provide the shape in logical view.

PMIX_FABRIC_SHAPE_STRING "pmix.fab.shapestr" (string)

Network shape expressed as a string (e.g., "10x12x2"). If no plane is specified, then the shape of each plane in the overall system will be returned in a pmix_data_array_t array where each element is itself a two-element array containing the PMIX FABRIC PLANE followed by that plane's fabric shape string. Default is to provide the shape in logical view.

PMIX_SWITCH_PEERS "pmix.speers" (pmix_data_array_t)

Peer ranks that share the same switch as the process specified in the call to PMIx Get. Returns a pmix_data_array_t array of pmix_info_t results, each element containing the PMIX SWITCH PEERS key with a three-element pmix data array t array of pmix info t containing the PMIX DEVICE ID of the local fabric device, the PMIX FABRIC SWITCH identifying the switch to which it is connected, and a comma-delimited string of peer ranks sharing the switch to which that device is connected.

PMIX_FABRIC_PLANE "pmix.fab.plane" (string)

ID string of a fabric plane (e.g., CIDR for Ethernet). When used as a modifier in a request for information, specifies the plane whose information is to be returned. When used directly as a key in a request, returns a pmix_data_array_t of string identifiers for all fabric planes in the overall system.

PMIX_FABRIC_SWITCH "pmix.fab.switch" (string)

ID string of a fabric switch. When used as a modifier in a request for information, specifies the switch whose information is to be returned. When used directly as a key in a request, returns a pmix_data_array_t of string identifiers for all fabric switches in the overall system.

1 2 3	PMIX_FABRIC_DEVICE "pmix.fabdev" (pmix_data_array_t) An array of pmix_info_t describing a particular fabric device using one or more of the attributes defined below. The first element in the array shall be the PMIX_DEVICE_ID of the device.
4 5	PMIX_FABRIC_DEVICE_INDEX "pmix.fabdev.idx" (uint32_t) Index of the device within an associated communication cost matrix.
6 7 8	PMIX_FABRIC_DEVICE_NAME "pmix.fabdev.nm" (string) The operating system name associated with the device. This may be a logical fabric interface name (e.g. "eth0" or "eno1") or an absolute filename.
9 10	<pre>PMIX_FABRIC_DEVICE_VENDOR "pmix.fabdev.vndr" (string)</pre>
11 12	PMIX_FABRIC_DEVICE_BUS_TYPE "pmix.fabdev.btyp" (string) The type of bus to which the device is attached (e.g., "PCI", "GEN-Z").
13 14	<pre>PMIX_FABRIC_DEVICE_VENDORID "pmix.fabdev.vendid" (string)</pre>
15 16	<pre>PMIX_FABRIC_DEVICE_DRIVER "pmix.fabdev.driver" (string) The name of the driver associated with the device.</pre>
17 18	<pre>PMIX_FABRIC_DEVICE_FIRMWARE "pmix.fabdev.fmwr" (string)</pre>
19 20 21	<pre>PMIX_FABRIC_DEVICE_ADDRESS "pmix.fabdev.addr" (string) The primary link-level address associated with the device, such as a MAC address. If multiple addresses are available, only one will be reported.</pre>
22 23 24	<pre>PMIX_FABRIC_DEVICE_COORDINATES "pmix.fab.coord" (pmix_geometry_t) The pmix_geometry_t fabric coordinates for the device, including values for all supported coordinate views.</pre>
25 26	PMIX_FABRIC_DEVICE_MTU "pmix.fabdev.mtu" (size_t) The maximum transfer unit of link level frames or packets, in bytes.
27 28	<pre>PMIX_FABRIC_DEVICE_SPEED "pmix.fabdev.speed" (size_t) The active link data rate, given in bits per second.</pre>
29 30 31 32	PMIX_FABRIC_DEVICE_STATE "pmix.fabdev.state" (pmix_link_state_t) The last available physical port state for the specified device. Possible values are PMIX_LINK_STATE_UNKNOWN, PMIX_LINK_DOWN, and PMIX_LINK_UP, to indicate if the port state is unknown or not applicable (unknown), inactive (down), or active (up).
33 34	<pre>PMIX_FABRIC_DEVICE_TYPE "pmix.fabdev.type" (string)</pre>
35 36 37 38 39	PMIX_FABRIC_DEVICE_PCI_DEVID "pmix.fabdev.pcidevid" (string) A node-level unique identifier for a PCI device. Provided only if the device is located on a PCI bus. The identifier is constructed as a four-part tuple delimited by colons comprised of the PCI 16-bit domain, 8-bit bus, 8-bit device, and 8-bit function IDs, each expressed in zero-extended hexadecimal form. Thus, an example identifier might be "abc1:0f:23:01". The combination of node identifier

1 2	(PMIX_HOSTNAME or PMIX_NODEID) and PMIX_FABRIC_DEVICE_PCI_DEVID shall be unique within the overall system.
3 4 5 6	Device attributes PMIX_DEVICE_DISTANCES "pmix.dev.dist" (pmix_data_array_t) Return an array of pmix_device_distance_t containing the minimum and maximum distances of the given process location to all devices of the specified type on the local node.
7 8 9	<pre>PMIX_DEVICE_TYPE "pmix.dev.type" (pmix_device_type_t)</pre> Bitmask specifying the type(s) of device(s) whose information is being requested. Only used as a directive/qualifier.
0 1	PMIX_DEVICE_ID "pmix.dev.id" (string) System-wide UUID or node-local OS name of a particular device.
2 3 4 5	Sets-Groups attributes PMIX_QUERY_NUM_PSETS "pmix.qry.psetnum" (size_t) Return the number of process sets defined in the specified range (defaults to PMIX_RANGE_SESSION).
6 7 8	<pre>PMIX_QUERY_PSET_NAMES "pmix.qry.psets" (pmix_data_array_t*) Return a pmix_data_array_t containing an array of strings of the process set names defined in the specified range (defaults to PMIX_RANGE_SESSION).</pre>
9 20	<pre>PMIX_QUERY_PSET_MEMBERSHIP "pmix.qry.pmems" (pmix_data_array_t*) Return an array of pmix_proc_t containing the members of the specified process set.</pre>
21 22	<pre>PMIX_PSET_NAME "pmix.pset.nm" (char*) The name of the newly defined process set.</pre>
23 24	PMIX_PSET_MEMBERS "pmix.pset.mems" (pmix_data_array_t*) An array of pmix_proc_t containing the members of the newly defined process set.
25 26	<pre>PMIX_PSET_NAMES "pmix.pset.nms" (pmix_data_array_t*) Returns an array of char* string names of the process sets in which the given process is a member.</pre>
27 28 29	PMIX_QUERY_NUM_GROUPS "pmix.qry.pgrpnum" (size_t) Return the number of process groups defined in the specified range (defaults to session). OPTIONAL QUALIFERS: PMIX_RANGE.
80 81 82	<pre>PMIX_QUERY_GROUP_NAMES "pmix.qry.pgrp" (pmix_data_array_t*) Return a pmix_data_array_t containing an array of string names of the process groups defined in the specified range (defaults to session). OPTIONAL QUALIFERS: PMIX_RANGE.</pre>
33 34 35	<pre>PMIX_QUERY_GROUP_MEMBERSHIP "pmix.qry.pgrpmems" (pmix_data_array_t*) Return a pmix_data_array_t of pmix_proc_t containing the members of the specified process group. REQUIRED QUALIFIERS: PMIX_GROUP_ID.</pre>
86 87 88 89	PMIX_GROUP_ID "pmix.grp.id" (char*) User-provided group identifier - as the group identifier may be used in PMIx operations, the user is required to ensure that the provided ID is unique within the scope of the host environment (e.g., by including some user-specific or application-specific prefix or suffix to the string).

```
1
                 PMIX_GROUP_LEADER "pmix.grp.ldr" (bool)
 2
                       This process is the leader of the group.
 3
                 PMIX_GROUP_OPTIONAL "pmix.grp.opt" (bool)
 4
                       Participation is optional - do not return an error if any of the specified processes terminate without
 5
                       having joined. The default is false.
 6
                 PMIX_GROUP_NOTIFY_TERMINATION "pmix.grp.notterm" (bool)
 7
                       Notify remaining members when another member terminates without first leaving the group.
 8
                 PMIX_GROUP_FT_COLLECTIVE "pmix.grp.ftcoll" (bool)
 9
                       Adjust internal tracking on-the-fly for terminated processes during a PMIx group collective operation.
10
                 PMIX_GROUP_ASSIGN_CONTEXT_ID "pmix.grp.actxid" (bool)
11
                       Requests that the RM assign a new context identifier to the newly created group. The identifier is an
12
                       unsigned, size t value that the RM guarantees to be unique across the range specified in the request.
13
                       Thus, the value serves as a means of identifying the group within that range. If no range is specified,
14
                       then the request defaults to PMIX RANGE SESSION.
15
                 PMIX_GROUP_LOCAL_ONLY "pmix.grp.lcl" (bool)
16
                       Group operation only involves local processes. PMIx implementations are required to automatically
17
                       scan an array of group members for local vs remote processes - if only local processes are detected, the
18
                       implementation need not execute a global collective for the operation unless a context ID has been
19
                       requested from the host environment. This can result in significant time savings. This attribute can be
20
                       used to optimize the operation by indicating whether or not only local processes are represented, thus
21
                       allowing the implementation to bypass the scan.
22
                 PMIX GROUP CONTEXT ID "pmix.grp.ctxid" (size t)
23
                       Context identifier assigned to the group by the host RM.
24
                 PMIX_GROUP_ENDPT_DATA "pmix.grp.endpt" (pmix_byte_object_t)
25
                       Data collected during group construction to ensure communication between group members is
26
                       supported upon completion of the operation.
27
                 PMIX_GROUP_NAMES "pmix.pgrp.nm" (pmix_data_array_t*)
28
                       Returns an array of char* string names of the process groups in which the given process is a member.
29
30
                 Process Mamt attributes
31
                 PMIX_OUTPUT_TO_DIRECTORY "pmix.outdir" (char*)
32
                       Direct output into files of form "<directory>/<jobid>/rank.<rank>/stdout[err]" -
33
                       can be assigned to the entire job (by including attribute in the job_info array) or on a per-application
34
                       basis in the info array for each pmix_app_t.
35
                 PMIX_TIMEOUT_STACKTRACES "pmix.tim.stack" (bool)
36
                       Include process stacktraces in timeout report from a job.
37
                 PMIX TIMEOUT REPORT STATE "pmix.tim.state" (bool)
38
                       Report process states in timeout report from a job.
39
                 PMIX NOTIFY JOB EVENTS "pmix.note.jev" (bool)
```

37 38 39 40	Tool environmental variables PMIX_LAUNCHER_RNDZ_URI PMIX_LAUNCHER_RNDZ_FILE PMIX_KEEPALIVE_PIPE
B.8.3	Added Environmental Variables
33 34 35	Event attributes PMIX_EVENT_TIMESTAMP "pmix.evtstamp" (time_t) System time when the associated event occurred.
30 31 32	<pre>PMIX_FIRST_ENVAR "pmix.envar.first" (pmix_envar_t*) Ensure the given value appears first in the specified envar using the separator character, creating the envar if it doesn't already exist</pre>
24 25 26 27 28 29	PMIX_LOG_COMPLETION "pmix.logcomp" (bool) Requests that the launcher log the PMIX_EVENT_JOB_END event for normal or abnormal termination of the spawned job using PMIx_Log, subject to the logging attributes of Section 12.4.3. The event shall include the returned status code (PMIX_JOB_TERM_STATUS) for the corresponding job; the identity (PMIX_PROCID) and exit status (PMIX_EXIT_CODE) of the first failed process, if applicable; and a PMIX_EVENT_TIMESTAMP indicating the time the termination occurred.
20 21 22 23	PMIX_LOG_JOB_EVENTS "pmix.log.jev" (bool) Requests that the launcher log the PMIX_EVENT_JOB_START, PMIX_LAUNCH_COMPLETE, and PMIX_EVENT_JOB_END events using PMIx_Log, subject to the logging attributes of Section 12.4.3.
17 18 19	PMIX_LOG_PROC_ABNORMAL_TERMINATION "pmix.logabproc" (bool) Requests that the launcher log the PMIX_EVENT_PROC_TERMINATED event only when a process abnormally terminates.
14 15 16	PMIX_LOG_PROC_TERMINATION "pmix.logproc" (bool) Requests that the launcher log the PMIX_EVENT_PROC_TERMINATED event whenever a process either normally or abnormally terminates.
1 2 3	<pre>PMIX_NOTIFY_PROC_ABNORMAL_TERMINATION "pmix.noteabproc" (bool) Requests that the launcher generate the PMIX_EVENT_PROC_TERMINATED event only when a process abnormally terminates.</pre>
8 9 10	PMIX_NOTIFY_PROC_TERMINATION "pmix.noteproc" (bool) Requests that the launcher generate the PMIX_EVENT_PROC_TERMINATED event whenever a process either normally or abnormally terminates.
2 3 4 5 6 7	and PMIX_EVENT_JOB_END events. Each event is to include at least the namespace of the corresponding job and a PMIX_EVENT_TIMESTAMP indicating the time the event occurred. Note that the requester must register for these individual events, or capture and process them by registering a default event handler instead of individual handlers and then process the events based on the returned status code. Another common method is to register one event handler for all job-related events, with a separate handler for non-job events - see PMIx_Register_event_handler for details.

B.8.4 Added Macros

1

5

11

24

26

27

28

29

30

- 2 PMIX CHECK RESERVED KEY PMIX INFO WAS PROCESSED PMIX INFO PROCESSED
- 3 PMIX_INFO_LIST_START PMIX_INFO_LIST_ADD PMIX_INFO_LIST_XFER
- 4 PMIX_INFO_LIST_CONVERT PMIX_INFO_LIST_RELEASE

B.8.5 Deprecated APIs

- 6 pmix_evhdlr_reg_cbfunc_t Renamed to pmix_hdlr_reg_cbfunc_t
- 7 The pmix_server_client_connected_fn_t server module entry point has been deprecated in favor of pmix_server_client_connected2_fn_t
- 9 PMIx_tool_connect_to_server Replaced by PMIx_tool_attach_to_server to allow return of the process identifier of the server to which the tool has attached.

B.8.6 Deprecated constants

- The following constants were deprecated in v4.0:
- 13 PMIX_ERR_DEBUGGER_RELEASE Renamed to PMIX_DEBUGGER_RELEASE
- 14 PMIX_ERR_JOB_TERMINATED Renamed to PMIX_EVENT_JOB_END
- 15 PMIX_EXISTS Renamed to PMIX_ERR_EXISTS
- 16 PMIX_ERR_PROC_ABORTED Consolidated with PMIX_EVENT_PROC_TERMINATED
- 17 PMIX_ERR_PROC_ABORTING Consolidated with PMIX_EVENT_PROC_TERMINATED
- 18 PMIX_ERR_LOST_CONNECTION_TO_SERVER Consolidated into PMIX_ERR_LOST_CONNECTION
- 19 PMIX ERR LOST PEER CONNECTION Consolidated into PMIX ERR LOST CONNECTION
- 20 PMIX_ERR_LOST_CONNECTION_TO_CLIENT Consolidated into PMIX_ERR_LOST_CONNECTION
- 21 PMIX ERR INVALID TERMINATION Renamed to PMIX ERR JOB TERM WO SYNC
- 22 PMIX_PROC_TERMINATED Renamed to PMIX_EVENT_PROC_TERMINATED
- 23 PMIX ERR NODE DOWN Renamed to PMIX EVENT NODE DOWN
 - PMIX_ERR_NODE_OFFLINE Renamed to PMIX_EVENT_NODE_OFFLINE
- 25 PMIX_ERR_SYS_OTHER Renamed to PMIX_EVENT_SYS_OTHER
 - **PMIX_CONNECT_REQUESTED** Connection has been requested by a PMIx-based tool deprecated as not required.
 - PMIX_PROC_HAS_CONNECTED A tool or client has connected to the PMIx server deprecated in favor of the new pmix_server_client_connected2_fn_t server module API

B.8.7 Removed constants

- The following constants were removed from the PMIx Standard in v4.0 as they are internal to a particular PMIx implementation.
- 33 PMIX ERR HANDSHAKE FAILED Connection handshake failed
- 34 PMIX_ERR_READY_FOR_HANDSHAKE Ready for handshake
- 35 PMIX ERR IN ERRNO Error defined in errno
- 36 PMIX_ERR_INVALID_VAL_LENGTH Invalid value length

```
1
               PMIX_ERR_INVALID_LENGTH
                                               Invalid argument length
 2
                                                  Invalid number of arguments
               PMIX ERR INVALID NUM ARGS
 3
               PMIX_ERR_INVALID_ARGS
                                             Invalid arguments
 4
               PMIX ERR INVALID NUM PARSED
                                                    Invalid number parsed
 5
               PMIX_ERR_INVALID_KEYVALP
                                                 Invalid key/value pair
 6
               PMIX ERR INVALID SIZE
                                             Invalid size
 7
               PMIX ERR PROC REQUESTED ABORT
                                                       Process is already requested to abort
 8
               PMIX_ERR_SERVER_FAILED_REQUEST
                                                        Failed to connect to the server
 9
               PMIX ERR PROC ENTRY NOT FOUND
                                                       Process not found
10
               PMIX_ERR_INVALID_ARG
                                            Invalid argument
11
               PMIX ERR INVALID KEY
                                            Invalid key
12
               PMIX ERR INVALID KEY LENGTH
                                                    Invalid key length
13
               PMIX_ERR_INVALID_VAL
                                           Invalid value
14
               PMIX ERR INVALID NAMESPACE
                                                   Invalid namespace
15
               PMIX_ERR_SERVER_NOT_AVAIL
                                                  Server is not available
16
               PMIX ERR SILENT
                                     Silent error
                                              Pack mismatch
17
               PMIX_ERR_PACK_MISMATCH
18
               PMIX_ERR_DATA_VALUE_NOT_FOUND
                                                       Data value not found
19
               PMIX ERR NOT IMPLEMENTED
                                                 Not implemented
20
               PMIX_GDS_ACTION_COMPLETE
                                                 The GDS action has completed
21
               PMIX NOTIFY ALLOC COMPLETE
                                                   Notify that a requested allocation operation is complete - the result
22
                    of the request will be included in the info array
```

B.8.8 Deprecated attributes

```
The following attributes were deprecated in v4.0:
```

```
25
              PMIX_TOPOLOGY "pmix.topo" (hwloc_topology_t)
26
                   Renamed to PMIX_TOPOLOGY2.
27
              PMIX_DEBUG_JOB "pmix.dbg.job" (char*)
28
                   Renamed to PMIX DEBUG TARGET)
29
              PMIX_RECONNECT_SERVER "pmix.tool.recon" (bool)
30
                   Renamed to the PMIx_tool_connect_to_server API
31
              PMIX_ALLOC_NETWORK "pmix.alloc.net" (array)
32
                   Renamed to PMIX_ALLOC_FABRIC
33
              PMIX ALLOC NETWORK ID "pmix.alloc.netid" (char*)
34
                   Renamed to PMIX_ALLOC_FABRIC_ID
35
              PMIX_ALLOC_NETWORK_QOS "pmix.alloc.netqos" (char*)
36
                   Renamed to PMIX_ALLOC_FABRIC_QOS
37
              PMIX_ALLOC_NETWORK_TYPE "pmix.alloc.nettype" (char*)
38
                   Renamed to PMIX ALLOC FABRIC TYPE
39
              PMIX_ALLOC_NETWORK_PLANE "pmix.alloc.netplane" (char*)
40
                   Renamed to PMIX_ALLOC_FABRIC_PLANE
41
              PMIX_ALLOC_NETWORK_ENDPTS "pmix.alloc.endpts" (size_t)
42
                   Renamed to PMIX_ALLOC_FABRIC_ENDPTS
```

```
PMIX_ALLOC_NETWORK_ENDPTS_NODE "pmix.alloc.endpts.nd" (size_t)
1
2
                     Renamed to PMIX ALLOC FABRIC ENDPTS NODE
 3
               PMIX_ALLOC_NETWORK_SEC_KEY "pmix.alloc.nsec" (pmix_byte_object_t)
4
                     Renamed to PMIX ALLOC FABRIC SEC KEY
5
               PMIX_PROC_DATA "pmix.pdata" (pmix_data_array_t)
6
                     Renamed to PMIX_PROC_INFO_ARRAY
7
               PMIX LOCALITY "pmix.loc" (pmix locality t)
8
                     Relative locality of the specified process to the requester, expressed as a bitmask as per the description
9
                     in the pmix locality t section. This value is unique to the requesting process and thus cannot be
10
                     communicated by the server as part of the job-level information. Its use has been replaced by the
                     PMIx_Get_relative_locality function.
11
```

B.8.9 Removed attributes

12 13

14

15

16

17

18

19 20

21

22

23

24

25

26

27

28

29

30

31

32

33

34

35

36 37

38

39

40

41

42

43

44

45

The following attributes were removed from the PMIx Standard in v4.0 as they are internal to a particular PMIx implementation. Users are referred to the PMIx_Load_topology API for obtaining the local topology description.

```
PMIX_LOCAL_TOPO "pmix.ltopo" (char*)
      XML representation of local node topology.
PMIX_TOPOLOGY_XML "pmix.topo.xml" (char*)
      XML-based description of topology
PMIX_TOPOLOGY_FILE "pmix.topo.file" (char*)
      Full path to file containing XML topology description
PMIX_TOPOLOGY_SIGNATURE "pmix.toposig" (char*)
      Topology signature string.
PMIX_HWLOC_SHMEM_ADDR "pmix.hwlocaddr" (size_t)
      Address of the HWLOC shared memory segment.
PMIX_HWLOC_SHMEM_SIZE "pmix.hwlocsize" (size_t)
      Size of the HWLOC shared memory segment.
PMIX_HWLOC_SHMEM_FILE "pmix.hwlocfile" (char*)
      Path to the HWLOC shared memory file.
PMIX_HWLOC_XML_V1 "pmix.hwlocxml1" (char*)
      XML representation of local topology using HWLOC's v1.x format.
PMIX_HWLOC_XML_V2 "pmix.hwlocxml2" (char*)
      XML representation of local topology using HWLOC's v2.x format.
PMIX_HWLOC_SHARE_TOPO "pmix.hwlocsh" (bool)
      Share the HWLOC topology via shared memory
PMIX_HWLOC_HOLE_KIND "pmix.hwlocholek" (char*)
      Kind of VM "hole" HWLOC should use for shared memory
PMIX_DSTPATH "pmix.dstpath" (char*)
      Path to shared memory data storage (dstore) files. Deprecated from Standard as being implementation
      specific.
PMIX_COLLECTIVE_ALGO "pmix.calgo" (char*)
      Comma-delimited list of algorithms to use for the collective operation. PMIx does not impose any
```

requirements on a host environment's collective algorithms. Thus, the acceptable values for this

attribute will be environment-dependent - users are encouraged to check their host environment for

supported values.

```
PMIX_COLLECTIVE_ALGO_REQD "pmix.calreqd" (bool)
 1
2
                    If true, indicates that the requested choice of algorithm is mandatory.
 3
               PMIX_PROC_BLOB "pmix.pblob" (pmix_byte_object_t)
4
                    Packed blob of process data.
5
               PMIX_MAP_BLOB "pmix.mblob" (pmix_byte_object_t)
6
                    Packed blob of process location.
7
               PMIX MAPPER "pmix.mapper" (char*)
8
                    Mapping mechanism to use for placing spawned processes - when accessed using PMIx_Get, use the
9
                    PMIX RANK WILDCARD value for the rank to discover the mapping mechanism used for the
10
                    provided namespace.
11
               PMIX NON PMI "pmix.nonpmi" (bool)
12
                    Spawned processes will not call PMIx_Init.
               PMIX_PROC_URI "pmix.puri" (char*)
13
14
                    URI containing contact information for the specified process.
15
               PMIX_ARCH "pmix.arch" (uint32_t)
16
                    Architecture flag.
     B.9 Version 4.1: Oct. 2021
17
18
               The v4.1 update includes clarifications and corrections from the v4.0 document:
19
               • Remove some stale language in Chapter 9.1.
20
               • Provisional Items:
21

    Storage Chapter 18 on page 423

               Added Functions (Provisional)
     B.9.1
22
23
               • PMIx Data load
24
               • PMIx Data unload
25
               • PMIx Data compress
26
               • PMIx Data decompress
     B.9.2 Added Data Structures (Provisional)
27
28
               • pmix_storage_medium_t
29
               • pmix_storage_accessibility_t
30
               • pmix storage persistence t
31
               • pmix_storage_access_type_t
     B.9.3 Added Macros (Provisional)
32
33
               • PMIX NSPACE INVALID
34
               • PMIX RANK IS VALID
35
               • PMIX_PROCID_INVALID
36
               • PMIX PROCID XFER
```

B.9.4 Added Constants (Provisional)

1

3

5

6

7

8

9

10

11

12

13

14

15

16

17

18

19

20

21

22

23

24

25

26

27

28 29

30

31 32

33

34

35 36

37

38

Storage constants

- PMIX STORAGE MEDIUM UNKNOWN
- PMIX STORAGE MEDIUM TAPE
- PMIX STORAGE MEDIUM HDD
- PMIX_STORAGE_MEDIUM_SSD
- PMIX_STORAGE_MEDIUM_NVME
- PMIX STORAGE MEDIUM PMEM
 - PMIX STORAGE MEDIUM RAM
 - PMIX_STORAGE_ACCESSIBILITY_NODE
 - PMIX STORAGE ACCESSIBILITY SESSION
 - PMIX_STORAGE_ACCESSIBILITY_JOB
 - PMIX STORAGE ACCESSIBILITY RACK
 - PMIX_STORAGE_ACCESSIBILITY_CLUSTER
 - PMIX STORAGE ACCESSIBILITY REMOTE
 - PMIX STORAGE PERSISTENCE TEMPORARY
 - PMIX_STORAGE_PERSISTENCE_NODE
 - PMIX STORAGE PERSISTENCE SESSION
 - PMIX STORAGE PERSISTENCE JOB
- PMIX STORAGE PERSISTENCE SCRATCH
 - PMIX_STORAGE_PERSISTENCE_PROJECT
 - PMIX STORAGE PERSISTENCE ARCHIVE
 - PMIX STORAGE ACCESS RD
 - PMIX_STORAGE_ACCESS_WR
 - PMIX STORAGE ACCESS RDWR

B.9.5 Added Attributes (Provisional)

Storage attributes

```
PMIX_STORAGE_ID "pmix.strg.id" (char*)
```

An identifier for the storage system (e.g., lustre-fs1, daos-oss1, home-fs)

PMIX_STORAGE_PATH "pmix.strg.path" (char*)

Mount point path for the storage system (valid only for file-based storage systems)

PMIX_STORAGE_TYPE "pmix.strg.type" (char*)

Type of storage system (i.e., "lustre", "gpfs", "daos", "ext4")

PMIX_STORAGE_VERSION "pmix.strg.ver" (char*)

Version string for the storage system

PMIX_STORAGE_MEDIUM "pmix.strg.medium" (pmix_storage_medium_t)

Types of storage mediums utilized by the storage system (e.g., SSDs, HDDs, tape)

1 2 3	<pre>PMIX_STORAGE_ACCESSIBILITY "pmix.strg.access" (pmix_storage_accessibility_t)</pre>
4 5	<pre>PMIX_STORAGE_PERSISTENCE "pmix.strg.persist" (pmix_storage_persistence_t) Persistence level of the storage system (e.g., sratch storage or achive storage)</pre>
6 7 8	<pre>PMIX_QUERY_STORAGE_LIST "pmix.strg.list" (char*) Comma-delimited list of storage identifiers (i.e., PMIX_STORAGE_ID types) for available storage systems</pre>
9 0	<pre>PMIX_STORAGE_CAPACITY_LIMIT "pmix.strg.caplim" (double) Overall limit on capacity (in bytes) for the storage system</pre>
1 2	<pre>PMIX_STORAGE_CAPACITY_USED "pmix.strg.capuse" (double) Overall used capacity (in bytes) for the storage system</pre>
3 4	<pre>PMIX_STORAGE_OBJECT_LIMIT "pmix.strg.objlim" (uint64_t) Overall limit on number of objects (e.g., inodes) for the storage system</pre>
5 6	<pre>PMIX_STORAGE_OBJECTS_USED "pmix.strg.objuse" (uint64_t) Overall used number of objects (e.g., inodes) for the storage system</pre>
7 8 9	<pre>PMIX_STORAGE_MINIMAL_XFER_SIZE "pmix.strg.minxfer" (double) Minimal transfer size (in bytes) for the storage system - this is the storage system's atomic unit of transfer (e.g., block size)</pre>
20 21	<pre>PMIX_STORAGE_SUGGESTED_XFER_SIZE "pmix.strg.sxfer" (double) Suggested transfer size (in bytes) for the storage system</pre>
22 23 24	<pre>PMIX_STORAGE_BW_MAX "pmix.strg.bwmax" (double) Maximum bandwidth (in bytes/sec) for storage system - provided as the theoretical maximum or the maximum observed bandwidth value</pre>
25 26 27 28	PMIX_STORAGE_BW_CUR "pmix.strg.bwcur" (double) Observed bandwidth (in bytes/sec) for storage system - provided as a recently observed bandwidth value, with the exact measurement interval depending on the storage system and/or PMIx library implementation
9 80 81	<pre>PMIX_STORAGE_IOPS_MAX "pmix.strg.iopsmax" (double) Maximum IOPS (in I/O operations per second) for storage system - provided as the theoretical maximum or the maximum observed IOPS value</pre>
32 33 34 35	PMIX_STORAGE_IOPS_CUR "pmix.strg.iopscur" (double) Observed IOPS (in I/O operations per second) for storage system - provided as a recently observed IOPS value, with the exact measurement interval depending on the storage system and/or PMIx library implementation
86 87 88 89	PMIX_STORAGE_ACCESS_TYPE "pmix.strg.atype" (pmix_storage_access_type_t) Qualifier describing the type of storage access to return information for (e.g., for qualifying PMIX_STORAGE_BW_CUR, PMIX_STORAGE_IOPS_CUR, or PMIX_STORAGE_SUGGESTED_XFER_SIZE attributes)

B.10 Version 4.2: TBD

- 2 The v4.2 update includes the following changes from the v4.1 document:
- Define when PMIX PARENT ID is set
 - Add a definition for tool
 - Clarify PMIX CMD LINE in PMIx Spawn
 - Add that using PMIx Info load with a NULL PMIX BOOL data sets the value to true
 - Revision history now contains a list of errata changes

B.10.1 Errata

4

5

6

7

8 9

10

11

12

13

14 15

16

17 18

19

20

21 22

23

24

25

26

27

28

29

30

31

32

33

34

The following errors were corrected in v4.2:

- Parameter type for the key argument in PMIx_Get_nb has been changed to the equivalent type pmix_key_t so that it is uniform with the argument in PMIx_Get.
- Parameter type for the payload argument in pmix_iof_cbfunc_t has been changed to a pointer to the type pmix_byte_object_t.

B.10.2 Deprecated constants

The following constants were deprecated in v4.2:

PMIX DEBUG WAITING FOR NOTIFY Renamed to PMIX READY FOR DEBUG

B.10.3 Deprecated attributes

The following attributes were deprecated in v4.2:

```
PMIX_DEBUG_WAIT_FOR_NOTIFY "pmix.dbg.notify" (bool)
Renamed to PMIX_DEBUG_STOP_IN_APP
```

B.10.4 Deprecated macros

The following macros were deprecated in v4.2:

- PMIX VALUE LOAD Replaced by the PMIx Value load API
- PMIX VALUE UNLOAD Replaced by the PMIx Value unload API
- PMIX_VALUE_XFER Replaced by the PMIx_Value_xfer API
- PMIX INFO LOAD Replaced by the PMIx Info load API
 - PMIX_INFO_XFER Replaced by the PMIx_Info_xfer API
 - PMIX_INFO_LIST_START Replaced by the PMIx_Info_list_start API
 - PMIX INFO LIST ADD Replaced by the PMIx Info list add API
- PMIX_INFO_LIST_XFER Replaced by the PMIx_Info_list_xfer API
 - PMIX INFO LIST CONVERT Replaced by the PMIx Info list convert API
 - PMIX_INFO_LIST_RELEASE Replaced by the PMIx_Info_list_release API
 - PMIX TOPOLOGY DESTRUCT Replaced by the PMIx Topology destruct API
 - PMIX TOPOLOGY FREE Not replaced.

B.10.5 Added Functions (Provisional)

- 2 PMIx Data embed

4

5

6

7

8

9

14

15

16

17

18

19

20

21

22

23

24

25

26

27

29

30

31

33 34

35

36

37

- PMIx Value unload
 - PMIx_Value_xfer
- PMIx_Info_list_start
 - PMIx Info list add
 - PMIx Info list xfer
 - PMIx Info list convert
- 10 PMIx Info list release

12 B.10.6 Added Macros (Provisional)

- 13 PMIX_APP_STATIC_INIT
 - PMIX_BYTE_OBJECT_STATIC_INIT
 - PMIX_COORD_STATIC_INIT
 - PMIX_CPUSET_STATIC_INIT
 - PMIX DATA ARRAY STATIC INIT
 - PMIX DATA BUFFER STATIC INIT
 - PMIX_DEVICE_DIST_STATIC_INIT
 - PMIX ENDPOINT STATIC INIT
 - PMIX ENVAR STATIC INIT
 - PMIX_FABRIC_STATIC_INIT
 - PMIX_GEOMETRY_STATIC_INIT
 - PMIX INFO STATIC INIT
 - PMIX LOOKUP STATIC INIT
 - PMIX PROC INFO STATIC INIT
 - PMIX PROC STATIC INIT
- 28 PMIX_QUERY_STATIC_INIT
 - PMIX_REGATTR_STATIC_INIT
 - PMIX_TOPOLOGY_STATIC_INIT
 - PMIX_VALUE_STATIC_INIT

32 B.10.7 Added Constants (Provisional)

Spawn constants

- PMIX_ERR_JOB_EXE_NOT_FOUND
- PMIX_ERR_JOB_INSUFFICIENT_RESOURCES
- PMIX ERR JOB SYS OP FAILED
 - PMIX ERR JOB WDIR NOT FOUND

B.10.8 Added Attributes (Provisional)

Spawn attributes

```
PMIX_ENVARS_HARVESTED "pmix.evar.hvstd" (bool)
```

Environmental parameters have been harvested by the spawn requestor - the server does not need to harvest them.

```
PMIX_JOB_TIMEOUT "pmix.job.time" (int)
```

Time in seconds before the spawned job should time out and be terminated (0 => infinite), defined as the total runtime of the job (equivalent to the walltime limit of typical batch schedulers).

```
PMIX_LOCAL_COLLECTIVE_STATUS "pmix.loc.col.st" (pmix_status_t)
```

Status code for local collective operation being reported to the host by the server library. PMIx servers may aggregate the participation by local client processes in a collective operation - e.g., instead of passing individual client calls to <code>PMIx_Fence</code> up to the host environment, the server may pass only a single call to the host when all local participants have executed their <code>PMIx_Fence</code> call, thereby reducing the burden placed on the host. However, in cases where the operation locally fails (e.g., if a participating client abnormally terminates prior to calling the operation), the server upcall functions to the host do not include a <code>pmix_status_t</code> by which the PMIx server can alert the host to that failure. This attribute resolves that problem by allowing the server to pass the status information regarding the local collective operation.

```
PMIX_NODE_OVERSUBSCRIBED "pmix.ndosub" (bool)
```

True if the number of processes from this job on this node exceeds the number of slots allocated to it

```
PMIX_SINGLETON "pmix.singleton" (char*)
```

String representation (nspace.rank) of proc ID for the singleton the server was started to support

```
PMIX_SPAWN_TIMEOUT "pmix.sp.time" (int)
```

Time in seconds before spawn operation should time out (0 => infinite). Logically equivalent to passing the **PMIX_TIMEOUT** attribute to the **PMIX_Spawn** API, it is provided as a separate attribute to distinguish it from the **PMIX_JOB_TIMEOUT** attribute

Tool attributes

```
PMIX_IOF_FILE_PATTERN "pmix.iof.fpt" (bool)
```

Specified output file is to be treated as a pattern and not automatically annotated by nspace, rank, or other parameters. The pattern can use **%n** for the namespace, and **%r** for the rank wherever those quantities are to be placed. The resulting filename will be appended with ".stdout" for the **stdout** stream and ".stderr" for the **stderr** stream. If **PMIX_IOF_MERGE_STDERR_STDOUT** was given, then only the **stdout** file will be created and both streams will be written into it.

```
PMIX_IOF_FILE_ONLY "pmix.iof.fonly" (bool)
```

Output only into designated files - do not also output a copy to the console's stdout/stderr

```
PMIX_IOF_LOCAL_OUTPUT "pmix.iof.local" (bool)
```

Write output streams to local stdout/err

```
PMIX_IOF_MERGE_STDERR_STDOUT "pmix.iof.mrg" (bool)
```

Merge stdout and stderr streams from application procs

```
PMIX IOF RANK OUTPUT "pmix.iof.rank" (bool)
```

1			
2 3			
4 5 6 7 8			
9 0 1 2			
3 4			
5 6 7			
8 9 20			
21 22 23 24			

25

26

Tag output with the rank it came from

PMIX_IOF_OUTPUT_RAW "pmix.iof.raw" (bool)

Do not buffer output to be written as complete lines - output characters as the stream delivers them

PMIX_IOF_OUTPUT_TO_DIRECTORY "pmix.iof.dir" (char*)

Direct application output into files of form "<directory>/<nspace>/rank.<rank>/stdout" (for **stdout**) and "<directory>/<nspace>/rank.<rank>/stderr" (for **stderr**). If

PMIX_IOF_MERGE_STDERR_STDOUT was given, then only the **stdout** file will be created and both streams will be written into it.

PMIX_IOF_OUTPUT_TO_FILE "pmix.iof.file" (char*)

Direct application output into files of form "<filename>.<nspace>.<rank>.stdout" (for **stdout**) and "<filename>.<nspace>.<rank>.stderr" (for **stderr**). If **PMIX_IOF_MERGE_STDERR_STDOUT** was given, then only the **stdout** file will be created and both streams will be written into it.

PMIX_BREAKPOINT "pmix.brkpnt" (char*)

String ID of the breakpoint where the process(es) is(are) waiting.

PMIX_DEBUG_STOP_IN_APP "pmix.dbg.notify" (varies)

Direct specified ranks to stop at application-specific point and notify they are ready-to-debug. The attribute's value can be any of three data types:

- bool true indicating all ranks
- pmix_rank_t the rank of one proc, or PMIX_RANK_WILDCARD for all
- a pmix_data_array_t if an array of individual processes are specified

The resulting application processes are to notify their server (by generating the <code>PMIX_READY_FOR_DEBUG</code> event) when they reach some application-determined location - the event shall include the <code>PMIX_BREAKPOINT</code> attribute indicating where the application has stopped. The application shall pause at that point until released by debugger modification of an appropriate variable. The launcher (RM or IL) is responsible for generating the <code>PMIX_READY_FOR_DEBUG</code> event when all processes have indicated they are at the pause point.

APPENDIX C

1

2

3

6

9

11

12

14 15

16 17

18

22

23

24

Acknowledgements

This document represents the work of many people who have contributed to the PMIx community. Without the hard work and dedication of these people this document would not have been possible. The sections below list some of the active participants and organizations in the various PMIx standard iterations.

4 C.1 Version 4.0

- 5 The following list includes some of the active participants in the PMIx v4 standardization process.
 - Ralph H. Castain and Danielle Sikich
 - Joshua Hursey and David Solt
 - Dirk Schubert
 - John DelSignore
 - Aurelien Bouteiller
 - Michael A Raymond
 - Howard Pritchard and Nathan Hjelm
- Brice Goglin
 - Kathryn Mohror and Stephen Herbein
 - Thomas Naughton and Swaroop Pophale
 - William E. Allcock and Paul Rich
 - Michael Karo
 - Artem Polyakov
- The following institutions supported this effort through time and travel support for the people listed above.
- Intel Corporation
- IBM, Inc.
 - Allinea (ARM)
 - Perforce
 - University of Tennessee, Knoxville
- The Exascale Computing Project, an initiative of the US Department of Energy

1 • National Science Foundation • HPE Co. 3 • Los Alamos National Laboratory 4 • INRIA • Lawrence Livermore National Laboratory 5 6 • Oak Ridge National Laboratory 7 • Argonne National Laboratory 8 • Altair 9 NVIDIA C.2 Version 3.0 10 11 The following list includes some of the active participants in the PMIx v3 standardization process. 12 • Ralph H. Castain, Andrew Friedley, Brandon Yates 13 • Joshua Hursey and David Solt 14 • Aurelien Bouteiller and George Bosilca 15 Dirk Schubert • Kevin Harms 16 17 · Artem Polyakov

The following institutions supported this effort through time and travel support for the people listed above.

19 20

18

- IBM, Inc.
- University of Tennessee, Knoxville

• Intel Corporation

- The Exascale Computing Project, an initiative of the US Department of Energy
- National Science Foundation
- Argonne National Laboratory
- Allinea (ARM)
- e NVIDIA €

1 C.3 Version 2.0

2	The following list includes some of the active participants in the PMIx v2 standardization process.
3	• Ralph H. Castain, Annapurna Dasari, Christopher A. Holguin, Andrew Friedley, Michael Klemm and Terry
4	Wilmarth
5	 Joshua Hursey, David Solt, Alexander Eichenberger, Geoff Paulsen, and Sameh Sharkawi
6	Aurelien Bouteiller and George Bosilca
7	 Artem Polyakov, Igor Ivanov and Boris Karasev
8	Gilles Gouaillardet
9	Michael A Raymond and Jim Stoffel
10	Dirk Schubert
11	Moe Jette
12	Takahiro Kawashima and Shinji Sumimoto
13	Howard Pritchard
14	David Beer
15	Brice Goglin
16	 Geoffroy Vallee, Swen Boehm, Thomas Naughton and David Bernholdt
17	Adam Moody and Martin Schulz
18	Ryan Grant and Stephen Olivier
19	Michael Karo
20	The following institutions supported this effort through time and travel support for the people listed above.
21	• Intel Corporation
22	• IBM, Inc.
23	University of Tennessee, Knoxville
24	• The Exascale Computing Project, an initiative of the US Department of Energy
25	National Science Foundation
26	• Mellanox, Inc.
27	Research Organization for Information Science and Technology
28	• HPE Co.
29	• Allinea (ARM)
30	• SchedMD, Inc.
31	Fujitsu Limited

- Los Alamos National Laboratory
- Adaptive Solutions, Inc.
- INRIA
- Oak Ridge National Laboratory
- Lawrence Livermore National Laboratory
 - Sandia National Laboratory
- 7 Altair

6

12

13

15

20

C.4 Version 1.0

- 9 The following list includes some of the active participants in the PMIx v1 standardization process.
- Ralph H. Castain, Annapurna Dasari and Christopher A. Holguin
- Joshua Hursey and David Solt
 - Aurelien Bouteiller and George Bosilca
 - Artem Polyakov, Elena Shipunova, Igor Ivanov, and Joshua Ladd
- Gilles Gouaillardet
 - Gary Brown
- Moe Jette
- 17 The following institutions supported this effort through time and travel support for the people listed above.
- Intel Corporation
- IBM, Inc.
 - University of Tennessee, Knoxville
- Mellanox, Inc.
- Research Organization for Information Science and Technology
- Adaptive Solutions, Inc.
- SchedMD, Inc.

Bibliography

- [1] Ralph H. Castain, David Solt, Joshua Hursey, and Aurelien Bouteiller. PMIx: Process management for exascale environments. In *Proceedings of the 24th European MPI Users' Group Meeting*, EuroMPI '17, pages 14:1–14:10, New York, NY, USA, 2017. ACM.
- [2] Balaji P. et al. PMI: A scalable parallel process-management interface for extreme-scale systems. In *Recent Advances in the Message Passing Interface*, EuroMPI '10, pages 31–41, Berlin, Heidelberg, 2010. Springer.

Index

General terms and other items not induced in the other indices.

```
application, 6, 90, 101, 286, 288, 291, 496, 499
attribute, 8
client, <u>7</u>, <u>57</u>
clients, 7
clone, 7
clones, 7, 65, 68, 69, 172, 174, 176, 178, 198, 201, 506
data realm, 92, 254, 255
data realms, 92
device, 8
devices, 8
Direct Modex, 243, 301
fabric, 8
fabric device, 8
fabric devices, 8
fabric plane, 8, 157, 162, 191, 194, 195, 259, 303
fabric planes, 8
fabrics, 8
host environment, 7
instant on, 8, 105, 242
job, <u>6</u>, 7, 90, 94–97, 101, 278–281, 283, 286–288, 290, 291, 302, 304, 305, 480, 496, 499, 508, 510
key, 8
namespace, 6
node, 7, 90, 101, 157, 163, 191, 194, 195, 286, 304
package, 7, 98, 284, 510
peer, 7, 100, 283
peers, 7
process, 7, 90, 101, 157, 163, 191, 194, 195, 286, 304
processing unit, 7
rank, <u>7</u>, <u>292</u>
realm, 92
```

```
realms, <u>92</u>
resource manager, <u>7</u>
RM, <u>7</u>
scheduler, <u>7</u>, 257
session, <u>6</u>, 90, 93, 101, 278, 286, 287, 496, 499, 508
thread, <u>7</u>
threads, <u>7</u>
tool, <u>7</u>, 524
tools, <u>7</u>
workflow, <u>7</u>
workflows, <u>7</u>, 367
```

Index of APIs

```
PMIx_Abort, 25, 152, 153, 324, 325, 436, 450, 494
     PMIxClient.abort (Python), 450
PMIx_Alloc_directive_string, 55, 471, 495
     PMIxClient.alloc_directive_string (Python), 471
PMIx_Allocation_request, 91, 189, 189, 194, 458, 497, 499, 502
     PMIxClient.allocation_request (Python), 458
PMIx_Allocation_request_nb, 192, 194, 196, 495
PMIx_Commit, 65, 67, 68, 106, 108, 108, 109, 301, 302, 326, 330, 452, 494
     PMIxClient.commit (Python), 451
PMIx_Compute_distances, 183, 184, 468, 502
     PMIxClient.compute_distances (Python), 467
PMIx_Compute_distances_nb, 184, 502
PMIx_Connect, 171, 173, 175, 178, 218–220, 408, 455, 494, 496
     PMIxClient.connect (Python), 455
PMIx_Connect_nb, 173, 173, 494
pmix_connection_cbfunc_t, 349, 350
pmix_credential_cbfunc_t, 265, 365, 366
PMIx Data compress, 149, 150, 521
PMIx_Data_copy, 145, 495
PMIx_Data_copy_payload, 147, 495
PMIx_Data_decompress, 149, 521
PMIx_Data_embed, 150, 525
PMIx_Data_load, 147, 151, 521
PMIx_Data_pack, 142, 143, 276, 495
PMIx_Data_print, 146, 495
PMIx_Data_range_string, 55, 470, 495
     PMIxClient.data_range_string (Python), 470
PMIx_Data_type_string, 55, 471, 495
     PMIxClient.data_type_string (Python), 470
PMIx_Data_unload, 148, 521
PMIx Data unpack, 144, 148, 495
PMIx_Deregister_event_handler, 134, 464, 495, 502
     PMIxClient.deregister event handler (Python), 463
pmix_device_dist_cbfunc_t, 184, 184, 503
PMIx_Device_type_string, 56, 473, 502
     PMIxClient.device_type_string (Python), 473
PMIx_Disconnect, 175, 176–178, 220, 408, 456, 494, 496
     PMIxClient.disconnect (Python), 455
PMIx_Disconnect_nb, <u>177</u>, 178, 220, 494
pmix_dmodex_response_fn_t, 301, 301
PMIx_Error_string, 54, 468, 494
```

```
PMIxClient.error_string (Python), 468
pmix_event_notification_cbfunc_fn_t, 133, 138, 138
PMIx Fabric deregister, 261, 262, 466, 502
     PMIxClient.fabric_deregister (Python), 465
PMIx_Fabric_deregister_nb, 262, 502
PMIx Fabric register, 251, 258, 260, 465, 502
     PMIxClient.fabric_register (Python), 464
PMIx Fabric register nb, 259, 502
PMIx_Fabric_update, 259, 260, 261, 465, 502
     PMIxClient.fabric_update (Python), 465
PMIx_Fabric_update_nb, 260, 502
PMIx_Fence, 4, 64, 65–69, 105, 173, 176, 217, 225, 229, 243, 273, 301, 325–327, 342, 343, 375, 437, 452,
          494, 506, 526
     PMIxClient.fence (Python), 452
PMIx_Fence_nb, 52, 66, 325, 327, 437, 494, 501
PMIx_Finalize, 25, 60, 62, 62, 63, 171, 323, 408, 436, 450, 494
     PMIxClient.finalize (Python), 450
PMIx_generate_ppn, 276, 475, 494, 499
     PMIxServer.generate ppn (Python), 475
PMIx_generate_regex, 275, 276, 287, 475, 494, 499
     PMIxServer.generate regex (Python), 475
PMIx_Get, 3, 8, 28, 60, 61, 65, 67, 69, 69–71, 73, 74, 77, 78, 80, 82, 85, 89–94, 96–101, 105, 108, 155, 156,
          160, 161, 164–166, 180–182, 194, 202, 208, 214, 216, 218, 222, 225, 243, 245, 254, 255, 257, 280,
          284, 287, 315, 338, 340, 384, 393–395, 409, 425, 453, 494, 496, 501, 506, 507, 512, 513, 521, 524
     PMIxClient.get (Python), 452
PMIx_Get_attribute_name, 56, 473, 502
     PMIxClient.get_attribute_name (Python), 472
PMIx_Get_attribute_string, 56, 472, 502
     PMIxClient.get_attribute_string (Python), 472
PMIx_Get_cpuset, 182, 467, 502
     PMIxClient.get_cpuset (Python), 467
PMIx_Get_credential, 264, 266, 366, 460, 497, 502
     PMIxClient.get_credential (Python), 459
PMIx Get credential nb, 265
PMIx_Get_nb, 53, 71, 494, 524
PMIx_Get_relative_locality, 179, 181, 284, 315, 466, 502, 520
     PMIxClient.get_relative_locality (Python), 466
PMIx_Get_version, 10, 58, 449, 494
     PMIxClient.get_version (Python), 449
PMIx_Group_construct, 217, 218, 222, 224, 225, 227, 461, 502
     PMIxClient.group_construct (Python), 460
PMIx_Group_construct_nb, 225, 227, 502
PMIx_Group_destruct, 220, 228, 229, 230, 239, 463, 502
     PMIxClient.group_destruct (Python), 462
PMIx_Group_destruct_nb, 229, 230, 502
PMIx_Group_invite, 219, 230, 232, 233, 235, 461, 502
     PMIxClient.group invite (Python), 461
```

```
PMIx_Group_invite_nb, 233, 502
PMIx_Group_join, 219, 232, 233, 235, 235–238, 462, 502
     PMIxClient.group_join (Python), 461
PMIx_Group_join_nb, 235, 237, 238, 502
PMIx_Group_leave, 220, 239, 239-241, 462, 502
     PMIxClient.group leave (Python), 462
PMIx_Group_leave_nb, 240, 502
pmix_hdlr_reg_cbfunc_t, 54, 129, 418, 420, 518
pmix info cbfunc t, 52, 53, 53, 81, 184, 192, 199, 201, 205, 207, 226, 233, 238, 313, 351, 358, 360, 362, 363,
          374, 377
PMIx_Info_directives_string, 55, 470, 495
     PMIxClient.info_directives_string (Python), 470
PMIx_Info_list_add, 36, 524, 525
PMIx_Info_list_convert, 37, 524, 525
PMIx_Info_list_release, 38, 524, 525
PMIx_Info_list_start, 36, 37, 38, 524, 525
PMIx_Info_list_xfer, 37, 524, 525
PMIx_Info_load, 34, 524
PMIx Info xfer, 35, 287, 524
PMIx_Init, 7, 57, 58, 60, 61, 78, 82, 98, 322, 389, 393, 402, 403, 409, 449, 495, 501, 521
     PMIxClient.init (Python), 449
PMIx_Initialized, 57, 449, 494
     PMIxClient.initialized (Python), 449
pmix_iof_cbfunc_t, 372, 418, 435, 524
     iofcbfunc (Python), 434
PMIx_IOF_channel_string, 56, 471, 497
     PMIxClient.iof_channel_string (Python), 471
PMIx_IOF_deregister, 419, 487, 497, 502
     PMIxTool.iof_deregister (Python), 487
PMIx_IOF_pull, 339, 354, 386, 387, 391, 392, 395, 397, 417, 420, 487, 497, 502
     PMIxTool.iof_pull (Python), 486
PMIx_IOF_push, 339, 354, 386, 391, 395, 397–399, 401, 420, 422, 488, 497, 502, 511
     PMIxTool.iof_push (Python), 487
PMIx Job control, 189, 196, 198, 200–202, 362, 404, 459, 497, 502
     PMIxClient.job_ctrl (Python), 458
PMIx_Job_control_nb, 75, 196, 199, 285, 495
PMIx_Job_state_string, <u>56</u>, 472, 502
     PMIxClient.job_state_string (Python), 472
PMIx_Link_state_string, 56, 473, 502
     PMIxClient.link_state_string (Python), 473
PMIx_Load_topology, 178, 466, 502, 520
     PMIxClient.load_topology (Python), 466
PMIx_Log, 167, 208, 211, 214, 388, 389, 407, 458, 497, 517
     PMIxClient.log (Python), 457
PMIx_Log_nb, 211, 214, 495
PMIx_Lookup, 110, 114, 116, 118, 453, 454, 494
     PMIxClient.lookup (Python), 453
```

```
pmix_lookup_cbfunc_t, 121, 121, 332
PMIx_Lookup_nb, 116, 121, 494
pmix_modex_cbfunc_t, 52, 326, 328, 328, 329
pmix_notification_fn_t, 128, 133, 133, 435
     evhandler (Python), 435
PMIx Notify event, 135, 349, 464, 495, 502
     PMIxClient.notify_event (Python), 464
pmix_op_cbfunc_t, 52, 52, 112, 124, 135, 136, 139, 174, 177, 211, 229, 240, 259, 261, 262, 277, 295–299,
          306, 311, 312, 314, 321–324, 330, 334, 341, 343, 345, 347, 348, 356, 370, 373, 421
PMIx_Parse_cpuset_string, 181, 316, 467, 502
     PMIxClient.parse_cpuset_string (Python), 467
PMIx_Persistence_string, 55, 469, 495
     PMIxClient.persistence_string (Python), 469
PMIx_Proc_state_string, 54, 469, 495
     PMIxClient.proc_state_string (Python), 468
PMIx_Process_monitor, 189, 203, 207, 459, 497, 502
     PMIxClient.monitor (Python), 459
PMIx_Process_monitor_nb, 205, 207, 208, 495
PMIx Progress, 59, 63, 272, 275, 412, 474, 502, 510
     PMIxClient.progress (Python), 474
PMIx_Publish, 110, 111, 113, 114, 332, 453, 454, 494
     PMIxClient.publish (Python), 453
PMIx_Publish_nb, 111, 114, 494
PMIx_Put, 28, 64–68, 89, 92, 105, 106, 106–109, 171, 225, 232, 301, 302, 326, 330, 451, 494
     PMIxClient.put (Python), 451
PMIx_Query_info, 8, 76, 80, 84, 85, 87, 89, 90, 216, 218, 254, 255, 379, 383, 403, 425, 457, 507
     PMIxClient.query (Python), 457
PMIx_Query_info_nb, 75, 80, 81, 91, 171, 287, 307, 495, 496
PMIx_Register_attributes, 306, 480, 501, 502
     PMIxServer.register_attributes (Python), 480
PMIx_Register_event_handler, 75, 128, 166, 388, 407, 463, 495, 502, 517
     PMIxClient.register_event_handler (Python), 463
pmix_release_cbfunc_t, 52, 52
PMIx Resolve nodes, 76, 457, 494
     PMIxClient.resolve_nodes (Python), 456
PMIx_Resolve_peers, 75, 99, 282, 283, 456, 494
     PMIxClient.resolve_peers (Python), 456
PMIx_Scope_string, 55, 469, 495
     PMIxClient.scope_string (Python), 469
pmix_server_abort_fn_t, 324, 437
     clientaborted (Python), 436
pmix_server_alloc_fn_t, 357, 444
     allocate (Python), 444
pmix_server_client_connected2_fn_t, 52, 263, 298, 321, 321, 322, 436, 503, 518
     clientconnected2 (Python), 436
pmix_server_client_finalized_fn_t, 323, 323, 436
     clientfinalized (Python), 436
```

```
PMIx_server_collect_inventory, 313, 315, 482, 497
     PMIxServer.collect_inventory (Python), 481
pmix_server_connect_fn_t, 171, 341, 342, 344, 440
     connect (Python), 440
PMIx_server_define_process_set, 216, 318, 483, 503
     PMIxServer.define process set (Python), 482
PMIx_server_delete_process_set, 216, 318, 483, 503
     PMIxServer.delete_process_set (Python), 483
PMIx_server_deliver_inventory, 314, 482, 497
     PMIxServer.deliver_inventory (Python), 482
PMIx_server_deregister_client, 299, 479, 494
     PMIxServer.deregister_client (Python), 478
pmix_server_deregister_events_fn_t, 346, 442
     deregister_events (Python), 441
PMIx_server_deregister_nspace, 294, 299, 477, 494
     PMIxServer.deregister_nspace (Python), 477
PMIx_server_deregister_resources, 296, 478, 484, 503
     PMIxServer.deregister_resources (Python), 478, 484
pmix server disconnect fn t, 342, 344, 441
     disconnect (Python), 440
pmix_server_dmodex_req_fn_t, 100, 109, 328, 328, 438, 497, 498
     dmodex (Python), 437
PMIx_server_dmodex_request, 300, 301, 302, 479, 494
     PMIxServer.dmodex_request (Python), 479
pmix_server_fabric_fn_t, 251, 257, 376, 448, 503
     fabric (Python), 448
pmix_server_fencenb_fn_t, 325, 327, 328, 437, 499
     fence (Python), 437
PMIx_server_finalize, 273, 475, 494
     PMIxServer.finalize (Python), 474
PMIx_server_generate_cpuset_string, 182, 316, 476, 503
     PMIxServer.generate_cpuset_string (Python), 476
PMIx_server_generate_locality_string, 178, 179, 315, 476, 502
     PMIxServer.generate_locality_string (Python), 476
pmix_server_get_cred_fn_t, 365, 369, 446
     get_credential (Python), 445
pmix_server_grp_fn_t, 374, 448, 503
     group (Python), 447
PMIx_server_init, 57, 270, 274, 307, 319, 380, 381, 384, 474, 494, 502
     PMIxServer.init (Python), 474
PMIx_server_IOF_deliver, 312, 396, 481, 497
     PMIxServer.iof_deliver (Python), 481
pmix_server_iof_fn_t, 370, 447
     iof_pull (Python), 446
pmix_server_job_control_fn_t, 360, 445
     job_control (Python), 444
pmix_server_listener_fn_t, 349
```

```
pmix_server_log_fn_t, 355, 444
     log (Python), 443
pmix_server_lookup_fn_t, 332, 439
     lookup (Python), 438
pmix_server_module_t, 270, 273, 307, 319, 319, 320, 474
pmix server monitor fn t, 362, 445
     monitor (Python), 445
pmix_server_notify_event_fn_t, 134, 138, 348, 349, 442
     notify_event (Python), 442
pmix_server_publish_fn_t, 330, 438
     publish (Python), 438
pmix_server_query_fn_t, 350, 443
     query (Python), 442
PMIx_server_register_client, 263, 297, 299, 322, 323, 478, 494
     PMIxServer.register_client (Python), 478
pmix_server_register_events_fn_t, 344, 441
     register_events (Python), 441
PMIx_server_register_nspace, 10, 52, 275, 276, 276, 278, 286, 287, 290, 296, 312, 315, 316, 477, 494, 496,
          508
     PMIxServer.register_nspace (Python), 476
PMIx_server_register_resources, 279, 282, 283, 296, 477, 483, 503
     PMIxServer.register_resources (Python), 477, 483
PMIx_server_setup_application, 302, 305, 306, 312, 315, 480, 495, 499
     PMIxServer.setup_application (Python), 480
PMIx_server_setup_fork, 299, 479, 494
     PMIxServer.setup_fork (Python), 479
PMIx_server_setup_local_support, 311, 481, 495
     PMIxServer.setup_local_support (Python), 480
pmix_server_spawn_fn_t, 170, 336, 390, 440
     spawn (Python), 439
pmix_server_stdin_fn_t, 373, 447
     iof_push (Python), 447
pmix_server_tool_connection_fn_t, 263, 353, 380, 443
     tool connected (Python), 443
pmix_server_unpublish_fn_t, 334, 439
     unpublish (Python), 439
pmix_server_validate_cred_fn_t, 367, 446
     validate_credential (Python), 446
pmix_setup_application_cbfunc_t, 302, 305
PMIx_Spawn, 95, 96, 98, <u>153</u>, 153, 158, 159, 163, 164, 167, 192, 194, 284, 285, 300, 336, 337, 339, 340, 358,
          384, 386, 390, 391, 393, 394, 396, 402–406, 409, 439, 455, 494, 499, 509, 510, 524, 526
     PMIxClient.spawn (Python), 454
pmix_spawn_cbfunc_t, 159, 170, 170, 336
PMIx_Spawn_nb, 98, 159, 167, 170, 337, 494
PMIx_Store_internal, 105, <u>107</u>, 107, 451, 494
     PMIxClient.store_internal (Python), 450
PMIx_tool_attach_to_server, 382, 384, 393, 413, 414, 485, 503, 518
```

```
PMIxTool.attach_to_server (Python), 485
PMIx_tool_connect_to_server, 497, 519
pmix_tool_connection_cbfunc_t, 353, 354, 355
PMIx_tool_disconnect, 414, 485, 503
     PMIxTool.disconnect (Python), 485
PMIx_tool_finalize, 413, 485, 495
     PMIxTool.finalize (Python), 484
PMIx_tool_get_servers, 416, 486, 503
     PMIxTool.get_servers (Python), 486
PMIx_tool_init, 7, 57, 379, 382, 384, 385, 393, 394, 396, 408, 410, 413, 484, 495
     PMIxTool.init (Python), 484
PMIx_tool_set_server, 381, 394, 415, 416, 486, 503
     PMIxTool.set_server (Python), 486
PMIx_Topology_destruct, 180, 524, 525
PMIx_Unpublish, 122, 123, 125, 454, 494
     PMIxClient.unpublish (Python), 454
PMIx_Unpublish_nb, 123, 494
PMIx_Validate_credential, 266, 460, 497, 502
     PMIxClient.validate_credential (Python), 460
PMIx_Validate_credential_nb, 268
pmix_validation_cbfunc_t, 268, 368, 369
pmix_value_cbfunc_t, 53, 53
PMIx_Value_load, 31, 524, 525
PMIx_Value_unload, 31, 524, 525
PMIx_Value_xfer, <u>32</u>, 524, 525
pmix_evhdlr_reg_cbfunc_t
     (Deprecated), 518
pmix_server_client_connected_fn_t
     (Deprecated), <u>321</u>, 518
PMIx_tool_connect_to_server
     (Deprecated), 518
```

Index of Support Macros

```
PMIX_APP_CONSTRUCT, 168
PMIX_APP_CREATE, 169
PMIX_APP_DESTRUCT, 169
PMIX_APP_FREE, 169
PMIX APP INFO CREATE, 170, 497, 498
PMIX_APP_RELEASE, 169
PMIX_APP_STATIC_INIT, 168, 525
PMIX ARGV APPEND, 46
PMIX_ARGV_APPEND_UNIQUE, 47
PMIX_ARGV_COPY, 49
PMIX_ARGV_COUNT, 49
PMIX_ARGV_FREE, 48
PMIX_ARGV_JOIN, 48
PMIX_ARGV_PREPEND, 47
PMIX_ARGV_SPLIT, 48
PMIX_BYTE_OBJECT_CONSTRUCT, 43
PMIX_BYTE_OBJECT_CREATE, 44
PMIX BYTE OBJECT DESTRUCT, 44
PMIX_BYTE_OBJECT_FREE, 44
PMIX_BYTE_OBJECT_LOAD, 44
PMIX_BYTE_OBJECT_STATIC_INIT, 43, 525
PMIX_CHECK_KEY, 17
PMIX_CHECK_NSPACE, 18
PMIX_CHECK_PROCID, 22
PMIX_CHECK_RANK, 20
PMIX_CHECK_RESERVED_KEY, 17, 518
PMIX_COORD_CONSTRUCT, 247
PMIX COORD CREATE, 248
PMIX_COORD_DESTRUCT, 248
PMIX_COORD_FREE, 248
PMIX COORD STATIC INIT, 247, 525
PMIX_CPUSET_CONSTRUCT, 317
PMIX_CPUSET_CREATE, 317
PMIX_CPUSET_DESTRUCT, 317
PMIX_CPUSET_FREE, 317
PMIX_CPUSET_STATIC_INIT, 317, 525
PMIX_DATA_ARRAY_CONSTRUCT, 45
PMIX_DATA_ARRAY_CREATE, 46
PMIX_DATA_ARRAY_DESTRUCT, 45
PMIX_DATA_ARRAY_FREE, 46
PMIX_DATA_ARRAY_STATIC_INIT, 45, 525
```

```
PMIX_DATA_BUFFER_CONSTRUCT, 141, 143, 145
PMIX_DATA_BUFFER_CREATE, 141, 143, 145
PMIX DATA BUFFER DESTRUCT, 141
PMIX_DATA_BUFFER_LOAD, 142
PMIX_DATA_BUFFER_RELEASE, 141
PMIX DATA BUFFER STATIC INIT, 141, 525
PMIX_DATA_BUFFER_UNLOAD, 142, 276
PMIX_DEVICE_DIST_CONSTRUCT, 187
PMIX_DEVICE_DIST_CREATE, 187
PMIX_DEVICE_DIST_DESTRUCT, 187
PMIX_DEVICE_DIST_FREE, 188
PMIX_DEVICE_DIST_STATIC_INIT, 187, 525
PMIX_ENDPOINT_CONSTRUCT, 246
PMIX_ENDPOINT_CREATE, 246
PMIX_ENDPOINT_DESTRUCT, 246
PMIX_ENDPOINT_FREE, 246
PMIX_ENDPOINT_STATIC_INIT, 245, 525
PMIX_ENVAR_CONSTRUCT, 42
PMIX ENVAR CREATE, 42
PMIX_ENVAR_DESTRUCT, 12, 42
PMIX ENVAR FREE, 42
PMIX_ENVAR_LOAD, 43
PMIX_ENVAR_STATIC_INIT, 42, 525
PMIX_FABRIC_CONSTRUCT, 254
PMIX_FABRIC_STATIC_INIT, 254, 525
PMIX_GEOMETRY_CONSTRUCT, 249
PMIX_GEOMETRY_CREATE, 250
PMIX_GEOMETRY_DESTRUCT, 249
PMIX_GEOMETRY_FREE, 250
PMIX_GEOMETRY_STATIC_INIT, 249, 525
PMIx_Heartbeat, 207, 495
PMIX_INFO_CONSTRUCT, 34
PMIX_INFO_CREATE, 34, 39, 41
PMIX INFO DESTRUCT, 34
PMIX_INFO_FREE, 34
PMIX_INFO_IS_END, 41, 497, 498
PMIX INFO IS OPTIONAL, 40
PMIX_INFO_IS_REQUIRED, 39, 40
PMIX_INFO_LIST_ADD, 518
PMIX_INFO_LIST_CONVERT, 518
PMIX_INFO_LIST_RELEASE, 518
PMIX_INFO_LIST_START, 518
PMIX_INFO_LIST_XFER, 518
PMIX INFO OPTIONAL, 40
PMIX_INFO_PROCESSED, 40, 518
PMIX_INFO_REQUIRED, 38, 39
PMIX INFO STATIC INIT, 33, 525
```

```
PMIX_INFO_TRUE, 36
PMIX_INFO_WAS_PROCESSED, 41, 518
PMIX_LOAD_KEY, 17
PMIX_LOAD_NSPACE, 19
PMIX_LOAD_PROCID, 22, 23
PMIX LOOKUP STATIC INIT, 119, 525
PMIX_MULTICLUSTER_NSPACE_CONSTRUCT, 24
PMIX_MULTICLUSTER_NSPACE_PARSE, 24
PMIX_NSPACE_INVALID, 19, 521
PMIX_PDATA_CONSTRUCT, 119
PMIX_PDATA_CREATE, 119
PMIX_PDATA_DESTRUCT, 119
PMIX_PDATA_FREE, 120
PMIX_PDATA_LOAD, 120
PMIX_PDATA_RELEASE, 119
PMIX_PDATA_XFER, 121
PMIX_PROC_CONSTRUCT, 21
PMIX_PROC_CREATE, 21
PMIX PROC DESTRUCT, 21
PMIX_PROC_FREE, 22, 76
PMIX_PROC_INFO_CONSTRUCT, 26
PMIX_PROC_INFO_CREATE, 27
PMIX_PROC_INFO_DESTRUCT, 27
PMIX PROC INFO FREE, 27
PMIX_PROC_INFO_RELEASE, 27
PMIX_PROC_INFO_STATIC_INIT, 26, 525
PMIX_PROC_LOAD, 22
PMIX_PROC_RELEASE, 22
PMIX_PROC_STATIC_INIT, 21, 525
PMIX_PROCID_INVALID, 23, 521
PMIX_PROCID_XFER, 24, 521
PMIX_QUERY_CONSTRUCT, 88
PMIX_QUERY_CREATE, 88
PMIX_QUERY_DESTRUCT, 88
PMIX_QUERY_FREE, 89
PMIX_QUERY_QUALIFIERS_CREATE, 89, 497, 498
PMIX_QUERY_RELEASE, 89
PMIX_QUERY_STATIC_INIT, 88, 525
PMIX_RANK_IS_VALID, 20, 521
PMIX_REGATTR_CONSTRUCT, 309
PMIX_REGATTR_CREATE, 310
PMIX_REGATTR_DESTRUCT, 309
PMIX_REGATTR_FREE, 310
PMIX_REGATTR_LOAD, 310
PMIX_REGATTR_STATIC_INIT, 309, 525
PMIX_REGATTR_XFER, 311
PMIX_SETENV, 49
```

```
PMIX_SYSTEM_EVENT, 131
PMIX_TOPOLOGY_CONSTRUCT, 180
PMIX_TOPOLOGY_CREATE, 181
PMIX_TOPOLOGY_STATIC_INIT, 180, 525
PMIX_VALUE_CONSTRUCT, 30
PMIX VALUE CREATE, 30
PMIX_VALUE_DESTRUCT, 30, 70, 74, 506
PMIX_VALUE_FREE, 31
PMIX_VALUE_GET_NUMBER, 33
PMIX_VALUE_RELEASE, 30
PMIX_VALUE_STATIC_INIT, 29, 525
PMIX INFO LIST ADD
    (Deprecated), 524
PMIX_INFO_LIST_CONVERT
    (Deprecated), 524
PMIX_INFO_LIST_RELEASE
    (Deprecated), 524
PMIX_INFO_LIST_START
    (Deprecated), 524
PMIX_INFO_LIST_XFER
    (Deprecated), <u>524</u>
PMIX_INFO_LOAD
    (Deprecated), 524
PMIX_INFO_XFER
    (Deprecated), <u>524</u>
PMIX_TOPOLOGY_DESTRUCT
    (Deprecated), 524
PMIX_TOPOLOGY_FREE
    (Deprecated), 524
PMIX_VALUE_LOAD
    (Deprecated), 524
PMIX_VALUE_UNLOAD
    (Deprecated), <u>524</u>
PMIX_VALUE_XFER
    (Deprecated), 524
```

Index of Data Structures

```
pmix_alloc_directive_t, 51, 55, 189, 192, 195, 195, 357, 431, 471
pmix_app_t, 46, 47, 50, 154-156, 159, 161, 165, 167, 167-170, 336, 337, 339, 386, 389, 391, 393, 394, 402,
          405, 409, 432, 497, 498, 516
pmix_bind_envelope_t, 182, 182, 433, 503
pmix byte object t, 43, 43, 44, 51, 147, 148, 150, 264, 265, 267, 268, 312, 367, 368, 372, 373, 421, 430, 524
pmix_coord_t, 51, 247, 247–249, 433, 503
pmix_coord_view_t, 250, 433, 503
pmix_cpuset_t, 51, 183, 184, 315, 316, 316, 317, 432, 503
pmix_data_array_t, 28, 37, 38, 45, 45, 46, 51, 79, 80, 83, 85, 86, 91, 100, 191, 193, 195, 218, 221, 252, 253,
          255-258, 278, 279, 281-283, 290-292, 303, 352, 359, 378, 389, 403, 409, 410, 431, 497, 498,
          513-515, 527
pmix_data_buffer_t, 140, 140–144, 147, 148
pmix_data_range_t, 51, 55, 114, 114, 136, 348, 430, 470
pmix data type t, 31, 33, 35, 37, 45, 46, 50, 50, 51, 55, 120, 143, 144, 146, 310, 429, 470
pmix_device_distance_t, 51, 183, 185, 186, 186–188, 285, 433, 503, 515
pmix_device_type_t, 51, 56, 185, 185, 257, 433, 473, 503
pmix_endpoint_t, 51, 245, 245, 246, 257, 432, 513
pmix_envar_t, 12, 41, 41-43, 51, 431
pmix_fabric_operation_t, 251, 251, 377
pmix_fabric_t, 245, 251, 251, 254, 255, 258–262, 378, 432, 503, 512
pmix_geometry_t, 51, 244, 248, 248–250, 256, 433, 503, 513, 514
pmix_group_operation_t, 374, 376, 376, 503
pmix group opt t, 235, 237, 238, 238, 462, 503
pmix_info_directives_t, 38, 38, 39, 51, 55, 431, 470
pmix_info_t, 4, 5, 8, 17, 33, 33–41, 51, 53, 54, 58, 60, 62, 76, 80, 85, 86, 88, 89, 91, 111, 113–116, 133, 136,
           139, 170, 183, 184, 189–193, 195, 196, 198, 201–203, 207, 210, 213, 215, 223, 224, 226, 228, 229,
          231, 233, 235, 237, 239, 240, 251, 253, 256, 257, 264, 265, 267, 268, 270, 273, 277–279, 281, 282,
          286, 287, 290–292, 303, 308, 310, 312–314, 319, 321, 339, 348, 353, 354, 357, 359, 360, 362, 363,
          369, 370, 372, 378, 386, 389, 391, 393, 395, 402, 409, 411, 414, 417, 418, 420, 421, 431, 434, 495,
          497, 498, 507–509, 512–514
pmix_iof_channel_t, 51, 56, 312, 370, 372, 400, 400, 418, 431, 471
pmix_job_state_t, 28, 28, 51, 56, 432, 472, 503
pmix key t, 8, 16, 16, 69, 106, 310, 429, 524
pmix_link_state_t, 51, 56, 244, 251, 251, 253, 256, 432, 473, 503, 514
pmix_locality_t, 51, 180, 181, 181, 432, 503, 520
pmix nspace t, 18, 18, 19, 22-24, 51, 170, 429, 430
pmix_pdata_t, 115, 116, 118, 118-121, 431
pmix_persistence_t, 51, 55, 114, 114, 430, 469
pmix_proc_info_t, 26, 26, 27, 51, 78, 79, 82, 83, 85, 352, 403, 410, 430
pmix_proc_state_t, 25, 25, 51, 54, 430, 468
pmix_proc_t, 19, 20, 20–24, 50, 60, 64, 66, 67, 71, 86, 99, 120, 130, 132, 133, 136, 137, 143, 144, 152, 153,
          218, 221, 222, 226, 231, 233, 236, 283, 298–301, 310, 312, 318, 321–325, 329, 330, 332, 334, 336,
```

```
341, 343, 348, 350, 355–357, 360, 363, 365, 368, 370, 372–374, 376, 377, 411, 413, 414, 416, 417, 430, 515

pmix_query_t, 51, 78, 83, 85, <u>87</u>, 87–90, 350, 352, 432, 497, 498, 507

pmix_rank_t, <u>19</u>, 19, 20, 22, 23, 51, 389, 403, 409, 430, 527

pmix_regattr_t, 51, 91, 307, <u>308</u>, 308–311, 432, 501, 503, 509

pmix_scope_t, 51, 55, <u>107</u>, 107, 430, 469

pmix_status_t, <u>14</u>, 14, 33, 46, 47, 49, 50, 53, 54, 68, 128, 131, 133, 136, 139, 185, 302, 306, 326, 342, 343, 345, 347, 348, 355, 367, 369, 375, 429, 442, 468, 526

pmix_storage_access_type_t, <u>424</u>, 424, 521

pmix_storage_accessibility_t, <u>424</u>, 424, 521

pmix_storage_persistence_t, <u>424</u>, 424, 521

pmix_storage_persistence_t, <u>424</u>, 424, 521

pmix_storage_persistence_t, <u>424</u>, 424, 521

pmix_storage_persistence_t, <u>424</u>, 424, 521

pmix_topology_t, 51, 179, <u>180</u>, 180, 181, 183, 184, 503

pmix_value_t, 8, <u>28</u>, 28–33, 50, 53, 70, 71, 74, 106, 431, 506
```

Index of Constants

```
PMIX_ALLOC_DIRECTIVE, 51
PMIX_ALLOC_EXTEND, 195
PMIX_ALLOC_EXTERNAL, 195
PMIX_ALLOC_NEW, 195
PMIX_ALLOC_REAQUIRE, 195
PMIX_ALLOC_RELEASE, 195
PMIX_APP, 51
PMIX_APP_WILDCARD, 13
PMIX_BOOL, 50
PMIX_BUFFER, 51
PMIX_BYTE, 50
PMIX_BYTE_OBJECT, 51
PMIX_COMMAND, 51
PMIX_COMPRESSED_BYTE_OBJECT, 51
PMIX_COMPRESSED_STRING, 51
PMIX_COORD, 51
PMIX_COORD_LOGICAL_VIEW, 250
PMIX COORD PHYSICAL VIEW, 250
PMIX_COORD_VIEW_UNDEF, 250
PMIX CPUBIND PROCESS, 182
PMIX_CPUBIND_THREAD, 182
PMIX_DATA_ARRAY, 51
PMIX_DATA_RANGE, 51
PMIX_DATA_TYPE, 51
PMIX_DATA_TYPE_MAX, 51
PMIX_DEBUGGER_RELEASE, 408
PMIX_DEVICE_DIST, 51
PMIX DEVTYPE, 51
PMIX_DEVTYPE_BLOCK, 185
PMIX_DEVTYPE_COPROC, 186
PMIX DEVTYPE DMA, 186
PMIX_DEVTYPE_GPU, 185
PMIX DEVTYPE NETWORK, 185
PMIX_DEVTYPE_OPENFABRICS, 185
PMIX_DEVTYPE_UNKNOWN, 185
PMIX DOUBLE, 50
PMIX_ENDPOINT, 51
PMIX_ENVAR, 51
PMIX_ERR_BAD_PARAM, 15
PMIX_ERR_COMM_FAILURE, 15
PMIX_ERR_CONFLICTING_CLEANUP_DIRECTIVES, 201
```

```
PMIX_ERR_DUPLICATE_KEY, 113
PMIX_ERR_EMPTY, 15
PMIX_ERR_EVENT_REGISTRATION, 131
PMIX_ERR_EXISTS, 14
PMIX_ERR_EXISTS_OUTSIDE_SCOPE, 14
PMIX ERR INIT, 15
PMIX_ERR_INVALID_CRED, 14
PMIX ERR INVALID OPERATION, 15
PMIX_ERR_IOF_COMPLETE, 400
PMIX_ERR_IOF_FAILURE, 400
PMIX_ERR_JOB_ABORTED, 408
PMIX_ERR_JOB_ABORTED_BY_SIG, 408
PMIX_ERR_JOB_ABORTED_BY_SYS_EVENT, 408
PMIX_ERR_JOB_ALLOC_FAILED, 164
PMIX_ERR_JOB_APP_NOT_EXECUTABLE, 164
PMIX_ERR_JOB_CANCELED, 408
PMIX_ERR_JOB_EXE_NOT_FOUND, 164
PMIX_ERR_JOB_FAILED_TO_LAUNCH, 164
PMIX ERR JOB FAILED TO MAP, 164
PMIX_ERR_JOB_INSUFFICIENT_RESOURCES, 164
PMIX ERR JOB KILLED BY CMD, 408
PMIX_ERR_JOB_NO_EXE_SPECIFIED, 164
PMIX_ERR_JOB_NON_ZERO_TERM, 408
PMIX ERR JOB SENSOR BOUND EXCEEDED, 408
PMIX_ERR_JOB_SYS_OP_FAILED, 164
PMIX_ERR_JOB_TERM_WO_SYNC, 408
PMIX_ERR_JOB_WDIR_NOT_FOUND, 164
PMIX_ERR_LOST_CONNECTION, 15
PMIX_ERR_NO_PERMISSIONS, 14
PMIX_ERR_NOMEM, 15
PMIX_ERR_NOT_FOUND, 15
PMIX_ERR_NOT_SUPPORTED, 15
PMIX_ERR_OUT_OF_RESOURCE, 15
PMIX ERR PACK FAILURE, 14
PMIX_ERR_PARAM_VALUE_NOT_SUPPORTED, 15
PMIX_ERR_PARTIAL_SUCCESS, 15
PMIX ERR PROC CHECKPOINT, 201
PMIX_ERR_PROC_MIGRATE, 201
PMIX_ERR_PROC_RESTART, 201
PMIX_ERR_PROC_TERM_WO_SYNC, 408
PMIX_ERR_REPEAT_ATTR_REGISTRATION, 308
PMIX_ERR_RESOURCE_BUSY, 15
PMIX_ERR_TIMEOUT, 14
PMIX ERR TYPE MISMATCH, 14
PMIX_ERR_UNKNOWN_DATA_TYPE, 14
PMIX_ERR_UNPACK_FAILURE, 14
PMIX ERR UNPACK INADEQUATE SPACE, 14
```

```
PMIX_ERR_UNPACK_READ_PAST_END_OF_BUFFER, 14
PMIX_ERR_UNREACH, 15
PMIX_ERR_WOULD_BLOCK, 14
PMIX_ERROR, 14
PMIX_EVENT_ACTION_COMPLETE, 139
PMIX EVENT ACTION DEFERRED, 139
PMIX_EVENT_JOB_END, 407
PMIX_EVENT_JOB_START, 407
PMIX_EVENT_NO_ACTION_TAKEN, 139
PMIX_EVENT_NODE_DOWN, 131
PMIX_EVENT_NODE_OFFLINE, 131
PMIX_EVENT_PARTIAL_ACTION_TAKEN, 139
PMIX_EVENT_PROC_TERMINATED, 407
PMIX_EVENT_SESSION_END, 407
PMIX_EVENT_SESSION_START, 407
PMIX_EVENT_SYS_BASE, 131
PMIX_EVENT_SYS_OTHER, 131
PMIX_EXTERNAL_ERR_BASE, 15
PMIX FABRIC REQUEST INFO, 251
PMIX_FABRIC_UPDATE_ENDPOINTS, 245
PMIX FABRIC UPDATE INFO, 251
PMIX_FABRIC_UPDATE_PENDING, 245
PMIX_FABRIC_UPDATED, 245
PMIX FLOAT, 50
PMIX_FWD_ALL_CHANNELS, 400
PMIX_FWD_NO_CHANNELS, 400
PMIX_FWD_STDDIAG_CHANNEL, 400
PMIX_FWD_STDERR_CHANNEL, 400
PMIX_FWD_STDIN_CHANNEL, 400
PMIX_FWD_STDOUT_CHANNEL, 400
PMIX_GEOMETRY, 51
PMIX_GLOBAL, 107
PMIX_GROUP_ACCEPT, 238
PMIX GROUP CONSTRUCT, 376
PMIX_GROUP_CONSTRUCT_ABORT, 221
PMIX_GROUP_CONSTRUCT_COMPLETE, 221
PMIX_GROUP_CONTEXT_ID_ASSIGNED, 221
PMIX_GROUP_DECLINE, 238
PMIX_GROUP_DESTRUCT, 376
PMIX_GROUP_INVITE_ACCEPTED, 220
PMIX_GROUP_INVITE_DECLINED, 220
PMIX_GROUP_INVITE_FAILED, 220
PMIX_GROUP_INVITED, 220
PMIX_GROUP_LEADER_FAILED, 221
PMIX_GROUP_LEADER_SELECTED, 221
PMIX_GROUP_LEFT, 220
PMIX_GROUP_MEMBER_FAILED, 220
```

```
PMIX_GROUP_MEMBERSHIP_UPDATE, 220
PMIX_INFO, 51
PMIX_INFO_ARRAY_END, 39
PMIX_INFO_DIR_RESERVED, 39
PMIX_INFO_DIRECTIVES, 51
PMIX INFO REOD, 39
PMIX_INFO_REQD_PROCESSED, 39
PMIX_INT, 50
PMIX_INT16, 50
PMIX_INT32, 50
PMIX_INT64, 50
PMIX_INT8, <u>50</u>
PMIX_INTERNAL, 107
PMIX_IOF_CHANNEL, 51
PMIX_JCTRL_CHECKPOINT, 201
PMIX_JCTRL_CHECKPOINT_COMPLETE, 201
PMIX_JCTRL_PREEMPT_ALERT, 201
PMIX_JOB_STATE, 51
PMIX JOB STATE AWAITING ALLOC, 28
PMIX_JOB_STATE_CONNECTED, 28
PMIX_JOB_STATE_LAUNCH_UNDERWAY, 28
PMIX_JOB_STATE_RUNNING, 28
PMIX_JOB_STATE_SUSPENDED, 28
PMIX_JOB_STATE_TERMINATED, 28
PMIX_JOB_STATE_TERMINATED_WITH_ERROR, 28
PMIX_JOB_STATE_UNDEF, 28
PMIX_JOB_STATE_UNTERMINATED, 28
PMIX_KVAL, 51
PMIX_LAUNCH_COMPLETE, 407
PMIX_LAUNCHER_READY, 396
PMIX_LINK_DOWN, 251
PMIX_LINK_STATE, 51
PMIX_LINK_STATE_UNKNOWN, 251
PMIX LINK UP, 251
PMIX_LOCAL, 107
PMIX_LOCALITY_NONLOCAL, 181
PMIX_LOCALITY_SHARE_CORE, 181
PMIX_LOCALITY_SHARE_HWTHREAD, 181
PMIX_LOCALITY_SHARE_L1CACHE, 181
PMIX_LOCALITY_SHARE_L2CACHE, 181
PMIX_LOCALITY_SHARE_L3CACHE, 181
PMIX_LOCALITY_SHARE_NODE, 181
PMIX_LOCALITY_SHARE_NUMA, 181
PMIX_LOCALITY_SHARE_PACKAGE, 181
PMIX_LOCALITY_UNKNOWN, 181
PMIX_LOCTYPE, 51
PMIX_MAX_KEYLEN, 13
```

```
PMIX_MAX_NSLEN, 13
PMIX_MODEL_DECLARED, 61
PMIX_MODEL_RESOURCES, 61
PMIX_MONITOR_FILE_ALERT, 207
PMIX_MONITOR_HEARTBEAT_ALERT, 207
PMIX OPENMP PARALLEL ENTERED, 61
PMIX_OPENMP_PARALLEL_EXITED, 61
PMIX_OPERATION_IN_PROGRESS, 15
PMIX_OPERATION_SUCCEEDED, 15
PMIX_PDATA, 51
PMIX_PERSIST, 51
PMIX_PERSIST_APP, 114
PMIX_PERSIST_FIRST_READ, 114
PMIX_PERSIST_INDEF, 114
PMIX_PERSIST_INVALID, 114
PMIX_PERSIST_PROC, 114
PMIX_PERSIST_SESSION, 114
PMIX_PID, 50
PMIX POINTER, 51
PMIX_PROC, 50
PMIX PROC CPUSET, 51
PMIX_PROC_INFO, 51
PMIX_PROC_NSPACE, 51
PMIX PROC RANK, 51
PMIX_PROC_STATE, 51
PMIX_PROC_STATE_ABORTED, 25
PMIX_PROC_STATE_ABORTED_BY_SIG, 25
PMIX_PROC_STATE_CALLED_ABORT, 25
PMIX_PROC_STATE_CANNOT_RESTART, 25
PMIX_PROC_STATE_COMM_FAILED, 25
PMIX_PROC_STATE_CONNECTED, 25
PMIX_PROC_STATE_ERROR, 25
PMIX_PROC_STATE_FAILED_TO_LAUNCH, 25
PMIX PROC STATE FAILED TO START, 25
PMIX_PROC_STATE_HEARTBEAT_FAILED, 25
PMIX_PROC_STATE_KILLED_BY_CMD, 25
PMIX_PROC_STATE_LAUNCH_UNDERWAY, 25
PMIX_PROC_STATE_MIGRATING, 25
PMIX_PROC_STATE_PREPPED, 25
PMIX_PROC_STATE_RESTART, 25
PMIX_PROC_STATE_RUNNING, 25
PMIX_PROC_STATE_SENSOR_BOUND_EXCEEDED, 25
PMIX_PROC_STATE_TERM_NON_ZERO, 25
PMIX_PROC_STATE_TERM_WO_SYNC, 25
PMIX_PROC_STATE_TERMINATE, 25
PMIX_PROC_STATE_TERMINATED, 25
PMIX_PROC_STATE_UNDEF, 25
```

```
PMIX_PROC_STATE_UNTERMINATED, 25
PMIX_PROCESS_SET_DEFINE, 217
PMIX_PROCESS_SET_DELETE, 217
PMIX_QUERY, 51
PMIX_QUERY_PARTIAL_SUCCESS, 85
PMIX RANGE CUSTOM, 114
PMIX_RANGE_GLOBAL, 114
PMIX RANGE INVALID, 114
PMIX_RANGE_LOCAL, 114
PMIX_RANGE_NAMESPACE, 114
PMIX_RANGE_PROC_LOCAL, 114
PMIX_RANGE_RM, 114
PMIX_RANGE_SESSION, 114
PMIX_RANGE_UNDEF, 114
PMIX_RANK_INVALID, 20
PMIX_RANK_LOCAL_NODE, 19
PMIX_RANK_LOCAL_PEERS, 20
PMIX_RANK_UNDEF, 19
PMIX RANK VALID, 20
PMIX_RANK_WILDCARD, 19
PMIX_READY_FOR_DEBUG, 408
PMIX_REGATTR, 51
PMIX_REGEX, 51
PMIX REMOTE, 107
PMIX_SCOPE, 51
PMIX_SCOPE_UNDEF, 107
PMIX_SIZE, 50
PMIX_STATUS, 50
PMIX_STORAGE_ACCESS_RD, 424
PMIX_STORAGE_ACCESS_RDWR, 424
PMIX_STORAGE_ACCESS_WR, 424
PMIX_STORAGE_ACCESSIBILITY_CLUSTER, 424
PMIX_STORAGE_ACCESSIBILITY_JOB, 424
PMIX STORAGE ACCESSIBILITY NODE, 424
PMIX_STORAGE_ACCESSIBILITY_RACK, 424
PMIX_STORAGE_ACCESSIBILITY_REMOTE, 424
PMIX_STORAGE_ACCESSIBILITY_SESSION, 424
PMIX_STORAGE_MEDIUM_HDD, 423
PMIX_STORAGE_MEDIUM_NVME, 423
PMIX_STORAGE_MEDIUM_PMEM, 423
PMIX_STORAGE_MEDIUM_RAM, 423
PMIX_STORAGE_MEDIUM_SSD, 423
PMIX_STORAGE_MEDIUM_TAPE, 423
PMIX STORAGE MEDIUM UNKNOWN, 423
PMIX_STORAGE_PERSISTENCE_ARCHIVE, 424
PMIX_STORAGE_PERSISTENCE_JOB, 424
PMIX STORAGE PERSISTENCE NODE, 424
```

```
PMIX_STORAGE_PERSISTENCE_PROJECT, 424
PMIX_STORAGE_PERSISTENCE_SCRATCH, 424
PMIX_STORAGE_PERSISTENCE_SESSION, 424
PMIX_STORAGE_PERSISTENCE_TEMPORARY, 424
PMIX_STRING, 50
PMIX_SUCCESS, 14
PMIX_TIME, 50
PMIX_TIMEVAL, 50
PMIX_TOPO, 51
PMIX_UINT, 50
PMIX_UINT16, 50
PMIX_UINT32, 50
PMIX_UINT64, 50
PMIX_UINT8, 50
PMIX_UNDEF, 50
PMIX_VALUE, 50
PMIX_CONNECT_REQUESTED
    Deprecated, <u>518</u>
PMIX_DEBUG_WAITING_FOR_NOTIFY
    Deprecated, 524
PMIX_ERR_DATA_VALUE_NOT_FOUND
    Deprecated, 499
    Removed, 519
PMIX_ERR_DEBUGGER_RELEASE
    Deprecated, 518
PMIX_ERR_HANDSHAKE_FAILED
    Deprecated, 499
    Removed, 518
PMIX_ERR_IN_ERRNO
    Deprecated, 499
    Removed, <u>518</u>
PMIX_ERR_INVALID_ARG
    Deprecated, 499
    Removed, 519
PMIX_ERR_INVALID_ARGS
    Deprecated, 499
    Removed, 519
PMIX_ERR_INVALID_KEY
    Deprecated, 499
    Removed, 519
PMIX_ERR_INVALID_KEY_LENGTH
    Deprecated, 499
    Removed, <u>519</u>
PMIX_ERR_INVALID_KEYVALP
    Deprecated, 499
    Removed, <u>519</u>
```

```
PMIX_ERR_INVALID_LENGTH
    Deprecated, 499
    Removed, 519
PMIX_ERR_INVALID_NAMESPACE
    Deprecated, 499
    Removed, 519
PMIX_ERR_INVALID_NUM_ARGS
    Deprecated, 499
    Removed, 519
PMIX_ERR_INVALID_NUM_PARSED
    Deprecated, 499
    Removed, 519
PMIX_ERR_INVALID_SIZE
    Deprecated, 499
    Removed, 519
PMIX_ERR_INVALID_TERMINATION
    Deprecated, 518
PMIX_ERR_INVALID_VAL
    Deprecated, 499
    Removed, 519
PMIX_ERR_INVALID_VAL_LENGTH
    Deprecated, 500
    Removed, 518
PMIX_ERR_JOB_TERMINATED
    Deprecated, 518
PMIX_ERR_LOST_CONNECTION_TO_CLIENT
    Deprecated, 518
PMIX_ERR_LOST_CONNECTION_TO_SERVER
    Deprecated, 518
PMIX_ERR_LOST_PEER_CONNECTION
    Deprecated, 518
PMIX_ERR_NODE_DOWN
    Deprecated, 518
PMIX_ERR_NODE_OFFLINE
    Deprecated, 518
PMIX_ERR_NOT_IMPLEMENTED
    Deprecated, 500
    Removed, 519
PMIX_ERR_PACK_MISMATCH
    Deprecated, 500
    Removed, 519
PMIX_ERR_PROC_ABORTED
    Deprecated, 518
PMIX_ERR_PROC_ABORTING
    Deprecated, 518
PMIX_ERR_PROC_ENTRY_NOT_FOUND
    Deprecated, 500
```

```
Removed, <u>519</u>
PMIX_ERR_PROC_REQUESTED_ABORT
    Deprecated, 500
    Removed, <u>519</u>
PMIX_ERR_READY_FOR_HANDSHAKE
    Deprecated, 500
    Removed, 518
PMIX_ERR_SERVER_FAILED_REQUEST
    Deprecated, 500
    Removed, 519
PMIX_ERR_SERVER_NOT_AVAIL
    Deprecated, <u>500</u>
    Removed, 519
PMIX_ERR_SILENT
    Deprecated, 500
    Removed, 519
PMIX_ERR_SYS_OTHER
    Deprecated, 518
PMIX EXISTS
    Deprecated, 518
PMIX_GDS_ACTION_COMPLETE
    Deprecated, 500
    Removed, 519
PMIX_INFO_ARRAY
    Deprecated, 495
PMIX_MODEX
    Deprecated, 495
PMIX_NOTIFY_ALLOC_COMPLETE
    Deprecated, 500
    Removed, <u>519</u>
PMIX_PROC_HAS_CONNECTED
    Deprecated, 518
PMIX_PROC_TERMINATED
    Deprecated, 518
```

Index of Environmental Variables

PMIX_KEEPALIVE_PIPE, <u>384</u>, 393, 394, 517 PMIX_LAUNCHER_RNDZ_FILE, 381, <u>384</u>, 517 PMIX_LAUNCHER_RNDZ_URI, <u>384</u>, 393, 394, 517

Index of Attributes

```
PMIX_ACCESS_GRPIDS, 113, 509
PMIX ACCESS PERMISSIONS, 111, 113, 113, 509
PMIX_ACCESS_USERIDS, 113, 509
PMIX_ADD_ENVAR, 156, 162, 167
PMIX ADD HOST, 155, 160, 164, 338
PMIX_ADD_HOSTFILE, 155, 160, 164, 338
PMIX_ALL_CLONES_PARTICIPATE, 65, 68, 69, 172, 174, 176, 178, 506
PMIX_ALLOC_BANDWIDTH, 157, 162, 191, 193, 195, 195, 303, 304, 359
PMIX_ALLOC_CPU_LIST, 157, 162, 190, 193, 194, 359
PMIX_ALLOC_FABRIC, 190, 193, 194, 303, 359, 519
PMIX_ALLOC_FABRIC_ENDPTS, 157, 162, 190, 191, 193, 194, 195, 195, 303, 359, 519
PMIX_ALLOC_FABRIC_ENDPTS_NODE, 157, 163, 191, 194, 195, 304, 520
PMIX_ALLOC_FABRIC_ID, 190, 191, 193, 195, 195, 303, 359, 519
PMIX_ALLOC_FABRIC_PLANE, 157, 162, 191, 193, 194, 195, 195, 303, 359, 519
PMIX_ALLOC_FABRIC_QOS, 157, 162, 191, 193, 195, 195, 303, 304, 359, 519
PMIX_ALLOC_FABRIC_SEC_KEY, 191, 193, 194, 195, 195, 303, 359, 520
PMIX_ALLOC_FABRIC_TYPE, 157, 162, 190, 191, 193, 195, 195, 303, 359, 519
PMIX ALLOC ID, 192, 194, 358, 499, 509
PMIX_ALLOC_MEM_SIZE, 157, 162, 190, 193, 194, 359
PMIX ALLOC NODE LIST, 157, 162, 190, 193, 194, 359
PMIX_ALLOC_NUM_CPU_LIST, 157, 162, 190, 193, 194, 359
PMIX_ALLOC_NUM_CPUS, 157, 162, 190, 193, 194, 358
PMIX_ALLOC_NUM_NODES, 157, 162, 190, 193, 194, 358
PMIX_ALLOC_QUEUE, 79, 83, 85, 157, 162, 194, 351, 509
PMIX_ALLOC_REQ_ID, 190, 192, 194, 499
PMIX_ALLOC_TIME, 157, 162, 190, 193, 195, 358
PMIX_ALLOCATED_NODELIST, 94, 279
PMIX ANL MAP, 94, 96, 280
PMIX_APP_ARGV, 96, 96, 281, 510
PMIX_APP_INFO, 70, 73, 77, 82, 92, 96, 100, 281, 282
PMIX APP INFO ARRAY, 278, 281, 286, 286, 291, 508
PMIX_APP_MAP_REGEX, 97, 281
PMIX APP MAP TYPE, 97, 281
PMIX_APP_RANK, 98, 283
PMIX_APP_SIZE, 96, 281, 291
PMIX_APPEND_ENVAR, 157, 162, 167
PMIX_APPLDR, 96, 281, 291
PMIX_APPNUM, 70, 73, 77, 82, 92, 96, 97, 100, 278, 281–283, 286, 291, 508
PMIX_ATTR_UNDEF, 5
PMIX_AVAIL_PHYS_MEMORY, 87, 99, 283
PMIX_BINDTO, 155, 160, 165, 280, 338
```

```
PMIX_BREAKPOINT, 389, 403, 408, 409, 409, 527
PMIX_CLEANUP_EMPTY, 197, 200, 203
PMIX CLEANUP IGNORE, 197, 200, 203
PMIX_CLEANUP_LEAVE_TOPDIR, 197, 200, 203
PMIX_CLEANUP_RECURSIVE, 197, 200, 202
PMIX CLIENT ATTRIBUTES, 78, 82, 87, 90, 403, 501, 507
PMIX_CLIENT_AVG_MEMORY, 80, 84, 87
PMIX_CLIENT_FUNCTIONS, 78, 82, 86, 87, 90, 507
PMIX_CLUSTER_ID, 93, 279
PMIX_CMD_LINE, 96, 510, 524
PMIX_COLLECT_DATA, 65, 67, 68, 105, 326
PMIX_COLLECT_GENERATED_JOB_INFO, 65, 67, 68, 69, 243, 326, 506
PMIX_COLLECTIVE_ALGO, 496
PMIX_CONNECT_MAX_RETRIES, 385, 412
PMIX_CONNECT_RETRY_DELAY, 385, 412
PMIX_CONNECT_SYSTEM_FIRST, 382, 385, 411, 415
PMIX_CONNECT_TO_SYSTEM, 382, <u>385</u>, 411, 415
PMIX_COSPAWN_APP, 157, 163, 409
PMIX CPU LIST, 156, 161, 166, 340
PMIX_CPUS_PER_PROC, 156, 161, 165, 339
PMIX CPUSET, 98, 182, 284, 316
PMIX_CPUSET_BITMAP, 98, 285, 510
PMIX_CRED_TYPE, 266, 366
PMIX CREDENTIAL, 98, 353
PMIX_CRYPTO_KEY, 266, 280
PMIX_DAEMON_MEMORY, 80, 84, 87
PMIX_DATA_SCOPE, 70, 73, 74
PMIX_DEBUG_DAEMONS_PER_NODE, 339, 404, 405, 409, 410, 512
PMIX_DEBUG_DAEMONS_PER_PROC, 339, 404, 405, 409, 410, 512
PMIX_DEBUG_STOP_IN_APP, 389, 402, 403, 409, 524, 527
PMIX_DEBUG_STOP_IN_INIT, 389, 393, 394, 402, 403, 405, 409
PMIX_DEBUG_STOP_ON_EXEC, 389, 394, 402, 403, 409
PMIX_DEBUG_TARGET, 339, 403–405, 409, 409, 410, 511, 512, 519
PMIX DEBUGGER DAEMONS, 339, 404, 405, 409
PMIX_DEVICE_DISTANCES, 188, 257, 285, 515
PMIX_DEVICE_ID, 188, 243, 253, 256, 257, 297, 513–515
PMIX DEVICE TYPE, 188, 515
PMIX_DISPLAY_MAP, 155, 160, 164, 338
PMIX_EMBED_BARRIER, 62, 63
PMIX_ENUM_VALUE, 308, 309, 501, 509
PMIX_ENVARS_HARVESTED, 158, 163, 167, 526
PMIX_EVENT_ACTION_TIMEOUT, 132, 137
PMIX_EVENT_AFFECTED_PROC, 130, 132, 137, 407
PMIX_EVENT_AFFECTED_PROCS, 130, 132, 137, 407
PMIX_EVENT_BASE, <u>59</u>, 272, 412
PMIX_EVENT_CUSTOM_RANGE, 130, 132, 137
PMIX EVENT DO NOT CACHE, 132, 137
```

```
PMIX_EVENT_HDLR_AFTER, 129, 131
PMIX_EVENT_HDLR_APPEND, 129, 131
PMIX EVENT HDLR BEFORE, 129, 131
PMIX_EVENT_HDLR_FIRST, 129, 131
PMIX_EVENT_HDLR_FIRST_IN_CATEGORY, 129, 131
PMIX EVENT HDLR LAST, 129, 131
PMIX_EVENT_HDLR_LAST_IN_CATEGORY, 129, 131
PMIX EVENT HDLR NAME, 129, 131
PMIX_EVENT_HDLR_PREPEND, 129, 131
PMIX_EVENT_NON_DEFAULT, 132, 137
PMIX_EVENT_PROXY, 132, 137
PMIX_EVENT_RETURN_OBJECT, 130, 132
PMIX_EVENT_SILENT_TERMINATION, 158, 163, 167
PMIX_EVENT_TERMINATE_JOB, 132, 137
PMIX_EVENT_TERMINATE_NODE, 132, 137
PMIX_EVENT_TERMINATE_PROC, 132, 137
PMIX_EVENT_TERMINATE_SESSION, 132, 137
PMIX_EVENT_TEXT_MESSAGE, 132, 137
PMIX EVENT TIMESTAMP, 132, 166, 167, 388-390, 407, 517
PMIX_EXEC_AGENT, 393, 395, 406, 511
PMIX EXIT CODE, 98, 166, 167, 388–390, 407, 517
PMIX_EXTERNAL_PROGRESS, 59, 272, 275, 412, 510
PMIX_FABRIC_COORDINATES, 256, 513
PMIX FABRIC COST MATRIX, 252, 254, 512
PMIX_FABRIC_DEVICE, 243, 253, 256, 256, 514
PMIX_FABRIC_DEVICE_ADDRESS, 244, 253, 256, 514
PMIX_FABRIC_DEVICE_BUS_TYPE, 243, 254, 256, 514
PMIX_FABRIC_DEVICE_COORDINATES, 244, 256, 514
PMIX_FABRIC_DEVICE_DRIVER, 244, 253, 256, 514
PMIX_FABRIC_DEVICE_FIRMWARE, 244, 253, 256, 514
PMIX_FABRIC_DEVICE_INDEX, 244, 256, 378, 514
PMIX_FABRIC_DEVICE_MTU, 244, 253, 256, 514
PMIX_FABRIC_DEVICE_NAME, 243, 253, 256, 297, 514
PMIX FABRIC DEVICE PCI DEVID, 244, 254, 257, 257, 514, 515
PMIX_FABRIC_DEVICE_SPEED, 244, 253, 256, 514
PMIX_FABRIC_DEVICE_STATE, 244, 253, 256, 514
PMIX_FABRIC_DEVICE_TYPE, 244, 254, 257, 514
PMIX_FABRIC_DEVICE_VENDOR, 243, 253, 256, 514
PMIX_FABRIC_DEVICE_VENDORID, 244, 256, 514
PMIX_FABRIC_DEVICES, 243, 256
PMIX_FABRIC_DIMS, 252, 255, 513
PMIX_FABRIC_ENDPT, 257, 513
PMIX_FABRIC_GROUPS, 252, 255, 512
PMIX FABRIC IDENTIFIER, 252, 255, 258, 377, 512
PMIX_FABRIC_INDEX, 251, 255, 255, 512
PMIX_FABRIC_NUM_DEVICES, 252, 255, 512
PMIX FABRIC PLANE, 252, 253, 255, 256, 258, 259, 377, 513
```

```
PMIX_FABRIC_SHAPE, 252, 255, 513
PMIX_FABRIC_SHAPE_STRING, 253, 255, 513
PMIX FABRIC SWITCH, 255, 257, 513
PMIX_FABRIC_VENDOR, 252, 255, 258, 377, 512
PMIX_FIRST_ENVAR, 157, 162, 167, 517
PMIX FORKEXEC AGENT, 392, 394, 395, 406, 511
PMIX_FWD_STDDIAG, 387, 391, 395, 498
PMIX FWD STDERR, 339, 354, 386, 391, 395, 396
PMIX_FWD_STDIN, 339, 354, 386, 391, 395, 396
PMIX_FWD_STDOUT, 339, 354, 386, 391, 394, 395, 396
PMIX_GET_POINTER_VALUES, 70, 71, 73, 74, 506
PMIX_GET_REFRESH_CACHE, 70, 73, 74, 108, 506
PMIX_GET_STATIC_VALUES, 69-71, 74, 74, 506
PMIX_GLOBAL_RANK, 97, 283
PMIX_GROUP_ASSIGN_CONTEXT_ID, 221, 223, 227, 231, 234, 375, 376, 516
PMIX_GROUP_CONTEXT_ID, 222, 376, 516
PMIX_GROUP_ENDPT_DATA, 222, 375, 376, 516
PMIX_GROUP_FT_COLLECTIVE, 221, 223, 227, 231, 234, 516
PMIX GROUP ID, 221, 221, 376, 515
PMIX_GROUP_LEADER, 221, 223, 224, 227, 233, 237, 516
PMIX GROUP LOCAL ONLY, 222, 223, 227, 375, 516
PMIX_GROUP_MEMBERSHIP, 221, 224, 376
PMIX_GROUP_NAMES, 222, 516
PMIX_GROUP_NOTIFY_TERMINATION, 221, 223, 224, 227, 229, 232, 234, 516
PMIX_GROUP_OPTIONAL, 221, 223, 225, 227, 231, 234, 376, 516
PMIX_GRPID, 78, 83, 110, 112, 115, 117, 123, 124, 190, 192, 197, 199, 204, 206, 209, 212, 264, 265, 267,
         269, 331–337, 345, 351, 353, 355, 356, 358, 361, 364, 366, 368, 370, 371, 374
PMIX_HOMOGENEOUS_SYSTEM, 273, 275, 509
PMIX_HOST, 154, 159, 164, 338
PMIX_HOST_ATTRIBUTES, 78, 83, 87, 91, 403, 501, 507
PMIX HOST FUNCTIONS, 78, 82, 86, 87, 91, 507
PMIX_HOSTFILE, 154, 160, 164, 338
PMIX_HOSTNAME, 70, 73, 77, 79, 80, 82–84, 86, 87, 93, 99, 99, 243, 244, 253, 254, 257, 278, 282, 284,
         286, 297, 352, 403, 410, 509, 515
PMIX_HOSTNAME_ALIASES, 99, 282, 510
PMIX_HOSTNAME_KEEP_FQDN, 93, 280, 510
PMIX_IMMEDIATE, 70, 72, 74, 100, 108
PMIX_INDEX_ARGV, 156, 161, 165, 339
PMIX_IOF_BUFFERING_SIZE, 371, 387, 392, 400, 419, 422
PMIX_IOF_BUFFERING_TIME, 371, 387, 392, 400, 419, 422
PMIX_IOF_CACHE_SIZE, 371, 387, 392, 400, 418, 421
PMIX_IOF_COMPLETE, 372, 398, 401, 401, 422, 435, 511
PMIX_IOF_COPY, 397, 401, 511
PMIX IOF DROP NEWEST, 371, 387, 392, 400, 418, 421
PMIX_IOF_DROP_OLDEST, 371, 387, 392, 400, 418, 421
PMIX_IOF_FILE_ONLY, 388, 389, 398, 401, 526
PMIX IOF FILE PATTERN, 388, 398, 401, 526
```

```
PMIX_IOF_LOCAL_OUTPUT, 273, 400, 413, 526
PMIX_IOF_MERGE_STDERR_STDOUT, 388, 398, 400, 401, 526, 527
PMIX IOF OUTPUT RAW, 387, 400, 527
PMIX_IOF_OUTPUT_TO_DIRECTORY, 388, 389, 398, 401, 527
PMIX_IOF_OUTPUT_TO_FILE, 387, 389, 398, 401, 527
PMIX IOF PUSH STDIN, 398, 401, 422, 511
PMIX_IOF_RANK_OUTPUT, 387, 398, 401, 526
PMIX_IOF_REDIRECT, 397, 401, 511
PMIX_IOF_TAG_OUTPUT, 387, 392, 397, 401, 419
PMIX_IOF_TIMESTAMP_OUTPUT, 387, 392, 397, 401, 419
PMIX_IOF_XML_OUTPUT, 387, 392, 398, 401, 419
PMIX_JOB_CONTINUOUS, 156, 161, 166, 340
PMIX_JOB_CTRL_CANCEL, 198, 200, 202, 362
PMIX_JOB_CTRL_CHECKPOINT, 198, 200, 202, 362
PMIX_JOB_CTRL_CHECKPOINT_EVENT, 198, 200, 202, 362
PMIX_JOB_CTRL_CHECKPOINT_METHOD, 198, 201, 202, 362
PMIX_JOB_CTRL_CHECKPOINT_SIGNAL, 198, 200, 202, 362
PMIX_JOB_CTRL_CHECKPOINT_TIMEOUT, 198, 201, 202, 362
PMIX JOB CTRL ID, 197–200, 202, 202, 361, 362
PMIX_JOB_CTRL_KILL, 197, 200, 202, 361
PMIX JOB CTRL PAUSE, 197, 199, 202, 361
PMIX_JOB_CTRL_PREEMPTIBLE, 198, 201, 202, 362
PMIX_JOB_CTRL_PROVISION, 198, 201, 202, 362
PMIX JOB CTRL PROVISION IMAGE, 198, 201, 202, 362
PMIX_JOB_CTRL_RESTART, 198, 200, 202, 362
PMIX_JOB_CTRL_RESUME, 197, 200, 202, 361
PMIX_JOB_CTRL_SIGNAL, 197, 200, 202, 361
PMIX_JOB_CTRL_TERMINATE, 197, 200, 202, 361
PMIX_JOB_INFO, 70, 73, 77, 82, 92, 94
PMIX_JOB_INFO_ARRAY, 277, 279, 286, 286, 290, 497, 508
PMIX_JOB_NUM_APPS, 96, 280, 290
PMIX_JOB_RECOVERABLE, 156, 161, 166, 340
PMIX_JOB_SIZE, 96, 279, 290, 496, 499
PMIX JOB TERM STATUS, 166, 167, 388–390, 407, 408, 408, 517
PMIX_JOB_TIMEOUT, 158, 163, 167, 167, 340, 526
PMIX_JOBID, 95, 278, 279, 286, 290, 407, 508
PMIX LAUNCH DIRECTIVES, 394, 395, 512
PMIX_LAUNCHER, 379, 384, 385
PMIX_LAUNCHER_DAEMON, 392, 395, 511
PMIX_LAUNCHER_RENDEZVOUS_FILE, 381, 385, 511
PMIX_LOCAL_COLLECTIVE_STATUS, 68, 326, 342, 343, 375, 526
PMIX_LOCAL_CPUSETS, 99, 283, 294
PMIX_LOCAL_PEERS, 99, 100, 282, 283, 292
PMIX LOCAL PROCS, 99, 283
PMIX_LOCAL_RANK, 98, 283, 404-406, 410, 512
PMIX_LOCAL_SIZE, 100, 282
PMIX LOCALITY STRING, 180, 181, 284, 315
```

```
PMIX_LOCALLDR, 99, 282
PMIX_LOG_COMPLETION, 167, 388, 407, 517
PMIX_LOG_EMAIL, 210, 213, 215, 357
PMIX_LOG_EMAIL_ADDR, 210, 213, 215, 357
PMIX_LOG_EMAIL_MSG, 210, 213, 215, 357
PMIX LOG EMAIL SENDER ADDR, 210, 213, 215
PMIX_LOG_EMAIL_SERVER, 210, 213, 215
PMIX_LOG_EMAIL_SRVR_PORT, 210, 213, 215
PMIX_LOG_EMAIL_SUBJECT, 210, 213, 215, 357
PMIX_LOG_GENERATE_TIMESTAMP, 210, 213, 214
PMIX_LOG_GLOBAL_DATASTORE, 211, 213, 215
PMIX_LOG_GLOBAL_SYSLOG, 210, 212, 214
PMIX_LOG_JOB_EVENTS, <u>167</u>, 388, 407, 517
PMIX_LOG_JOB_RECORD, 210, 213, 215
PMIX_LOG_LOCAL_SYSLOG, 209, 212, 214
PMIX_LOG_MSG, 215, 357
PMIX_LOG_ONCE, 210, 212, 214
PMIX_LOG_PROC_ABNORMAL_TERMINATION, 166, 517
PMIX LOG PROC TERMINATION, 166, 517
PMIX_LOG_SOURCE, 210, 213, 214
PMIX LOG STDERR, 209, 212, 214, 356
PMIX_LOG_STDOUT, 209, 212, 214, 356
PMIX_LOG_SYSLOG, 209, 212, 214, 356
PMIX_LOG_SYSLOG_PRI, 210, 212, 214
PMIX_LOG_TAG_OUTPUT, 210, 213, 214
PMIX_LOG_TIMESTAMP, 210, 213, 214
PMIX_LOG_TIMESTAMP_OUTPUT, 210, 213, 214
PMIX_LOG_XML_OUTPUT, 210, 213, 214
PMIX_MAPBY, 155, 160, 164, 164, 280, 338
PMIX_MAX_PROCS, 93, 94, 94–97, 278–281, 283, 308, 499
PMIX_MAX_RESTARTS, 156, 161, 166, 340
PMIX MAX VALUE, 308, 309, 501, 509
PMIX_MERGE_STDERR_STDOUT, 156, 161, 165, 339
PMIX_MIN_VALUE, 308, 309, 501, 509
PMIX_MODEL_AFFINITY_POLICY, 60, 62
PMIX_MODEL_CPU_TYPE, 60, 62
PMIX_MODEL_LIBRARY_NAME, 59, 61, 282, 304
PMIX_MODEL_LIBRARY_VERSION, 60, 61, 282, 304
PMIX_MODEL_NUM_CPUS, 60, 62
PMIX_MODEL_NUM_THREADS, 60, 62
PMIX_MODEL_PHASE_NAME, 62, 132
PMIX_MODEL_PHASE_TYPE, 62, 132
PMIX_MONITOR_APP_CONTROL, 204, 206, 208, 364
PMIX MONITOR CANCEL, 204, 206, 208, 364
PMIX_MONITOR_FILE, 204–206, 208, 364
PMIX_MONITOR_FILE_ACCESS, 204, 206, 208, 364
PMIX MONITOR FILE CHECK TIME, 204, 207, 208, 364
```

```
PMIX_MONITOR_FILE_DROPS, 204, 207, 208, 365
PMIX_MONITOR_FILE_MODIFY, 204, 206, 208, 364
PMIX MONITOR FILE SIZE, 204, 206, 208, 364
PMIX_MONITOR_HEARTBEAT, 204, 206, 208, 364
PMIX_MONITOR_HEARTBEAT_DROPS, 204, 206, 208, 364
PMIX MONITOR HEARTBEAT TIME, 204, 206, 208, 364
PMIX_MONITOR_ID, 204, 206, 208, 364
PMIX NO OVERSUBSCRIBE, 156, 161, 166, 340
PMIX_NO_PROCS_ON_HEAD, 156, 161, 165, 340
PMIX_NODE_INFO, 70, 73, 77, 82, 93, 99, 283
PMIX_NODE_INFO_ARRAY, 278, 282, 286, 286, 291, 292, 296, 297, 509
PMIX_NODE_LIST, 94, 95, 97
PMIX_NODE_MAP, 94, 95, 97, 280, 290, 291, 304, 305, 499
PMIX_NODE_MAP_RAW, 94, 510
PMIX_NODE_OVERSUBSCRIBED, 100, 282, 526
PMIX_NODE_RANK, 98, 284, 405
PMIX_NODE_SIZE, 99, 282
PMIX_NODEID, 70, 73, 77, 80, 82, 84, 87, 93, 99, 99, 243, 244, 254, 257, 278, 282, 284, 286, 297, 509, 515
PMIX NOHUP, 388, 392, 395, 511
PMIX_NOTIFY_COMPLETION, 166, 388, 407
PMIX NOTIFY JOB EVENTS, 166, 388, 407, 516
PMIX_NOTIFY_PROC_ABNORMAL_TERMINATION, 166, 517
PMIX_NOTIFY_PROC_TERMINATION, 166, 517
PMIX NPROC OFFSET, 95, 280
PMIX_NSDIR, 96, 98, 283, 284
PMIX_NSPACE, 78-80, 82-86, <u>95</u>, 278, 279, 286, 290, 351, 352, 403, 407, 410, 507, 508
PMIX_NUM_ALLOCATED_NODES, 94, 510
PMIX_NUM_NODES, 92, 94, 95, 96, 290, 510
PMIX_NUM_SLOTS, 94, 95, 97
PMIX_OPTIONAL, 70, 72, 74, 108
PMIX_OUTPUT_TO_DIRECTORY, 165, 516
PMIX_OUTPUT_TO_FILE, 156, 161, 165, 339
PMIX_PACKAGE_RANK, 98, 284, 510
PMIX PARENT ID, 98, 337, 393, 524
PMIX_PERSISTENCE, 111, 112, 113, 331, 430
PMIX_PERSONALITY, 155, 160, 164, 338
PMIX PPR, 155, 160, 164, 338
PMIX_PREFIX, 154, 159, 164, 338
PMIX_PRELOAD_BIN, 155, 160, 165, 338
PMIX_PRELOAD_FILES, 155, 160, <u>165</u>, 338
PMIX_PREPEND_ENVAR, 156, 162, 167
PMIX_PRIMARY_SERVER, 385, 415, 511
PMIX_PROC_INFO, 77, 82, 92
PMIX_PROC_INFO_ARRAY, 278, 283, 286, 292, 508, 520
PMIX_PROC_MAP, <u>94</u>, 94–97, 280, 290, 304, 305, 499
PMIX_PROC_MAP_RAW, 94, 510
PMIX PROC PID, 80, 84, 98
```

```
PMIX_PROC_STATE_STATUS, 80, 84, 408
PMIX_PROC_TERM_STATUS, 407, 408
PMIX PROCDIR, 98, 284
PMIX_PROCID, 77–79, 82–84, 86, 98, 166, 167, 278, 286, 352, 388–390, 407, 508, 517
PMIX_PROGRAMMING_MODEL, 59, 61, 281, 304
PMIX PSET MEMBERS, 217, 218, 515
PMIX_PSET_NAME, 217, 218, 515
PMIX_PSET_NAMES, 216, 218, 281, 515
PMIX_QUERY_ALLOC_STATUS, 79, 84, 86, 352
PMIX_QUERY_ATTRIBUTE_SUPPORT, 78, 82, 86, 90, 403, 507
PMIX_QUERY_AUTHORIZATIONS, 80, 84, 86
PMIX_QUERY_AVAIL_SERVERS, 86, 383, 507
PMIX_QUERY_DEBUG_SUPPORT, 79, 84, 86, 352
PMIX_QUERY_GROUP_MEMBERSHIP, 221, 515
PMIX_QUERY_GROUP_NAMES, 221, 515
PMIX_QUERY_JOB_STATUS, 79, 83, 85, 351
PMIX_QUERY_LOCAL_ONLY, 86, 352
PMIX_QUERY_LOCAL_PROC_TABLE, 79, 83, 85, 352, 403, 410
PMIX QUERY MEMORY USAGE, 79, 84, 86, 352
PMIX_QUERY_NAMESPACE_INFO, 85, 507
PMIX QUERY NAMESPACES, 79, 83, 85, 351, 403
PMIX_QUERY_NUM_GROUPS, 221, 515
PMIX_QUERY_NUM_PSETS, 86, 218, 515
PMIX_QUERY_PROC_TABLE, 79, 83, 85, 351, 403, 410
PMIX_QUERY_PSET_MEMBERSHIP, 86, 218, 515
PMIX_QUERY_PSET_NAMES, 86, 218, 515
PMIX_QUERY_QUALIFIERS, 80, 85, 85, 507
PMIX_QUERY_QUEUE_LIST, 79, 83, 85, 351
PMIX_QUERY_QUEUE_STATUS, 79, 83, 85, 351
PMIX_QUERY_REFRESH_CACHE, 77, 80, 81, 85, 90
PMIX_QUERY_REPORT_AVG, 79, 84, 86, 352
PMIX_QUERY_REPORT_MINMAX, 79, 84, 86, 352
PMIX_QUERY_RESULTS, 80, 85, 506
PMIX OUERY SPAWN SUPPORT, 79, 83, 86, 352
PMIX_QUERY_STORAGE_LIST, 425, 523
PMIX_QUERY_SUPPORTED_KEYS, 85, 507
PMIX_QUERY_SUPPORTED_QUALIFIERS, 85, 507
PMIX_RANGE, 111, 112, 113, 116, 118, 123, 124, 130, 205, 221, 331, 333, 335, 349, 376, 430, 515
PMIX_RANK, 78, 79, 82–84, 86, 97, 158, 163, 278, 283, 286, 352, 406, 409, 508
PMIX_RANKBY, 155, 160, 165, 280, 338
PMIX_REGISTER_CLEANUP, 197, 200, 202
PMIX_REGISTER_CLEANUP_DIR, 197, 200, 202
PMIX_REGISTER_NODATA, 277, 286
PMIX REINCARNATION, 98, 284, 510
PMIX_REPORT_BINDINGS, 156, 161, 166, 340
PMIX_REQUESTOR_IS_CLIENT, 337, 341
PMIX REQUESTOR IS TOOL, 337, 341
```

```
PMIX_REQUIRED_KEY, 329, 330, 509
PMIX_RM_NAME, 93, 279
PMIX RM VERSION, 94, 279
PMIX_SEND_HEARTBEAT, 204, 207, 208
PMIX_SERVER_ATTRIBUTES, 78, 83, 87, 91, 501, 507
PMIX SERVER ENABLE MONITORING, 273, 274
PMIX_SERVER_FUNCTIONS, 78, 82, 86, 87, 90, 507
PMIX SERVER GATEWAY, 271, 274
PMIX_SERVER_HOSTNAME, 279, 385
PMIX_SERVER_INFO_ARRAY, 86, 86, 507
PMIX_SERVER_NSPACE, 271, 274, 279, 382, 411, 415
PMIX_SERVER_PIDINFO, 382, 384, 411, 415
PMIX_SERVER_RANK, 271, 274, 279
PMIX_SERVER_REMOTE_CONNECTIONS, 272, 274
PMIX_SERVER_SCHEDULER, 254, 257, 271, 275, 508, 512
PMIX_SERVER_SESSION_SUPPORT, 271, 274, 508
PMIX_SERVER_SHARE_TOPOLOGY, 272, 274, 508
PMIX_SERVER_START_TIME, 274, 508
PMIX SERVER SYSTEM SUPPORT, 271, 274, 380
PMIX_SERVER_TMPDIR, 271, 273, 274, 380, 381
PMIX SERVER TOOL SUPPORT, 263, 271, 273, 274
PMIX_SERVER_URI, 80, 84, 382, 383, 385, 411, 415
PMIX_SESSION_ID, 93, 93, 95, 101, 277–279, 286, 290, 407, 508
PMIX_SESSION_INFO, 70, 73, 77, 81, 92, 94, 101, 278, 280, 304
PMIX_SESSION_INFO_ARRAY, 277, 278, 286, 286, 290, 497
PMIX_SET_ENVAR, 156, 161, 167
PMIX_SET_SESSION_CWD, 154, 159, 165, 337
PMIX_SETUP_APP_ALL, 303, 306
PMIX_SETUP_APP_ENVARS, 303, 306
PMIX_SETUP_APP_NONENVARS, 303, 306
PMIX_SINGLE_LISTENER, 58, 271, 274
PMIX_SINGLETON, 273, 275, 526
PMIX_SOCKET_MODE, 58, 271, 274, 412
PMIX SPAWN TIMEOUT, 158, 163, 167, 340, 526
PMIX_SPAWN_TOOL, 158, 163, 166, 394
PMIX_SPAWNED, 98, 284, 337
PMIX_STDIN_TGT, 155, 160, 165, 338
PMIX_STORAGE_ACCESS_TYPE, 426, 523
PMIX_STORAGE_ACCESSIBILITY, 425, 523
PMIX_STORAGE_BW_CUR, <u>425</u>, 426, 523
PMIX_STORAGE_BW_MAX, 425, 523
PMIX_STORAGE_CAPACITY_LIMIT, 425, 523
PMIX_STORAGE_CAPACITY_USED, 425, 523
PMIX_STORAGE_ID, 425, 425, 522, 523
PMIX_STORAGE_IOPS_CUR, <u>426</u>, 426, 523
PMIX_STORAGE_IOPS_MAX, 425, 523
PMIX_STORAGE_MEDIUM, 425, 522
```

```
PMIX_STORAGE_MINIMAL_XFER_SIZE, 425, 523
PMIX_STORAGE_OBJECT_LIMIT, 425, 523
PMIX STORAGE OBJECTS USED, 425, 523
PMIX_STORAGE_PATH, 425, 522
PMIX_STORAGE_PERSISTENCE, 425, 523
PMIX STORAGE SUGGESTED XFER SIZE, 425, 426, 523
PMIX_STORAGE_TYPE, 425, 522
PMIX STORAGE VERSION, 425, 522
PMIX_SWITCH_PEERS, 257, 257, 513
PMIX_SYSTEM_TMPDIR, 271, 274, 380, 381
PMIX_TAG_OUTPUT, 155, 160, 165, 339
PMIX_TCP_DISABLE_IPV4, 59, 61, 272, 412
PMIX_TCP_DISABLE_IPV6, 59, 61, 272, 412
PMIX_TCP_IF_EXCLUDE, 59, 61, 272, 412
PMIX_TCP_IF_INCLUDE, 59, 61, 272, 412
PMIX_TCP_IPV4_PORT, 59, 61, 272, 412
PMIX_TCP_IPV6_PORT, 59, 61, 272, 412
PMIX_TCP_REPORT_URI, 59, 61, 271, 412
PMIX TCP URI, 61, 382, 383, 411, 415
PMIX_TDIR_RMCLEAN, 93, 280
PMIX THREADING MODEL, 60, 61
PMIX_TIME_REMAINING, 75, 79, 84, 86, 352
PMIX_TIMEOUT, 4, 65, 68, 71, 74, 74, 100, 109, 111, 112, 116, 118, 123, 124, 158, 163, 167, 172, 174, 176,
         178, 220, 224, 225, 227, 228, 230, 232, 235, 236, 238, 264, 266, 268, 269, 326, 329, 331, 333, 335,
         340, 342, 344, 366, 369, 385, 417, 512, 526
PMIX_TIMEOUT_REPORT_STATE, 166, 516
PMIX_TIMEOUT_STACKTRACES, 166, 516
PMIX_TIMESTAMP_OUTPUT, 155, 161, 165, 339
PMIX_TMPDIR, 93, 96, 282, 283
PMIX_TOOL_ATTACHMENT_FILE, 382, 383, 385, 411, 415, 510
PMIX_TOOL_ATTRIBUTES, 78, 83, 87, 91, 501, 508
PMIX_TOOL_CONNECT_OPTIONAL, 385, 510
PMIX_TOOL_DO_NOT_CONNECT, 381, 382, 385, 411, 413
PMIX TOOL FUNCTIONS, 78, 82, 86, 87, 91, 507, 508
PMIX_TOOL_NSPACE, 353, 381, 384, 411, 413
PMIX_TOOL_RANK, 353, 381, 384, 411, 413
PMIX TOPOLOGY2, 272, 274, 508, 519
PMIX_UNIV_SIZE, 8, 93, 278, 290, 496, 499
PMIX_UNSET_ENVAR, 156, 161, 167
PMIX_USERID, 78, 83, 110, 112, 115, 117, 123, 124, 190, 192, 197, 199, 204, 206, 209, 212, 264, 265, 267,
         269, 331–337, 345, 351, 353, 355, 356, 358, 361, 364, 366, 368, 370, 371, 374
PMIX_USOCK_DISABLE, 58, 271, 274
PMIX_VERSION_INFO, 354, 355
PMIX WAIT, 73, 74, 116, 118, 333
PMIX_WAIT_FOR_CONNECTION, 385, 417, 512
PMIX_WDIR, 154, 159, 164, 281, 337
PMIX_ALLOC_NETWORK
```

```
Deprecated, 519
PMIX_ALLOC_NETWORK_ENDPTS
    Deprecated, 519
PMIX_ALLOC_NETWORK_ENDPTS_NODE
    Deprecated, 520
PMIX_ALLOC_NETWORK_ID
    Deprecated, 519
PMIX_ALLOC_NETWORK_PLANE
    Deprecated, 519
PMIX_ALLOC_NETWORK_QOS
    Deprecated, 519
PMIX_ALLOC_NETWORK_SEC_KEY
    Deprecated, 520
PMIX_ALLOC_NETWORK_TYPE
    Deprecated, 519
PMIX_ARCH
    Deprecated, 500
    Removed, 521
PMIX COLLECTIVE ALGO
    Deprecated, 500
    Removed, 520
PMIX_COLLECTIVE_ALGO_REQD
    Deprecated, 498
    Removed, 521
PMIX_DEBUG_JOB
    Deprecated, 519
PMIX_DEBUG_WAIT_FOR_NOTIFY
    Deprecated, 524
PMIX_DSTPATH
    Deprecated, 500
    Removed, 520
PMIX ERROR GROUP ABORT
    Deprecated, 496
    Removed, 498
PMIX_ERROR_GROUP_COMM
    Deprecated, 496
    Removed, 498
PMIX_ERROR_GROUP_GENERAL
    Deprecated, 496
    Removed, 498
PMIX_ERROR_GROUP_LOCAL
    Deprecated, 496
    Removed, 498
PMIX_ERROR_GROUP_MIGRATE
    Deprecated, 496
    Removed, 498
PMIX_ERROR_GROUP_NODE
```

```
Deprecated, 496
    Removed, 498
PMIX_ERROR_GROUP_RESOURCE
    Deprecated, 496
    Removed, 498
PMIX_ERROR_GROUP_SPAWN
    Deprecated, 496
    Removed, <u>498</u>
PMIX_ERROR_HANDLER_ID
    Deprecated, 496
    Removed, 498
PMIX_ERROR_NAME
    Deprecated, 496
    Removed, 498
PMIX_HWLOC_HOLE_KIND
    Deprecated, 500
    Removed, 520
PMIX_HWLOC_SHARE_TOPO
    Deprecated, 500
    Removed, 520
PMIX_HWLOC_SHMEM_ADDR
    Deprecated, 500
    Removed, 520
PMIX_HWLOC_SHMEM_FILE
    Deprecated, 500
    Removed, 520
PMIX_HWLOC_SHMEM_SIZE
    Deprecated, 500
    Removed, 520
PMIX_HWLOC_XML_V1
    Deprecated, 500
    Removed, 520
PMIX_HWLOC_XML_V2
    Deprecated, 500
    Removed, 520
PMIX_LOCAL_TOPO
    Deprecated, 500
    Removed, 520
PMIX_LOCALITY
    Deprecated, 520
PMIX_MAP_BLOB
    Deprecated, 501
    Removed, 521
PMIX MAPPER
    Deprecated, 500
    Removed, 521
PMIX_NON_PMI
```

Deprecated, 501 **Removed**, <u>521</u> $PMIX_PROC_BLOB$ Deprecated, 501 **Removed**, <u>**521**</u> PMIX_PROC_DATA Deprecated, <u>520</u> PMIX_PROC_URI Deprecated, 501 **Removed**, <u>521</u> PMIX_RECONNECT_SERVER Deprecated, <u>519</u> PMIX_TOPOLOGY Deprecated, <u>519</u> $PMIX_TOPOLOGY_FILE$ Deprecated, 501 Removed, 520 PMIX_TOPOLOGY_SIGNATURE Deprecated, 501 Removed, 520 $PMIX_TOPOLOGY_XML$ Deprecated, 501 **Removed**, <u>520</u>